Docker Provider

The Docker provider is used to interact with Docker containers and images. It uses the Docker API to manage the lifecycle of Docker containers. Because the Docker provider uses the Docker API, it is immediately compatible not only with single server Docker but Swarm and any additional Docker-compatible API hosts.

Use the navigation to the left to read about the available resources.

Example Usage

```
# Configure the Docker provider
provider "docker" {
  host = "tcp://127.0.0.1:2376/"
}

# Create a container
resource "docker_container" "foo" {
  image = "${docker_image.ubuntu.latest}"
  name = "foo"
}

resource "docker_image" "ubuntu" {
  name = "ubuntu:latest"
}
```

Registry Credentials

Registry credentials can be provided on a per-registry basis with the registry_auth field, passing either a config file or the username/password directly.

Note The location of the config file is on the machine terraform runs on, nevertheless if the specified docker host is on another machine.

```
provider "docker" {
  host = "tcp://localhost:2376"

registry_auth {
  address = "registry.hub.docker.com"
  config_file = "~/.docker/config.json"
}

registry_auth {
  address = "quay.io:8181"
  username = "someuser"
  password = "somepass"
  }
}

data "docker_registry_image" "quay" {
  name = "myorg/privateimage"
}

data "docker_registry_image" "quay" {
  name = "quay.io:8181/myorg/privateimage"
}
```

Note When passing in a config file make sure every repo in the auths object should have a corresponding auth string.

In this case, either use username and password directly or set the environment variables DOCKER_REGISTRY_USER and DOCKER_REGISTRY_PASS or add the string manually via

```
echo -n "user:pass" | base64
# dXNlcjpwYXNz=
```

and paste it into ~/.docker/config.json:

```
{
    "auths": {
        "repo.mycompany:8181": {
             "auth": "dXNlcjpwYXNz="
        }
    }
}
```

Certificate information

Specify certificate information either with a directory or directly with the content of the files for connecting to the Docker host via TLS.

```
provider "docker" {
  host = "tcp://your-host-ip:2376/"

# -> specify either
  cert_path = "${pathexpand("~/.docker")}"

# -> or the following
  ca_material = "${file(pathexpand("~/.docker/ca.pem"))}" # this can be omitted
  cert_material = "${file(pathexpand("~/.docker/cert.pem"))}"
  key_material = "${file(pathexpand("~/.docker/key.pem"))}"
}
```

Argument Reference

The following arguments are supported:

- host (Required) This is the address to the Docker host. If this is blank, the DOCKER_HOST environment variable will also be read.
- cert_path (Optional) Path to a directory with certificate information for connecting to the Docker host via TLS. It is expected that the 3 files {ca, cert, key}.pem are present in the path. If the path is blank, the DOCKER_CERT_PATH will also be checked.
- ca_material, cert_material, key_material, (Optional) Content of ca.pem, cert.pem, and key.pem files for TLS authentication. Cannot be used together with cert_path. If ca_material is omitted the client does not check the servers certificate chain and host name.
- registry_auth (Optional) A block specifying the credentials for a target v2 Docker registry.
 - o address (Required) The address of the registry.
 - username (Optional) The username to use for authenticating to the registry. Cannot be used with the config_file option. If this is blank, the DOCKER_REGISTRY_USER will also be checked.
 - password (Optional) The password to use for authenticating to the registry. Cannot be used with the config_file option. If this is blank, the DOCKER_REGISTRY_PASS will also be checked.
 - config_file (Optional) The path to a config file containing credentials for authenticating to the registry. Cannot be used with the username/password options. If this is blank, the DOCKER_CONFIG will also be checked.

NOTE on Certificates and docker-machine: As per Docker Remote API documentation

(https://docs.docker.com/engine/reference/api/docker_remote_api/), in any docker-machine environment, the Docker daemon uses an encrypted TCP socket (TLS) and requires cert_path for a successful connection. As an alternative, if using docker-machine, run eval \$(docker-machine env <machine-name>) prior to running Terraform, and the host and certificate path will be extracted from the environment.

docker_registry_image

Reads the image metadata from a Docker Registry. Used in conjunction with the docker_image (/docs/providers/docker/r/image.html) resource to keep an image up to date on the latest available version of the tag.

Example Usage

```
data "docker_registry_image" "ubuntu" {
  name = "ubuntu:precise"
}

resource "docker_image" "ubuntu" {
  name = "${data.docker_registry_image.ubuntu.name}"
  pull_triggers = ["${data.docker_registry_image.ubuntu.sha256_digest}"]
}
```

Argument Reference

The following arguments are supported:

• name - (Required, string) The name of the Docker image, including any tags. e.g. alpine:latest

Attributes Reference

The following attributes are exported in addition to the above configuration:

• sha256_digest (string) - The content digest of the image, as stored on the registry.

docker_config

Manages the configuration of a Docker service in a swarm.

Example Usage

Basic

```
# Creates a config
resource "docker_config" "foo_config" {
  name = "foo_config"
  data = "ewogICJzZXJIfQo="
}
```

Advanced

Dynamically set config with a template

In this example you can use the \${var.foo_port} variable to dynamically set the \${port} variable in the foo.configs.json.tpl template and create the data of the foo_config with the help of the base64encode interpolation function.

File foo.config.json.tpl

```
{
    "server": {
      "public_port": ${port}
    }
}
```

File main.tf

```
# Creates the template in renders the variable
data "template_file" "foo_config_tpl" {
  template = "${file("foo.config.json.tpl")}"

  vars {
    port = "${var.foo_port}"
  }
}

# Creates the config
resource "docker_config" "foo_config" {
    name = "foo_config"
    data = "${base64encode(data.template_file.foo_config_tpl.rendered)}"
}
```

Update config with no downtime

To update a config, Terraform will destroy the existing resource and create a replacement. To effectively use a docker_config resource with a docker_service resource, it's recommended to specify create_before_destroy in a lifecycle block. Provide a unique name attribute, for example with one of the interpolation functions unid or timestamp as shown in the example below. The reason is moby-35803 (https://github.com/moby/moby/issues/35803).

```
resource "docker_config" "service_config" {
  name = "${var.service_name}-config-${replace(timestamp(),":", ".")}"
  data = "${base64encode(data.template_file.service_config_tpl.rendered)}"
 lifecycle {
    ignore_changes = ["name"]
    create_before_destroy = true
  }
}
resource "docker_service" "service" {
   configs = [
      config_id = "${docker_config.service_config.id}"
      config_name = "${docker_config.service_config.name}"
     file_name = "/root/configs/configs.json"
    },
  ]
}
```

Argument Reference

The following arguments are supported:

- name (Required, string) The name of the Docker config.
- data (Required, string) The base64 encoded data of the config.

Attributes Reference

The following attributes are exported in addition to the above configuration:

• id (string)

docker_container

Manages the lifecycle of a Docker container.

Example Usage

```
# Start a container
resource "docker_container" "ubuntu" {
  name = "foo"
  image = "${docker_image.ubuntu.latest}"
}

# Find the latest Ubuntu precise image.
resource "docker_image" "ubuntu" {
  name = "ubuntu:precise"
}
```

Argument Reference

The following arguments are supported:

- name (Required, string) The name of the Docker container.
- image (Required, string) The ID of the image to back this container. The easiest way to get this value is to use the docker_image resource as is shown in the example above.
- command (Optional, list of strings) The command to use to start the container. For example, to run /usr/bin/myprogram -f baz.conf set the command to be ["/usr/bin/myprogram", "-f", "baz.conf"].
- entrypoint (Optional, list of strings) The command to use as the Entrypoint for the container. The Entrypoint allows you to configure a container to run as an executable. For example, to run /usr/bin/myprogram when starting a container, set the entrypoint to be ["/usr/bin/myprogram"].
- user (Optional, string) User used for run the first process. Format is user or user: group which user and group can be passed literraly or by name.
- dns (Optional, set of strings) Set of DNS servers.
- dns_opts (Optional, set of strings) Set of DNS options used by the DNS provider(s), see resolv.conf documentation for valid list of options.
- dns_search (Optional, set of strings) Set of DNS search domains that are used when bare unqualified hostnames are used inside of the container.
- env (Optional, set of strings) Environment variables to set.
- labels (Optional, map of strings) Key/value pairs to set as labels on the container.
- links (Optional, set of strings) Set of links for link based connectivity between containers that are running on the same host.

Warning The --link flag is a legacy feature of Docker. It may eventually be removed. It exposes *all* environment variables originating from Docker to any linked containers. This could have serious security implications if sensitive data is stored in them. See [the docker documentation][linkdoc] for more details.

- hostname (Optional, string) Hostname of the container.
- domainname (Optional, string) Domain name of the container.
- restart (Optional, string) The restart policy for the container. Must be one of "no", "on-failure", "always", "unless-stopped".
- max_retry_count (Optional, int) The maximum amount of times to an attempt a restart when restart is set to "onfailure"
- rm (Optional, bool) If true, then the container will be automatically removed after his execution. Terraform won't check this container after creation.
- start (Optional, bool) If true, then the Docker container will be started after creation. If false, then the container is only created.
- attach (Optional, bool) If true attach to the container after its creation and waits the end of his execution.
- logs (Optional, bool) Save the container logs (attach must be enabled).
- must_run (Optional, bool) If true, then the Docker container will be kept running. If false, then as long as the container
 exists, Terraform assumes it is successful.
- capabilities (Optional, block) See Capabilities below for details.
- ports (Optional, block) See Ports below for details.
- host (Optional, block) See Extra Hosts below for details.
- privileged (Optional, bool) Run container in privileged mode.
- devices (Optional, bool) See Devices below for details.
- publish_all_ports (Optional, bool) Publish all ports of the container.
- volumes (Optional, block) See Volumes below for details.
- memory (Optional, int) The memory limit for the container in MBs.
- memory_swap (Optional, int) The total memory limit (memory + swap) for the container in MBs. This setting may compute to -1 after terraform apply if the target host doesn't support memory swap, when that is the case docker will use a soft limitation.
- cpu_shares (Optional, int) CPU shares (relative weight) for the container.
- cpu_set (Optional, string) A comma-separated list or hyphen-separated range of CPUs a container can use, e.g. 0-1.
- log_driver (Optional, string) The logging driver to use for the container. Defaults to "json-file".
- log_opts (Optional, map of strings) Key/value pairs to use as options for the logging driver.
- network_alias (Optional, set of strings) Network aliases of the container for user-defined networks only. *Deprecated:* use networks_advanced instead.

- network_mode (Optional, string) Network mode of the container.
- networks (Optional, set of strings) Id of the networks in which the container is. *Deprecated:* use networks_advanced instead.
- networks_advanced (Optional, block) See Networks Advanced below for details.
- destroy_grace_seconds (Optional, int) If defined will attempt to stop the container before destroying. Container will be destroyed after n seconds or on successful stop.
- upload (Optional, block) See File Upload below for details.
- ulimit (Optional, block) See Ulimits below for details.
- pid_mode (Optional, string) The PID (Process) Namespace mode for the container. Either container: <name|id> or host.
- userns_mode (Optional, string) Sets the usernamespace mode for the container when usernamespace remapping
 option is enabled.
- healthcheck (Optional, block) See Healthcheck below for details.

Capabilities

capabilities is a block within the configuration that allows you to add or drop linux capabilities. For more information about what capabilities you can add and drop please visit the docker run documentation.

- add (Optional, set of strings) list of linux capabilities to add.
- drop (Optional, set of strings) list of linux capabilities to drop.

Example:

```
resource "docker_container" "ubuntu" {
  name = "foo"
  image = "${docker_image.ubuntu.latest}"
  capabilities {
   add = ["ALL"]
   drop = ["SYS_ADMIN"]
  }
}
```

Ports

ports is a block within the configuration that can be repeated to specify the port mappings of the container. Each ports block supports the following:

- internal (Required, int) Port within the container.
- external (Optional, int) Port exposed out of the container. If not given a free random port >= 32768 will be used.
- ip (Optional, string) IP address/mask that can access this port, default to 0.0.0.0
- protocol (Optional, string) Protocol that can be used over this port, defaults to tcp.

Extra Hosts

host is a block within the configuration that can be repeated to specify the extra host mappings for the container. Each host block supports the following:

- host (Required, string) Hostname to add.
- ip (Required, string) IP address this hostname should resolve to.

This is equivalent to using the --add-host option when using the run command of the Docker CLI.

Volumes

volumes is a block within the configuration that can be repeated to specify the volumes attached to a container. Each volumes block supports the following:

- from_container (Optional, string) The container where the volume is coming from.
- host_path (Optional, string) The path on the host where the volume is coming from.
- volume_name (Optional, string) The name of the docker volume which should be mounted.
- container_path (Optional, string) The path in the container where the volume will be mounted.
- read_only (Optional, bool) If true, this volume will be readonly. Defaults to false.

One of from_container, host_path or volume_name must be set.

File Upload

upload is a block within the configuration that can be repeated to specify files to upload to the container before starting it. Each upload supports the following

- content (Required, string) A content of a file to upload.
- file (Required, string) path to a file in the container.
- executable (Optional, bool) If true, the file will be uploaded with user executable permission. Defaults to false.

Network advanced

networks_advanced is a block within the configuration that can be repeated to specify files to upload to the container before starting it. Each networks_advanced supports the following:

- name (Required, string) A content of a file to upload.
- aliases (Optional, set of strings) The network aliases of the container in the specific network.
- ipv4_address (Optional, string) The IPV4 address of the container in the specific network.
- ipv6_address (Optional, string) The IPV6 address of the container in the specific network.

Devices

devices is a block within the configuration that can be repeated to specify the devices exposed to a container. Each devices block supports the following:

- host_path (Required, string) The path on the host where the device is located.
- container_path (Optional, string) The path in the container where the device will be binded.
- permissions (Optional, string) The cgroup permissions given to the container to access the device. Defaults to rwm.

Ulimits

ulimit is a block within the configuration that can be repeated to specify the extra ulimits for the container. Each ulimit block supports the following:

- name (Required, string)
- soft (Required, int)
- hard (Required, int)

Healthcheck

healthcheck is a block within the configuration that can be repeated only **once** to specify the extra healthcheck configuration for the container. The healthcheck block is a test to perform to check that the container is healthy and supports the following:

- test (Required, list of strings) Command to run to check health. For example, to run curl -f http://localhost/health set the command to be ["CMD", "curl", "-f", "http://localhost/health"].
- interval (Optional, string) Time between running the check (ms|s|m|h). Default: 0s.
- timeout (Optional, string) Maximum time to allow one check to run (ms|s|m|h). Default: 0s.
- start_period (Optional, string) Start period for the container to initialize before counting retries towards unstable (ms|s|m|h). Default: 0s.
- retries (Optional, int) Consecutive failures needed to report unhealthy. Default: 0.

Attributes Reference

The following attributes are exported:

- exit_code The exit code of the container if its execution is done (must_run must be disabled).
- container_logs The logs of the container if its execution is done (attach must be disabled).
 - network_data (Map of a block) The IP addresses of the container on each network. Key are the network names,
 values are the IP addresses.
 - ip_address The IP address of the container.

- ip_prefix_length The IP prefix length of the container.
- gateway The network gateway of the container.
- bridge The network bridge of the container as read from its NetworkSettings.
- ip_address Deprecated: Use network_data instead. The IP address of the container's first network it.
- ip_prefix_length *Deprecated:* Use network_data instead. The IP prefix length of the container as read from its NetworkSettings.
- gateway *Deprecated:* Use network_data instead. The network gateway of the container as read from its NetworkSettings.

[linkdoc] https://docs.docker.com/network/links/ (https://docs.docker.com/network/links/)

docker_image

Pulls a Docker image to a given Docker host from a Docker Registry.

This resource will *not* pull new layers of the image automatically unless used in conjunction with docker_registry_image (/docs/providers/docker/d/registry_image.html) data source to update the pull_triggers field.

Example Usage

```
# Find the latest Ubuntu precise image.
resource "docker_image" "ubuntu" {
  name = "ubuntu:precise"
}
# Access it somewhere else with ${docker_image.ubuntu.latest}
```

Dynamic image

```
data "docker_registry_image" "ubuntu" {
  name = "ubuntu:precise"
}

resource "docker_image" "ubuntu" {
  name = "${data.docker_registry_image.ubuntu.name}"
  pull_triggers = ["${data.docker_registry_image.ubuntu.sha256_digest}"]
}
```

Argument Reference

The following arguments are supported:

- name (Required, string) The name of the Docker image, including any tags or SHA256 repo digests.
- keep_locally (Optional, boolean) If true, then the Docker image won't be deleted on destroy operation. If this is false, it will delete the image from the docker local storage on destroy operation.
- pull_triggers (Optional, list of strings) List of values which cause an image pull when changed. This is used to store
 the image digest from the registry when using the docker_registry_image data source
 (/docs/providers/docker/d/registry_image.html) to trigger an image update.
- pull_trigger **Deprecated**, use pull_triggers instead.

Attributes Reference

The following attributes are exported in addition to the above configuration:

• latest (string) - The ID of the image.

docker_network

Manages a Docker Network. This can be used alongside docker_container (/docs/providers/docker/r/container.html) to create virtual networks within the docker environment.

Example Usage

```
# Create a new docker network
resource "docker_network" "private_network" {
  name = "my_network"
}
# Access it somewhere else with ${docker_network.private_network.name}
```

Argument Reference

The following arguments are supported:

- name (Required, string) The name of the Docker network.
- labels (Optional, map of string/string key/value pairs) User-defined key/value metadata.
- check_duplicate (Optional, boolean) Requests daemon to check for networks with same name.
- driver (Optional, string) Name of the network driver to use. Defaults to bridge driver.
- options (Optional, map of strings) Network specific options to be used by the drivers.
- internal (Optional, boolean) Restrict external access to the network. Defaults to false.
- attachable (Optional, boolean) Enable manual container attachment to the network. Defaults to false.
- ingress (Optional, boolean) Create swarm routing-mesh network. Defaults to false.
- ipv6 (Optional, boolean) Enable IPv6 networking. Defaults to false.
- ipam_driver (Optional, string) Driver used by the custom IP scheme of the network.
- ipam_config (Optional, block) See IPAM config below for details.

IPAM config

Configuration of the custom IP scheme of the network.

The ipam_config block supports:

- subnet (Optional, string)
- ip_range (Optional, string)
- gateway (Optional, string)

• aux_address - (Optional, map of string)

Attributes Reference

The following attributes are exported in addition to the above configuration:

- id (string)
- scope (string)

docker_secret

Manages the secrets of a Docker service in a swarm.

Example Usage

Basic

```
# Creates a secret
resource "docker_secret" "foo_secret" {
  name = "foo_secret"
  data = "ewogICJzZXJsaasIfQo="
}
```

Update secret with no downtime

To update a secret, Terraform will destroy the existing resource and create a replacement. To effectively use a docker_secret resource with a docker_service resource, it's recommended to specify create_before_destroy in a lifecycle block. Provide a unique name attribute, for example with one of the interpolation functions unid or timestamp as shown in the example below. The reason is moby-35803 (https://github.com/moby/moby/issues/35803).

```
resource "docker_secret" "service_secret" {
 name = "${var.service_name}-secret-${replace(timestamp(),":", ".")}"
 data = "${base64encode(data.template_file.service_secret_tpl.rendered)}"
 lifecycle {
   ignore_changes = ["name"]
   create_before_destroy = true
}
resource "docker_service" "service" {
  # ...
  secrets = [
     secret_id = "${docker_secret.service_secret.id}"
     secret_name = "${docker_secret.service_secret.name}"
                = "/root/configs/configs.json"
     file name
   },
  ]
}
```

Argument Reference

The following arguments are supported:

- name (Required, string) The name of the Docker secret.
- data (Required, string) The base64 encoded data of the secret.

• labels - (Optional, map of string/string key/value pairs) User-defined key/value metadata.

Attributes Reference

The following attributes are exported in addition to the above configuration:

• id (string)

docker_service

This resource manages the lifecycle of a Docker service. By default, the creation, update and delete of services are detached.

With the Converge Config the behavior of the docker cli is imitated to guarantee that for example, all tasks of a service are running or successfully updated or to inform terraform that a service could not be updated and was successfully rolled back.

Example Usage

The following examples show the basic and advanced usage of the Docker Service resource assuming the host machine is already part of a Swarm.

Basic

The following configuration starts a Docker Service with - the given image, - 1 replica - exposes the port 8080 in vip mode to the host machine - moreover, uses the container runtime

The following command is the equivalent:

```
$ docker service create -d -p 8080 --name foo-service repo.mycompany.com:8080/foo-service:v1
```

Advanced

The following configuration shows the full capabilities of a Docker Service. Currently, the Docker API 1.32 (https://docs.docker.com/engine/api/v1.32) is implemented.

```
resource "docker_volume" "test_volume" {
    name = "tftest-volume"
}

resource "docker_config" "service_config" {
    name = "tftest-full-myconfig"
    data = "ewogICJwcmVmaXgiOiAiMTIzIgp9"
}
```

```
resource "docker_secret" "service_secret" {
   name = "tftest-mysecret"
   data = "ewogICJrZXkiOiAiUVdFUlRZIgp9"
resource "docker_network" "test_network" {
   name = "tftest-network"
   driver = "overlay"
}
resource "docker_service" "foo" {
   name = "tftest-service-basic"
   task_spec {
       container_spec {
           image = "repo.mycompany.com:8080/foo-service:v1"
           labels {
               foo = "bar"
           command = ["ls"]
           args = ["-las"]
           hostname = "my-fancy-service"
           env {
               MYFOO = "BAR"
           dir = "/root"
           user = "root"
           groups = ["docker", "foogroup"]
           privileges {
               se_linux_context {
                   disable = true
                   user = "user-label"
                   role = "role-label"
                   type = "type-label"
                   level = "level-label"
               }
           }
           read_only = true
           mounts = Γ
                            = "/mount/test"
                   target
                             = "${docker_volume.test_volume.name}"
                   source
                             = "volume"
                   type
                   read_only = true
                   bind_options {
                      propagation = "private"
               },
           1
           stop_signal = "SIGTERM"
           stop_grace_period = "10s"
           healthcheck {
               test = ["CMD", "curl", "-f", "http://localhost:8080/health"]
               interval = "5s"
```

```
timeout = "2s"
       retries = 4
   }
   hosts {
       host = "testhost"
       ip = "10.0.1.0"
   }
   dns_config {
       nameservers = ["8.8.8.8"]
                 = ["example.org"]
                   = ["timeout:3"]
       options
   }
   secrets = [
       {
           secret_id = "${docker_secret.service_secret.id}"
           secret_name = "${docker_secret.service_secret.name}"
           file_name = "/secrets.json"
       },
   ]
   configs = [
       {
           config_id = "${docker_config.service_config.id}"
           config_name = "${docker_config.service_config.name}"
           file_name = "/configs.json"
       },
   ]
}
resources {
   limits {
       nano_cpus = 1000000
       memory_bytes = 536870912
       generic_resources {
           named_resources_spec = [
               "GPU=UUID1"
           discrete_resources_spec = [
               "SSD=3"
           ]
       }
   }
   reservation {
       nano_cpus
                  = 1000000
       memory_bytes = 536870912
       generic_resources {
           named_resources_spec = [
               "GPU=UUID1"
           discrete_resources_spec = [
               "SSD=3"
           ]
       }
   }
restart_policy {
               = "on-failure"
   condition
```

```
delay
                  = "3s"
        max_attempts = 4
               = "10s"
        window
    }
    placement {
        constraints = [
            "node.role==manager",
        prefs = [
           "spread=node.role.manager",
        ]
    }
    force_update = 0
            = "container"
    runtime
    networks
                = ["${docker_network.test_network.id}"]
    log_driver {
        name = "json-file"
        options {
           max-size = "10m"
           max-file = "3"
        }
    }
mode {
    replicated {
       replicas = 2
    }
}
update_config {
                     = 2
    parallelism
                     = "10s"
    delay
    failure_action = "pause"
   monitor
                     = "5s"
   max_failure_ratio = "0.1"
                     = "start-first"
   order
}
rollback_config {
    parallelism
                     = "5ms"
    delay
    failure_action = "pause"
   monitor
                     = "10h"
   max_failure_ratio = "0.9"
                     = "stop-first"
   order
}
endpoint_spec {
   mode = "vip"
    ports {
                      = "random"
        name
                      = "tcp"
        protocol
                    = "8080"
        target_port
        published_port = "8080"
        publish_mode = "ingress"
    }
}
```

}

See also the TestAccDockerService_full test or all the other tests for a complete overview.

Argument Reference

The following arguments are supported:

- auth (Optional, block) See Auth below for details.
- name (Required, string) The name of the Docker service.
- task_spec (Required, block) See TaskSpec below for details.
- mode (Optional, block) See Mode below for details.
- update_config (Optional, block) See UpdateConfig below for details.
- rollback_config (Optional, block) See RollbackConfig below for details.
- endpoint_spec (Optional, block) See EndpointSpec below for details.
- converge_config (Optional, block) See Converge Config below for details.

Auth

auth can be used additionally to the registry_auth. If both properties are given the auth wins and overwrites the auth of the provider.

- server_address (Required, string) The address of the registry server
- username (Optional, string) The username to use for authenticating to the registry. If this is blank, the DOCKER_REGISTRY_USER is also be checked.
- password (Optional, string) The password to use for authenticating to the registry. If this is blank, the DOCKER_REGISTRY_PASS is also be checked.

TaskSpec

task_spec is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The task_spec block is the user modifiable task configuration and supports the following:

- container_spec (Required, block) See ContainerSpec below for details.
- resources (Optional, block) See Resources below for details.
- restart_policy (Optional, block) See Restart Policy below for details.
- placement (Optional, block) See Placement below for details.
- force_update (Optional, int) A counter that triggers an update even if no relevant parameters have been changed. See Docker Spec (https://github.com/docker/swarmkit/blob/master/api/specs.proto#L126).
- runtime (Optional, string) Runtime is the type of runtime specified for the task executor. See Docker Runtime

(https://github.com/moby/moby/blob/master/api/types/swarm/runtime.go).

- networks (Optional, set of strings) lds of the networks in which the container will be put in.
- log_driver (Optional, block) See Log Driver below for details.

ContainerSpec

container_spec is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The container_spec block is the spec for each container and supports the following:

- image (Required, string) The image used to create the Docker service.
- labels (Optional, map of string/string key/value pairs) User-defined key/value metadata.
- command (Optional, list of strings) The command to be run in the image.
- args (Optional, list of strings) Arguments to the command.
- hostname (Optional, string) The hostname to use for the container, as a valid RFC 1123 hostname.
- env (Optional, map of string/string) A list of environment variables in the form VAR=value.
- dir (Optional, string) The working directory for commands to run in.
- user (Optional, string) The user inside the container.
- groups (Optional, list of strings) A list of additional groups that the container process will run as.
- privileges (Optional, block) See Privileges below for details.
- read_only (Optional, bool) Mount the container's root filesystem as read only.
- mounts (Optional, set of blocks) See Mounts below for details.
- stop_signal (Optional, string) Signal to stop the container.
- stop_grace_period (Optional, string) Amount of time to wait for the container to terminate before forcefully removing it (ms|s|m|h).
- healthcheck (Optional, block) See Healthcheck below for details.
- host (Optional, map of string/string) A list of hostname/IP mappings to add to the container's hosts file.
 - o ip (Required string) The ip
 - host (Required string) The hostname
- dns_config (Optional, block) See DNS Config below for details.
- secrets (Optional, set of blocks) See Secrets below for details.
- configs (Optional, set of blocks) See Configs below for details.
- isolation (Optional, string) Isolation technology of the containers running the service. (Windows only). Valid values are: default|process|hyperv

privileges is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The privileges block holds the security options for the container and supports the following:

- credential_spec (Optional, block) For managed service account (Windows only)
 - file (Optional, string) Load credential spec from this file.
 - registry (Optional, string) Load credential spec from this value in the Windows registry.
- se_linux_context (Optional, block) SELinux labels of the container
 - o disable (Optional, bool) Disable SELinux
 - o user (Optional, string) SELinux user label
 - role (Optional, string) SELinux role label
 - type (Optional, string) SELinux type label
 - o level (Optional, string) SELinux level label

Mounts

mount is a block within the configuration that can be repeated to specify the extra mount mappings for the container. Each mount block is the Specification for mounts to be added to containers created as part of the service and supports the following:

- target (Required, string) The container path.
- source (Required, string) The mount source (e.g., a volume name, a host path)
- type (Required, string) The mount type: valid values are bind | volume | tmpfs.
- read_only (Optional, string) Whether the mount should be read-only
- bind_options (Optional, map) Optional configuration for the bind type.
 - propagation (Optional, string) A propagation mode with the value.
- volume options (Optional, map) Optional configuration for the volume type.
 - o no_copy (Optional, string) Whether to populate volume with data from the target.
 - o labels (Optional, map of key/value pairs) Adding labels.
 - o driver_config (Optional, map) The name of the driver to create the volume.
 - o name (Optional, string) The name of the driver to create the volume.
 - o options (Optional, map of key/value pairs) Options for the driver.
- tmpf_options (Optional, map) Optional configuration for the tmpf type.
 - size_bytes (Optional, int) The size for the tmpfs mount in bytes.
 - mode (Optional, int) The permission mode for the tmpfs mount in an integer.

Healthcheck

healthcheck is a block within the configuration that can be repeated only **once** to specify the extra healthcheck configuration for the containers of the service. The healthcheck block is a test to perform to check that the container is

healthy and supports the following:

- test (Required, list of strings) Command to run to check health. For example, to run curl -f http://localhost/health set the command to be ["CMD", "curl", "-f", "http://localhost/health"].
- interval (Optional, string) Time between running the check (ms|s|m|h). Default: 0s.
- timeout (Optional, string) Maximum time to allow one check to run (ms|s|m|h). Default: 0s.
- start_period (Optional, string) Start period for the container to initialize before counting retries towards unstable (ms|s|m|h). Default: 0s.
- start_period Start period for the container to initialize before counting retries towards unstable (ms|s|m|h).

 Default: 0s.
- retries (Optional, int) Consecutive failures needed to report unhealthy. Default: 0.

DNS Config

dns_config is a block within the configuration that can be repeated only **once** to specify the extra DNS configuration for the containers of the service. The dns_config block supports the following:

- nameservers (Required, list of strings) The IP addresses of the name servers, for example, 8.8.8.8
- search (Optional, list of strings)A search list for host-name lookup.
- options (Optional, list of strings) A list of internal resolver variables to be modified, for example, debug, ndots:3

Secrets

secrets is a block within the configuration that can be repeated to specify the extra mount mappings for the container. Each secrets block is a reference to a secret that will be exposed to the service and supports the following:

- secret_id (Required, string) ConfigID represents the ID of the specific secret.
- secret_name (Optional, string) The name of the secret that this references, but internally it is just provided for lookup/display purposes
- file_name (Required, string) Represents the final filename in the filesystem. The specific target file that the secret data is written within the docker container, e.g. /root/secret/secret.json

Configs

configs is a block within the configuration that can be repeated to specify the extra mount mappings for the container. Each configs is a reference to a secret that is exposed to the service and supports the following:

- config_id (Required, string) ConfigID represents the ID of the specific config.
- config_name (Optional, string) The name of the config that this references, but internally it is just provided for lookup/display purposes
- file_name (Required, string) Represents the final filename in the filesystem. The specific target file that the config data is written within the docker container, e.g. /root/config/config.json

Resources

resources is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The resources block represents the requirements which apply to each container created as part of the service and supports the following:

- limits (Optional, list of strings) Describes the resources which can be advertised by a node and requested by a task.
 - o nano_cpus (Optional, int) CPU shares in units of 1/1e9 (or 10⁻⁹⁾ of the CPU. Should be at least 1000000
 - memory_bytes (Optional, int) The amount of memory in bytes the container allocates
 - generic_resources (Optional, map) User-defined resources can be either Integer resources (e.g, SSD=3) or
 String resources (e.g, GPU=UUID1)
 - named_resources_spec (Optional, set of string) The String resources, delimited by =
 - discrete_resources_spec (Optional, set of string) The Integer resources, delimited by =
- reservation (Optional, list of strings) An object describing the resources which can be advertised by a node and requested by a task.
 - o nano_cpus (Optional, int) CPU shares in units of 1/1e9 (or 10⁻⁹⁾ of the CPU. Should be at least 1000000
 - memory_bytes (Optional, int) The amount of memory in bytes the container allocates
 - generic_resources (Optional, map) User-defined resources can be either Integer resources (e.g, SSD=3) or
 String resources (e.g, GPU=UUID1)
 - named_resources_spec (Optional, set of string) The String resources
 - discrete_resources_spec (Optional, set of string) The Integer resources

Restart Policy

restart_policy is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The restart_policy block specifies the restart policy which applies to containers created as part of this service and supports the following:

- condition (Optional, string) Condition for restart: (none|on-failure|any)
- delay (Optional, string) Delay between restart attempts (ms|s|m|h)
- max_attempts (Optional, string) Maximum attempts to restart a given container before giving up (default value is 0, which is ignored)
- window (Optional, string) The time window used to evaluate the restart policy (default value is 0, which is unbounded) (ms|s|m|h)

Placement

placement is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The placement block specifies the placement preferences and supports the following:

- constraints (Optional, set of strings) An array of constraints. e.g.: node.role==manager
- prefs (Optional, set of string) Preferences provide a way to make the scheduler aware of factors such as topology.

 They are provided in order from highest to lowest precedence, e.g.: spread=node.role.manager
- platforms (Optional, set of) Platforms stores all the platforms that the service's image can run on
 - o architecture (Required, string) The architecture, e.g., amd64
 - os (Required, string) The operation system, e.g., linux

Log Driver

log_driver is a block within the configuration that can be repeated only **once** to specify the extra log_driver configuration for the containers of the service. The log_driver specifies the log driver to use for tasks created from this spec. If not present, the default one for the swarm will be used, finally falling back to the engine default if not specified. The block supports the following:

- name (Required, string) The logging driver to use. Either (none|json-file|syslog|journald|gelf|fluentd|awslogs|splunk|etwlogs|gcplogs).
- options (Optional, a map of strings and strings) The options for the logging driver, e.g.

```
options {
  awslogs-region = "us-west-2"
  awslogs-group = "dev/foo-service"
}
```

Mode

mode is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The mode block supports the following:

• global - (Optional, bool) set it to true to run the service in the global mode

```
resource "docker_service" "foo" {
    ...
    mode {
      global = true
    }
    ...
}
```

• replicated - (Optional, map), which contains atm only the amount of replicas

```
resource "docker_service" "foo" {
    ...
    mode {
       replicated {
         replicas = 2
       }
    }
    ...
}
```

NOTE on mode: if neither global nor replicated is specified, the service is started in replicated mode with 1 replica. A change of service mode is not possible. The service has to be destroyed an recreated in the new mode.

UpdateConfig and RollbackConfig

update_config or rollback_config is a block within the configuration that can be repeated only **once** to specify the extra update configuration for the containers of the service. The update_config rollback_config block supports the following:

- parallelism (Optional, int) The maximum number of tasks to be updated in one iteration simultaneously (0 to update all at once).
- delay (Optional, int) Delay between updates (ns|us|ms|s|m|h), e.g. 5s.
- failure_action (Optional, int) Action on update failure: pause|continue|rollback.
- monitor (Optional, int) Duration after each task update to monitor for failure (ns|us|ms|s|m|h)
- max_failure_ratio (Optional, string) The failure rate to tolerate during an update as float. **Important:** the floatneed to be wrapped in a string to avoid internal casting and precision errors.
- order (Optional, int) Update order either 'stop-first' or 'start-first'.

EndpointSpec

endpoint_spec is a block within the configuration that can be repeated only **once** to specify properties that can be configured to access and load balance a service. The block supports the following:

- mode (Optional, string) The mode of resolution to use for internal load balancing between tasks. (vip|dnsrr). Default: vip.
- ports (Optional, block) See Ports below for details.

Ports

ports is a block within the configuration that can be repeated to specify the port mappings of the container. Each ports block supports the following:

- name (Optional, string) A random name for the port.
- protocol (Optional, string) Protocol that can be used over this port: tcp|udp|sctp. Default: tcp.

- target_port (Required, int) Port inside the container.
- published_port (Required, int) The port on the swarm hosts. If not set the value of target_port will be used.
- publish_mode (Optional, string) Represents the mode in which the port is to be published: ingress|host

Converge Config

converge_config is a block within the configuration that can be repeated only **once** to specify the extra Converging configuration for the containers of the service. This is the same behavior as the docker cli. By adding this configuration, it is monitored with the given interval that, e.g., all tasks/replicas of a service are up and healthy

The converge_config block supports the following:

- delay (Optional, string) Time between each the check to check docker endpoint (ms|s|m|h). For example, to check if all tasks are up when a service is created, or to check if all tasks are successfully updated on an update. Default: 7s.
- timeout (Optional, string) The timeout of the service to reach the desired state (s|m). Default: 3m.

Attributes Reference

The following attributes are exported in addition to the above configuration:

• id (string)

docker_volume

Creates and destroys a volume in Docker. This can be used alongside docker_container (/docs/providers/docker/r/container.html) to prepare volumes that can be shared across containers.

Example Usage

```
# Creates a docker volume "shared_volume".
resource "docker_volume" "shared_volume" {
  name = "shared_volume"
}
# Reference the volume with ${docker_volume.shared_volume.name}
```

Argument Reference

The following arguments are supported:

- name (Optional, string) The name of the Docker volume (generated if not provided).
- labels (Optional, map of string/string key/value pairs) User-defined key/value metadata.
- driver (Optional, string) Driver type for the volume (defaults to local).
- driver_opts (Optional, map of strings) Options specific to the driver.

Attributes Reference

The following attributes are exported in addition to the above configuration:

• mountpoint (string) - The mountpoint of the volume.