

Connectors Guide

OpenIDM 4.5

Lana Frost

ForgeRock AS 201 Mission St., Suite 2900 San Francisco, CA 94105, USA +1 415-599-1100 (US) www.forgerock.com

Copyright © 2011-2017 ForgeRock AS.

Abstract

This guide describes the connectors that are supported with OpenIDM 4.5. The guide provides installation and configuration instructions for each connectors, and examples that demonstrate how to use the connectors in a deployment.



This work is licensed under the Creative Commons Attribution-NonCommercial-NoDerivs 3.0 Unported License.

To view a copy of this license, visit https://creativecommons.org/licenses/by-nc-nd/3.0/ or send a letter to Creative Commons, 444 Castro Street, Suite 900, Mountain View, California, 94041, USA.

ForgeRock® and ForgeRock Identity Platform™ are trademarks of ForgeRock Inc. or its subsidiaries in the U.S. and in other countries. Trademarks are the property of their respective owners

UNLESS OTHERWISE MUTUALLY AGREED BY THE PARTIES IN WRITING, LICENSOR OFFERS THE WORK AS-IS AND MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND CONCERNING THE WORK, EXPRESS, MINDIED, STATUTIORY OR OTHERWISE, INCLUDING, WITHOUT LIMITATION, WARRANTIES OF THILE, MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, NONINPRINGEMENT, OR THE ABSENCE OF LATENT OR OTHER DEFECTS, ACCURACY, OR THE PRESENCE OF ABSENCE OF FROM, WHETHER OR NOT DISCOVERABLE. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OF IMPLIED WARRANTIES, SO SUCH EXCLUSION MAY NOT APPLY TO YOU.

EXCEPT TO THE EXTENT REQUIRED BY APPLICABLE LAW, IN NO EVENT WILL LICENSOR BE LIABLE TO YOU ON ANY LEGAL THEORY FOR ANY SPECIAL, INCIDENTAL, CONSEQUENTIAL, PUNITIVE OR EXEMPLARY DAMAGES ARISING OUT OF THIS LICENSE OR THE USE OF THE WORK, EVEN IF LICENSOR HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

DeiaVu Fonts

Bitstream Vera Fonts Copyright

Copyright (c) 2003 by Bitstream, Inc. All Rights Reserved. Bitstream Vera is a trademark of Bitstream, Inc.

Permission is hereby granted, free of charge, to any person obtaining a copy of the fonts accompanying this license ("Fonts") and associated documentation files (the "Font Software"), to reproduce and distribute the Font Software, including without limitation the rights to use, copy, merge, publish, distribute, and/or sell copies of the Font Software, and to permit persons to whom the Font Software is furnished to do so, subject to the following conditions:

The above copyright and trademark notices and this permission notice shall be included in all copies of one or more of the Font Software typefaces

The Font Software may be modified, altered, or added to, and in particular the designs of glyphs or characters in the Fonts may be modified and additional glyphs or characters may be added to the Fonts, only if the fonts are renamed to names not containing either the words "Bitstream" or the word "Vera".

This License becomes null and void to the extent applicable to Fonts or Font Software that has been modified and is distributed under the "Bitstream Vera" names.

The Font Software may be sold as part of a larger software package but no copy of one or more of the Font Software typefaces may be sold by itself.

THE FONT SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF COPYRIGHT, PATENT, TRADEMARK, OR OTHER RIGHT. IN NO EVENT SHALL BITSTREAM OR THE GNOME FOUNDATION BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, INCLUDING ANY GENERAL, SPECIAL, INDIRECT, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF THE USE OR INABILITY TO USE THE FONT SOFTWARE.

Except as contained in this notice, the names of Gnome, the Gnome Foundation, and Bitstream Inc., shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Font Software without prior written authorization from the Gnome Foundation or Bitstream Inc., respectively. For further information, contact: fonts at gnome dot org.

Arev Fonts Copyrigh

Copyright (c) 2006 by Tavmjong Bah. All Rights Reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of the fonts accompanying this license ("Fonts") and associated documentation files (the "Font Software"), to reproduce and distribute the modifications to the Bistream Vera Font Software, including without limitation the rights to use, copy, merge, publish, distribute, and/or sell copies of the Font Software, and to permit persons to whom the Font Software is furnished to do so, subject to the following conditions:

The above copyright and trademark notices and this permission notice shall be included in all copies of one or more of the Font Software type faces.

The Font Software may be modified, altered, or added to, and in particular the designs of glyphs or characters in the Fonts may be modified and additional glyphs or characters may be added to the Fonts, only if the fonts are renamed to names not containing either the words "Tavmjong Bah" or the word "Arev".

This License becomes null and void to the extent applicable to Fonts or Font Software that has been modified and is distributed under the "Tavmjong Bah Arev" names.

The Font Software may be sold as part of a larger software package but no copy of one or more of the Font Software typefaces may be sold by itself.

THE FONT SOFTWARE IS PROVIDED 'AS IS', WITHOUT WARRANTY OF ANY KIND, EXPRESS OR INFILID, INCLUDING BUT NOT LIMITED TO ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF COPYRIGHT, PARTENT, TRADEMAR, OR OTHER RIGHT. IN NO EVEN'S HALL TAXMYJONG BAH BE LIABLE FOR ANY CLAM, DAMAGES OR OTHER LIABLITY, INCLUDING ANY GENERAL, SPECIAL, INDIRECT, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF THE USE OR INABILITY TO USE THE FONT SOFTWARE.

Except as contained in this notice, the name of Tavmjong Bah shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Font Software without prior written authorization from Tavmjong Bah. For further information, contact: tavmjong @ free . fr.

FontAwesome Copyright

Copyright (c) 2017 by Dave Gandy, http://fontawesome.io.

This Font Software is licensed under the SIL Open Font License, Version 1.1. This license is available with a FAQ at: http://scripts.sil.org/OFL



Table of Contents

Preface	
1. Who Should Use This Guide	v
2. Formatting Conventions	. v
3. Accessing Documentation Online	. vi
4. Joining the ForgeRock Community	vi
1. Overview of the Connectors Supported With OpenIDM 4.5	1
1.1. Overview of the Connectors Supported With OpenIDM	
2. Generic LDAP Connector	
2.1. Setting Up the Generic LDAP Connector	4
2.2. Controlling What the LDAP Connector Synchronizes	10
2.3. Using the Generic LDAP Connector With Active Directory	12
2.4. OpenICF Interfaces Implemented by the LDAP Connector	17
2.5. LDAP Connector Configuration	18
3. CSV File Connector	
3.1. Configuring the CSV File Connector	
3.2. OpenICF Interfaces Implemented by the CSV File Connector	
3.3. CSV File Connector Configuration	
4. Database Table Connector	
4.1. Configuring the Database Table Connector	
4.2. OpenICF Interfaces Implemented by the Database Table Connector	
4.3. Database Table Connector Configuration	
5. PowerShell Connector Toolkit	
5.1. Before You Start	
5.2. Setting Up the PowerShell Connector	
5.3. Testing the PowerShell Connector	
6. Groovy Connector Toolkit	39
6.1. Groovy Connector Toolkit	39
6.2. OpenICF Interfaces Implemented by the Scripted Groovy Connector	
6.3. Scripted Groovy Connector Configuration	
7. Scripted SAP Connector	
7.1. Before You Start	
7.2. Setting Up the SAP Connector	
7.3. Using the SAP Connector With an SAP HR System	
7.4. Using the SAP Connector to Manage SAP Basis System (R/3) Users	51
7.5. OpenICF Interfaces Implemented by the SAP Connector	
7.6. SAP Connector Configuration	
8. Scripted SSH Connector	75
8.1. Configuring Authentication to the SSH Server	
8.2. Configuring the SSH Connector	77
8.3. OpenICF Interfaces Implemented by the SSH Connector	
8.4. SSH Connector Configuration	
9. Google Apps Connector	
9.1. Configuring the Google Apps Connector	
10. Scripted Kerberos Connector	88



10.1. Kerberos Connector Schema	
10.2. Configuring the Kerberos Connector	. 89
10.3. OpenICF Interfaces Implemented by the Kerberos Connector	. 92
10.4. Kerberos Connector Configuration	. 93
11. Salesforce Connector	
12. Active Directory Connector	
12.1. Configuring the Active Directory Connector	
12.2. Using PowerShell Scripts With the Active Directory Connector	
13. RACF Connector	
13.1. OpenICF Interfaces Implemented by the RACF	
13.2. RACF Configuration	
14. XML File Connector	
14.1. Configuring the XML File Connector	
A. OpenICF Interfaces	
A.1. AttributeNormalizer	146
A.2. Authenticate	146
A.3. Batch	
A.4. Connector Event	
A.5. Create	
A.6. Delete	
A.7. Get	
A.8. PoolableConnector	
A.9. Resolve Username	
A.10. Schema	
A.11. Script on Connector	
A.11. Script on Connector A.12. Script On Resource	
A.12. Script on Resource A.13. Search	
A.14. Sync	
A.15. Sync Event	
A.16. Test	
A.17. Update	
A.18. Update Attribute Values B. OpenICF Operation Options	
B.1. Scope	
B.2. Container	
B.3. Run as User	
B.4. Run with Password	
B.5. Attributes to Get	150
B.6. Paged Results Cookie	150
B.7. Paged Results Offset	150
B.8. Page Size	
B.9. Sort Keys	
B.10. Fail on Error	
B.11. Require Serial	
C. Connection Pooling Configuration	152



Preface

This guide describes the OpenICF connectors that are supported in the context of an OpenIDM deployment. The guide focuses on getting the connectors installed and configured with OpenIDM. This guide does not describe all OpenICF connectors. Additional OpenICF connectors are available on the OpenICF download site but have not been tested with OpenIDM and are not described in this guide.

1. Who Should Use This Guide

This guide is written for anyone using supported OpenICF connectors with OpenIDM.

You do not need to be an OpenIDM wizard to learn something from this guide, although a background in identity management and maintaining web application software can help. You do need some background in managing services on your operating systems and in your application servers. You can nevertheless get started with this guide, and then learn more as you go along.

2. Formatting Conventions

Most examples in the documentation are created in GNU/Linux or Mac OS X operating environments. If distinctions are necessary between operating environments, examples are labeled with the operating environment name in parentheses. To avoid repetition file system directory names are often given only in UNIX format as in /path/to/server, even if the text applies to C:\path\to\server as well.

Absolute path names usually begin with the placeholder /path/to/. This path might translate to /opt/, C:\Program Files\, or somewhere else on your system.

Command-line, terminal sessions are formatted as follows:

```
$ echo $JAVA_HOME
/path/to/jdk
```

Command output is sometimes formatted for narrower, more readable output even though formatting parameters are not shown in the command.

Program listings are formatted as follows:

```
class Test {
    public static void main(String [] args) {
        System.out.println("This is a program listing.");
    }
}
```



3. Accessing Documentation Online

ForgeRock publishes comprehensive documentation online:

- The ForgeRock Knowledge Base offers a large and increasing number of up-to-date, practical articles that help you deploy and manage ForgeRock software.
 - While many articles are visible to community members, ForgeRock customers have access to much more, including advanced information for customers using ForgeRock software in a mission-critical capacity.
- ForgeRock product documentation, such as this document, aims to be technically accurate and complete with respect to the software documented. It is visible to everyone and covers all product features and examples of how to use them.

4. Joining the ForgeRock Community

Visit the Community resource center where you can find information about each project, browse the resource catalog, ask and answer questions on the forums, find community events near you, and find the source code for open source software.



Chapter 1

Overview of the Connectors Supported With OpenIDM 4.5

This chapter provides a high-level overview of the connectors supported with OpenIDM 4.5. Additional OpenICF connectors, not supported with OpenIDM, are available on the OpenICF download site, but are not described in this guide.

For instructions on building connector configurations interactively, see Section 11.6, "Creating Default Connector Configurations" in the *Integrator's Guide*.

Warning

This guide is still a work in progress and does not yet list all the connectors that are supported with OpenIDM.

1.1. Overview of the Connectors Supported With OpenIDM

OpenIDM provides a number of samples in the openidm/samples directory. This section describes the purpose of each sample, and corresponds to the list of samples described in the README, in the openidm/samples directory.

Generic LDAP Connector

The generic LDAP connector is based on JNDI, and can be used to connect to any LDAPv3-compliant directory server, such as OpenDJ, Active Directory, SunDS, Oracle Directory Server Enterprise Edition, IBM Security Directory Server, and OpenLDAP.

For information about installing and configuring the LDAP connector, see Chapter 2, "Generic LDAP Connector".

CSV File Connector

The CSV file connector is useful when importing users, either for initial provisioning or for ongoing updates. When used continuously in production, a CSV file serves as a change log, often containing only user records that have changed.

For information about installing and configuring the CSV file connector, see Chapter 3, "CSV File Connector".

Database Table Connector

The Database Table connector enables provisioning to a single table in a JDBC database.



For information about installing and configuring the Database Table connector, see Chapter 4, "Database Table Connector".

PowerShell Connector

The scripted PowerShell Connector toolkit allows you to create a connector customized to communicate with Microsoft systems such as Azure AD and Active Directory.

For information about installing and configuring the PowerShell connector, see Chapter 5, "PowerShell Connector Toolkit".

Groovy Connector

The scripted Groovy Connector toolkit enables you to run a Groovy script for any OpenICF operation, such as search, update, create, and others, on any external resource.

For information about installing and configuring the Groovy connector, see Chapter 6, "Groovy Connector Toolkit".

Scripted SAP Connector

The scripted SAP connector is an implementation of the Scripted Groovy Connector Toolkit that connects to any SAP system using the SAP JCo Java libraries.

For information about installing and configuring the SAP connector, see Chapter 7, "Scripted SAP Connector".

Google Apps Connector

The Google Apps connector enables you to interact with Google's web applications.

For information about installing and configuring the Google Apps connector, see Chapter 9, "Google Apps Connector".

Salesforce Connector

The Salesforce connector enables provisioning, reconciliation, and synchronization between Salesforce and the OpenIDM repository.

For information about installing and configuring the Salesforce connector, see Chapter 11, "Salesforce Connector".

XML File Connector

The XML File connector is really useful only in a demonstration context and should not be used in the general provisioning of XML data stores.

For information about configuring the XML File connector, see Chapter 14, "XML File Connector".



Active Directory Connector

The Active Directory connector is a legacy connector, written in C# for the .NET platform.

For information about installing and configuring the Active Directory connector, see Chapter 12, "Active Directory Connector".



Chapter 2 Generic LDAP Connector

The generic LDAP connector is based on JNDI, and can be used to connect to any LDAPv3-compliant directory server, such as OpenDJ, Active Directory, SunDS, Oracle Directory Server Enterprise Edition, IBM Security Directory Server, and OpenLDAP.

OpenICF provides a legacy Active Directory (AD) .NET connector. Note, however, that the AD Connector will be deprecated in a future OpenICF release, and, ultimately, support for its use with OpenIDM will be discontinued. For simple Active Directory (and Active Directory LDS) deployments, the generic LDAP Connector works better than the Active Directory connector, in most circumstances. Using the generic LDAP connector avoids the need to install a remote connector server in the overall deployment. In addition, the generic LDAP connector has significant performance advantages over the Active Directory connector. For more complex Active Directory deployments, use the PowerShell Connector Toolkit, as described in Chapter 5, "PowerShell Connector Toolkit".

2.1. Setting Up the Generic LDAP Connector

OpenIDM 4.5 bundles version 1.4.1.2 of the LDAP connector. Three sample LDAP connector configurations are provided in the path/to/openidm/samples/provisioners/ directory:

- provisioner.openicf-opendjldap.json provides a sample LDAP connector configuration for an OpenDJ directory server.
- provisioner.openicf-adldap.json provides a sample LDAP connector configuration for an Active Directory server.
- provisioner.openicf-adldsldap.json provides a sample LDAP connector configuration for an Active Directory Lightweight Directory Services (AD LDS) server.

You should be able to adapt one of these sample configurations for any LDAPv3-compliant server.

The connectorRef configuration property provides information about the LDAP connector bundle, and is the same in all three sample LDAP connector configurations:

```
{
  "connectorRef": {
     "connectorHostRef": "#LOCAL",
     "connectorName": "org.identityconnectors.ldap.LdapConnector",
     "bundleName": "org.forgerock.openicf.connectors.ldap-connector",
     "bundleVersion": "[1.4.0.0,2.0.0.0)"
  }
}
```



The connectorHostRef property is optional, if you use the connector .jar provided in openidm/connectors, and you use a local connector server.

The following excerpt shows the configuration properties in the sample LDAP connector for OpenDJ. These properties are described in detail later in this section. For additional information on the properties that affect synchronization, see Section 2.2, "Controlling What the LDAP Connector Synchronizes". For a complete list of the configuration properties for the LDAP connector, see Section 2.5, "LDAP Connector Configuration":

```
"configurationProperties" : {
    "host" : "localhost",
    "port" : 1389,
    "ssl" : false,
    "startTLS" : false,
    "principal" : "cn=Directory Manager",
    "credentials" : "password",
    "baseContexts" : [
        "dc=example,dc=com"
    "baseContextsToSynchronize" : [
        "dc=example,dc=com"
    "accountSearchFilter" : null,
    "accountSynchronizationFilter" : null,
    "groupSearchFilter" : null,
    "groupSynchronizationFilter" : null,
    "passwordAttributeToSynchronize" : null,
    "synchronizePasswords" : false,
    "removeLogEntryObjectClassFromFilter" : true,
    "modifiersNamesToFilterOut" : [ ],
   "passwordDecryptionKey" : null, "changeLogBlockSize" : 100,
   "attributesToSynchronize" : [ ],
"changeNumberAttribute" : "changeNumber",
    "passwordDecryptionInitializationVector" : null,
    "filterWithOrInsteadOfAnd" : false,
    "objectClassesToSynchronize" : [
        "inetOrgPerson"
   "vlvSortAttribute" : "uid",
    "passwordAttribute" : "userPassword",
    "useBlocks" : false,
    "maintainPosixGroupMembership" : false,
    "failover" : [ ],
    "readSchema" : true,
    "accountObjectClasses" : [
        "top",
        "person",
        "organizationalPerson",
        "inetOrgPerson"
    "accountUserNameAttributes" : [
        "uid"
    "groupMemberAttribute" : "uniqueMember",
    "passwordHashAlgorithm" : null,
    "usePagedResultControl" : true,
    "blockSize" : 100,
```



```
"uidAttribute" : "dn",
    "maintainLdapGroupMembership" : false,
    "respectResourcePasswordPolicyChangeAfterReset" : false
},
```

host

The host name or IP address of the server on which the LDAP instance is running.

port

The port on which the LDAP server listens for LDAP requests. The sample configuration specifies a default port of 1389.

ssl

If true, the specified port listens for LDAPS connections.

If you use the LDAP connector over SSL, set the ssl property to true, and the port to 636 in the connector configuration file. You must also specify the path to a truststore in your project's conf/system.properties file. A truststore is provided by default at openidm/security/truststore. Add the following line to the system.properties file, substituting the path to your own truststore if you do not want to use the default:

```
# Set the truststore
javax.net.ssl.trustStore=/path/to/openidm/security/truststore
```

startTLS

Specifies whether to use the startTLS operation to initiate a TLS/SSL session. To use startTLS, set "startTLS":true, and "ssl":false. Your connection should use the insecure LDAP port (typically 389 or 1389 for an OpenDJ server).

principal

The bind DN that is used to connect to the LDAP server.

credentials

The password of the principal that is used to connect to the LDAP server.

baseContexts

One or more starting points in the LDAP tree that will be used when searching the tree. Searches are performed when discovering users from the LDAP server or when looking for the groups of which a user is a member. During reconciliation operations, OpenIDM searches through the base contexts listed in this property for changes. (See also Section 2.2, "Controlling What the LDAP Connector Synchronizes").

baseContextsToSynchronize

One or more starting points in the LDAP tree that will be used to determine if a change should be synchronized. During LiveSync operations, OpenIDM searches through the base contexts listed



in this property for changes. If no value is specified here, the values in listed in the baseContexts property are used. (See also Section 2.2, "Controlling What the LDAP Connector Synchronizes").

accountSynchronizationFilter

Used during synchronization actions to filter out LDAP accounts. (See also Section 2.2, "Controlling What the LDAP Connector Synchronizes").

accountObjectClasses

This property lists all the object classes that represent an account. If this property has multiple values, an OR filter is used to determine the affected entries. For example, if the value of this property is ["organizationalPerson", "inetOrgPerson"], any entry with the object class organizationalPerson OR the object class inetOrgPerson is considered as an account entry. The value of this property must not include the top object class.

accountSearchFilter

Search filter that user accounts must match. (See also Section 2.2, "Controlling What the LDAP Connector Synchronizes").

accountUserNameAttributes

Attributes holding the account's user name. Used during authentication to find the LDAP entry matching the user name.

attributesToSynchronize

List of attributes used during object synchronization. OpenIDM ignores change log updates that do not include any of the specified attributes. If empty, OpenIDM considers all changes. (See also Section 2.2, "Controlling What the LDAP Connector Synchronizes").

blockSize

Block size for simple paged results and VLV index searches, reflecting the maximum number of entries retrieved at any one time.

changeLogBlockSize

Block size used when fetching change log entries.

changeNumberAttribute

Change log attribute containing the last change number.

failover

LDAP URLs specifying alternative LDAP servers to connect to if OpenIDM cannot connect to the primary LDAP server specified in the host and port properties.



filterWithOrInsteadOfAnd

In most cases, the filter to fetch change log entries is AND-based. If this property is set, the filter ORs the required change numbers instead.

groupMemberAttribute

LDAP attribute holding members for non-POSIX static groups.

groupSearchFilter

Search filter that group entries must match.

maintainLdapGroupMembership

If true, OpenIDM modifies group membership when entries are renamed or deleted.

In the sample LDAP connector configuration file provided with OpenIDM, this property is set to false. This means that LDAP group membership is not modified when entries are renamed or deleted in OpenIDM. To ensure that entries are removed from LDAP groups when the entries are deleted, set this property to true or enable referential integrity on the LDAP server. For information about configuring referential integrity in OpenDJ, see *Configuring Referential Integrity* in the *OpenDJ Administration Guide*.

maintainPosixGroupMembership

If true, OpenIDM modifies POSIX group membership when entries are renamed or deleted.

modifiersNamesToFilterOut

Use this property to avoid loops caused by changes made to managed user objects being synchronized. For more information, see Section 2.2, "Controlling What the LDAP Connector Synchronizes".

objectClassesToSynchronize

OpenIDM synchronizes only entries that have these object classes. See also Section 2.2, "Controlling What the LDAP Connector Synchronizes".

passwordAttribute

Attribute to which OpenIDM writes the predefined PASSWORD attribute.

passwordAttributeToSynchronize

OpenIDM synchronizes password values on this attribute.

passwordDecryptionInitializationVector

This is a legacy attribute, and its value should remain set to null. To configure password synchronization between an LDAP server and OpenIDM, use one of the password synchronization



plugins, described in Section 15.4, "Synchronizing Passwords Between OpenIDM and an LDAP Server" in the *Integrator's Guide*.

passwordDecryptionKey

This is a legacy attribute, and its value should remain set to null. To configure password synchronization between an LDAP server and OpenIDM, use one of the password synchronization plugins, described in Section 15.4, "Synchronizing Passwords Between OpenIDM and an LDAP Server" in the *Integrator's Guide*.

passwordHashAlgorithm

Hash password values with the specified algorithm, if the LDAP server stores them in clear text.

The hash algorithm can be one of the following:

- NONE Clear text
- WIN-AD Used for password changes to Active Directory
- SHA Secure Hash Algorithm
- SHA-1 A 160-bit hash algorithm that resembles the MD5 algorithm
- SSHA Salted SHA
- MD5 A 128-bit message-digest algorithm
- SMD5 Salted MD5

readSchema

If true, read the schema from the LDAP server.

This property is used only during the connector setup, to generate the object types.

If this property is false, the LDAP connector provides a basic default schema that can manage LDAP users and groups. The default schema maps inetOrgPerson to the OpenICF __ACCOUNT__ property, and groupOfUniqueNames to the OpenICF __GROUP__ property. The following LDAP object classes are also included in the default schema:

organization organizationalUnit person organizationalPerson account groupOfNames

removeLogEntryObjectClassFromFilter

If true, the filter to fetch change log entries does not contain the changeLogEntry object class, and OpenIDM expects no entries with other object types in the change log. The default setting is true.



respectResourcePasswordPolicyChangeAfterReset

If true, bind with the Password Expired and Password Policy controls, and throw PasswordExpiredException and other exceptions appropriately.

synchronizePasswords

This is a legacy attribute, and its value should remain set to false. To configure password synchronization between an LDAP server and OpenIDM, use one of the password synchronization plugins, described in Section 15.4, "Synchronizing Passwords Between OpenIDM and an LDAP Server" in the *Integrator's Guide*.

uidAttribute

Specifies the LDAP attribute that should be used as the immutable ID ($_$ UID $_$) for the entry. For an OpenDJ resource, you should use the $_{\tt entry}$ UUID $_$ Nou can use the $_{\tt DN}$ as the UID attribute but note that this is not immutable.

useBlocks

If useBlocks is false, no pagination is used. If useBlocks is true, the connector uses block-based LDAP controls, either the simple paged results control, or the virtual list view control, depending on the setting of the usePagedResultControl property.

usePagedResultControl

Taken into account only if useBlocks is true. If usePagedResultControl is false, the connector uses the virtual list view (VLV) control, if it is available. If usePagedResultControl is true, the connector uses the simple paged results control for search operations.

useTimestampsForSync

If true, use timestamps for LiveSync operations, instead of the change log.

By default, the LDAP connector has a change log strategy for LDAP servers that support a change log (such as OpenDJ and Oracle Directory Server Enterprise Edition). If the LDAP server does not support a change log, or if the change log is disabled, LiveSync for create and modify operations can still occur, based on the timestamps of modifications.

vlvSortAttribute

Attribute used as the sort key for virtual list view.

2.2. Controlling What the LDAP Connector Synchronizes

To control the set of LDAP entries that are affected by reconciliation and automatic synchronization operations, set the following properties in the provisioner configuration. Automatic synchronization operations includes LiveSync (synchronization of changes from the LDAP server to OpenIDM) and implicit sync (synchronization from the OpenIDM repository to the LDAP server).



baseContexts

The starting points in the LDAP tree that are used when searching the directory tree, for example, dc=example, dc=com. These base contexts must include the set of users and the set of groups that must be searched during reconciliation operations.

baseContextsToSynchronize

The starting points in the LDAP tree that are used to determine if a change should be synchronized. This property is used only for automatic synchronization operations. Only entries that fall under these base contexts are considered during synchronization operations.

accountSearchFilter

Only user accounts that match this filter are searched, and therefore affected by reconciliation and synchronization operations. If you do not set this property, all accounts within the base contexts specified previously are searched.

accountSynchronizationFilter

This property is used during reconciliation and automatic synchronization operations, and filters out any LDAP accounts that you specifically want to exclude from these operations.

objectClassesToSynchronize

During automatic synchronization operations, only the object classes listed here are considered for changes. OpenIDM ignores change log updates (or changes to managed objects) which do not have any of the object classes listed here. If this property is not set, OpenIDM considers changes to all attributes specified in the mapping.

attributesToSynchronize

During automatic synchronization operations, *only* the attributes listed here are considered for changes. Objects that include these attributes are synchronized. Objects that do not include these attributes are ignored. If this property is not set, OpenIDM considers changes to all attributes specified in the mapping. Automatic synchronization includes LiveSync and implicit synchronization operations. For more information, see Section 12.1, "Types of Synchronization" in the *Integrator's Guide*

This attribute works only with LDAP servers that log changes in a change log, not with servers (such as Active Directory) that use other mechanisms to track changes.

modifiersNamesToFilterOut

This property enables you to define a list of DNs. During synchronization operations, the connector ignores changes made by these DNs.

When a managed user object is updated, and that change is synchronized to the LDAP server, the change made on the LDAP server is recorded in the change log. A LiveSync operation picks up

the change, and attempts to replay the change on the managed user object, effectively resulting in a loop of updates.

To avoid this situation, you can specify a unique user in your LDAP directory, that will be used *only* for the LDAP connector. The unique user must be something other than <code>cn=directory</code> <code>manager</code>, for example <code>cn=openidmuser</code>. You can then include that user DN as the value of <code>modifiersNamesToFilterOut</code>. When a change is made through the LDAP connector, and that change is recorded in the change log, the modifier's name (<code>cn=openidmuser</code>) is flagged and OpenIDM does not attempt to replay the change back to the managed user repository. So you are effectively indicating that OpenIDM should not synchronized changes back to managed user that originated from managed user, thus preventing the update loop.

This attribute works only with LDAP servers that log changes in a change log, not with servers (such as Active Directory) that use other mechanisms to track changes.

2.3. Using the Generic LDAP Connector With Active Directory

The LDAP connector provides new functionality for managing Active Directory users and groups. Among other changes, the new connector can handle the following operational attributes to manage Active Directory accounts:

• ENABLE - uses the userAccountControl attribute to get or set the account status of an object.

The LDAP connector reads the <u>userAccountControl</u> to determine if an account is enabled or disabled. The connector modifies the value of the <u>userAccountControl</u> attribute if OpenIDM changes the value of <u>ENABLE</u>.

- ACCOUNT EXPIRES gets or sets the account Expires attribute of an Active Directory object.
- _LOCK_OUT__ uses the msDS-User-Account-Control-Computed system attribute to check if a user account
 has been locked.

If OpenIDM sets the <u>LOCK_OUT</u> to <u>FALSE</u>, the LDAP connector sets the Active Directory <u>lockoutTime</u> to 0 to unlock the account.

If OpenIDM sets the <u>LOCK_OUT_</u> to <u>TRUE</u>, the LDAP connector ignores the change and logs a message.

• __PASSWORD_EXPIRED__ - uses the msDS-User-Account-Control-Computed system attribute to check if a user password has expired.

To force password expiration (to force a user to change their password when they next log in), pwdLastSet must be set to 0. The LDAP connector sets pwdLastSet to 0, if OpenIDM sets PASSWORD EXPIRED to TRUE.

To remove password expiration, pwdLastSet must be set to 0 and then -1. This sets the value of pwdLastSet to the current time. The LDAP connector sets pwdLastSet to -1 if OpenIDM sets __PASSWORD_EXPIRED__ to FALSE.



Note

You must update your provisioner configuration to be able to use these new operational attributes. You can use this sample provisioner configuration as a guide.

2.3.1. Managing Active Directory Users With the LDAP Connector

If you create or update users in Active Directory, and those user entries include passwords, you *must* use the LDAP connector over SSL. You cannot create or update an Active Directory user password in clear text. To use the connector over SSL, set "ssl": true in the provisioner configuration and set the path to your truststore in your project's conf/system.properties file. For example, add the following line to that file:

```
# Set the truststore
javax.net.ssl.trustStore=/path/to/openidm/security/truststore
```

The following command adds an Active Directory user. The output shows the operational attributes described in the previous section:

```
$ curl \
 --header "Content-Type: application/json" \
 --header "X-OpenIDM-Username: openidm-admin" \
 --header "X-OpenIDM-Password: openidm-admin" \
 --request POST \
 --data '{
 "dn": "CN=Brian Smith, CN=Users, DC=example, DC=com",
 "cn": "Brian Smith",
 "sAMAccountName": "bsmith"
 "userPrincipalName": "bsmith@example.com",
 "userAccountControl": "512",
 "givenName": "Brian",
 "mail": "bsmith@example.com",
   PASSWORD ": "Passw0rd"
 http://localhost:8080/openidm/system/ad/account? action=create
  " id": "<GUID=cb2f8cbc032f474c94c896e69db2feb3>",
  "mobile": null,
  "postalCode": null,
  "st": null,
  "employeeType": null,
  "objectGUID": "<GUID=cb2f8cbc032f474c94c896e69db2feb3>",
  "cn": "Brian Smith",
  "department": null,
  "l": null,
  "description": null,
  "info": null,
  "manager": null,
  "sAMAccountName": "bsmith",
  "sn": null,
  "whenChanged": "20151217131254.0Z",
  "userPrincipalName": "bsmith@example.com",
  "userAccountControl": "512",
  " ENABLE ": true,
```



```
"displayName": null,
"givenName": "Brian",
"middleName": null,
"facsimileTelephoneNumber": null,
"lastLogon": "0",
"countryCode": "0"
"employeeID": null,
"co": null,
"physicalDeliveryOfficeName": null,
"pwdLastSet": "2015-12-17T13:12:54Z",
"streetAddress": null,
"homePhone": null,
 __PASSWORD_NOTREQD ": false,
"telephoneNumber": null,
"dn": "CN=Brian Smith, CN=Users, DC=example, DC=com",
"title": null,
"mail": "bsmith@example.com",
"postOfficeBox": null,
  _SMARTCARD_REQUIRED__": false,
"uSNChanged": "86144",
 __PASSWORD_EXPIRED__": false,
"initials": null,
"__LOCK_OUT__": false,
"company": null,
"employeeNumber": null,
"accountExpires": "0",
"c": null,
"whenCreated": "20151217131254.0Z",
"uSNCreated": "86142",
"division": null,
"groups": [],
 DONT EXPIRE PASSWORD ": false,
"otherHomePhone": []
```

Note that the command sets the <u>userAccountControl</u> to 512, which is an <u>enabled</u> account. The value of the <u>userAccountControl</u> determines the account policy. The following list describes the common values for the <u>userAccountControl</u>.

512

Enabled account.

514

Disabled account.

544

Enabled account, password not required.

546

Disabled account, password not required.



66048

Enabled account, password does not expire.

66050

Disabled account, password does not expire.

66080

Enabled account, password does not expire and is not required.

66082

Disabled account, password does not expire and is not required.

262656

Enabled account, smartcard required.

262658

Disabled account, smartcard required.

262688

Enabled account, smartcard required, password not required.

262690

Disabled account, smartcard required, password not required.

328192

Enabled account, smartcard required, password does not expire.

328192

Enabled account, smartcard required, password does not expire.

328194

Disabled account, smartcard required, password does not expire.

328224

Enabled account, smartcard required, password does not expire and is not required.

328226

Disabled account, smartcard required, password does not expire and is not required.



2.3.2. Managing Active Directory Groups With the LDAP Connector

The following command creates a basic Active Directory group with the LDAP connector:

```
$ curl \
--header "Content-Type: application/json" \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--request POST \
--data '{
    "dn": "CN=Employees, DC=example, DC=com"
}' \
http://localhost:8080/openidm/system/ad/group?_action=create
{
    "_id": "<GUID=240da4e959d81547ad8629f5b2b5114d>"
}
```

The LDAP connector exposes two special attributes to handle Active Directory group scope and type: GROUP SCOPE and GROUP TYPE.

The GROUP_SCOPE attribute is defined in the provisioner configuration as follows:

```
...
"__GROUP_SCOPE__" : {
    "type" : "string",
    "nativeName" : "__GROUP_SCOPE__",
    "nativeType" : "string"
},
```

The value of the GROUP_SCOPE attribute can be global, domain, or universal. If no group scope is set when the group is created, the scope is global by default. For more information about the different group scopes, see the corresponding Microsoft documentation.

The GROUP TYPE attribute is defined in the provisioner configuration as follows:

```
...
"__GROUP_TYPE__" : {
"type" : "string",
"nativeName" : "__GROUP_TYPE__",
"nativeType" : "string"
},
```

The value of the GROUP_TYPE attribute can be security or distribution. If no group type is set when the group is created, the type is security by default. For more information about the different group types, see the corresponding Microsoft documentation.

The following example creates a new distribution group, with universal scope:



```
$ curl \
--header "Content-Type: application/json" \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--request POST \
--data '{
   "dn": "CNNewGroup,DC=example,DC=com",
   "__GROUP_SCOPE__": "universal",
   "__GROUP_TYPE__": "distribution"
} \
http://localhost:8080/openidm/system/ad/group?_action=create
{
   "_id": "<GUID=f189df8a276f91478ad5055b1580cbcb>"
}
```

2.3.3. Handling Active Directory Dates

Most dates in Active Directory are represented as the number of 100-nanosecond intervals since January 1, 1601 (UTC). For example:

```
pwdLastSet: 130698687542272930
```

OpenIDM generally represents dates as an ISO 8601-compliant string with yyyy-MM-dd'T'HH:mm:ssZ format. For example:

```
2015-03-02T20:17:48Z
```

The generic LDAP connector therefore converts any dates from Active Directory to ISO 8601 format, for fields such as pwdLastSet, accountExpires, lockoutTime, and lastLogon.

2.4. OpenICF Interfaces Implemented by the LDAP Connector

The LDAP Connector implements the following OpenICF interfaces.

Authenticate

Provides simple authentication with two parameters, presumed to be a user name and password.

Create

Creates an object and its uid.

Delete

Deletes an object, referenced by its uid.

Resolve Username

Resolves an object by its username and returns the uid of the object.



Schema

Describes the object types, operations, and options that the connector supports.

Script on Connector

Enables an application to run a script in the context of the connector. Any script that runs on the connector has the following characteristics:

- The script runs in the same execution environment as the connector and has access to all the classes to which the connector has access.
- The script has access to a connector variable that is equivalent to an initialized instance of the connector. At a minimum, the script can access the connector configuration.
- The script has access to any script-arguments passed in by the application.

Search

Searches the target resource for all objects that match the specified object class and filter.

Sync

Polls the target resource for synchronization events, that is, native changes to objects on the target resource.

Test

Tests the connector configuration. Testing a configuration checks all elements of the environment that are referred to by the configuration are available. For example, the connector might make a physical connection to a host that is specified in the configuration to verify that it exists and that the credentials that are specified in the configuration are valid.

This operation might need to connect to a resource, and, as such, might take some time. Do not invoke this operation too often, such as before every provisioning operation. The test operation is not intended to check that the connector is alive (that is, that its physical connection to the resource has not timed out).

You can invoke the test operation before a connector configuration has been validated.

Update

Updates (modifies or replaces) objects on a target resource.

2.5. LDAP Connector Configuration

The LDAP Connector has the following configurable properties.



2.5.1. Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
accountSynchronizationFilter	String	null		Sync
An optional LDAP filter for the objupdates only objects that match t t matches the filter and includes	he specified filter. If	you specify a fi		
passwordAttributeToSynchronize	String	null		Sync
The name of the password attribu	ite to synchronize wh	en performing	password synchroniz	zation.
synchronizePasswords	boolean	false		Sync
If true, the connector will synchropassword synchronization to worl	onize passwords. The	Password Cap	ture Plugin needs to	be installed for
removeLogEntryObjectClassFromFil	ter boolean	true		Sync
If this property is set (the default "changeLogEntry" object class, ex				
modifiersNamesToFilterOut	String[]	[]		Sync
The list of names (DNs) to filter frentries in this list will be filtered prevent loops. Entries should be o	out. The standard val	lue is the admir	nistrator name used l	
passwordDecryptionKey	GuardedByteArray	null	Yes	Sync
The key to decrypt passwords wit	h when performing p	assword synch	ronization.	
groupSynchronizationFilter	String	null		Sync
An optional LDAP filter for the ob- updates only objects that match t it matches the filter and includes	he specified filter. If	you specify a fi		
credentials	GuardedString	null	Yes	No
Password for the principal.				
changeLogBlockSize	int	100		Sync
The number of change log entries	to fetch per query.			
paseContextsToSynchronize	String[]	[]		Sync
One or more starting points in the synchronized. The base contexts a				
attributesToSynchronize	String[]	[]		Sync
The names of the attributes to synany of the named attributes. For a				



"department" will be processed. A	Туре	Default	Encrypted ^a	Required ^b
processed.	All other updates a	are ignored. If blank (the default), then	all changes are
changeNumberAttribute	String	changeNumber		Sync
The name of the change number	attribute in the ch	ange log entry.		·
passwordDecryptionInitialization	nVec GuardedByteAr	ray null	Yes	Sync
The initialization vector to decryp	ot passwords with	when performing pas	ssword synchroniza	ation.
filterWithOrInsteadOfAnd	boolean	false		Sync
Normally the filter used to fetch centries. If this property is set, the				
useTimestampsForSync	boolean	false		Sync
f true, the connector will use the Create/Update) on the directory Jpdate Sequence Number -USN-	instead of native of	change detection med	hanism (cn=chan	
bjectClassesToSynchronize	String[]	['inetOrgPersor	1"	Sync
ist "top", otherwise no object wo	uld be filtered.			you should never
oort	int	389		
	int municate with the	389 LDAP server.		No
TCP/IP port number used to com	municate with the			
TCP/IP port number used to comp	municate with the	LDAP server.		No
TCP/IP port number used to compare vivSortAttribute Specify the sort attribute to use f	String For VLV indexes on	LDAP server.		No
TCP/IP port number used to composite to composite to the control of the sort attribute to use for the control of the LDAP attribute to the control of the control of the LDAP attribute to the control of the LDAP attribute to the control of the contro	String For VLV indexes on	LDAP server. uid the resource. userPassword	g a users password	No No No
TCP/IP port number used to composite to the composite to the sort attribute to use for the composite to the	String For VLV indexes on	LDAP server. uid the resource. userPassword	g a users passwore	No No No
TCP/IP port number used to compare the com	String For VLV indexes on String Shat holds the pass boolean ased LDAP controls large numbers of	LDAP server. uid the resource. userPassword word. When changin false s, like the simple pag	ed results or VLV	No No No No No No Control. When
TCP/IP port number used to community vivSortAttribute Specify the sort attribute to use for passwordAttribute The name of the LDAP attribute the is set to this attribute. Specifies whether to use block-base performing search operations on amount of memory used by the operation of the community of memory used by the operation of the community of the commu	String For VLV indexes on String Shat holds the pass boolean ased LDAP controls large numbers of	LDAP server. uid the resource. userPassword word. When changin false s, like the simple pag	ed results or VLV	No No No No No No No One No Control. When



	Туре	Default	Encrypted ^a	Required ^b
failover	String[]	П		No
List all servers that should be fails, JNDI will connect to the ldap.example.com:389/", whic port parts of the URL are rele	next available server ch follows the standard	in the list. List all serv	vers in the form o	of "ldap://
ssl	boolean	false		No
Select the check box to conne	ect to the LDAP server	using SSL.		
getGroupMemberId	boolean	false		No
Specifies whether to add an e	xtra _memberId attrik	oute to get the group r	nembersUID	-
referralsHandling	String	follow		No
Defines how to handle LDAP	referrals. Possible valu	ues can be follow, igno	ore or throw.	
principal	String	null		No
The distinguished name with	which to authenticate	to the LDAP server.		
baseContexts	String[]	П		No
One or more starting points in performed when discovering member.				
readSchema	boolean	true		No
readSchema If true, the connector will rea schema based on the object cobject classes.	d the schema from the	e server. If false, the c		vide a default
If true, the connector will rea schema based on the object c	d the schema from the	e server. If false, the c		vide a default
If true, the connector will rea schema based on the object c object classes.	d the schema from the classes in the configura String	e server. If false, the cation. This property management	ust be true in ord	ovide a default der to use extended
If true, the connector will reaschema based on the object cobject classes.	d the schema from the classes in the configura String	e server. If false, the cation. This property management	ust be true in ord	ovide a default der to use extended
If true, the connector will rea schema based on the object c object classes. authType The authentication mechanism	String m to use: Simple or SA String[] String[]	simple ASL-GSSAPI. Defaults ['top', 'person', 'organizational 'inetOrgPerson' when creating new user	to "simple".	ovide a default der to use extended No
If true, the connector will rea schema based on the object c object classes. authType The authentication mechanism accountObjectClasses The default list of object class	String m to use: Simple or SA String[] String[]	simple ASL-GSSAPI. Defaults ['top', 'person', 'organizational 'inetOrgPerson' when creating new user	to "simple".	ovide a default der to use extended No
If true, the connector will rea schema based on the object cobject classes. authType The authentication mechanism accountObjectClasses The default list of object class be overridden by specifying the schema of	String m to use: Simple or SA String[] sees that will be used whe user object classes String[] holds the account's us	simple ASL-GSSAPI. Defaults ['top', 'person', 'organizational 'inetOrgPerson' then creating new used during the Create ope	to "simple". Tobjects in the Leration.	No DAP tree. This can



Property	Туре	Default	Encrypted ^a	Required ^b
The name or IP address of the ho	st where the LDA	P server is running.		
groupMemberAttribute	String	uniqueMember		No
The name of the group attribute added to the group.	that will be updat	ed with the distingu	ished name of the u	ser when the user i
passwordHashAlgorithm	String	null		No
Indicates the algorithm that the lare SSHA, SHA, SMD5, MD5 and will not hash passwords. This wil performs the hash (as Forgerock	l WIN-AD (when A l cause clear text	AD is the target). A because to be stopping to be s	lank value indicates	s that the system
accountSearchFilter	String	null		No
An optional LDAP filter to contro only accounts that include all spe			ne LDAP resource. I	f no filter is specifie
usePagedResultControl	boolean	false		No
When enabled, the LDAP Paged I	Results control is	preferred over the V	LV control when re	trieving entries.
blockSize	int	100		No
The maximum number of entries	that can be in a b	lock when retrieving	g entries in blocks.	
startTLS	boolean	false		No
Specifies whether to use the star	tTLS operation to	initiate a TLS/SSL s	session.	,
groupObjectClasses	String[]	['top', 'groupOfUniq	ueN	No
The default list of object classes to be overridden by specifying the control of				LDAP tree. This ca
uidAttribute	String	entryUUID		No
The name of the LDAP attribute t	that is mapped to	the OpenICF UID at	tribute.	
groupSearchFilter	String	null		No
An optional LDAP filter to contro only groups that include all speci	l which groups ar ified object classe	e returned from the s are returned.	LDAP resource. If n	o filter is specified
maintainLdapGroupMembership	boolean	false		No
When enabled and a user is rena the new name. Otherwise, the LI membership.				



When this resource is specified in a Login Module (i.e., this resource is a pass-through authentication target) and the resource's password policy is configured for change-after-reset, a user whose resource account password has been administratively reset will be required to change that password after successfully authenticating.

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

^b A list of operations in this column indicates that the property is required for those operations.



CSV File Connector

The CSV file connector is useful when importing users, either for initial provisioning or for ongoing updates. When used continuously in production, a CSV file serves as a change log, often containing only user records that have changed.

3.1. Configuring the CSV File Connector

A sample CSV file connector configuration is provided in openidm/samples/provisioners/provisioner.openicf-csv.json.

The following example shows an excerpt of the provisioner configuration. The connectorHostRef property is optional and must be provided only if the connector runs remotely.

```
{
    "connectorRef": {
        "connectorHostRef": "#LOCAL",
        "connectorName": "org.forgerock.openicf.csvfile.CSVFileConnector",
        "bundleName": "org.forgerock.openicf.connectors.csvfile-connector",
        "bundleVersion": "1.5.1.4"
    }
}
```

The following excerpt shows the *required* configuration properties:

```
"configurationProperties" : {
   "csvFile" : "&{launcher.project.location}/data/hr.csv",
   "headerUid" : "uid"
},
```

csvFile

The path to the CSV file that is the data source for this connector.

headerUid

The CSV header that maps to the uid (or name) for each row.

Default: uid

The CSV file connector also supports following optional configuration properties:

encoding

Default: utf-8



headerPassword

The CSV header that maps to the password for each row. Use this property when password-based authentication is required.

fieldDelimiter

The character in the CSV file that is used to separate field values.

Default: ,

quoteCharacter

The character in the CSV file that is used to encapsulate strings.

Default: "

newlineString

The character string in the CSV file that is used to terminate each line.

Default: \n

syncFileRetentionCount

The number of historical copies of the CSV file to retain when performing synchronization operations.

Default: 3

3.2. OpenICF Interfaces Implemented by the CSV File Connector

The CSV File Connector implements the following OpenICF interfaces.

Authenticate

Provides simple authentication with two parameters, presumed to be a user name and password.

Batch

Execute a series of operations in a single request.

Create

Creates an object and its uid.



Delete

Deletes an object, referenced by its uid.

Resolve Username

Resolves an object by its username and returns the uid of the object.

Schema

Describes the object types, operations, and options that the connector supports.

Script on Connector

Enables an application to run a script in the context of the connector. Any script that runs on the connector has the following characteristics:

- The script runs in the same execution environment as the connector and has access to all the classes to which the connector has access.
- The script has access to a connector variable that is equivalent to an initialized instance of the connector. At a minimum, the script can access the connector configuration.
- The script has access to any script-arguments passed in by the application.

Search

Searches the target resource for all objects that match the specified object class and filter.

Sync

Polls the target resource for synchronization events, that is, native changes to objects on the target resource.

Test

Tests the connector configuration. Testing a configuration checks all elements of the environment that are referred to by the configuration are available. For example, the connector might make a physical connection to a host that is specified in the configuration to verify that it exists and that the credentials that are specified in the configuration are valid.

This operation might need to connect to a resource, and, as such, might take some time. Do not invoke this operation too often, such as before every provisioning operation. The test operation is not intended to check that the connector is alive (that is, that its physical connection to the resource has not timed out).

You can invoke the test operation before a connector configuration has been validated.

Update

Updates (modifies or replaces) objects on a target resource.



3.3. CSV File Connector Configuration

The CSV File Connector has the following configurable properties.

3.3.1. Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
csvFile	File	null		Yes
Full path to the CSV file				
headerUid	String	uid		No
Name of the uid column as four	nd in the CSV file			
quoteCharacter	String	II .		No
Character used to quote fields				
headerPassword	String	password		No
Name of the password column	as found in the CSV	file		
fieldDelimiter	String	,		No
Character used to delimit colur	nnar fields			
syncFileRetentionCount	int	3		No
Number of sync history files to	retain			·
newlineString	String			No
Character(s) used to terminate	a line in the CSV fil	e		

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

^b A list of operations in this column indicates that the property is required for those operations.



Chapter 4

Database Table Connector

The Database Table connector enables provisioning to a single table in a JDBC database.

4.1. Configuring the Database Table Connector

A sample connector configuration for the Database Table connector is provided in samples/
provisioners/provisioner.openicf-contractordb.json. The corresponding data definition language file is
provided in samples/provisioners/provisioner.openicf-contractordb.sql.

The following excerpt shows the settings for the connector configuration properties in the sample Database Table connector:

```
"configurationProperties" :
    {
        "quoting" : ""
       "host" : "localhost",
        "port" : "3306",
       "user" : "root"
        "password" : ""
       "database" : "contractordb",
       "table" : "people",
"keyColumn" : "UNIQUE_ID",
       "passwordColumn" : ""
       "jdbcDriver" : "com.mysql.jdbc.Driver",
       "jdbcUrlTemplate" : "jdbc:mysql://%h:%p/%d",
"enableEmptyString" : false,
       "rethrowAllSQLExceptions" : true,
       "nativeTimestamps" : true,
       "allNative" : false,
       "validConnectionQuery" : null,
       "changeLogColumn" : "CHANGE TIMESTEMP",
       "datasource" : "",
        "jndiProperties" : null
    },
```

The mandatory configurable properties are as follows:

database

The JDBC database that contains the table to which you are provisioning.

table

The name of the table in the JDBC database that contains the user accounts.



keyColumn

The column value that is used as the unique identifier for rows in the table.

4.2. OpenICF Interfaces Implemented by the Database Table Connector

The Database Table Connector implements the following OpenICF interfaces.

Authenticate

Provides simple authentication with two parameters, presumed to be a user name and password.

Create

Creates an object and its uid.

Delete

Deletes an object, referenced by its uid.

Resolve Username

Resolves an object by its username and returns the uid of the object.

Schema

Describes the object types, operations, and options that the connector supports.

Script on Connector

Enables an application to run a script in the context of the connector. Any script that runs on the connector has the following characteristics:

- The script runs in the same execution environment as the connector and has access to all the classes to which the connector has access.
- The script has access to a connector variable that is equivalent to an initialized instance of the connector. At a minimum, the script can access the connector configuration.
- The script has access to any script-arguments passed in by the application.

Search

Searches the target resource for all objects that match the specified object class and filter.

Sync

Polls the target resource for synchronization events, that is, native changes to objects on the target resource.



Test

Tests the connector configuration. Testing a configuration checks all elements of the environment that are referred to by the configuration are available. For example, the connector might make a physical connection to a host that is specified in the configuration to verify that it exists and that the credentials that are specified in the configuration are valid.

This operation might need to connect to a resource, and, as such, might take some time. Do not invoke this operation too often, such as before every provisioning operation. The test operation is not intended to check that the connector is alive (that is, that its physical connection to the resource has not timed out).

You can invoke the test operation before a connector configuration has been validated.

Update

Updates (modifies or replaces) objects on a target resource.

4.3. Database Table Connector Configuration

The Database Table Connector has the following configurable properties.

4.3.1. Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
quoting	String			No
Select whether database column na By default, database column names Brackets), column names will appea SQL generated to access the database	are not quoted (No r between single qu	ne). For other sele	ctions (Single, Dou	ble, Back, or
host	String			No
Enter the name of the host on which	the database is ru	nning.		
port	String			No
Enter the port number on which the	database server is	listening.		
user	String			No
Enter the name of the mandatory Da	atabase user with p	ermission to acces	s the accounts table	e.
password	GuardedString	null	Yes	No
Enter a user account that has permi	ssion to access the	accounts table.		
database	String			No
Enter the name of the database on t	he database server	that contains the t	table.	



Property	Туре	Default	Encrypted ^a	Required ^b
table	String			Yes
Enter the name of the table in	the database that co	ntains the accounts.		
keyColumn	String			Yes
This mandatory column value	will be used as the ur	nique identifier for row	s in the table.	
passwordColumn	String			No
Enter the name of the column resources and passwords.	in the table that will	hold the password valu	es. If empty, no	validation is done
jdbcDriver	String	oracle.jdbc .driver .OracleDriver		No
Specify the JDBC Driver class org.gjt.mm.mysql.Driver. Can			Driver. For MyS	QL:
jdbcUrlTemplate	String	jdbc:oracle:thin %h:%p:%d		No
Specify the JDBC Driver Conn MySQL template is jdbc:mysq Could be empty if datasource	l://[host]:[port(3306)]	emplate is jdbc:oracle:t /[db], for more info, rea	hin:@[host]:[por ad the JDBC driv	t(1521)]:[DB]. er documentation.
enableEmptyString	boolean	false		No
Select to enable support for w defined as not-null in the table based tables. By default empt	e schema. This option	does not influence the		
rethrowAllSQLExceptions	boolean	true		No
If this is not checked, SQL sta exception caught and suppres				
	boolean	false		No
nativeTimestamps				110
·		nns in java.sql.Timestar	np format from	
Select to retrieve Timestamp		mns in java.sql.Timestar	mp format from	
Select to retrieve Timestamp (data type of the columboolean	false		the database table
Select to retrieve Timestamp of allNative Select to retrieve all data type	data type of the columboolean	false		the database table
Select to retrieve Timestamp of allNative Select to retrieve all data type validConnectionQuery Specify whether the check conthe connection by switching a	boolean es of columns in nativ String nnection alive query s	false re format from the datal null should be used. If empty	pase table. y, the default im	No No No plementation check
nativeTimestamps Select to retrieve Timestamp of allNative Select to retrieve all data type of validConnectionQuery Specify whether the check conthe connection by switching a from a dummy table. changeLogColumn	boolean es of columns in nativ String nnection alive query s	false re format from the datal null should be used. If empty	pase table. y, the default im	No No No plementation check



Property	Туре	Default	Encrypted ^a	Required ^b	
datasource	String			No	
If specified, the connector will attempt to connect using only this data source, and will ignore other specified resource parameters. For example: jdbc/SampleDataSourceName					
jndiProperties	String[]	null		No	
Could be empty or enter the JDBC JNDI Initial context factory, context provider in a format: key = value.					
suppressPassword	boolean	true		No	
If set to true then the password will false then the password will be return			it is explicitly reque	ested. If set to	

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

^b A list of operations in this column indicates that the property is required for those operations.



Chapter 5 PowerShell Connector Toolkit

The PowerShell Connector Toolkit is not a complete connector in the traditional sense. Rather, it is a framework within which you must write your own PowerShell scripts to address the requirements of your Microsoft Windows ecosystem. You can use the PowerShell Connector Toolkit to create connectors that can provision any Microsoft system, including, but not limited to, Active Directory, MS SQL, MS Exchange, SharePoint, Azure, and Office365. Essentially, any task that can be performed with PowerShell can be executed through connectors based on this toolkit.

The PowerShell Connector Toolkit is available, with a subscription, from the ForgeRock Backstage site.

OpenIDM includes Active Directory and Azure sample scripts for the PowerShell connector that can help you get started with this toolkit. For more information, see Chapter 5, "Samples That Use the PowerShell Connector Toolkit to Create Scripted Connectors" in the OpenIDM Samples Guide.

The sample scripts illustrate the following scenarios:

- Synchronization of users between Windows AD DS and OpenIDM.
- · Synchronization of users between Windows Azure AD and OpenIDM.

5.1. Before You Start

To implement the scripted PowerShell connector, you need to install the following:

- Microsoft .NET Framework 4.5 or later. Connectors created with the PowerShell Connector Toolkit run on the .NET platform and require the installation of a .NET connector server on the Windows system. To install the .NET connector, follow the instructions in Section 11.4.1, "Installing and Configuring a .NET Connector Server" in the *Integrator's Guide*.
- PowerShell version 2.0 or above. The PowerShell Connector Toolkit is not bundled with OpenIDM, but is available, with a ForgeRock community account, from ForgeRock Backstage. To install the connector, download the archive (mspowershell-connector-1.4.2.0.zip) and extract the MsPowerShell.Connector.dll to the same directory where the Connector Server (ConnectorServerService.exe or the legacy version ConnectorServer.exe) is located.

If you're running a supported version of Microsoft Windows Server, as described in Chapter 2, "Before You Install OpenIDM Software" in the Release Notes, you should already meet these requirements.



5.2. Setting Up the PowerShell Connector

To run the commands in this procedure, start with the PowerShell command line. Some of the commands in this procedure require administrative privileges.

1. Install, configure, and start the .NET connector server on a Windows host. If you are running an Active Directory Domain Controller, install that .NET connector server on the same host on which the Windows PowerShell module is installed.

For instructions on installing the .NET connector server, see Section 11.4.1, "Installing and Configuring a .NET Connector Server" in the *Integrator's Guide*.

2. Configure OpenIDM to connect to the .NET connector server.

To do so, copy the remote connector provisioner file from the openidm\samples\provisioners directory to your project's conf\ directory, and edit the file to match your configuration.

```
PS C:\ cd \path\to\openidm
PS C:\path\to\openidm cp samples\provisioners\provisioner.openicf.connectorinfoprovider.json conf
```

For instructions on editing this file, see Procedure 11.7, "Configuring OpenIDM to Connect to the .NET Connector Server" in the *Integrator's Guide*.

3. Download the PowerShell Connector Toolkit archive (mspowershell-connector-1.4.2.0.zip) from the ForgeRock Backstage site.

Extract the archive and move the MsPowerShell.Connector.dll to the folder in which the connector server application executable files (ConnectorServerService.exe and the legacy ConnectorServer.exe) are located.

4. OpenIDM includes PowerShell scripts in openidm\samples subdirectories, including powershell2AD/ for Active Directory, and powershell2AzureAD for Azure AD. Copy these scripts to the host on which the .NET connector server is installed.

The location of the scripts must be referenced in your connector configuration file, for example:

```
"CreateScriptFileName" : "C:/openidm/samples/powershell2AD/tools/ADCreate.ps1", ...
```

5. Copy the sample connector configuration for the PowerShell connector from the samples provisioners directory to your project's conf directory.

OpenIDM includes two sample PowerShell connector configurations:

- Active Directory: provisioner.openicf-adpowershell.json
- Azure AD: provisioner.openicf-azureadpowershell.json

Each sample connector configuration file points to scripts in a specific directory. You may need to change them to match your deployment. If you're connecting to a remote system such as Azure



AD, you should also specify the Host and Port for your .NET server, as well as authentication information for your remote Azure AD deployment.

```
"configurationProperties" : {
    ...
    "CreateScriptFileName" : "C:/openidm/samples/powershell2AD/tools/ADCreate.ps1",
    "DeleteScriptFileName" : "C:/openidm/samples/powershell2AD/tools/ADDelete.ps1",
    ...
    "Host" : "[substitute Hostname or IP Address]",
    "Port" : [substitute port number],
    "Login" : "[substitute Windows Server auth]",
    "Password" : "[substitute password]",
    ...
},
```

Note

In provisioner files, the OpenICF framework requires the path to use forward slash characters and not the backslash characters that you would expect in a Windows path.

5.3. Testing the PowerShell Connector

Start OpenIDM with the configuration for your PowerShell connector project.

The following tests assume that the configuration is in the default path/to/openidm directory. If your PowerShell project is in a different directory, use the startup command with the -p option to point to that directory.

```
$ cd path/to/openidm
$ ./startup.sh
```

5.3.1. Confirming the Connector Configuration

To test that the PowerShell connector has been configured correctly, run the following REST call:



```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--request POST \
"http://localhost:8080/openidm/system?_action=test"
{
    "name" : "azureadpowershell",
    "enabled" : true,
    "config" : "config/provisioner.openicf/azureadpowershell",
    "objectTypes" : [ "__ALL__", "group", "account ],
    "connectorRef" : {
        "connectorName" : "Org.Forgerock.OpenICF.Connectors.MsPowerShell.MsPowerShellConnector",
        "bundleName" : "MsPowerShell.Connector",
        "bundleVersion" : "1.4.2.0"
        },
        "displayName" : "PowerShell Connector",
        "ok" : true
}
```

The displayed output demonstrates a successful configuration of an Azure AD connector.

When you run this test, you should also see a log entry associated with the .NET connector server, in the logs/ subdirectory of that server.

5.3.2. Searching With the Connector

You can use the connector, with a PowerShell search script, to retrieve information from a target system. The PowerShell search script accepts OpenIDM queries, including query-all-ids and _queryFilter

With the following command, you can retrieve a list of existing users on an Azure AD system. You can also use any system-enabled filter, such as those described in Section 7.3.4.2, "Presence Expressions" in the *Integrator's Guide*.

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--request GET \
"http://localhost:8080/openidm/system/azureadpowershell/account?_queryId=query-all-ids"
```

5.3.3. Creating With the Connector

You can use the connector to create new users or groups on the target system, based options listed in the relevant provisioner.openicf-* configuration file.

For example, the following command creates a new user on a remote Azure AD instance:



```
$ curl \
--header "X-OpenIDM-Username: openidm-admin"
--header "X-OpenIDM-Password: openidm-admin"
\
--request POST
\
--header "content-type: application/json"
\
--data '{
    "PasswordNeverExpires": false,
    "AlternateEmailAddresses": ["Robert.Smith@example.com"],
    "LastName": "Smith",
    "PreferredLanguage": "en-US",
    "FirstName": "Robert"
    "UserPrincipalName": "Robert.Smith@example.onmicrosoft.com",
    "DisplayName": "Robert Smith"
"http://localhost:8080/openidm/system/azureadpowershell/account?_action=create"
```

5.3.4. Updating With the Connector

The PowerShell scripts associated with update functionality support changes to the following properties:

- Password
- Principal Name
- License
- Common user attributes

As an example, you could use the following command to change the password for the user with the noted id:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin"
\-header "X-OpenIDM-Password: openidm-admin"
\--request PATCH
\--header "content-type: application/json"
\--data '{
    "operation": "replace",
    "Field": "_PASSWORD__",
    "value": "Passw1rd"
}' \
"http://localhost:8080/openidm/system/azureadpowershell/account/1d4c9276-6937-4d9e-9c60-67e8b4207f4e"
```



5.3.5. Deleting With the Connector

You can use the PowerShell connector to delete user and group objects. As an example, the following command deletes one user from an Azure AD deployment, based on their <u>lid</u>:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin"
\
--header "X-OpenIDM-Password: openidm-admin"
\
--request DELETE \
"http://localhost:8080/openidm/system/azureadpowershell/account/1d4c9276-6937-4d9e-9c60-67e8b4207f4e"
```



Chapter 6

Groovy Connector Toolkit

OpenICF provides a generic Groovy Connector Toolkit that enables you to run a Groovy script for any OpenICF operation, such as search, update, create, and others, on any external resource.

The Groovy Connector Toolkit is not a complete connector in the traditional sense. Rather, it is a framework within which you must write your own Groovy scripts to address the requirements of your implementation. Specific scripts are provided within these samples, which demonstrate how the Groovy Connector Toolkit can be used. These scripts cannot be used as is in your deployment, but are a good starting point on which to base your customization.

6.1. Groovy Connector Toolkit

The Groovy Connector Toolkit is bundled with OpenIDM 4.5, in the JAR openidm/connectors/groovy-connector-1.4.2.1.jar.

Sample implementations are provided in Chapter 4, "Samples That Use the Groovy Connector Toolkit to Create Scripted Connectors" in the OpenIDM Samples Guide.

6.2. OpenICF Interfaces Implemented by the Scripted Groovy Connector

The Scripted Groovy Connector implements the following OpenICF interfaces.

Authenticate

Provides simple authentication with two parameters, presumed to be a user name and password.

Create

Creates an object and its uid.

Delete

Deletes an object, referenced by its uid.

Resolve Username

Resolves an object by its username and returns the uid of the object.



Schema

Describes the object types, operations, and options that the connector supports.

Script on Connector

Enables an application to run a script in the context of the connector. Any script that runs on the connector has the following characteristics:

- The script runs in the same execution environment as the connector and has access to all the classes to which the connector has access.
- The script has access to a connector variable that is equivalent to an initialized instance of the connector. At a minimum, the script can access the connector configuration.
- The script has access to any script-arguments passed in by the application.

Script on Resource

Runs a script on the target resource that is managed by this connector.

Search

Searches the target resource for all objects that match the specified object class and filter.

Sync

Polls the target resource for synchronization events, that is, native changes to objects on the target resource.

Test

Tests the connector configuration. Testing a configuration checks all elements of the environment that are referred to by the configuration are available. For example, the connector might make a physical connection to a host that is specified in the configuration to verify that it exists and that the credentials that are specified in the configuration are valid.

This operation might need to connect to a resource, and, as such, might take some time. Do not invoke this operation too often, such as before every provisioning operation. The test operation is not intended to check that the connector is alive (that is, that its physical connection to the resource has not timed out).

You can invoke the test operation before a connector configuration has been validated.

Update

Updates (modifies or replaces) objects on a target resource.

6.3. Scripted Groovy Connector Configuration

The Scripted Groovy Connector has the following configurable properties.



6.3.1. Operation Script Files Properties

Property	Туре	Default	Encrypted ^a	Required ^b
authenticateScriptFileName	String	null		Authenticate
The name of the file used to perform	m the AUTHEN	TICATE operation.		
deleteScriptFileName	String	null		Delete
The name of the file used to perform	m the DELETE	operation.		
schemaScriptFileName	String	null		Schema
The name of the file used to perform	m the SCHEMA	operation.		
customizerScriptFileName	String	null		No
The script used to customize some	function of the	connector. Read th	e documentation for	more details.
resolveUsernameScriptFileName	String	null		Resolve Username
The name of the file used to perform	m the RESOLVI	E_USERNAME oper	ration.	
testScriptFileName	String	null		Test
The name of the file used to perform	m the TEST ope	eration.		
updateScriptFileName	String	null		Update
The name of the file used to perform	m the UPDATE	operation.		
searchScriptFileName	String	null		Get Search
The name of the file used to perform	m the SEARCH	operation.		
scriptOnResourceScriptFileName	String	null		Script On Resource
The name of the file used to perform	m the RUNSCR	IPTONRESOURCE	operation.	
createScriptFileName	String	null		Create
The name of the file used to perform	m the CREATE	operation.		
syncScriptFileName	String	null		Sync
The name of the file used to perform	rm the SYNC op	eration.		

a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

 $^{^{\}mathrm{b}}$ A list of operations in this column indicates that the property is required for those operations.



6.3.2. Groovy Engine configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
warningLevel	int	1		No
Warning Level of the compiler				
minimumRecompilationInterval	int	100		No
Sets the minimum of time after a so	ript can be reco	mpiled.		
scriptRoots	String[]	null		Yes
The root folder to load the scripts f	rom. If the value	is null or empty the	e classpath value is	used.
debug	boolean	false		No
If true, debugging code should be a	ctivated			
targetDirectory	File	null		No
Directory into which to write classe	S.			
disabledGlobalASTTransformations	String[]	null		No
Sets a list of global AST transforma org.codehaus.groovy.transform.AS	tions which show	uld not be loaded ev files. By default, no	ren if they are defin one is disabled.	ed in META-INF/
classpath	String[]	П		No
Classpath for use during compilation	on.			
scriptExtensions	String[]	['groovy']		No
Description is not available				
	Chainn			
sourceEncoding	String	UTF-8		No
SourceEncoding Encoding for source files	String	UTF-8		No
Encoding for source files	String	Null		No No
•	String	null		
Encoding for source files scriptBaseClass Base class name for scripts (must d	String	null		
Encoding for source files scriptBaseClass Base class name for scripts (must d	String Lerive from Scrip	null ot) false		No
Encoding for source files scriptBaseClass Base class name for scripts (must d	String Lerive from Scrip	null ot) false		No
Encoding for source files scriptBaseClass Base class name for scripts (must diverbose If true, the compiler should produce	String lerive from Scrip boolean e action informa boolean	null ot) false		No No

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.



^b A list of operations in this column indicates that the property is required for those operations.

6.3.3. Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b		
customConfiguration	String	null		No		
Custom Configuration script for Groovy ConfigSlurper						
customSensitiveConfiguration	GuardedString	null	Yes	No		
Custom Sensitive Configuration script for Groovy ConfigSlurper						

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

^b A list of operations in this column indicates that the property is required for those operations.



Chapter 7 Scripted SAP Connector

The scripted SAP connector is an implementation of the Scripted Groovy Connector Toolkit that connects to any SAP system using the SAP JCo Java libraries. This chapter describes how to install and configure the scripted SAP connector, and how to test the sample scripts that are bundled with the connector.

The sample scripts illustrate the following scenarios:

- Synchronization of users between an SAP HR module and OpenIDM
- Synchronization of users between OpenIDM and an SAP (R/3) system

7.1. Before You Start

- The SAP connector is provided only with the OpenIDM Enterprise build, and is available on the ForgeRock Backstage site.
- The SAP connector requires the SAP Java Connector (JCo) libraries, version 3.0.12 or later. ForgeRock distributes the SAP connector without these JCo libraries. Before you can use the SAP connector, you must obtain the JCo libraries that correspond to your architecture.

7.2. Setting Up the SAP Connector

- 1. Download the SAP connector from the ForgeRock Backstage site.
- 2. Copy the SAP connector JAR file (sap-connector-1.4.0.0.jar) to the openidm/connectors directory:
 - \$ cp ~/Downloads/sap-connector-1.4.0.0.jar /path/to/openidm/connectors
- Copy the SAP JCo libraries that correspond to your architecture to the /path/to/openidm/lib directory. For example:

```
$ cp sapjco3.jar /path/to/openidm/lib
$ cp libsapjco3.so /path/to/openidm/lib
```

4. Change your OpenIDM logging configuration to log messages from the SAP connector.

By default, OpenIDM logs nothing for the SAP connector. To troubleshoot any issues with the connector, set the following properties in your project's conf/logging.properties file:



SAP Connector Logging
org.forgerock.openicf.connectors.sap.level=FINER
samples.r3.level=FINER
samples.hr.level=FINER
samples.level=FINER

7.3. Using the SAP Connector With an SAP HR System

The SAP HR sample scripts enable you to manage the email address and global employee UID of records in an SAP HR system.

The following sections explain how to configure OpenIDM to use these sample scripts, how to test the connection to the SAP HR system, and how to update user records.

7.3.1. Setting up OpenIDM for the SAP HR Samples

 Create a connector configuration file for the SAP connector and place it in your project's conf/ directory.

You can use this sample provisioner.openicf-saphr.json as a guide.

Edit that file with the connection details for your SAP HR system. Specifically, set at least the following properties:

destination

An alias to the SAP system to which you are connecting, for example, SAP1. If you are connecting to more than one SAP system, the destination property for each system must be unique.

The sample connector configuration assumes a connection to a single SAP system, so the value for this property in the sample configuration is OPENIDM.

asHost

The FQDN of your SAP Application Server, for example sap.example.com.

user

Your SAP user account.

password

The password of this SAP user account.

client

The SAP Client number that will be used to connect to the SAP system.



systemNumber

The SAP system number.

directConnection

A boolean (true/false). If true, the connection goes directly to an SAP ABAP Application server or SAP router. If false, the connection goes to a group of SAP instances, through an SAP message server.

sapRouter

The IP address and port of the SAP router, if applicable. The syntax is /H/host[/S/port], for example /H/203.0.113.0/S/3299.

poolCapacity

The maximum number of idle connections kept open by the destination. If there is no connection pooling, set this to 0. The default value is 1.

For optimum performance, set this value to an integer between 5 and 10.

2. To test this connector, you can use the sample Groovy scripts available from the *ForgeRock Artifact Repository Browser*. You can find the source for these scripts in this location, in the samples/ directory, as well as the samples/hr/ subdirectory.

```
TestSAP.groovy
SearchSAPHR.groovy
UpdateSAPHR.groovy
SchemaSAPHR.groovy
EmplComm.groovy
```

Update your connector configuration to point to those scripts. The sample connector configuration assumes the following locations for the scripts (relative to the value of the scriptRoots property):

```
"testScriptFileName" : "samples/TestSAP.groovy",
"searchScriptFileName" : "samples/hr/SearchSAPHR.groovy",
"updateScriptFileName" : "samples/hr/UpdateSAPHR.groovy",
"schemaScriptFileName" : "samples/hr/SchemaSAPHR.groovy",
```

The EmplComm.groovy must be placed in the same location as the Search, Update, and Schema scripts.

Important

The Groovy scripts belong to a specific package. The parent directory where the scripts are located must be the same as the package name. So the TestSAP.groovy script must be under a samples directory (because



it belongs to the samples package) and the remaining HR scripts must be under a samples/hr directory (because they belong to the hr package).

7.3.2. Testing the Connection to the SAP HR System

1. Start OpenIDM with the configuration for your SAP connector project.

This procedure assumes that the configuration is in the default path/to/openidm directory. If your SAP project is in a different directory, use the -p option with the startup command to point to that directory.

```
$ cd path/to/openidm
$ ./startup.sh
```

2. Test that the connector has been configured correctly and that the SAP HR system can be reached:

```
$ curl \
 --header "X-OpenIDM-Username: openidm-admin" \
 --header "X-OpenIDM-Password: openidm-admin" \
 --request POST \
 "http://localhost:8080/openidm/system/saphr/?_action=test"
{
  "name" : "saphr",
  "enabled" : true,
  "config" : "config/provisioner.openicf/saphr2",
  "objectTypes" : [ "__ALL__", "employee" ],
  "connectorRef" : {
    "connectorName": "org.forgerock.openicf.connectors.sap.SapConnector",
    "bundleName" : "org.forgerock.openicf.connectors.sap-connector",
    "bundleVersion": "1.4.0.0"
  "displayName" : "Sap Connector",
  "ok" : true
}
```

3. Retrieve a list of the existing users (with their employee number) in the SAP HR system:



```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--request GET \
"http://localhost:8080/openidm/system/saphr/employee?_queryId=query-all-ids"
{
    "result" : [ {
        "_id" : "00000010",
        "_NAME__" : "00000010"
}, {
        "_id" : "00000069",
        "_NAME__" : "00000069"
}, {
        "_id" : "00000070",
        "_id" : "000000070",
        "_NAME__" : "000000070"
}
```

4. Retrieve the complete record of an employee in the SAP HR system by including the employee's ID in the URL.

The following command retrieves the record for employee Maria Gonzales:

```
--header "X-OpenIDM-Username: openidm-admin" \
 --header "X-OpenIDM-Password: openidm-admin" \
 --request GET \
 "http://localhost:8080/openidm/system/saphr/employee/55099307"
{
  " id" : "55099307",
  "PERSONAL DATA" : {
    "PERNO" : "55099307",
    "INFOTYPE" : "0002",
    "TO DATE" : "Fri Dec 31 00:00:00 CET 9999",
    "FROM DATE" : "Tue Mar 30 00:00:00 CET 1954",
    "SEQNO": "000",
    "CH ON" : "Thu Mar 27 00:00:00 CET 2003",
    "CHANGED BY" : "MAYROCK",
    "LAST_NAME" : "Gonzales",
    "FIRSTNAME" : "Maria",
    "NAME FORM" : "00",
    "FORMOFADR" : "2",
    "GENDER" : "2"
    "BIRTHDATE" : "Tue Mar 30 00:00:00 CET 1954",
    "LANGU" : "D",
    "NO O CHLDR" : "0",
    "BIRTHYEAR" : "1954".
    "BIRTHMONTH" : "03",
    "BIRTHDAY" : "30".
    "LASTNAME M" : "GONZALES",
    "FSTNAME M" : "MARIA"
 }
}
```



7.3.3. Using the SAP Connector to Manage Employee Information (SAP HR)

The following sample commands show how the SAP connector is used to manage the email account of user Maria Gonzales, retrieved in the previous step. Management of the global UID (SYS-UNAME) works in the same way.

 Check if Maria Gonzales already has an email account on the SAP HR system by filtering a query on her user account for the EMAIL field:

```
$ curl \
    --header "X-OpenIDM-Username: openidm-admin" \
    --header "X-OpenIDM-Password: openidm-admin" \
    --request GET \
    "http://localhost:8080/openidm/system/saphr/employee/55099307?_fields=EMAIL"
    {
        "_id" : "55099307",
}
```

No email account is found for Maria Gonzales.

2. Add an email account by sending a PUT request. The JSON payload should include the email address as the value of the ID property:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--request PUT \
--data '{
 "EMAIL": { "ID": "maria.gonzales@example.com" }
"http://localhost:8080/openidm/system/saphr/employee/55099307"
  " id" : "55099307",
 "EMAIL" : [ {
    "EMPLOYEENO": "55099307",
    "SUBTYPE" : "0010",
    "VALIDEND" : "Fri Dec 31 00:00:00 CET 9999",
    "VALIDBEGIN": "Fri March 18 00:00:00 CET 2016",
    "RECORDNR" : "000"
    "COMMTYPE" : "0010"
    "NAMEOFCOMMTYPE" : "E-mail",
    "ID" : "Maria.Gonzales@example.com"
 } ]
```

By default, the connector sets the VALIDBEGIN date to the current date, and the VALIDEND date to the SAP "END" date (12/31/9999). You can specify different temporal constraints by including these properties in the JSON payload, with the format YYYYMMDD. For example:



```
{
   "EMAIL": {
      "ID": "maria.gonzales@example.com"
      "VALIDBEGIN": "20160401",
      "VALIDEND": "20161231"
   }
}
```

3. To change the value of an existing email account, provide a new value for the ID.

The JSON payload of the change request must also include the RECORDNR attribute, as well as the VALIDEEGIN and VALIDEND dates, in SAP format (YYYYMMDD).

The following example changes Maria Gonzales' email address to maria.gonzales-admin@example.com:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--request PUT \
--data '{
    "EMAIL": {
        "ID": "maria.gonzales-admin@example.com",
        "RECORDNR": "000",
        "VALIDEND": "99991231",
        "VALIDBEGIN": "20000101"
    }
}' \
"http://localhost:8080/openidm/system/saphr/employee/55099307"
```

4. To change the temporal constraint (VALIDEND date) of the record, include the existing VALIDEND data in the JSON payload, and specify the new end date as a value of the DELIMIT DATE attribute.

The following example changes the end date of Maria Gonzale's new mail address to December 31st, 2016:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--request PUT \
--data '{
    "EMAIL": {
        "ID": "maria.gonzales-admin@example.com",
        "RECORDNR": "000",
        "VALIDEND": "99991231",
        "VALIDBEGIN": "20000101",
        "DELIMIT_DATE": "20161231"
    }
}' \
"http://localhost:8080/openidm/system/saphr/employee/55099307"
```

5. To delete the email address of the record, send a PUT request with the current RECORDNR, VALIDBEGIN, and VALIDEND attributes, but without the ID.



The following request removes the email address from Maria Gonzales' record:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--request PUT \
--data '{
    "EMAIL": {
        "RECORDNR" : "000",
        "VALIDEND" : "99991231",
        "VALIDBEGIN" : "20000101"
    }
}' \
"http://localhost:8080/openidm/system/saphr/employee/55099307"
```

7.4. Using the SAP Connector to Manage SAP Basis System (R/3) Users

The SAP Connector enables you to perform the following operations on SAP system user accounts:

- · List all users
- List all activity groups (roles)
- · Manage user profiles
- List all user companies
- · Obtain a user's details
- · Create a user
- Update a user
- · Assign roles to a user
- · Lock a user account
- · Unlock a user account
- · Delete a user account

Currently, the SAP connector cannot detect changes on the SAP system in real time. You must run an OpenIDM reconciliation operation to detect changes on the SAP system.

7.4.1. Setting up OpenIDM for the SAP R/3 Samples

 Create a connector configuration file for the SAP connector and place it in your project's conf/ directory.



You can use this sample provisioner.openicf-sapr3.json as a guide.

Edit that file with the connection details for your SAP R/3 system. Specifically, set at least the following properties:

destination

An alias to the SAP system to which you are connecting, for example, SAP1. If you are connecting to more than one SAP system, the destination property for each system must be unique.

The sample connector configuration assumes a connection to a single SAP system, MYSAP.

asHost

The FQDN of your SAP Application Server, for example sap.example.com.

user

Your SAP user account.

password

The password of this SAP user account.

client

The SAP Client number that will be used to connect to the SAP system.

systemNumber

The SAP system number.

directConnection

A boolean (true/false). If true, the connection goes directly to an SAP ABAP Application server or SAP router. If false, the connection goes to a group of SAP instances, through an SAP message server.

sapRouter

The IP address and port of the SAP router, if applicable. The syntax is /H/host[/S/port], for example /H/203.0.113.0/S/3299.

poolCapacity

The maximum number of idle connections kept open by the destination. If there is no connection pooling, set this to 0. The default value is 1.

For optimum performance, set this value to an integer between 5 and 10.



2. To test this connector, you can use the sample Groovy scripts available from the *ForgeRock Artifact Repository Browser*. You can find the source for these scripts in this location, in the samples/ directory, as well as the samples/r3/ subdirectory.

```
TestSAP.groovy
SearchSAPR3.groovy
CreateSAPR3.groovy
UpdateSAPR3.groovy
DeleteSAPR3.groovy
SchemaSAPR3.groovy
```

Update your connector configuration to point to those scripts. The sample connector configuration assumes the following locations for the scripts (relative to the value of the scriptRoots property):

```
"testScriptFileName" : "samples/TestSAP.groovy",
"searchScriptFileName" : "samples/r3/SearchSAPR3.groovy",
"createScriptFileName" : "samples/r3/CreateSAPR3.groovy",
"updateScriptFileName" : "samples/r3/UpdateSAPR3.groovy",
"deleteScriptFileName" : "samples/r3/DeleteSAPR3.groovy",
"schemaScriptFileName" : "samples/r3/SchemaSAPR3.groovy",
```

Important

The Groovy scripts belong to a specific package. The parent directory where the scripts are located must be the same as the package name. So the TestSAP.groovy script must be under a samples directory (because it belongs to the samples package) and the R/3 scripts must be under a samples/r3 directory (because they belong to the r3 package).

7.4.2. Testing the Connection to the SAP R/3 System

1. Start OpenIDM with the configuration for your SAP R/3 project.

This procedure assumes that the configuration is in the default path/to/openidm directory. If your SAP project is in a different directory, use the -p option with the startup command to point to that directory.

```
$ cd path/to/openidm
$ ./startup.sh
```

2. Test that the connector has been configured correctly and that the SAP R/3 system can be reached:



```
$ curl \
 --header "X-OpenIDM-Username: openidm-admin" \
 --header "X-OpenIDM-Password: openidm-admin" \
 --request POST \
 "http://localhost:8080/openidm/system/mysap/?_action=test"
  "name": "mysap",
  "enabled": true,
  "config": "config/provisioner.openicf/mysap",
  "objectTypes": [
    "__ALL__",
    "user",
    "activity group",
    "company",
"profile"
 ],
  "connectorRef": {
    "connectorName": "org.forgerock.openicf.connectors.sap.SapConnector",
    "bundleName": "org.forgerock.openicf.connectors.sap-connector",
    "bundleVersion": "1.4.0.0"
  "displayName": "Sap Connector",
  "ok": true
}
```

7.4.3. Using the SAP Connector to Manage SAP R/3 Users

This section provides sample commands for managing users in an SAP system.

7.4.3.1. Listing the Users in the SAP System

The following command returns a list of the existing users in the SAP system, with their IDs:

```
$ curl \
 --header "X-OpenIDM-Username: openidm-admin" \
 --header "X-OpenIDM-Password: openidm-admin" \
 --request GET \
 "http://localhost:8080/openidm/system/mysap/user?_queryId=query-all-ids"
  "result": [
    {
      " id": "BJENSEN",
        NAME ": "BJENSEN"
    {
        id": "DDIC",
         NAME _": "DDIC"
    },
      " id": "USER4"
        NAME ": "USER4"
    },
      " id": "USER6",
```



```
"__NAME__": "USER6"
},
{
    "_id": "USER7",
    "__NAME__": "USER7"
}

],
    "resultCount": 9,
    "pagedResultsCookie": null,
    "totalPagedResultsPolicy": "NONE",
    "totalPagedResults": -1,
    "remainingPagedResults": -1
}
```

7.4.3.2. Obtaining the Details of an SAP User

The following command uses the SAP connector to obtain a user's details from a target SAP system:

```
$ curl \
 --header "X-OpenIDM-Username: openidm-admin" \
 --header "X-OpenIDM-Password: openidm-admin" \
 --request GET \
 "http://localhost:8080/openidm/system/mysap/user/BJENSEN"
    "__NAME__": "BJENSEN",
"__ENABLE__": true,
    "__ENABLE_DATE__": "2015-09-01",
"_DISABLE_DATE__": "2016-09-01",
       _LOCK_OUT__": false,
    "ADDTEL": [
         {
              "COUNTRY": "DE",
              "TELEPHONE": "19851444",
         },
         . . .
    "PROFILES": [
         {
              "BAPIPROF": "T_ALM_CONF",
    "ISLOCKED": {
         "WRNG LOGON": "U",
    },
"ACTIVITYGROUPS": [
              "AGR_NAME": "MW_ADMIN", "FROM_DAT": "2015-07-15",
              "TO_DAT": "9999-12-31",
              "AGR_TEXT": "Middleware Administrator"
         },
    "DEFAULTS": {
```



```
"COMPANY": {
    "COMPANY": "SAP AG"
},
   "ADDRESS": {
    ...
},
   "UCLASS": {
    ...
},
   "LASTMODIFIED": {
        "MODDATE": "2015-07-15",
        "MODTIME": "14:22:57"
},
   "LOGONDATA": {
        "GLTGV": "2015-09-01",
        "GLTGB": "2016-09-01",
        ...
},
   "_id": "BJENSEN"
}
```

In addition to the standard user attributes, the GET request returns the following OpenICF operational attributes:

- __ENABLE__ indicates whether the account is enabled, based on the value of the LOGONDATA attribute
- ENABLE DATE set to the value of LOGONDATA/GLTGV (date from which the user account is valid)
- __DISABLE_DATE__ set to the value of LOGONDATA/GLTGB (date to which the user account is valid)
- LOCK OUT indicates whether the account is locked

7.4.3.3. Creating SAP User Accounts

To create a user, you must supply *at least* a username and password. If you do not provide a lastname, the connector uses the value of the username.

The following command creates a new SAP user, SCARTER:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--request POST \
--data '{
    "__NAME__": "SCARTER",
    "__PASSWORD__": "Passw0rd"
}' \
"http://localhost:8080/openidm/system/mysap/user/?_action=create"
{
    "_id": "SCARTER",
    "COMPANY": {
        "COMPANY": "SAP AG"
```



```
LOCK OUT ": false,
  "ADDRESS": {
    NAME ": "SCARTER",
  "LASTMODIFIED": {
    "MODDATE": "2016-04-20",
    "MODTIME": "04:14:29"
  "UCLASS": {
    "COUNTRY SURCHARGE": "0"
    "SUBSTITUTE_FROM": "0000-00-00"
    "SUBSTITUTE UNTIL": "0000-00-00"
    ENABLE ": true,
  "DEFAULTS": {
    "SPDB": "H",
    "SPDA": "K",
    "DATFM": "1"
    "TIMEFM": "0"
  "LOGONDATA": {
  "ISLOCKED": {
    "WRNG_LOGON": "U",
    "LOCAL LOCK": "U",
    "GLOB_LOCK": "U"
    "NO_USER_PW": "U"
 }
}
```

The SAP account that is created is valid and enabled, but the password is expired by default. To log into the SAP system, the newly created user must first provide a new password.

To create a user with a valid (non-expired) password, include the <u>__PASSWORD_EXPIRED__</u> attribute in the ISON payload, with a value of false. For example:

To create an account that is locked by default, include the <u>LOCK_OUT</u> attribute in the JSON payload, with a value of <u>true</u>. For example:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
```



```
--header "Content-Type: application/json" \
--request POST \
--data '{
           _" : "SCARTER",
     NAME
   "__PASSWORD__": "Passw0rd",
   "_LOCK_OUT_": true
"http://localhost:8080/openidm/system/mysap/user/?_action=create"
   "__NAME__": "SCARTER",
"__ENABLE__": false,
"__LOCK_OUT__": true,
   "LOGONDATA": {
       "GLTGV": "0000-00-00",
       "GLTGB": "0000-00-00",
       "USTYP": "A",
       "LTIME": "00:00:00"
       "BCODE": "2FCOD86C99AA5862",
       "CODVN": "B",
       "PASSCODE": "1DBBD983287D7CB4D8177B4333F439F808A395FA",
       "CODVC": "F"
       "PWDSALTEDHASH": "{x-issha, 1024}zrs3Zm/fX/l/KFGATp3kvOGlis3zLLiPmPVCDpJ9XF0=",
       "CODVS": "I"
  "MODDATE": "2015-10-01",
       "MODTIME": "15:25:18"
  },
"ISLOCKED": {
       "WRNG LOGON": "U",
       "LOCAL LOCK": "L",
                               // "L" indicates that the user is locked on the local system
       "GLOB_LOCK": "U",
       "NO USER PW": "U"
   }
```

7.4.3.3.1. Schema Used by the SAP Connector For User Accounts

For the most part, the SAP connector uses the standard SAP schema to create a user account. The most common attributes in an SAP user account are as follows:

- ADDRESS user address data
- LOGONDATA user logon data
- DEFAULTS user account defaults
- COMPANY the company to which the user is assigned
- REF USER the usernames of the Reference User
- ALIAS an alias for the username
- UCLASS license-related user classification



- LASTMODIFIED read-only attribute that indicates the date and time that the account was last changed
- ISLOCKED read-only attribute that indicates the lockout status of the account
- IDENTITY assignment of a personal identity to the user account
- PROFILES any profiles assigned to the user account (see Section 7.4.3.6, "Managing User Profiles").
- ACTIVITYGROUPS activity groups assigned to the user
- ADDTEL telephone numbers assigned to the user

In addition, the SAP connector supports the following OpenICF operational attributes for CREATE requests:

- LOCK OUT
- PASSWORD
- PASSWORD EXPIRED

The following example creates a user, KVAUGHAN, with all of the standard attributes:

```
$ curl \
 --header "X-OpenIDM-Username: openidm-admin" \
 --header "X-OpenIDM-Password: openidm-admin" \
 --header "Content-Type: application/json" \
 --request POST \
 --data '{
    "__NAME__" : "KVAUGHAN",
"__PASSWORD__": "Passw0rd",
       PASSWORD EXPIRED ": false,
    "LOGONDATA": {
        "GLTGV": "2016-04-01",
        "GLTGB": "2016-12-01",
        "USTYP": "A"
    "ADDRESS": {
       "FIRSTNAME": "Katie"
       "LASTNAME": "Vaughan"
       "TEL1_NUMBR": "33297603177",
       "E_MAIL": "katie.vaughan@example.com",
       "FUNCTION": "Test User"
   ),
"COMPANY": {
        "COMPANY": "EXAMPLE.COM"
    "ALIAS": {
        "USERALIAS": "KVAUGHAN"
 "http://localhost:8080/openidm/system/mysap/user/?_action=create"
  " id": "KVAUGHAN".
  "ADDRESS": {
```



```
"PERS NO": "0000010923".
  "ADDR NO": "0000010765",
  "FIRSTNAME": "Katie",
  "LASTNAME": "Vaughan",
  "FULLNAME": "Katie Vaughan",
  "E MAIL": "katie.vaughan@example.com",
  "LANGU CR P": "E",
  "LANGUCPISO": "EN"
"LOGONDATA": {
  "GLTGV": "2016-04-01",
  "GLTGB": "2016-12-01",
"COMPANY": {
  "COMPANY": "SAP AG"
},
"_ENABLE__": true,
"ADDTEL": [
  {
"ISLOCKED": {
  "WRNG_LOGON": "U",
  "LOCAL_LOCK": "U",
  "GLOB_LOCK": "U",
  "NO USER PW": "U"
"UCLASS": {
  "COUNTRY SURCHARGE": "0",
  "SUBSTITUTE_FROM": "0000-00-00", "SUBSTITUTE_UNTIL": "0000-00-00"
},
"ALIAS": {
  "USERALIAS": "KVAUGHAN"
"__NAME__": "KVAUGHAN",
"__LOCK_OUT__": false,
"LASTMODIFIED": {
  "MODDATE": "2016-04-20",
  "MODTIME": "04:55:08"
},
"__ENABLE_DATE__": "2016-04-01",
                                      // (Value of LOGONDATA/GLTGV)
"DEFAULTS": {
  "SPDB": "H",
  "SPDA": "K",
  "DATFM": "1"
  "TIMEFM": "0"
   _DISABLE_DATE__": "2016-12-01"
                                       // (Value of LOGONDATA/GLTGB)
```

7.4.3.4. Updating SAP User Accounts

The following sections provide sample commands for updating an existing user account.



7.4.3.4.1. Locking and Unlocking an Account

To lock or unlock a user's account, send a PUT request, and set the value of the user's <u>LOCK_OUT_</u> attribute to true.

The following example locks user KVAUGHAN's account:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--header "If-Match: *" \
--request PUT \
--data '{
    "_LOCK_OUT__": true
}' \
"http://localhost:8080/openidm/system/mysap/user/KVAUGHAN"
```

The following example unlocks KVAUGHAN's account:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--header "If-Match: *" \
--request PUT \
--data '{
    "__LOCK_OUT__": false
}' \
"http://localhost:8080/openidm/system/mysap/user/KVAUGHAN"
```

7.4.3.4.2. Updating the Standard Attributes of a User's Account

To update a user's standard attributes, send a PUT request to the user ID. The JSON payload must respect the structure for each attribute, as indicated in Section 7.4.3.3.1, "Schema Used by the SAP Connector For User Accounts".

The following command updates the ADDRESS attribute of user KVAUGHAN:



```
$ curl \
 --header "X-OpenIDM-Username: openidm-admin" \
 --header "X-OpenIDM-Password: openidm-admin" \
 --header "Content-Type: application/json" \
 --header "If-Match: *" \
 --request PUT \
 --data '{
    "ADDRESS": {
        "FIRSTNAME": "Katie"
        "LASTNAME": "Vaughan",
        "FULLNAME": "Katie Vaughan",
        "FUNCTION": "Administrator",
        "TITLE": "Company"
        "NAME": "EXAMPLE.COM"
        "CITY": "San Francisco",
        "POSTL COD1": "94105"
        "STREET": "Sacramento St",
        "HOUSE NO": "2912",
        "COUNTRY": "US",
        "COUNTRYISO": "US".
        "LANGU": "E",
        "LANGU ISO": "EN",
        "REGION": "CA",
        "TIME_ZONE": "PST"
        "TEL1 NUMBR": "33297603177",
        "E_MAIL": "katie.vaughan@example.com",
        "LANGU_CR_P": "E",
        "LANGUCPISO": "EN"
}' \
 "http://localhost:8080/openidm/system/mysap/user/KVAUGHAN"
```

7.4.3.4.3. Resetting a User's Password

To reset the user's password, provide the new password as the value of the <u>__PASSWORD__</u> attribute, in a PUT request. The following command resets KVAUGHAN's password to <u>MyPasswOrd</u>:

Note that unless you set the <u>__PASSWORD_EXPIRED_</u> attribute to false, the user will be required to reset her password the next time she logs into the SAP system.

The following command resets KVAUGHAN's password to MyPasswOrd, and ensures that she does not have to reset her password the next time she logs in:



```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--request PUT \
--data '{
    "__PASSWORD__": "MyPassw0rd",
    "__PASSWORD_EXPIRED__": false
}'
"http://localhost:8080/openidm/system/mysap/user/KVAUGHAN"
```

7.4.3.5. Deleting User Accounts

To delete a user account, send a DELETE request to the user ID. The following example deletes KVAUGHAN:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--request DELETE \
"http://localhost:8080/openidm/system/mysap/user/KVAUGHAN"
```

The command returns the complete user object that was deleted.

7.4.3.6. Managing User Profiles

An SAP system uses *profiles* to manage authorization. The following examples demonstrate how to add, change, and remove a user's profiles.

7.4.3.6.1. Creating a User With One or More Profiles

Profiles are added as an array of one or more objects.

The following command creates a user BJENSEN, with the system administrator profile (S A.SYSTEM):



```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--request POST \
--data '{
   "__NAME__" : "BJENSEN",
   "_PASSWORD ": "Password",
   "_PASSWORD_EXPIRED__": false,
   "PROFILES": [
       {"BAPIPROF": "S_A.SYSTEM"}
"http://localhost:8080/openidm/system/mysap/user/?_action=create"
  " id": "BJENSEN".
 "COMPANY": {
    "COMPANY": "SAP AG"
 "PROFILES": [
   {
      "BAPIPROF": "S A.SYSTEM",
      "BAPIPTEXT": "System administrator (Superuser)",
      "BAPITYPE": "S",
      "BAPIAKTPS": "A"
   }
 ],
    NAME ": "BJENSEN"
```

Note that the additional information regarding that profile is added to the user account automatically.

7.4.3.6.2. Updating a User's Profiles

To update a user's profiles, send a PUT request to the user's ID, specifying the new profiles as an array of values for the PROFILES attribute. The values provided in the PUT request will replace the current profiles, so you must include the existing profiles in the request.

The following example adds the SAP_ALL profile to user BJENSEN's account:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--header "If-Match: *" \
--request PUT \
--data '{
    "PROFILES": [
        {"BAPIPROF": "S_A.SYSTEM"},
        {"BAPIPROF": "SAP_ALL"}
    ]
}' \
"http://localhost:8080/openidm/system/mysap/user/BJENSEN"
{
    "_id": "BJENSEN",
```



```
"COMPANY": {
  "COMPANY": "SAP AG"
"PROFILES": [
  {
    "BAPIPROF": "SAP ALL"
    "BAPIPTEXT": "All SAP System authorizations",
    "BAPITYPE": "C",
    "BAPIAKTPS": "A"
  },
    "BAPIPROF": "S A.SYSTEM",
    "BAPIPTEXT": "System administrator (Superuser)",
    "BAPITYPE": "S",
    "BAPIAKTPS": "A"
  }
],
   NAME ": "BJENSEN"
```

7.4.3.6.3. Removing All Profiles From a User Account

To remove all profiles from a user's account, update the account with an empty array. The following example removes all profiles from BJENSEN's account:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--header "If-Match: *" \
--header "If-Match: *" \
--data '{
    "PROFILES": []
}' \
"http://localhost:8080/openidm/system/mysap/user/BJENSEN"

"_id": "BJENSEN",
"COMPANY": {
    "COMPANY": "SAP AG"
},
...
"__NAME__": "BJENSEN"
}
```

The output shows no PROFILES attribute, as this attribute is now empty for this user.

7.4.3.7. Managing User Roles

SAP user roles (or *activity groups*) are an alternative mechanism to grant authorization to an SAP system. Essentially, a role encapsulates a set of one or more profiles.



Roles can be granted with *temporal constraints*, that is, a period during which the role is valid. If no temporal constraints are specified, the SAP connector sets the FROM date to the current date and the TO date to 9999-12-31.

7.4.3.7.1. Creating a User With One or More Profiles

Roles are added as an array of one or more objects.

The following command creates a user SCARTER, with two roles: SAP_AUDITOR_SA_CCM_USR and SAP_ALM_ADMINISTRATOR. The auditor role has a temporal constraint, and is valid only from May 1st, 2016 to April 30th, 2017. The format of the temporal constraint is YYYY-mm-dd:

```
$ curl \
 --header "X-OpenIDM-Username: openidm-admin" \
 --header "X-OpenIDM-Password: openidm-admin" \
 --header "Content-Type: application/json" \
 --request POST \
 --data {
    " NAME
    "__NAME__" : "SCARTER",
"__PASSWORD__": "Passw0rd",
       PASSWORD_EXPIRED__": false,
    "ACTIVITYGROUPS": [
        {
             "AGR_NAME": "SAP_AUDITOR_SA_CCM_USR",
             "FROM_DAT": "2016-05-01",
            "TO DAT": "2017-04-30"
        },
        {
            "AGR_NAME": "SAP_ALM_ADMINISTRATOR"
        }
    ]
 "http://localhost:8080/openidm/system/mysap/user/? action=create"
  " id": "SCARTER",
  "COMPANY": {
    "COMPANY": "SAP AG"
  "PROFILES": [
      "BAPIPROF": "T_ALM_CONF",
      "BAPIPTEXT": "Profile for the Role SAP_ALM_ADMINISTRATOR",
      "BAPITYPE": "G",
      "BAPIAKTPS": "A"
    }
  ],
  "ACTIVITYGROUPS": [
      "AGR NAME": "SAP_ALM_ADMINISTRATOR",
      "FROM_DAT": "2016-04-20",
      "TO DAT": "9999-12-31",
      "AGR TEXT": "Alert Management Administrator"
    },
      "AGR NAME": "SAP AUDITOR SA CCM USR",
```



```
"FROM_DAT": "2016-05-01",
    "TO_DAT": "2017-04-30",
    "AGR_TEXT": "AIS - System Audit - Users and Authorizations"
    }
],
    "__NAME__": "SCARTER"
}
```

When a role is granted, the corresponding profiles are attached to the user account automatically.

7.4.3.7.2. Updating a User's Roles

To update a user's roles, send a PUT request to the user's ID, specifying the new roles as an array of values of the ACTIVITYGROUPS attribute. The values provided in the PUT request will replace the current ACTIVITYGROUPS.

The following example removes the SAP_AUDITOR_SA_CCM_USR role and changes the temporal constraints on the SAP_ALM_ADMINISTRATOR role for SCARTER's account:

```
$ curl \
 --header "X-OpenIDM-Username: openidm-admin" \
 --header "X-OpenIDM-Password: openidm-admin" \
 --header "Content-Type: application/json" \
 --header "If-Match: *" \
 --request PUT \
 --data {
  "ACTIVITYGROUPS": [
      "AGR_NAME": "SAP_ALM_ADMINISTRATOR",
"FROM_DAT": "2015-06-02",
      "TO_DAT": "2016-06-02"
  ]
 "http://localhost:8080/openidm/system/mysap/user/SCARTER"
  " id": "SCARTER",
  "COMPANY": {
    "COMPANY": "SAP AG"
  "PROFILES": [
      "BAPIPROF": "T_ALM_CONF",
      "BAPIPTEXT": "Profile for the Role SAP_ALM_ADMINISTRATOR",
      "BAPITYPE": "G",
      "BAPIAKTPS": "A"
    }
  ],
  "ACTIVITYGROUPS": [
      "AGR NAME": "SAP ALM ADMINISTRATOR",
      "FROM_DAT": "2015-06-02",
      "TO DAT": "2016-06-02",
      "AGR TEXT": "Alert Management Administrator"
```



```
],
"__NAME__": "SCARTER"
}
```

7.4.3.7.3. Removing All Roles From a User Account

To remove all roles from a user's account, update the value of the ACTIVITYGROUPS attribute with an empty array. The following example removes all roles from SCARTER's account:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--header "Content-Type: application/json" \
--header "If-Match: *" \
--request PUT \
--data '{
   "ACTIVITYGROUPS": []
"http://localhost:8080/openidm/system/mysap/user/SCARTER"
 " id": "SCARTER",
 "COMPANY": {
    "COMPANY": "SAP AG"
  "LASTMODIFIED": {
    "MODDATE": "2016-04-21",
    "MODTIME": "04:27:00"
    NAME ": "SCARTER"
```

The output shows no ACTIVITYGROUPS attribute, as this attribute is now empty.

7.5. OpenICF Interfaces Implemented by the SAP Connector

The SAP Connector implements the following OpenICF interfaces.

Authenticate

Provides simple authentication with two parameters, presumed to be a user name and password.

Create

Creates an object and its uid.

Delete

Deletes an object, referenced by its uid.

Resolve Username

Resolves an object by its username and returns the uid of the object.



Schema

Describes the object types, operations, and options that the connector supports.

Script on Connector

Enables an application to run a script in the context of the connector. Any script that runs on the connector has the following characteristics:

- The script runs in the same execution environment as the connector and has access to all the classes to which the connector has access.
- The script has access to a connector variable that is equivalent to an initialized instance of the connector. At a minimum, the script can access the connector configuration.
- The script has access to any script-arguments passed in by the application.

Script on Resource

Runs a script on the target resource that is managed by this connector.

Search

Searches the target resource for all objects that match the specified object class and filter.

Sync

Polls the target resource for synchronization events, that is, native changes to objects on the target resource.

Test

Tests the connector configuration. Testing a configuration checks all elements of the environment that are referred to by the configuration are available. For example, the connector might make a physical connection to a host that is specified in the configuration to verify that it exists and that the credentials that are specified in the configuration are valid.

This operation might need to connect to a resource, and, as such, might take some time. Do not invoke this operation too often, such as before every provisioning operation. The test operation is not intended to check that the connector is alive (that is, that its physical connection to the resource has not timed out).

You can invoke the test operation before a connector configuration has been validated.

Update

Updates (modifies or replaces) objects on a target resource.

7.6. SAP Connector Configuration

The SAP Connector has the following configurable properties.



7.6.1. Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
createScriptFileName	String	null		Create
Description is not available				
targetDirectory	File	null		No
Description is not available				
customizerScriptFileName	String	null		No
Description is not available				
warningLevel	int	1		No
Description is not available				
scriptExtensions	String[]	['groovy']		No
Description is not available		·		
scriptBaseClass	String	null		No
Description is not available	<u>'</u>	·		
scriptRoots	String[]	null		Yes
Description is not available				
resolveUsernameScriptFileName	String	null		Resolve Username
Description is not available				
tolerance	int	10		No
Description is not available				
updateScriptFileName	String	null		Update
Description is not available				
disabledGlobalASTTransformations	String[]	null		No
Description is not available				
schemaScriptFileName	String	null		Schema
Description is not available				
sourceEncoding	String	UTF-8		No
Description is not available				
recompileGroovySource	boolean	false		No



Property	Туре	Default	Encrypted ^a	Required ^b
Description is not available				
customSensitiveConfiguration	GuardedString	null	Yes	No
Description is not available				
authenticateScriptFileName	String	null		Authenticate
Description is not available				
scriptOnResourceScriptFileName	String	null		Script On Resource
Description is not available		'		·
minimumRecompilationInterval	int	100		No
Description is not available				
deleteScriptFileName	String	null		Delete
Description is not available				
customConfiguration	String	null		No
Description is not available				
searchScriptFileName	String	null		Get Search
Description is not available		'		·
debug	boolean	false		No
Description is not available				
classpath	String[]	[]		No
Description is not available				
verbose	boolean	false		No
Description is not available				
testScriptFileName	String	null		Test
Description is not available				
syncScriptFileName	String	null		Sync
Description is not available				
x509Cert	String	null		No
Description is not available				



Property	Туре	Default	Encrypted ^a	Required ^b
----------	------	---------	------------------------	-----------------------

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

7.6.2. Basic Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
asHost	String	null		Yes
Description is not available				
gwHost	String	null		Yes
Description is not available				
gwServ	String	null		Yes
Description is not available				
user	String	null		Yes
SAP Logon user				
password	GuardedString	null	Yes	Yes
SAP Logon password				
client	String	000		Yes
SAP client				,
systemNumber	String	00		Yes
SAP system number				
language	String	EN		Yes
SAP Logon language				
destination	String	OPENIDM		Yes
SAP JCo destination name				
directConnection	boolean	true		Yes
If true, direct connection to an SAP instances through an SAP		server or SAP r	outer. If false connec	tion to a group of
sapRouter	String	null		Yes
SAP router string to use for a	system protected by a fi	irewall. (/H/host	[/S/port])	

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

 $^{^{\}mathrm{b}}$ A list of operations in this column indicates that the property is required for those operations.

^b A list of operations in this column indicates that the property is required for those operations.



7.6.3. SAP Jco Logs Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b		
trace	String	Θ		No		
Enable/disable RFC trace (0 or 1)						
cpicTrace	String	0		No		
Enable/disable CPIC trace [03]						

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

7.6.4. Advanced Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
msHost	String	null		No
Description is not available				
group	String	null		No
Description is not available				
msServ	String	null		No
Description is not available				
r3Name	String	null		No
Description is not available				

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

7.6.5. SAP Secure Network Connection Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
sncMode	String	0		Yes
Description is not available				
sncQoP	String	null		No
Description is not available				
sncLibrary	String	null		No
Description is not available				
sncPartnerName	String	null		No

^b A list of operations in this column indicates that the property is required for those operations.

^b A list of operations in this column indicates that the property is required for those operations.



Property	Туре	Default	Encrypted ^a	Required ^b
Description is not available				
sncMyName	String	null		No
Description is not available				
sncSS0	String	1		No
Description is not available				

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

7.6.6. JCo Connection Pool Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b			
poolCapacity	String	1		No			
Maximum number of idle connections kept open by the destination. $0 = no$ connection pooling. Default is 1.							
expirationTime	String	60000		No			
Time in ms after that a free connect	ion can be closed. D	efault is one minu	te.				
maxGetTime	String	30000		No			
Maximum time in ms to wait for a cothe pool. Default is 30 seconds.	onnection, if the ma	ximum allowed nu	mber of connection	s is allocated by			
peakLimit	String	0		No			
Maximum number of active connections that can be created for a destination simultaneously. The default is 0 (unlimited).							
expirationPeriod	String	60000		No			
Period in ms after that the destination	on checks the releas	sed connections fo	r expiration. Defaul	t is one minute			

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

^b A list of operations in this column indicates that the property is required for those operations.

 $^{^{\}mathrm{b}}$ A list of operations in this column indicates that the property is required for those operations.




Chapter 8 Scripted SSH Connector

The scripted SSH connector is an implementation of the Scripted Groovy Connector Toolkit, and is based on Java Secure Channel (JSch) and the Java implementation of the Expect library (Expect4j). This connector enables you to interact with any SSH server, using Groovy scripts for the OpenICF operations.

The SSH connector is a *poolable connector*. This means that each connector instance is placed into a connection pool every time an action is completed. Subsequent actions can re-use connector instances from the connector pool. When a new connector instance is created, a new SSH client connection is created against the target SSH server. This SSH connection remains open as long as the connector instance is in the connection pool. Note that when a new action is performed, it finds the SSH connection in the exact state that it was left by the previous action.

The following image shows the relationship between SSH connector instances and SSH connections to the target server:





8.1. Configuring Authentication to the SSH Server

The SSH connector authenticates to the SSH server using either a login/password or a public/private key. The authentication method is specified in the authenticationType property in the connector configuration file (conf/provisioner.openicf-ssh.json).

Authenticating with a login and password

To authenticate with a login and password, set the authenticationType to PASSWORD in the connector configuration file, and set a user and password. For example:

```
"configurationProperties" : {
    ...
    "authenticationType" : "PASSWORD",
    "user" : "<USERNAME>",
    "password" : "<PASSWORD>",
    ...
```

The password is encrypted when OpenIDM loads the provisioner file.



Authenticating with a passphrase and private key

To authenticate with a secure certificate, generate a pair of public/private keys. Install the public key on the server side and the private key on the OpenIDM host (where the connector is located). Set the authenticationType to PUBKEY in the connector configuration file and set the user, password, passphrase and privateKey properties. For example:

```
"configurationProperties" : {
    "authenticationType" : "PUBKEY",
    "user" : "<USERNAME>",
    "password" : "<PASSWORD>",
    "passphrase" : "secret",
    "privateKey" : ["----BEGIN DSA PRIVATE KEY----"
              "MIIBugIBAAKBgQDcB0ztVMCFptpJhqlLNZSdN/5cDL3S7a0Vy52Ae7vwwCqQPCQr",
              "6NyUk+wtkDr07NlYd3sg7a9hbsEnlYChsuX+/WUIvb0KdMfeqcQ+jKK26YdkTCGj"
              "g86dBj9JYhobSHDoQ9ov31pYN/cfW5BAZwkm9TdpEjHPvMIa0xx7GPGKWwIVALbD"
              "CEuflyJk9UB7v0dmJS7bKkbxAoGARcbAuDP4rB6MsgAAkVwf+1sHXEiGPShYWrVV"
              "qBgCZ/S45ELqUuiaN/1N/nip/Cc/OSBPKqwl7o50CUg9GH9kTAjmXiwmbkwvtUv+"
              "Xjn5vCHS0w18yc3rGwyr2wj+D9KtDLFJ8+T5HmsbPoDQ3mIZ9xPmRQuRFfVMd9wr"
              "DYORs7cCgYAxjGjWDSKThowsvOUCiEOySz6tWggHH3LTrS4Mfh2tOtnbUfrXq2cw"
              "3CN+T6brgnpYbyX5XI17p859C+cw90MD8N6vvBxaN8QMDRFk+hHNUeSy8gXeem9x"
              "00vdIxCgKvA4dh5nSVb5VGKENEGNEHRlYxEPzbqlPa/C/ZvzIvdKXQIUQMoidPFC",
              "n9z+mE2dAADnPf2m9vk="
              "----END DSA PRIVATE KEY----"
             ],
```

The default value for the passphrase property is null. If you do not set a passphrase for the private key, the passphrase value must be equal to an empty string.

You *must* set a value for the password property, because the connector uses sudo to perform actions on the SSH server.

The private key (PEM certificate) must be defined as a ISON String array.

The values of the passphrase, password and privateKey are encrypted when OpenIDM loads the provisioner file.

8.2. Configuring the SSH Connector

OpenIDM provides a sample connector configuration (provisioner.openicf-ssh.json) in the /path/to/openidm/samples/ssh/conf/ directory. You can copy the sample connector configuration to your project's conf/ directory, and adjust it to match your Kerberos environment.

Set the authentication properties, as described in Section 8.1, "Configuring Authentication to the SSH Server". In addition, set at least the following properties:

host

Specify the hostname or IP address of the SSH server.



port

Set the port on which the SSH server listens.

Default: 22

user

The username of the account that connects to the SSH server.

This account must be able to ssh into the server, with the password provided in the next parameter.

password

The password of the account that is used to connect to the SSH server.

prompt

A string representing the remote SSH session prompt. This must be the exact prompt string, in the format username@target:, for example admin@myserver:. Include any trailing spaces.

The following list describes the configuration properties of the SSH connector shown in the sample connector configuration file. You can generally use the defaults provided in the sample connector configuration file, in most cases. For a complete list of all the configuration properties of the SSH connector, see Section 8.4.1, "Configuration Properties".

sudoCommand

A string that shows the full path to the **sudo** command, for example /usr/bin/sudo.

echoOff

If set to true (the default), the input command echo is disabled. If set to false, every character that is sent to the server is sent back to the client in the expect() call.

terminalType

Sets the terminal type to use for the session. The list of supported types is determined by your Linux/UNIX system. For more information, see the terminfo manual page (\$ man terminfo).

Default: vt102

setLocale

If set to true, indicates that the default environment locale should be changed to the value of the locale property.

Default: false

locale

Sets the locale for the LC_ALL, LANG and LANGUAGE environment variables, if ${\tt setLocale}$ is set to ${\tt true}$.



Default: en US.utf8

connectionTimeout

Specifies the connection timeout to the remote server, in milliseconds.

Default: 5000

expectTimeout

Specifies the timeout used by the expect() calls in scripts, in milliseconds.

Default: 5000

authenticationType

Sets the authentication type, either PASSWORD or PUBKEY. For more information, see Section 8.1, "Configuring Authentication to the SSH Server".

Default: PASSWORD

throwOperationTimeoutException

If true, the connector throws an exception when the expectTimeout is reached for an operation. Otherwise, the operation fails silently.

Default: true

scriptRoots

The path to the Groovy scripts that will perform the OpenICF operations, relative to your OpenIDM installation directory. The sample connector configuration expects the scripts in *project-dir/*tools, so this parameter is set to &{launcher.project.location}/tools in the sample configuration.

classpath

The directory in which the compiler should look for compiled classes. The default classpath, if not is specified, is install-dir/lib.

reloadScriptOnExecution

By default, scripts are loaded and compiled when a connector instance is created and initialized. Setting <code>reloadScriptOnExecution</code> to true makes the connector load and compile the script every time it is called. Do not set this property to <code>true</code> in a production environment, because it will have a significant impact on performance.

Default: false

*ScriptFileName

The name of the Groovy script that is used for each OpenICF operation.



8.3. OpenICF Interfaces Implemented by the SSH Connector

The SSH Connector implements the following OpenICF interfaces.

Authenticate

Provides simple authentication with two parameters, presumed to be a user name and password.

Create

Creates an object and its uid.

Delete

Deletes an object, referenced by its uid.

Resolve Username

Resolves an object by its username and returns the uid of the object.

Schema

Describes the object types, operations, and options that the connector supports.

Script on Connector

Enables an application to run a script in the context of the connector. Any script that runs on the connector has the following characteristics:

- The script runs in the same execution environment as the connector and has access to all the classes to which the connector has access.
- The script has access to a connector variable that is equivalent to an initialized instance of the connector. At a minimum, the script can access the connector configuration.
- The script has access to any script-arguments passed in by the application.

Script on Resource

Runs a script on the target resource that is managed by this connector.

Search

Searches the target resource for all objects that match the specified object class and filter.

Sync

Polls the target resource for synchronization events, that is, native changes to objects on the target resource.

Test

Tests the connector configuration. Testing a configuration checks all elements of the environment that are referred to by the configuration are available. For example, the connector might make a



physical connection to a host that is specified in the configuration to verify that it exists and that the credentials that are specified in the configuration are valid.

This operation might need to connect to a resource, and, as such, might take some time. Do not invoke this operation too often, such as before every provisioning operation. The test operation is not intended to check that the connector is alive (that is, that its physical connection to the resource has not timed out).

You can invoke the test operation before a connector configuration has been validated.

Update

Updates (modifies or replaces) objects on a target resource.

8.4. SSH Connector Configuration

The SSH Connector has the following configurable properties.

8.4.1. Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b		
customSensitiveConfiguration	GuardedString	null	Yes	No		
Custom Sensitive Configuration script for Groovy ConfigSlurper						
customConfiguration	String	null		No		
Custom Configuration script for Groovy ConfigSlurper						

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

8.4.2. Operation Script Files Properties

Property	Туре	Default	Encrypted ^a	Required ^b	
createScriptFileName	String	null		Create	
The name of the file used to perform the CREATE operation.					
customizerScriptFileName	String	null		No	
The script used to customize some f	unction of the conn	ector. Read the do	cumentation for mo	re details.	
authenticateScriptFileName	String	null		Authenticate	
The name of the file used to perform the AUTHENTICATE operation.					
scriptOnResourceScriptFileName	String	null		Script On Resource	

^b A list of operations in this column indicates that the property is required for those operations.



Property	Туре	Default	Encrypted ^a	Required ^b		
The name of the file used to perform the RUNSCRIPTONRESOURCE operation.						
deleteScriptFileName	String	null		Delete		
The name of the file used to perform the DELETE operation.						
resolveUsernameScriptFileName	String	null		Resolve Username		
The name of the file used to perform	n the RESOLVE_US	ERNAME operation	n.			
searchScriptFileName	String	null		Get Search		
The name of the file used to perform	n the SEARCH oper	ation.				
updateScriptFileName	String	null		Update		
The name of the file used to perform	n the UPDATE opera	ation.				
schemaScriptFileName	String	null		Schema		
The name of the file used to perform	n the SCHEMA oper	ration.				
testScriptFileName	String	null		Test		
The name of the file used to perform	n the TEST operatio	n.				
syncScriptFileName	String	null		Sync		
The name of the file used to perform	n the SYNC operation	on.				

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

8.4.3. Groovy Engine configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
targetDirectory	File	null		No
Directory into which to write clas	ses.			
warningLevel	int	1		No
Warning Level of the compiler				
scriptExtensions	String[]	['groovy']		No
Description is not available				
minimumRecompilationInterval	int	100		No
Sets the minimum of time after a	script can be reco	ompiled.		

^b A list of operations in this column indicates that the property is required for those operations.



Property	Туре	Default	Encrypted ^a	Required ^b
scriptBaseClass	String	null		No
Base class name for scripts (must d	erive from Scrip	ot)		
scriptRoots	String[]	null		Yes
The root folder to load the scripts f	rom. If the value	e is null or empty t	he classpath value is	used.
tolerance	int	10		No
The error tolerance, which is the nucompilation is aborted.	amber of non-fat	tal errors (per unit) that should be toler	ated before
debug	boolean	false		No
If true, debugging code should be a	ctivated	'	'	
classpath	String[]	[]		No
Classpath for use during compilation	n.	·		
disabledGlobalASTTransformations	String[]	null		No
Sets a list of global AST transforma org.codehaus.groovy.transform.AS				ed in META-INF/
verbose	boolean	false		No
If true, the compiler should produc	e action informa	ntion		
sourceEncoding	String	UTF-8		No
Encoding for source files				
recompileGroovySource	boolean	false		No
If set to true recompilation is enabl				

 $^{^{}m a}$ Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

8.4.4. Basic Configuration Properties Properties

Property	Туре	Default	Encrypted ^a	Required ^b		
host	String	null		Yes		
The hostname to connect to	The hostname to connect to					
port	int	22		Yes		
TCP port to use (defaults to 22)						
user	String	null		Yes		

^b A list of operations in this column indicates that the property is required for those operations.



Property	Туре	Default	Encrypted ^a	Required ^b
The user name used to login to re	mote server			
password	GuardedString	null	Yes	No
The password used to login to rem	note server			
passphrase	GuardedString	null	Yes	No
The passphrase used to read the p	private key when us	ing Public Key authe	entication	
privateKey	String[]	[]	Yes	No
The base 64 encoded value (PEM)	of the private key u	used for Public Key a	authentication	
authenticationType	String	PASSWORD		Yes
Defines which authentication type	should be use: PAS	SSWORD or PUBKEY	(defaults to PAS	SSWORD)
prompt	String	root@localhost:#	ŧ	Yes
A string representing the remote S	SSH session prompt	t (defaults to root@l	ocalhost:#)	
sudoCommand	String	/usr/bin/sudo		Yes
A string representing the sudo cor	nmand (defaults to	/usr/bin/sudo)		
echoOff	boolean	true		Yes
Disable the input command echo (default to true)			
terminalType	String	vt102		Yes
Defines the terminal type to use fo	or the session (defa	ult to vt102)		
locale	String	en_US.utf8		Yes
Define the locale for LC_ALL, LAN	IG and LANGUAGE	environment variab	les to use if setLo	ocale=true
setLocale	boolean	false		Yes
Defines if the default environment false)	locale should be ch	nanged with the valu	e provided for lo	ocale (defaults to
connectionTimeout	int	5000		Yes
Defines the connection timeout to	the remote server i	in milliseconds (defa	ult to 5000)	
expectTimeout	long	5000		Yes
Defines the timeout used by the ex	xpect() calls in the s	scripts in millisecond	ls (default to 500	00)
throwOperationTimeoutException	boolean	true		Yes

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.



 $^{\rm b}$ A list of operations in this column indicates that the property is required for those operations.



Chapter 9

Google Apps Connector

The Enterprise build of OpenIDM includes a Google Apps connector, along with a sample connector configuration. The Google Apps Connector enables you to interact with Google's web applications.

9.1. Configuring the Google Apps Connector

To use this connector, you need a Google Apps account.

If you have OpenIDM Enterprise, you can view a sample Google Apps connector configuration file in samples/provisioners/provisioner.openicf-google.json

The following is an excerpt of the provisioner configuration file. This example shows an excerpt of the provisioner configuration. The default location of the connector .jar is openidm/connectors. Therefore the value of the connectorHostRef property must be "#LOCAL":

```
{
  "connectorHostRef": "#LOCAL",
  "connectorName": "org.forgerock.openicf.connectors.googleapps.GoogleAppsConnector",
  "bundleName": "org.forgerock.openicf.connectors.googleapps-connector",
  "bundleVersion": "[1.4.0.0,2.0.0.0)"
},
```

The following excerpt shows the required configuration properties:

```
"configurationProperties": {
   "domain": "",
   "clientId": "",
   "clientSecret": null,
   "refreshToken": null
},
```

These configuration properties are fairly straightforward:

domain

Set to the domain name for OAuth 2-based authorization.

clientId

A client identifier, as issued by the OAuth 2 authorization server. For more information, see the following section of RFC 6749: *Client Identifier*.



clientSecret

Sometimes also known as the client password. OAuth 2 authorization servers can support the use of clientId and clientSecret credentials, as noted in the following section of RFC 6749: Client Password.

refreshToken

A client can use an OAuth 2 refresh token to continue accessing resources. For more information, see the following section of RFC 6749: *Refresh Tokens*.

For a sample Google Apps configuration that includes OAuth 2-based entries for configurationProperties, see Chapter 12, "Google Sample - Connecting to Google With the Google Apps Connector" in the OpenIDM Samples Guide.



Scripted Kerberos Connector

New in OpenIDM 4.5.0, the scripted Kerberos connector is an implementation of the scripted SSH connector, and is based on Java Secure Channel (JSch) and the Java implementation of the Expect library (Expect4j). The connector depends on the following files, provided with OpenIDM:

- /path/to/openidm/lib/ssh-connector-1.4.0.0.jar
- /path/to/openidm/lib/expect4j-<version>.jar
- /path/to/openidm/lib/jsch-<version>.jar

The Kerberos connector enables you to manage Kerberos user principals from OpenIDM. The connector is provided in <code>/path/to/openidm/connectors/kerberos-connector-1.4.0.0.jar</code> and bundles a number of Groovy scripts to interact with a Kerberos admin server. Users of the Kerberos connector are not expected to edit the bundled Groovy scripts. The bundled scripts use the <code>kadmin</code> utility to communicate with the Kerberos server.

The Kerberos connector enables you to perform the following operations on Kerberos user principals.

- List the existing principals
- · Display the details of a principal
- Add a user principal
- Change the password of a user principal and unlock the principal
- Delete a user principal

10.1. Kerberos Connector Schema

The Kerberos connector can only be used to manage the Kerberos principal object type (which maps to the OpenICF ACCOUNT object). The following attributes are supported in the schema:

- principal (maps to __NAME__ and __UID__)
- PASSWORD updatable, required when an object is created
- LOCK_OUT updatable only; unlock an account by setting this attribute to false
- policy the password policy used by the principal



- expirationDate the date that the user principal expires
- passwordExpiration the date that the password expires
- maximumTicketLife the maximum ticket life for the principal. At the end of the ticket lifetime, the ticket can no longer be used. However, if the renewable lifetime (maximumRenewableLife) is longer than the ticket lifetime, the ticket holder can present the ticket to the KDC and request a new ticket.
- maximumRenewableLife the period during which the ticket can be renewed. A renewed ticket usually has a new ticket lifetime, dating from the time that it was renewed, that is constrained by the renewable ticket lifetime.

In addition, the following read-only attributes are supported:

- lastPasswordChange
- lastModified
- lastSuccessfulAuthentication
- lastFailedAuthentication
- failedPasswordAttempts

10.2. Configuring the Kerberos Connector

OpenIDM provides a sample connector configuration (provisioner.openicf-kerberos.json) in the /path/to/openidm/samples/kerberos/conf/ directory. You can copy the sample connector configuration to your project's conf/ directory, and adjust it to match your Kerberos environment.

Set the authentication properties, as described in Section 8.1, "Configuring Authentication to the SSH Server". In addition, set at least the following properties:

customConfiguration

Specify the details of the user principal and the default realm here. The sample provisioner file has the following custom configuration:

```
"customConfiguration" : "kadmin{
  cmd = '/usr/sbin/kadmin.local';
  user = '<KADMIN USERNAME>';
  default_realm = '<REALM, e.g. EXAMPLE.COM>'
}",
```

A complete custom configuration will look something like this:

```
"customConfiguration" : "kadmin {
    cmd = '/usr/sbin/kadmin.local';
    user = 'openidm/admin';
    default_realm = 'EXAMPLE.COM' }",
```



customSensitiveConfiguration

Set the password for the user principal here. The sample provisioner has the following configuration:

```
"customSensitiveConfiguration" : "kadmin { password = '<KADMIN PASSWORD>'}",
```

Change this to reflect your user principal password, for example:

```
"customSensitiveConfiguration" : "kadmin { password = 'Passw0rd'}"
```

The following section describes the configuration parameters in the sample Kerberos connector configuration. For a complete list of the configuration properties for the Kerberos connector, see Section 10.4.1, "Configuration Properties":

host

The host name or IP address of the SSH server on which the kadmin command is run.

port

The port number on which the SSH server listens.

Default: 22 (the default SSH port)

user

The username of the account that is used to connect to the SSH server.

Note

This is *not* the same as your Kerberos user principal. This account must be able to **ssh** into the server on which Kerberos is running, with the password provided in the next parameter.

password

The password of the account that is used to connect to the SSH server.

prompt

A string representing the remote SSH session prompt. This must be the exact prompt string, in the format username@target:, for example root@localhost:~\$.

If the prompt includes a trailing space, you must include the space in the value of this property.

Consider customizing your Linux prompt with the PS1 and PS2 variables, to set a *safe* prompt. For information about customizing promtps, see this article.

sudoCommand

A string that shows the full path to the **sudo** command, for example /usr/bin/sudo.



echoOff

If set to true (the default), the input command echo is disabled. If set to false, every character that is sent to the server is sent back to the client in the expect() call.

terminalType

Sets the terminal type to use for the session. The list of supported types is determined by your Linux/UNIX system. For more information, see the terminfo manual page (\$ man terminfo).

Default: vt102

setLocale

If set to true, indicates that the default environment locale should be changed to the value of the locale property.

Default: false

locale

Sets the locale for LC_ALL, LANG and LANGUAGE environment variables, if setLocale is set to true.

Default: en US.utf8

connectionTimeout

Specifies the connection timeout to the remote server, in milliseconds.

Default: 5000

expectTimeout

Specifies the timeout used by the expect() calls in scripts, in milliseconds.

Default: 5000

authenticationType

Sets the authentication type, either PASSWORD or PUBKEY. For more information, see Section 8.1, "Configuring Authentication to the SSH Server".

Default: PASSWORD

throwOperationTimeoutException

If true, the connector throws an exception when the timeout is reached for an operation. Otherwise, the operation fails silently.

Default: true



scriptRoots

The path to the Groovy scripts that will perform the OpenICF operations, relative to your OpenIDM installation directory. For the Kerberos connector, the scripts are bundled up in the connector JAR file, so this path is set to jar:file:connectors/kerberos-connector-1.4.0.0.jar!/script/kerberos/ in the sample connector configuration.

classpath

The directory in which the compiler should look for compiled classes. The default classpath, if not is specified, is install-dir/lib.

reloadScriptOnExecution

By default, scripts are loaded and compiled when a connector instance is created and initialized. Setting reloadScriptOnExecution to true makes the connector load and compile the script every time it is called. Do not set this property to true in a production environment, because it will have a significant impact on performance.

Default: false

*ScriptFileName

The script that is used for each OpenICF operation. Do not change these script names in the bundled Kerberos connector.

10.3. OpenICF Interfaces Implemented by the Kerberos Connector

The Kerberos Connector implements the following OpenICF interfaces.

Authenticate

Provides simple authentication with two parameters, presumed to be a user name and password.

Create

Creates an object and its uid.

Delete

Deletes an object, referenced by its uid.

Resolve Username

Resolves an object by its username and returns the uid of the object.

Schema

Describes the object types, operations, and options that the connector supports.



Script on Connector

Enables an application to run a script in the context of the connector. Any script that runs on the connector has the following characteristics:

- The script runs in the same execution environment as the connector and has access to all the classes to which the connector has access.
- The script has access to a connector variable that is equivalent to an initialized instance of the connector. At a minimum, the script can access the connector configuration.
- The script has access to any script-arguments passed in by the application.

Script on Resource

Runs a script on the target resource that is managed by this connector.

Search

Searches the target resource for all objects that match the specified object class and filter.

Sync

Polls the target resource for synchronization events, that is, native changes to objects on the target resource.

Test

Tests the connector configuration. Testing a configuration checks all elements of the environment that are referred to by the configuration are available. For example, the connector might make a physical connection to a host that is specified in the configuration to verify that it exists and that the credentials that are specified in the configuration are valid.

This operation might need to connect to a resource, and, as such, might take some time. Do not invoke this operation too often, such as before every provisioning operation. The test operation is not intended to check that the connector is alive (that is, that its physical connection to the resource has not timed out).

You can invoke the test operation before a connector configuration has been validated.

Update

Updates (modifies or replaces) objects on a target resource.

10.4. Kerberos Connector Configuration

The Kerberos Connector has the following configurable properties.



10.4.1. Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
customSensitiveConfiguration	GuardedString	null	Yes	No
Custom Sensitive Configuration scri	pt for Groovy Confi	gSlurper		
customConfiguration	String	null		No
Custom Configuration script for Gro	ovy ConfigSlurper			

a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

10.4.2. Operation Script Files Properties

Property	Туре	Default	Encrypted ^a	Required ^b
createScriptFileName	String	null		Create
The name of the file used to perform	n the CREATE oper	ation.		
customizerScriptFileName	String	null		No
The script used to customize some	function of the conn	ector. Read the do	ocumentation for n	nore details.
authenticateScriptFileName	String	null		Authenticate
The name of the file used to perform	n the AUTHENTICA	TE operation.		
scriptOnResourceScriptFileName	String	null		Script On Resource
The name of the file used to perform	n the RUNSCRIPTO	NRESOURCE ope	ration.	
deleteScriptFileName	String	null		Delete
The name of the file used to perform	n the DELETE oper	ation.		
resolveUsernameScriptFileName	String	null		Resolve Username
The name of the file used to perform	n the RESOLVE_US	ERNAME operation	on.	
searchScriptFileName	String	null		Get Search
The name of the file used to perform	n the SEARCH oper	ation.		
updateScriptFileName	String	null		Update
The name of the file used to perform	n the UPDATE oper	ation.		
schemaScriptFileName	String	null		Schema

^b A list of operations in this column indicates that the property is required for those operations.



Property	Туре	Default	Encrypted ^a	Required ^b		
The name of the file used to perform the SCHEMA operation.						
testScriptFileName	String	null		Test		
The name of the file used to perform	n the TEST operatio	n.				
syncScriptFileName	String	null		Sync		
The name of the file used to perform	n the SYNC operation	on.				

a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

10.4.3. Groovy Engine configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b
targetDirectory	File	null		No
Directory into which to write classe	es.			
warningLevel	int	1		No
Warning Level of the compiler				
scriptExtensions	String[]	['groovy']		No
Description is not available				
minimumRecompilationInterval	int	100		No
Sets the minimum of time after a se	cript can be reco	ompiled.		
scriptBaseClass	String	null		No
Base class name for scripts (must o	lerive from Scrip	ot)		
scriptRoots	String[]	null		Yes
The root folder to load the scripts f	rom. If the value	e is null or empty the	e classpath value is	used.
tolerance	int	10		No
The error tolerance, which is the n compilation is aborted.	umber of non-fat	tal errors (per unit) t	that should be toler	rated before
debug	boolean	false		No
If true, debugging code should be a	activated			
classpath	String[]	[]		No
Classpath for use during compilation	on.			
disabledGlobalASTTransformations	String[]	null		No

^b A list of operations in this column indicates that the property is required for those operations.



Property	Туре	Default	Encrypted ^a	Required ^b
Sets a list of global AST transform org.codehaus.groovy.transform.AS				in META-INF/
verbose	boolean	false		No
If true, the compiler should produc	ce action information	on		
sourceEncoding	String	UTF-8		No
Encoding for source files				,
recompileGroovySource	boolean	false		No
If set to true recompilation is enab	oled			

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM. ^b A list of operations in this column indicates that the property is required for those operations.

10.4.4. Basic Configuration Properties Properties

Property	Туре	Default	Encrypted ^a	Required ^b
host	String	null		Yes
The hostname to connect to				
port	int	22		Yes
TCP port to use (defaults to 22)				
user	String	null		Yes
The user name used to login to remo	te server			
password	GuardedString	null	Yes	No
The password used to login to remot	e server			
passphrase	GuardedString	null	Yes	No
The passphrase used to read the pri	vate key when using	g Public Key authe	ntication	
privateKey	String[]	[]	Yes	No
The base 64 encoded value (PEM) of	the private key use	ed for Public Key a	uthentication	
authenticationType	String	PASSWORD		Yes
Defines which authentication type sl	nould be use: PASS	WORD or PUBKEY	(defaults to PASSV	VORD)
prompt	String	root@localhost:#		Yes
A string representing the remote SS	H session prompt (defaults to root@lo	ocalhost:#)	
sudoCommand	String	/usr/bin/sudo		Yes



Property	Туре	Default	Encrypted ^a	Required ^b
A string representing the sudo	command (defaults	to /usr/bin/sudo)		
echoOff	boolean	true		Yes
Disable the input command ec	ho (default to true)			
terminalType	String	vt102		Yes
Defines the terminal type to us	se for the session (de	efault to vt102)		
locale	String	en_US.utf8		Yes
Define the locale for LC_ALL, l	LANG and LANGUA	GE environment vari	ables to use if setLo	ocale=true
setLocale	boolean	false		Yes
Defines if the default environm false)	ent locale should be	e changed with the va	alue provided for lo	cale (defaults to
connectionTimeout	int	5000		Yes
Defines the connection timeou	t to the remote serve	er in milliseconds (de	efault to 5000)	
expectTimeout	long	5000		Yes
Defines the timeout used by th	e expect() calls in th	e scripts in milliseco	onds (default to 500	00)
throwOperationTimeoutExceptio	n boolean	true		Yes
Defines if an OperationTimeou	tException should b	e thrown if any call t	o expect times out	(defaults to true)

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM.

^b A list of operations in this column indicates that the property is required for those operations.



Chapter 11 Salesforce Connector

The Enterprise build of OpenIDM includes a Salesforce connector, along with a sample connector configuration. The Salesforce connector enables provisioning, reconciliation, and synchronization between Salesforce and the OpenIDM repository.

To use this connector, you need a Salesforce account, and a Connected App that has OAuth enabled, which will allow you to retrieve the required consumer key and consumer secret.

For additional instructions, and a sample Salesforce configuration, see Chapter 13, "Salesforce Sample - Salesforce With the Salesforce Connector" in the OpenIDM Samples Guide.



Active Directory Connector

The Active Directory connector is a legacy connector, written in C# for the .NET platform. OpenICF connects to Active Directory over ADSI, the native connection protocol for Active Directory. The connector therefore requires a .NET connector server that has access to the ADSI .dll files.

The Active Directory connector will be deprecated in a future OpenICF release, and, ultimately, support for its use with OpenIDM will be discontinued. For simple Active Directory (and Active Directory LDS) deployments, the generic LDAP Connector works better than the Active Directory connector, in most circumstances. Using the generic LDAP connector avoids the need to install a remote connector server in the overall deployment. In addition, the generic LDAP connector has significant performance advantages over the Active Directory connector. For more complex Active Directory deployments, use the PowerShell Connector Toolkit, as described in Chapter 5, "PowerShell Connector Toolkit".

12.1. Configuring the Active Directory Connector

Before you configure the Active Directory Connector, make sure that the .NET Connector Server is installed, configured and started, and that OpenIDM has been configured to use the Connector Server. For more information, see Section 11.4.1, "Installing and Configuring a .NET Connector Server" in the *Integrator's Guide*.

Procedure 12.1. Setting Up the Active Directory Connector

- 1. Download the Active Directory Connector from ForgeRock's download page.
- 2. Extract the contents of the AD Connector zip file into the directory in which you installed the Connector Server (by default c:\Program Files (x86)\Identity Connectors\Connector Server>).

Note that the files, specifically the connector itself (ActiveDirectory.Connector.dll) must be directly under the path\to\Identity Connectors\Connector Server directory, and not in a subdirectory.



Note

If the account that is used to install the Active Directory connector is different from the account under which the Connector Server runs, you must give the Connector Server runtime account the rights to access the Active Directory connector log files.

3. A sample Active Directory Connector configuration file is provided in openidm/samples/provisioners/provisioner.openicf-ad.json. On the OpenIDM host, copy the sample Active Directory connector configuration file to your project's conf/directory:

```
$ cd /path/to/openidm
$ cp samples/provisioners/provisioner.openicf-ad.json project-dir/conf/
```


4. Edit the Active Directory connector configuration to match your Active Directory deployment.

Specifically, check and edit the configurationProperties that define the connection details to the Active Directory server.

Also, check that the bundleVersion of the connector matches the version of the ActiveDirectory.Connector.dll in the Connector Server directory. The bundle version can be a range that includes the version of the connector bundle. To check the .dll version:

- Right click on the ActiveDirectory.Connector.dll file and select Properties.
- Select the Details tab and note the Product Version.





The following configuration extract shows sample values for the connectorRef and configurationProperties:



```
"connectorRef" :
  {
      "connectorHostRef" : "dotnet",
      "connectorName" : "Org.IdentityConnectors.ActiveDirectory.ActiveDirectoryConnector",
      "bundleName" : "ActiveDirectory.Connector",
      "bundleVersion" : "[1.4.0.0,2.0.0.0)"
  },
"configurationProperties":
      "DirectoryAdminName" : "EXAMPLE\\Administrator",
      "DirectoryAdminPassword" : "Passw0rd",
      "ObjectClass" : "User",
"Container" : "dc=example,dc=com",
      "CreateHomeDirectory" : true,
      "LDAPHostName" : "192.0.2.0",
      "SearchChildDomains" : false,
      "DomainName" : "example".
      "SyncGlobalCatalogServer" : null,
      "SvncDomainController" : null.
      "SearchContext" : ""
  },
```

The main configurable properties are as follows:

connectorHostRef

Must point to an existing connector info provider configuration in project-dir/conf/
provisioner.openicf.connectorinfoprovider.json. The connectorHostRef property is required because
the Active Directory connector must be installed on a .NET connector server, which is always
remote, relative to OpenIDM.

DirectoryAdminName and DirectoryAdminPassword

Specify the credentials of an administrator account in Active Directory, that the connector will use to bind to the server.

The DirectoryAdminName can be specified as a bind DN, or in the format DomainName\\samaccountname.

SearchChildDomains

Specifies if a Global Catalog (GC) should be used. This parameter is used in search and query operations. A Global Catalog is a read-only, partial copy of the entire forest, and is never used for create, update or delete operations.

Boolean, false by default.

LDAPHostName

Specifies a particular Domain Controller (DC) or Global Catalog (GC), using its hostname. This parameter is used for query, create, update, and delete operations.



If SearchChildDomains is set to true, this specific GC will be used for search and query operations. If the LDAPHostName is null (as it is by default), the connector will allow the ADSI libraries to pick up a valid DC or GC each time it needs to perform a query, create, update, or delete operation.

SyncGlobalCatalogServer

Specifies a Global Catalog server name for sync operations. This property is used in combination with the SearchChildDomains property.

If a value for <code>SyncGlobalCatalogServer</code> is set (that is, the value is not <code>null</code>) and <code>SearchChildDomains</code> is set to <code>true</code>, this GC server is used for sync operations. If no value for <code>SyncGlobalCatalogServer</code> is set and <code>SearchChildDomains</code> is set to <code>true</code>, the connector allows the ADSI libraries to pick up a valid GC.

SyncDomainController

Specifies a particular DC server for sync operations. If no DC is specified, the connector picks up the first available DC and retains this DC in future sync operations.

The updated configuration is applied immediately.

5. Check that the connector has been configured correctly by running the following command:

```
$ curl \
--header "X-OpenIDM-Username: openidm-admin" \
--header "X-OpenIDM-Password: openidm-admin" \
--request POST \
"http://localhost:8080/openidm/system?_action=test"
```

The command must return "ok": true for the Active Directory connector.

6. The connector is now configured. To verify the configuration, perform a RESTful GET request on the remote system URL, for example:

```
$ curl \
   --header "X-OpenIDM-Username: openidm-admin" \
   --header "X-OpenIDM-Password: openidm-admin" \
   --request GET \
   "http://localhost:8080/openidm/system/ActiveDirectory/account?_queryId=query-all-ids"
```

This request should return the user accounts in the Active Directory server.

7. (Optional) To configure reconciliation or LiveSync between OpenIDM and Active Directory, create a synchronization configuration file (sync.json) in your project's conf/ directory.

The synchronization configuration file defines the attribute mappings and policies that are used during reconciliation.

The following is a simple example of a sync. json file for Active Directory:



```
"mappings" : [
             "name" : "systemADAccounts managedUser",
             "source" : "system/ActiveDirectory/account",
             "target" : "managed/user",
             "properties" : [
                 { "source" : "cn", "target" : "displayName" },
                   "source" : "description", "target" : "description" },
"source" : "givenName", "target" : "givenName" },
                 { "source" : "sn", "target" : "familyName" },
                 { "source" : "sAMAccountName", "target" : "userName" }
             "policies" : [
                 { "situation" : "CONFIRMED", "action" : "UPDATE" },
                  "situation" : "FOUND", "action" : "UPDATE" },
"situation" : "ABSENT", "action" : "CREATE" },
                 { "situation" : "AMBIGUOUS", "action" : "EXCEPTION" },
                  "situation" : "MISSING", "action" : "UNLINK" },
                 { "situation" : "SOURCE_MISSING", "action" : "DELETE" },
                 { "situation" : "UNQUALIFIED", "action" : "DELETE" },
                 { "situation" : "UNASSIGNED", "action" : "DELETE" }
             ]
        }
    ]
}
```

8. To test the synchronization, run a reconciliation operation as follows:

```
$ curl \
   --header "X-OpenIDM-Username: openidm-admin" \
   --header "X-OpenIDM-Password: openidm-admin" \
   --request POST \
   "http://localhost:8080/openidm/recon?_action=recon&mapping=systemADAccounts_managedUser"
```

If reconciliation is successful, the command returns a reconciliation run ID, similar to the following:

```
{"_id":"0629d920-e29f-4650-889f-4423632481ad","state":"ACTIVE"}
```

9. Query the internal repository, using either a **curl** command, or the OpenIDM Admin UI, to make sure that the users in your Active Directory server were provisioned into the repository.

12.2. Using PowerShell Scripts With the Active Directory Connector

The Active Directory connector supports PowerShell scripting. The following example shows a simple PowerShell script that is referenced in the connector configuration and can be called over the REST interface.



Note

External script execution is disabled on system endpoints by default. For testing purposes, you can enable script execution over REST, on system endpoints by adding the script action to the system object, in the access.js file. For example:

```
$ more /path/to/openidm/script/access.js
...
{
    "pattern" : "system/ActiveDirectory",
    "roles" : "openidm-admin",
    "methods" : "action",
    "actions" : "script"
},
```

Be aware that scripts passed to clients imply a security risk in production environments. If you need to expose a script for direct external invocation, it might be better to write a custom authorization function to constrain the script ID that is permitted. Alternatively, do not expose the script action for external invocation, and instead, expose a custom endpoint that can make only the desired script calls. For more information about using custom endpoints, see Section 13.2, "Creating Custom Endpoints to Launch Scripts" in the *Integrator's Guide*.

The following PowerShell script creates a new MS SQL user with a username that is specified when the script is called. The script sets the user's password to Password and, optionally, gives the user a role. Save this script as project-dir/script/createUser.ps1:

```
if ($loginName -ne $NULL) {
    [System.Reflection.Assembly]::LoadWithPartialName('Microsoft.SqlServer.SMO') | Out-Null
    $sqlSrv = New-Object ('Microsoft.SqlServer.Management.Smo.Server') ('WIN-C2MSQ8G1TCA')

$login = New-Object -TypeName ('Microsoft.SqlServer.Management.Smo.Login') ($sqlSrv, $loginName)
    $login.LoginType = 'SqlLogin'
    $login.PasswordExpirationEnabled = $false
    $login.Create('Passw0rd')
# The next two lines are optional, and to give the new login a server role, optional
    $login.AddToRole('sysadmin')
    $login.Alter()
} else {
    $Error_Message = [string]"Required variables 'loginName' is missing!"
        Write-Error $Error_Message
        throw $Error_Message
}
```

Now edit the Active Directory connector configuration to reference the script. Add the following section to the connector configuration file (project-dir/conf/provisioner.openicf-ad.json):



To call the PowerShell script over the REST interface, use the following request, specifying the userName as input:

```
$ curl \
   --header "X-OpenIDM-Username: openidm-admin" \
   --header "X-OpenIDM-Password: openidm-admin" \
   --request POST \
   "http://localhost:8080/openidm/system/ActiveDirectory/?
   _action=script&scriptId=ConnectorScriptName&scriptExecuteMode=resource&loginName=myUser"
```



Chapter 13 RACF Connector

The RACF connector provisions the IBM RACF security database for zOS. The connector can operate in two modes - screen scraping (3270 Terminal emulation) or LDAP (when an RACF LDAP bridge has been installed on the mainframe).

The RACF connector is available, with a subscription, from the ForgeRock Backstage site. If you want to use this connector in production, contact ForgeRock Support.

This chapter lists the implemented interfaces and configurable properties for the RACF connector.

13.1. OpenICF Interfaces Implemented by the RACF

The RACF implements the following OpenICF interfaces.

Create

Creates an object and its uid.

Delete

Deletes an object, referenced by its uid.

Resolve Username

Resolves an object by its username and returns the wid of the object.

Schema

Describes the object types, operations, and options that the connector supports.

Script on Connector

Enables an application to run a script in the context of the connector. Any script that runs on the connector has the following characteristics:

- The script runs in the same execution environment as the connector and has access to all the classes to which the connector has access.
- The script has access to a connector variable that is equivalent to an initialized instance of the connector. At a minimum, the script can access the connector configuration.
- The script has access to any script-arguments passed in by the application.



Search

Searches the target resource for all objects that match the specified object class and filter.

Sync

Polls the target resource for synchronization events, that is, native changes to objects on the target resource.

Test

Tests the connector configuration. Testing a configuration checks all elements of the environment that are referred to by the configuration are available. For example, the connector might make a physical connection to a host that is specified in the configuration to verify that it exists and that the credentials that are specified in the configuration are valid.

This operation might need to connect to a resource, and, as such, might take some time. Do not invoke this operation too often, such as before every provisioning operation. The test operation is not intended to check that the connector is alive (that is, that its physical connection to the resource has not timed out).

You can invoke the test operation before a connector configuration has been validated.

Update

Updates (modifies or replaces) objects on a target resource.

13.2. RACF Configuration

The RACF has the following configurable properties.

13.2.1. Configuration Properties

Property	Туре	Default	Encrypted ^a	Required ^b	
activeSyncBlocksize	String	null		No	
Description is not available					
isTivoliDirectoryServer	boolean	true		No	
Description is not available					
activeSyncPrivateKey	String[]	null		No	
Description is not available					
convertToASCII	boolean	true		No	
Description is not available					
isSunIdm	boolean	false		No	



Property	Туре	Default	Encrypted ^a	Required b
Description is not available				
activeSyncFilterChangesBy	String[]	null		No
Description is not available				
activeSyncRemoveOCFromFilter	Boolean	null		No
Description is not available				
activeSyncFilterUseOrSearch	Boolean	null		No
Description is not available				
activeSyncResetToToday	Boolean	null		No
Description is not available				
activeSyncCertificate	String[]	null		No
Description is not available				
activeSyncPasswordDecryptorClass	String	null		No
Description is not available				
hostNameOrIpAddr	String	null		No
Host Name for RACF Connection				
hostPortNumber	Integer	null		No
Host Port for RACF LDAP Connecti	on			
suffix	String	null		No
LDAP suffix, such as cn=foo				
ldapUserName	String	null		No
User Name for RACF Connection				
groupQueries	String[]	null		No
Description is not available				
ldapPassword	GuardedString	null	Yes	No
Password for RACF Connection				
userQueries	String[]	null		No
Description is not available				
userObjectClasses	String[]	['racfUser', 'SAFTsoSegment'		No



Property	Туре	Default	Encrypted ^a	Required ^b
	-380	'racfUserOmvsSeg 'racfUserOvmSegg 'racfCicsSegmen' 'racfDCESegment' 'SAFDfpSegment' 'racfKerberosIn' 'racfLanguageSeg 'racfLNotesSegment' 'racfNDSSegment' 'racfNetviewSegg' 'racfOperparmSegg' 'racfProxySegment'		
Description is not available				
groupObjectClasses	String[]	<pre>['racfGroup', 'racfGroupOvmSed , 'racfGroupOmvsSd , 'SAFDfpSegment'</pre>		No
Description is not available				
hostTelnetPortNumber	Integer	null		No
Host Telnet Port for RACF Cor	nnection			
useSsl	Boolean	null		No
Use SSL				
userNames	String[]	null		No
UserNames used in command	line login; must be paire	d with passwords		
	GuardedString[]	null	Yes	No



Property	Туре	Default	Encrypted ^a	Required ^b
segmentNames	String[]	['ACCOUNT.RACF', 'ACCOUNT.TSO', 'ACCOUNT.NETVIEW', 'ACCOUNT.CICS', 'ACCOUNT.OMVS', 'ACCOUNT.CATALOG', 'ACCOUNT.OMVS', 'GROUP.RACF']		No
Segment names that have par	rsers; must be paired w	with segmentNames		
connectionClassName	String	null		No
Name of the RW3270Connect (org.identityconnectors.rw32			taking	
parserFactory	String	null		No
Description is not available				
segmentParsers	String[]	[' <maptransform> <patternnode ,8})'="" false'="" key="RACF*USERI pattern=" optional="false reset=" user="("> <patternnode false'="" key="RACF*NAME" optional="false reset=" pattern="NAME=(.*?)\s+(? =OWNER=)"> <patternnode false'="" key="RACF*OWNER pattern=" optional="false reset=" owner=",8})'"> </patternnode></patternnode></patternnode></maptransform>		



Property	Type	Default	Encrypted ^a	Required ^b
		,8})'		
		optional='false		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*PASSD/		
		<pre>pattern='PASSDA' ,6})'</pre>		
		<pre>optional='false reset='false'/</pre>		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*PASSW		
		INTERVAL'		
		pattern='PASS-		
		<pre>INTERVAL=(\S*)' optional='false</pre>		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*PHRASI		
		pattern='PHRASE		
		.*?)\s+\n'		
		optional='true'		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*ATTRII		
		pattern='((ATTR		
		.*\n\s*)+)'		
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='ATTRIB		
		+)\s+'		
		substitute='\$1		
		'/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='(
		.*)\s'		
		substitute='\$1'		
		/>		
		<pre><substitutetrans< pre=""></substitutetrans<></pre>		
		pattern='^\$'		
		substitute='NON		
		/>		
		<pre><splittransform< pre=""></splittransform<></pre>		
		splitPattern='\		
		+'/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*REV0KI		
		DATE'		
		pattern='REVOKE		
		DATE=(NONE \w		



Property	Туре	Default	Encrypted ^a	Required ^b
		+\s\d+,\s\d+)'		
		<pre>optional='false reset='false'/</pre>		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*RESUM		
		DATE'		
		pattern='RESUME		
		DATE=(NONE \w		
		+\s\d+,\s\d+)'		
		optional='false		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*LAST		
		ACCESS'		
		pattern='LAST		
		-ACCESS=(\S+)'		
		optional='false		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*CLAUTI		
		pattern='CLASS		
		AUTHORIZATIONS=		
		\n]*(\s{23}		
		.+\n)*)'		
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='(
		.*)\s'		
		substitute='\$1'		
		/> <splittransform< td=""><td></td><td></td></splittransform<>		
		splitPattern='\		
		+'/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*DATA'		
		pattern='INSTAL		
		-DATA=([^		
		\n]*(\s{20}		
		.+\n)*)'		
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^(
		.{50})[^\n]+'		
		substitute='\$1'		
		/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\n		
		\s{20}(.		



Property	Туре	Default	Encrypted ^a	Required ^b
		{50})[^\n]+'		
		substitute='\$1'		
		/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\n'		
		substitute=''		
		/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\s+\$'		
		substitute=''		
		/>		
		<pre><substitutetrans< pre=""></substitutetrans<></pre>		
		pattern='^\$'		
		substitute='NO		
		-INSTALLATION		
		-DATA'/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*MODEL		
		pattern='MODEL		
		-NAME=(\S+)'		
		optional='true'		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*GROUP!		
		pattern='((
		?:\s+GROUP=		
		\S+\s+AUTH=		
		\S*\s+CONNECT		
		-OWNER=(?:[^		
		\n]+\n){4})+)'		
		optional='true'		
		reset='true'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='		
		.*?GROUP=(\S		
		+)\s+AUTH=		
		.+?CONNECT-		
		OWNER=\S+([^		
		\n]+\n){4}'		
		substitute='\$1		
		'/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^		
		\s+(.*)'		
		substitute='\$1'		
		/>		
		<pre><substitutetrans< pre=""></substitutetrans<></pre>		
		pattern='(\s		
		+)\$'		
		substitute=''		



Property	Туре	Default	Encrypted ^a	Required ^b
		/>		
		<pre><splittransform <="" pre="" splitdattorn="\"></splittransform></pre>		
		splitPattern='\:		
		+'/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*CONNE(
		-OWNERS'		
		<pre>pattern='((?:\s+GROUP=</pre>		
		\S+\s+AUTH=		
		\S*\s+CONNECT		
		-OWNER=(?:[^		
		\n]+\n){4})+)'		
		optional='true'		
		reset='false'>		
		<pre><substitutetrans< pre=""></substitutetrans<></pre>		
		pattern='		
		.*?GROUP=\S		
		+\s+AUTH=.		
		+?CONNECT-		
		OWNER=(\S+)([^		
		\n]+\n){4}'		
		substitute='\$1		
		'/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^		
		\s+(.*)'		
		substitute='\$1'		
		/>		
		<pre><substitutetrans< pre=""></substitutetrans<></pre>		
		pattern='(\s		
		+)\$'		
		substitute=''		
		/>		
		<pre><splittransform< pre=""></splittransform<></pre>		
		splitPattern='\		
		+'/> </td <td></td> <td></td>		
		PatternNode> <		
		/MapTransform>		
		', ' </td <td></td> <td></td>		
		Sample output:		
		ACCTNUM=		
		D5888P		
		DEST= LOCAL		
		HOLDCLASS= H		
		JOBCLASS= C		
		MSGCLASS= R		
		PROC= PROC01		
		SIZE= 0001024		
		MAXSIZE=		



Property	Туре	Default	Encrypted ^a	Required ^b
		0004096		
		SYSOUTCLASS=		
		J UNIT= SYSDA		
		USERDATA= 1F09		
		SECLABEL=		
		SYSLOW		
		(from IBM		
		documentation)		
		http://publib		
		.boulder.ibm		
		.com/infocenter		
		/zos/v1r9/index		
		.jsp?topic=		
		/com.ibm.zos		
		.r9.icha100		
		/netinf.htm		
		TSO Specifies		
		that you want		
		to list the		
		information		
		contained		
		in the TSO		
		segment of the		
		user's profile		
		. The details		
		RACF lists		
		from the TSO		
		segment of the		
		user's profile are: The		
		user's default		
		account number		
		when logging		
		on from the		
		TSO/E logon		
		panel The		
		destination		
		ID for SYSOUT		
		data sets The		
		user's default		
		HOLDCLASS The		
		user's default		
		JOBCLASS The		
		user's default MSGCLASS		
		The user's		
		default SYS		
		The maximum		
		region size		
		The default		
		region size		



Property	Туре	Default	Encrypted ^a	Required ^b
Property	Type	The logon procedure name The unit name The optional user data The user's security label The default command to be run during the TSO/E logon . If there is no information in the fields of the TSO segment, the field name is not displayed (with the exception of SIZE, MAXSIZE , and USERDATA)> TSO INFORMATION <maptransform> <patternnode \s*([^\n]*)\n'="" acctnu="" key="TSO*ACCTNU pattern=" optional="true" reset="false"> <substitutetran pattern="\s*\$" substitute=""></substitutetran> <!-- PatternNode key='TSO*HOLDCL pattern='HOLDCL \s*(\S)' optional='true' reset='false'/ --> <patternnode \s*(\s)'="" jobcla="" key="TSO*JOBCLA pattern=" optional="true" reset="false"> <patternnode< td=""><td></td><td>Required b</td></patternnode<></patternnode></patternnode></maptransform>		Required b



Property	Туре	Default	Encrypted ^a	Required ^b
		pattern='MSGCLA		
		\s*(\S)'		
		optional='true'		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='TS0*PR0C'		
		pattern='PROC=		
		\s*(\S{1,8})'		
		optional='true'		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='TS0*SIZE'		
		pattern='SIZE=		
		\s*(\d+)'		
		optional='false		
		reset='false'>		
		<classtransform< td=""><td></td><td></td></classtransform<>		
		transform='java		
		.lang		
		.Integer'/> <		
		/PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='TS0*MAXSIZ		
		pattern='MAXSIZ		
		\s*(\d+)'		
		optional='false		
		reset='false'>		
		<classtransform< td=""><td></td><td></td></classtransform<>		
		transform='java		
		.lang		
		.Integer'/> <		
		/PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='TS0*SYS0UT		
		pattern='SYSOUT		
		\s*(\S)'		
		optional='true'		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='TS0*UNIT'		
		pattern='UNIT=		
		\s*(\S{1,8})'		
		optional='true'		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='TS0*USERDA		
		pattern='USERDA		
		\s*(\S{1,4})'		
		optional='false		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		



Property	Туре	Default E	Encrypted ^a	Required ^b
		key='TS0*SECLABI		
		pattern='SECLABI		
		\s*([^\n]*)\n'		
		optional='true'		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='TS0*COMMANI		
		pattern='COMMANI		
		\s*([^\n]*)\n'		
		optional='true'		
		reset='false'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='\s*\$'		
		substitute=''		
		/> </td <td></td> <td></td>		
		PatternNode> <		
		/MapTransform>		
		', ' </td <td></td> <td></td>		
		Sample output:		
		IC= START		
		CONSNAME=		
		DJONES1		
		CTL= GLOBAL		
		MSGRECVR= YES		
		OPCLASS= 1,2		
		DOMAINS= D1		
		,D2 NGMFADMN=		
		YES NGMFVSPN=		
		VNNN (from IBM		
		documentation)		
		http://publib		
		.boulder.ibm		
		.com/infocenter		
		/zos/v1r9/index		
		.jsp?topic=/		
		com.ibm.zos.r9		
		.icha100/netinf		
		.htm NETVIEW		
		Specifies		
		that you want		
		to list the		
		information		
		contained in		
		the NETVIEW		
		segment of		
		the user's		
		profile. The		
		details RACF		
		lists from		
		the NETVIEW		
		segment of		



Property	Туре	Default	Encrypted ^a	Required ^b
		the user's		
		profile are:		
		The command		
		or command		
		line to be		
		processed by		
		NetView® for		
		this operator		
		The default		
		MCS console		
		identifier		
		Whether		
		security		
		checking		
		should be		
		done for		
		this NetView		
		operator		
		·		
		Whether this		
		operator		
		can receive		
		unsolicited		
		messages		
		The count		
		of operator		
		class values		
		The list of		
		NetView scope		
		classes for		
		which this		
		operator has		
		authority		
		The number		
		of domains		
		this NetView		
		operator		
		controls		
		The list of		
		identifiers		
		of NetView		
		programs		
		in another		
		NetView domain		
		for which		
		this operator		
		has authority		
		Whether this		
		operator has		
		administrator		
		authority to		
		the NetView		



Property	Туре	Default	Encrypted ^a	Required ^b
		Graphic Monitor		
		Facility		
		(NGMF)> NETVIEW</td <td></td> <td></td>		
		INFORMATION		
		>		
		<maptransform< td=""><td></td><td></td></maptransform<>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='NETVIEW*	TC	
		pattern='IC=	10	
		\s*([^\n]*)\n'		
		optional='tru		
		reset='false'		
		<substitutetr< td=""><td></td><td></td></substitutetr<>		
		pattern='\s+\$		
		substitute=''		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='NETVIEW*	COI	
		pattern='CONS		
		\s*(\S+)'		
		optional='tru	e'	
		reset='false'		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='NETVIEW*	СТ	
		pattern='CTL=		
		\s*(\S+)'		
		optional='tru	e'	
		reset='false'	/	
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='NETVIEW*	MS(
		pattern='MSGR	EC	
		\s*(\S+)'		
		optional='tru		
		reset='false'		
		<substitutetr< td=""><td>an:</td><td></td></substitutetr<>	an:	
		pattern='N0'		
		substitute='F	AL!	
		/>		
		<substitutetr< td=""><td></td><td></td></substitutetr<>		
		pattern='YES'		
		substitute='T	RUI	
		/>		
		<booleantrans< td=""><td>to</td><td></td></booleantrans<>	to	
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='NETVIEW*		
		pattern='0PCL	AS:	



Property	Туре	Default	Encrypted ^a	Required ^b
		\s*([^\n]*)\n'		
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\n'		
		substitute=' '/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\s+\$'		
		substitute=''		
		/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^\s+'		
		substitute=''		
		/>		
		<pre><splittransform< pre=""></splittransform<></pre>		
		splitPattern='		
		,'/>		
		<listtransform></listtransform>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/> </td <td></td> <td></td>		
		ListTransform>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='NETVIEW*D0		
		pattern='DOMAIN		
		\s*([^\n]*)\n'		
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\n'		
		substitute='		
		'/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\s+\$'		
		substitute=''		
		/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^\s+'		
		substitute='' />		
		<pre><splittransform <="" splitpattorn="</pre></td><td></td><td></td></tr><tr><td></td><td></td><td>splitPattern=" td=""><td></td><td></td></splittransform></pre>		
		,'/> <br PatternNode>		
		<pre>PatternNode> <patternnode< pre=""></patternnode<></pre>		
		key='NETVIEW*NG		
		pattern='NGMFADI \s*(\S+)'		



Property	Туре	Default	Encrypted ^a	Required ^b
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='NO'		
		substitute='FAL		
		/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='YES'		
		substitute='TRU		
		/>		
		<booleantransfo< td=""><td></td><td></td></booleantransfo<>		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='NETVIEW*NGI		
		pattern='NGMFVS		
		\s*([^\n]*)\n'		
		optional='true'		
		reset='false'>		
		<pre><substitutetrans< pre=""></substitutetrans<></pre>		
		pattern='\s+\$'		
		substitute=''		
		/> </td <td></td> <td></td>		
		PatternNode> <		
		/MapTransform>		
		', ' </td <td></td> <td></td>		
		Sample output:		
		OPCLASS=		
		024 023 022		
		021 020 019		
		018 017 016		
		015 014 013		
		012 011 010		
		009 008 007		
		006 005 004		
		003 002 001		
		OPIDENT=		
		OPPRTY= 00255		
		TIMEOUT= 12:34		
		XRFS0FF=		
		NOFORCE		
		RSLKEYS= 00001		
		00003 TSLKEYS=		
		00001 00003		
		(from IBM		
		documentation)		
		http://publib		
		.boulder.ibm		
		.com/infocenter		
		/zos/v1r9/index		
		.jsp?topic=		



Property	Туре	Default	Encrypted ^a	Required ^b
		/com.ibm.zos		
		.r9.icha100		
		/netinf.htm		
		CICS Specifies		
		that you want		
		to list the		
		information		
		contained		
		in the CICS		
		segment of		
		the user's		
		profile. The		
		details RACF		
		lists from the		
		CICS segment		
		of the user's		
		profile are:		
		The classes		
		assigned to		
		this operator		
		to which BMS		
		messages are		
		sent Note:		
		The values of		
		the classes		
		are listed		
		in a three		
		digit format		
		, even though		
		a maximum of		
		two digits		
		are used to		
		define the		
		value. Whether		
		the operator		
		are forced		
		off when		
		an XRFS0FF		
		takeover		
		occurs The		
		operator		
		identification		
		The priority		
		of the		
		operator The		
		time in hours		
		and minutes		
		that the		
		operator is		
		allowed to be		
		idle before		



Property	Туре	Default	Encrypted ^a	Required ^b
		being signed		
		off. For		
		systems that		
		are running		
		levels of CICS		
		prior to CICS		
		4.1, the time		
		is reported		
		in minutes		
		. Resource		
		security		
		level (RSL)		
		keys, if any		
		are assigned to the user		
		. If 99 is		
		displayed,		
		this indicates		
		that all RSL		
		keys are		
		assigned to		
		the user (1 -		
		24, inclusive)		
		. If 0 is		
		displayed,		
		no RSL keys		
		are assigned		
		to the user		
		. Transaction		
		security		
		level (TSL)		
		keys, if any		
		are assigned		
		to the user		
		. If 99 is		
		displayed,		
		this indicates		
		that all TSL		
		keys are		
		assigned to		
		the user (1 -		
		64, inclusive)		
		. If 0 is		
		displayed,		
		no TSL keys		
		are assigned		
		to the user.		
		NOTE: We are		
		not guessing		
		at TSL keys		
		and RSL keys		



Property	Туре	Default	Encrypted ^a	Required ^b
		(no AttrParse		
		example to		
		crib)>		
		CICS</td <td></td> <td></td>		
		INFORMATION		
		>		
		<maptransform></maptransform>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='CICS*0PCLA	9	
		pattern='0PCLAS		
		+\d+)+((\s+		
		\d+)+\n)*)'		
		optional='true'		
		reset='false'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='\n'		
		substitute='		
		'/>		
		<pre>/> <substitutetran< pre=""></substitutetran<></pre>		
		pattern='\s+\$'		
		substitute=''		
		/>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='^\s+'		
		substitute=''		
		/>		
		<pre><splittransform< pre=""></splittransform<></pre>		
		splitPattern='\		
		+'/>		
		<listtransform></listtransform>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/> </td <td></td> <td></td>		
		ListTransform>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='CICS*OPIDE	I	
		pattern='0PIDEN	-	
		+) '		
		optional='true'		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='CICS*0PPRT		
		pattern='0PPRTY		
		+) '		
		optional='true'		
		reset='false'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='^0+(\d		
		partern- 0+(\u		



Property	Туре	Default	Encrypted ^a	Required ^b
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='CICS*TIMEO		
		pattern='TIMEOU		
		\n]*)\n'		
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\s*\$'		
		substitute=''		
		/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='(\d{2}		
		(\d{2})\s		
		\(HH:MM\)'		
		substitute='\$1\$		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='CICS*XRFS0		
		pattern='XRFS0F		
		,10})'		
		optional='true'		
		reset='false'/		
		> <patternnode< td=""><td></td><td></td></patternnode<>		
		key='CICS*RSLKE		
		pattern='RSLKEY		
		+\d+)+((\s+		
		\d+)+\n)*)'		
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\n'		
		substitute='		
		'/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\s+\$'		
		substitute=''		
		/>		
		<pre><substitutetrans< pre=""></substitutetrans<></pre>		
		pattern='^\s+'		
		substitute=''		
		/>		
		<pre>/> <splittransform< pre=""></splittransform<></pre>		
		splitPattern='\		
		+'/>		
		<listtransform></listtransform>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^0+(\d		
		substitute='\$1'		



Property	Туре	Default	Encrypted ^a	Required ^b
		/> </td <td></td> <td></td>		
		ListTransform>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='CICS*TSLKE		
		pattern='TSLKEY		
		+\d+)+((\s+		
		\d+)+\n)*)'		
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\n'		
		substitute='		
		'/>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\s+\$'		
		substitute=''		
		/>		
		<pre><substitutetrans< pre=""></substitutetrans<></pre>		
		pattern='^\s+'		
		substitute=''		
		/>		
		<pre><splittransform cplitdattorn-')<="" pre=""></splittransform></pre>		
		splitPattern='\s		
		<listtransform></listtransform>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/> </td <td></td> <td></td>		
		ListTransform>		
		</td <td></td> <td></td>		
		PatternNode> <		
		/MapTransform>		
		', ' </td <td></td> <td></td>		
		(from IBM		
		documentation)		
		http://publib		
		.boulder.ibm		
		.com/infocenter		
		/zos/v1r9/index		
		.jsp?topic=		
		/com.ibm.zos		
		.r9.icha100		
		/netinf.htm		
		OMVS Specifies		
		that you want		
		to list the		
		information		
		contained		
		in the OMVS		



Property	Туре	Default	Encrypted ^a	Required ^b
		segment of		
		the user's		
		profile. The		
		details RACF		
		lists from the		
		OMVS segment		
		are: The user		
		identifier		
		The initial		
		directory		
		pathname		
		The program		
		pathname The		
		CPU time,		
		in seconds		
		, the user's		
		processes		
		can use The		
		address space		
		region size		
		, in bytes,		
		the user's		
		processes		
		can use The		
		maximum number		
		of active or		
		open files		
		the user		
		can have The		
		maximum number		
		of active		
		processes the		
		user can have		
		The maximum		
		number of		
		threads the		
		user can have		
		The maximum		
		amount of		
		space, in		
		pages, the		
		user can map		
		in storage		
		. Note: If		
		CPUTIMEMAX		
		, ASSIZEMAX,		
		FILEPROCMAX,		
		PROCUSERMAX,		
		THREADSMAX, or		
		MMAPAREAMAX is		
		not specified,		



Property	Туре	Default	Encrypted ^a	Required ^b
		or is removed		
		with the		
		ALTUSER		
		command, the		
		word NONE		
		appears in		
		the listing		
		. In such		
		situations		
		, z/OS UNIX		
		uses its		
		system level		
		values for		
		limit values		
		. If there		
		is no HOME		
		or PROGRAM		
		information		
		, the field		
		name is not		
		displayed.		
		However, the		
		word NONE		
		appears in		
		the listing		
		if the UID was		
		not specified,		
		or if the UID		
		was removed		
		using the		
		NOUID operand		
		on the ALTUSER		
		command -> OMVS</td <td></td> <td></td>		
		INFORMATION		
		>		
		<maptransform></maptransform>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*UID' pattern='UID=		
		\s*(\S+)'		
		optional='false		
		reset='false'>		
		<pre><substitutetran< pre=""></substitutetran<></pre>		
		pattern='^0+(\d		
		substitute='\$1		
		/>		
		<pre>/> <nulltransform< pre=""></nulltransform<></pre>		
		pattern='NONE'		
		/> </td <td></td> <td></td>		
		/> <br PatternNode>		



Property	Туре	Default	Encrypted ^a	Required ^b
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*H0ME'		
		pattern='HOME=		
		\s*([^\n]*)\n'		
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\s+\$'		
		substitute=''		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*PR0GR		
		pattern='PROGRAI		
		\s*([^\n]*)\n'		
		optional='true'		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='\s+\$'		
		substitute=''		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*CPUTI		
		pattern='CPUTIM		
		\s*(NONE \d+)'		
		optional='false		
		reset='false'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/>		
		<nulltransform< td=""><td></td><td></td></nulltransform<>		
		pattern='NONE'		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*ASSIZ		
		pattern='ASSIZE		
		\s*(NONE \d+)'		
		optional='false		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/>		
		<pre><nulltransform< pre=""></nulltransform<></pre>		
		pattern='NONE'		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		



Property
Property



Property	Туре	Default	Encrypted ^a	Required ^b
		<pre>NullTransform pattern='NONE' /> </pre> PatternNode> /MapTransform> /, ' <maptransform> /, '<maptransform> /, '<maptransform> /, PatternNode key='CATALOG*CA' ALIAS' pattern='ALIAS \s+[-]+\s +([^]+)' optional='true' reset='false'/ > <patternnode catalog'="" key="CATALOG*MA" optional="true" pattern="IN -CAT\s+[-]+ \s+([^]+)" reset="false"> <patternnode -]+([^]+)'="" key="CATALOG*USI CATALOG" optional="true" pattern="USERCA" reset="false"> <!-- MapTransform--> /, '<!-- (from IBM documentation) http://publib .boulder.ibm .com/infocenter /zos/v1r9/index .jsp?topic= /com.ibm.zos .r9.ichal00 /netinf.htm OMVS Specifies that you want to list the information contained in the OMVS segment of the user's</pre--></patternnode></patternnode></maptransform></maptransform></maptransform>		



Property	Туре	Default	Encrypted ^a	Required ^b
Property	Type	profile. The details RACF lists from the OMVS segment are: The user identifier The initial directory pathname The program pathname The CPU time, in seconds the user's processes can use The address space region size in bytes, the user's processes can use The maximum number of active or open files the user can have The maximum number of active processes the user can have The maximum number of threads the user can have The maximum number of threads the user can have The maximum number of space, in pages, the user can map in storage . Note: If CPUTIMEMAX , ASSIZEMAX, FILEPROCMAX, PROCUSERMAX, THREADSMAX, or MMAPAREAMAX is not specified, or is removed	Encrypted ^a	Required b



Property	Туре	Default	Encrypted ^a	Required ^b
		ALTUSER command, the word NONE appears in the listing . In such situations , z/OS UNIX uses its system level values for limit values . If there is no HOME or PROGRAM information , the field name is not displayed. However, the word NONE appears in the listing if the UID was not specified, or if the UID was removed using the NOUID operand on the ALTUSER command> OMVS INFORMATION <maptransform> <patternnode false'="" key="OMVS*UID" optional="false reset=" pattern="UID= \s*(\S+)"> <substitutetran \$1="" pattern="^0+(\n substitute="></substitutetran> <nulltransform pattern="NONE"></nulltransform> <!-- PatternNode key='OMVS*HOME </PatternNode key='OMVS*HOME</td--><td></td><td></td></patternnode></maptransform>		



Property	Туре	Default	Encrypted ^a	Required ^b
		pattern='HOME=		
		\s*([^\n]*)\n'		
		optional='true'		
		reset='false'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='\s+\$'		
		substitute=''		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*PR0GR		
		pattern='PROGRA		
		\s*([^\n]*)\n'		
		optional='true'		
		reset='false'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='\s+\$'		
		substitute=''		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*CPUTI		
		pattern='CPUTIM		
		\s*(NONE \d+)'		
		optional='false		
		reset='false'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/>		
		<nulltransform< td=""><td></td><td></td></nulltransform<>		
		pattern='NONE'		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*ASSIZ		
		pattern='ASSIZE		
		\s*(NONE \d+)'		
		optional='false		
		reset='false'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/>		
		<pre><nulltransform< pre=""></nulltransform<></pre>		
		pattern='NONE'		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*FILEP		
		pattern='FILEPR		



Property	Туре	Default	Encrypted ^a	Required ^b
		\s*(NONE \d+)'		
		optional='false		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/>		
		<nulltransform< td=""><td></td><td></td></nulltransform<>		
		pattern='NONE'		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*PR0CU		
		pattern='PROCUS		
		\s*(NONE \d+)'		
		optional='false		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/>		
		<pre><nulltransform< pre=""></nulltransform<></pre>		
		pattern='NONE'		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*THREA		
		pattern='THREADS		
		\s*(NONE \d+)'		
		optional='false		
		reset='false'>		
		<substitutetrans< td=""><td></td><td></td></substitutetrans<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/>		
		<nulltransform< td=""><td></td><td></td></nulltransform<>		
		pattern='NONE'		
		/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='0MVS*MMAPAI		
		pattern='MMAPARI		
		\s*(NONE \d+)'		
		optional='false		
		reset='false'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='^0+(\d		
		substitute='\$1'		
		/>		
		<nulltransform< td=""><td></td><td></td></nulltransform<>		
		pattern='NONE'		



Property	Туре	Default	Encrypted ^a	Required b
		/> <br PatternNode> <		
		/MapTransform>		
		', ' </td <td></td> <td></td>		
		Sample output:		
		INFORMATION		
		FOR GROUP		
		DFPADMN		
		SUPERIOR		
		GROUP=SYSADMN		
		OWNER=SYSADMN		
		CREATED=06		
		.123 NO		
		INSTALLATION		
		DATA NO MODEL		
		DATA SET		
		TERMUACC		
		SUBGROUP(S)=		
		SYSCTLG		
		VSAMDSET		
		SYSTEM BHDS		
		ISP ISR		
		IPO1 GIM		
		ICQ MVSSMPE		
		PASSWORD		
		CATALOG ISF		
		EMP FDRABR		
		CPP 0S3901 SMPE CPAC		
		TEST1 CICSREG		
		CEE TTY		
		CAI CICS410		
		DSN510 DSN610		
		IMS610 BH7A		
		0EGROUP ADA612		
		CICSTS13		
		CICSTS21		
		IESDIVI		
		AOPADMIN		
		SYSIBM DSN710		
		CICSTS22		
		UUCPG IMS810		
		DSN810 STCGRPS		
		USER(S)=		
		ACCESS=		
		ACCESS COUNT=		
		UNIVERSAL		
		ACCESS=		
		IBMUSER JOIN		
		000000 ALTER		
		CONNECT		



Property	Туре	Default	Encrypted ^a	Required ^b
		ATTRIBUTES=NONE		
		REV0KE		
		DATE=NONE		
		RESUME		
		DATE=NONE		
		DSMITH JOIN		
		000002 READ		
		CONNECT		
		ATTRIBUTES=NONE		
		REV0KE		
		DATE=NONE		
		RESUME		
		DATE=NONE		
		HOTROD CONNECT		
		000004 READ		
		CONNECT		
		ATTRIBUTES=ADSP		
		SPECIAL		
		OPERATIONS REVOKE		
		DATE=NONE		
		RESUME		
		DATE=NONE		
		ESHAW USE		
		000000 READ		
		CONNECT		
		ATTRIBUTES=NONE		
		REVOKE		
		DATE=NONE		
		RESUME		
		DATE=NONE		
		PROJECTB		
		USE 000000		
		READ CONNECT		
		ATTRIBUTES=NONE		
		REV0KE		
		DATE=NONE		
		RESUME		
		DATE=NONE ADM1		
		JOIN 000000		
		READ CONNECT		
		ATTRIBUTES=0PERA		
		REV0KE		
		DATE=NONE		
		RESUME		
		DATE=NONE		
		AEHALL USE		
		000000 READ		
		CONNECT		
		ATTRIBUTES=REV0		
		REV0KE		



Property	Туре	Default	Encrypted ^a	Required ^b
Property	Type	Default DATE=NONE RESUME DATE=NONE DFP INFORMATION MGMTCLAS= DFP2MGMT STORCLAS= DFP2STOR DATACLAS= DFP2DATA DATAAPPL= DFP2APPL> <maptransform> <patternnode (\s{1,8})'="" false'="" for="" group="" inform="" key="RACF*USERI pattern=" optional="false reset="> <patternnode ,8})'="" false'="" group="(\S{1" key="RACF*SUPGR pattern=" optional="false reset=" superi=""> <patternnode false'="" key="RACF*OWNER pattern=" optional="false reset=" owner=",8})'"> <patternnode false'="" key="RACF*OWNER pattern=" optional="false reset=" owner=",8})'"> <substitutetran optional="true" pattern="INSTAL DATA=([^ \n]*(\s{20} .+\n)*)" racf*data'="" reset="false" substitute="UNK /> </ PatternNode key="> <substitutetran \formalle'="" \formalle'<="" \formalle'\formalle'="" pattern="\formalle" td=""><td></td><td>Required b</td></substitutetran></substitutetran></patternnode></patternnode></patternnode></patternnode></maptransform>		Required b



Property	Туре	Default	Encrypted ^a	Required ^b
Property	Type	<pre> <substitutetran. pattern="\n \s{20}(. {50})[^\n]+" substitute="\$1"></substitutetran.> <substitutetran. pattern="\n" substitute=""></substitutetran.> <substitutetran. pattern="\s+\$" substitute=""></substitutetran.> <substitutetran. pattern="\s" substitute="NO INSTALLATION DATA"></substitutetran.> <!-- PatternNode key='RACF*GROUP. pattern='(NO GROUPS)' optional='true' reset='true'--> <substitutetran. optional="true" pattern="(NO GROUPS)" reset="true"> <substitutetran. pattern="(NO GROUPS)" substitute="" substitutetran.=""></substitutetran.> <splittransform splitpattern="\\\ +"></splittransform> <!-- PatternNode key='RACF*GROUP. patternNode key='RACF*GROUP. patternNode (S\)=([^\n]* \n(\s{18}[^\ \n]+\n)*)'</pre--></substitutetran.></pre>		Required b
		<pre><splittransform splitpattern="\ +"></splittransform> <!-- PatternNode--> <patternnode \(s\)="([^\n]*" \n(\s{18}[^\="" \n]+\n)*)'<="" key="RACF*GROUP: pattern=" pre="" subgroi=""></patternnode></pre>		
		<pre>optional='true' reset='false'></pre>		



Property	Type	Default	Encrypted ^a	Required ^b
		substitute='\$1		
		'/>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='^		
		\s+(\S+)'		
		substitute='\$1'		
		/>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='(\S		
		+)\s+\$'		
		substitute='\$1'		
		/>		
		<pre><splittransform< pre=""></splittransform<></pre>		
		splitPattern='\		
		+'/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*MEMBE		
		pattern='(NO		
		USERS)'		
		optional='true'		
		reset='true'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='(NO		
		USERS) '		
		substitute=''		
		/>		
		<pre><splittransform< pre=""></splittransform<></pre>		
		splitPattern='\		
		+'/> </td <td></td> <td></td>		
		PatternNode>		
		<patternnode< td=""><td></td><td></td></patternnode<>		
		key='RACF*MEMBE		
		pattern='USER		
		\(S\)=[^\n]*		
		\n((\s{7}\S+([^		
		\n]+\n){3})*)'		
		optional='true'		
		reset='false'>		
		<substitutetran< td=""><td></td><td></td></substitutetran<>		
		pattern='\s{7}		
		(\S+)(?:[^		
		\n]+\n){3}'		
		substitute='\$1		
		'/>		
		<pre><splittransform< pre=""></splittransform<></pre>		
		splitPattern='\		
		+'/> </td <td></td> <td></td>		
		PatternNode> <		



Property	Туре	Default	Encrypted ^a	Required ^b	
		/MapTransform> ']			
XML for MapTransform objects	that can parse RAC	F segments; must be	paired with segme	ntNames	
commandTimeout	Integer	null		No	
Description is not available					
reaperMaximumIdleTime	Integer	null		No	
Description is not available					
disconnectScript	Script	null		No	
Groovy script used to close a 32	70 connection				
connectScript	Script	null		No	
Groovy script used to establish a 3270 connection					
connectionProperties	String[]	null	Yes	No	
Description is not available					

^a Indicates whether the property value is considered confidential, and therefore encrypted in OpenIDM. ^b A list of operations in this column indicates that the property is required for those operations.



XML File Connector

OpenIDM includes a simple XML file connector. This connector is really useful only in a demonstration context and should not be used in the general provisioning of XML data stores. In real deployments, if you need to connect to a custom XML data file, you should create your own scripted connector by using the Groovy connector toolkit.

The XML file connector is deprecated and support for its use in OpenIDM will be removed in a future release.

14.1. Configuring the XML File Connector

A sample XML connector configuration is provided in path/to/openidm/samples/provisioners/
provisioner.openicf-xml.json. The following excerpt of the provisioner configuration shows the main configurable properties:

```
"connectorRef": {
    "connectorHostRef": "#LOCAL",
    "bundleName": "org.forgerock.openicf.connectors.xml-connector",
    "bundleVersion": "1.1.0.3",
    "connectorName": "org.forgerock.openicf.connectors.xml.XMLConnector"
}
```

The connectorHostRef is optional if the connector server is local.

The configuration properties for the XML file connector set the relative path to the file containing the identity data, and also the paths to the required XML schemas:

```
{
    "configurationProperties": {
        "xsdIcfFilePath" : "&{launcher.project.location}/data/resource-schema-1.xsd",
        "xsdFilePath" : "&{launcher.project.location}/data/resource-schema-extension.xsd",
        "xmlFilePath" : "&{launcher.project.location}/data/xmlConnectorData.xml"
    }
}
```

&{launcher.project.location} refers to the project directory of your OpenIDM instance, for example, path/to/openidm/samples/sample1. Note that relative paths such as these work only if your connector server runs locally. For remote connector servers, you must specify the absolute path to the schema and data files.



xsdIcfFilePath

References the XSD file defining schema common to all XML file resources. Do not change the schema defined in this file.

xsdFilePath

References custom schema defining attributes specific to your project.

xmlFilePath

References the XML file that contains account entries.



Appendix A. OpenICF Interfaces

This chapter describes all of the interfaces supported by the OpenICF framework, along with notes about their implementation. Specific connectors may support only a subset of these interfaces.

A.1. AttributeNormalizer

Normalize attributes to ensure consistent filtering.

A.2. Authenticate

Provides simple authentication with two parameters, presumed to be a user name and password. If the connector does not implement the AuthenticateOp interface it can not be used in OpenIDM to provide pass-through authentication.

A.3. Batch

Execute a series of operations in a single request. If a resource does not support batch operations, the connector will not implement the batch operation interface. The OpenICF framework will still support batched requests but the operations will be executed iteratively through the connector.



A.4. Connector Event

Subscribe for notification of any specified event on the target resource. This operation can be used in the context of IoT device reports, to receive notification of events such as low battery signals, inactive devices, and so on.

A.5. Create

Create an object and return its uid.

A.6. Delete

Delete an object by its uid.

A.7. Get

Get an object by its uid.

A.8. PoolableConnector

Use pools of target resources.

A.9. Resolve Username

Resolve an object to its uid based on its username.

A.10. Schema

Describe supported object types, operations, and options.

A.11. Script on Connector

Allow script execution on connector.



A.12. Script On Resource

Allow script execution on the resource.

A.13. Search

Allow searches for resource objects.

Connectors that implement *only* this interface can only be used for reconciliation operations.

A.14. Sync

Poll for synchronization events, which are native changes to target objects.

A.15. Sync Event

Subscribe for notification of synchronization events, which are native changes to target objects.

A.16. Test

Test the connection configuration, including connecting to the resource.

A.17. Update

Allows an authorized caller to update (modify or replace) objects on the target resource.

A.18. Update Attribute Values

Allows an authorized caller to update (modify or replace) attribute values on the target resource. This operation is more advanced than the UpdateOp operation, and provides better performance and atomicity semantics.



Appendix B. OpenICF Operation Options

This chapter describes all of the predefined operation options by the OpenICF framework, along with notes about their use. Specific connectors may support only a subset of these options.

B.1. Scope

An option to use with Search (in conjunction with Container) that specifies how far beneath the specified container to search. Must be one of the following values:

- SCOPE_OBJECT
- SCOPE_ONE_LEVEL
- SCOPE_SUBTREE

B.2. Container

An option to use with Search that specifies the container under which to perform the search. Must be of type QualifiedUid. Should be implemented for those object classes whose ObjectClassInfo.isContainer() returns true.

B.3. Run as User

An option to use with Script on Resource and possibly others that specifies an account under which to execute the script/operation. The specified account will appear to have performed any action that the script/operation performs.



B.4. Run with Password

An option to use with Script on Resource and possibly others that specifies a password under which to execute the script/operation.

B.5. Attributes to Get

Determines which attributes to retrieve during Search and Sync. This option overrides the default behavior, which is for the connector to return exactly the set of attributes that are identified as returned by default in the schema for that connector. This option allows a client application to request additional attributes that would not otherwise not be returned (generally because such attributes are more expensive for a connector to fetch and to format) and/or to request only a subset of the attributes that would normally be returned.

B.6. Paged Results Cookie

An option to use with Search that specifies an opaque cookie which is used by the connector to track its position in the set of query results.

B.7. Paged Results Offset

An option to use with Search that specifies the index within the result set of the first result which should be returned.

B.8. Page Size

An option to use with Search that specifies the requested page results page size.

B.9. Sort Keys

An option to use with Search that specifies the sort keys which should be used for ordering the ConnectorObject returned by search request.

B.10. Fail on Error

This option is used with the Batch operation, to specify whether the batch process should be aborted when the first error is encountered. The default behavior is to continue processing regardless of errors.



B.11. Require Serial

This option instructs the connector to execute batched requests in a serial manner if possible. The default behavior of the Batch operation is to execute requests in parallel, for speed and efficiency. In either case the task ID must be reflected in the response for each task, so that tasks can be correctly reordered.



Appendix C. Connection Pooling Configuration

Certain connectors support the ability to be pooled. For a pooled connector, OpenICF maintains a pool of connector instances and reuses these instances for multiple provisioning and reconciliation operations. When an operation must be executed, an existing connector instance is taken from the connector pool. If no connector instance exists, a new instance is initialized. When the operation has been executed, the connector instance is released back into the connector pool, ready to be used for a subsequent operation.

For an unpooled connector, a new connector instance is initialized for every operation. When the operation has been executed, OpenICF disposes of the connector instance.

Because the initialization of a connector is an expensive operation, reducing the number of connector initializations can substantially improve performance.

To configure connection pooling, set the following values in the connector configuration file poolConfigOptions property:

- "max0bjects" the maximum number of connector instances in the pool (both idle and active). The default value is 10 instances.
- "maxIdle" the maximum number of idle connector instances in the pool. The default value is 10 idle instances.
- "maxWait" the maximum period to wait for a free connector instance to become available before failing. The default period is 150000 milliseconds, or 15 seconds.
- "minEvictableIdleTimeMillis" the minimum period to wait before evicting an idle connector instance from the pool. The default period is 120000 milliseconds, or 12 seconds.



• "minIdle" - the minimum n instance.	umber of idle connector	instances in the pool. Th	ne default value is 1