

Linear Mixed-Effects Models for Data from Split-Plot Experiments

Start with a Field






Partition the Field into Blocks



Partition Each Block into Plots




Randomly Assign Genotypes to Plots within Blocks

Field

Block 1	Genotype C	Genotype A	Genotype B
Block 2	Genotype B	Genotype A	Genotype C
Block 3	Genotype A	Genotype B	Genotype C
Block 4	Genotype B	Genotype C	Genotype A


Partition Each Whole Plot into Split Plots

Field




Randomly Assign Fertilizer Amounts within Split Plots





An Example Split-Plot Experiment




- This experiment has two factors: genotype and fertilizer amount.
- Genotype has levels A, B, and C.
- Fertilizer has levels 0, 50, 100, 150 lbs. N / acre.
- Genotype is called the whole-plot (or main-plot) factor because its levels are randomly assigned to whole plots (main plots).
- Fertilizer is called the split-plot factor because its levels are randomly assigned to split plots within each whole plot.

Experimental Units in Split-Plot Designs


- Whole plots are the whole-plot experimental units because the levels of the whole-plot factor (genotype) are randomly assigned to whole plots.
- The split-plots are the split-plot experimental units because the levels of the split-plot factor (amount of fertilizer) are randomly assigned to split plots within each whole plot.
- Thus, we have two different sizes of experimental units in split-plot experimental designs.

Same Treatment Structure in an RCBD



Same Treatment Structure in an CRD

Field



Why Use a Split-Plot Design?

- Split-plot designs usually arise because logistical constraints make a CRD or RCBD impractical.
- For example, it may be easier to change from one fertilizer level to another as a tractor drives through a field, while it may be more difficult to change from planting one genotype to planting another.
- In the engineering literature, split-plot designs are sometimes called designs with hard-to-change factors.

Recognizing Designs with Split-Plot Structures

- Many variations on split-plot designs are used for practical reasons.
- Examples include split-split-plot designs and split-block designs, but the names of these designs are not so important.
- Pay close attention to the experimental unit to which the levels of each factor are randomly assigned to recognize split-plot-like design structures.

Split-plot designs may not involve plots of land.

- Suppose eight pairs of mice from eight litters are housed in eight cages so that each cage holds two mice from the same litter.
- Suppose diets 1 and 2 are randomly assigned to the litters with four litters per diet.
- Within each cage, suppose drugs 1 and 2 are randomly assigned to the mice with one mouse per drug.

A Split-Plot Experimental Design

















- Diet is the whole-plot treatment factor.
- Litters are the whole-plot experiment units.
- Drug is the split-plot treatment factor.
- Mice are the split-plot experiment units.

Diet i = 1, 2, Drug j = 1, 2, Litter k = 1, 2, 3, 4 (within each Diet i)

$$y_{ijk} = \mu + \alpha_i + \beta_j + \gamma_{ij} + \ell_{ik} + e_{ijk} \ (i = 1, 2; j = 1, 2; k = 1, ..., 4)$$

 $\mu + \alpha_i + \beta_j + \gamma_{ij} = \text{mean for Diet } i \text{ and Drug } j$

 $\ell_{ik} = \text{random effect for } k \text{th litter that received Diet } i$

 $e_{ijk} = \text{random error effect for Diet } i, \text{ Drug } j, \text{ Litter } k$

	y ₁₁₁						e_{111}
	y ₁₂₁						e_{121}
	y ₁₁₂						e_{112}
	y ₁₂₂		Г,, Т				$ e_{122} $
y =	y ₁₁₃		μ		$\lceil \ell_{11} \rceil$		e_{113}
	y ₁₂₃		α_1		ℓ_{12}		e_{123}
	y ₁₁₄		$\begin{vmatrix} \alpha_2 \\ \beta_1 \end{vmatrix}$		ℓ_{13}		$ e_{114} $
	<i>y</i> 124	$\beta =$	$\begin{vmatrix} \beta_1 \\ \beta_2 \end{vmatrix}$	u =	ℓ_{14}	e =	e_{124}
	y ₂₁₁	ρ –			ℓ_{21}	· -	e_{211}
	y ₂₂₁		γ_{11}		ℓ_{22}		$ e_{221} $
	y ₂₁₂		γ_{12}		ℓ_{23}		$ e_{212} $
	y ₂₂₂		γ_{21}		ℓ_{24}		$ e_{222} $
	y ₂₁₃		$\lfloor \gamma_{22} floor$				e_{213}
	y ₂₂₃						$ e_{223} $
	y ₂₁₄						$ e_{214} $
	y ₂₂₄						e_{224}

$$X = \begin{bmatrix} \mathbf{1} \\ \mathbf{1}_{16 \times 1}, \mathbf{I}_{2 \times 2} \otimes \mathbf{1}_{8 \times 1}, \mathbf{1}_{8 \times 1} \otimes \mathbf{I}_{2 \times 2}, \mathbf{I}_{2 \times 2} \otimes \mathbf{1}_{4 \times 1} \otimes \mathbf{I}_{2 \times 2} \end{bmatrix}$$

$$Z = I_{8\times 8} \otimes 1_{2\times 1}$$

$$y = X\beta + Zu + e$$

$$\begin{bmatrix} \boldsymbol{u} \\ \boldsymbol{e} \end{bmatrix} \sim \boldsymbol{N} \left(\begin{bmatrix} \boldsymbol{0} \\ \boldsymbol{0} \end{bmatrix}, \ \begin{bmatrix} \sigma_{\ell}^2 \boldsymbol{I} & \boldsymbol{0} \\ \boldsymbol{0} & \sigma_{e}^2 \boldsymbol{I} \end{bmatrix} = \begin{bmatrix} \boldsymbol{G} & \boldsymbol{0} \\ \boldsymbol{0} & \boldsymbol{R} \end{bmatrix} \right)$$

$$\begin{aligned} \operatorname{Var}(\mathbf{Z}\boldsymbol{u}) &= \mathbf{Z}\boldsymbol{G}\mathbf{Z}' = \sigma_{\ell}^{2}\mathbf{Z}\mathbf{Z}' \\ &= \sigma_{\ell}^{2} \begin{bmatrix} \boldsymbol{I} \otimes \mathbf{1} \\ 8 \times 8 & 2 \times 1 \end{bmatrix} \begin{bmatrix} \boldsymbol{I} \otimes \mathbf{1} \\ 8 \times 8 & 2 \times 1 \end{bmatrix}' \\ &= \sigma_{\ell}^{2} \begin{bmatrix} \boldsymbol{I} \otimes \mathbf{1} \mathbf{1}' \\ 8 \times 8 & 2 \times 2 \end{bmatrix} \end{aligned}$$
$$= \operatorname{Block Diagonal with blocks} \begin{bmatrix} \sigma_{\ell}^{2} & \sigma_{\ell}^{2} \\ \sigma_{\ell}^{2} & \sigma_{\ell}^{2} \end{bmatrix}$$

$$\operatorname{Var}(\mathbf{y}) = \mathbf{Z}\mathbf{G}\mathbf{Z}' + \mathbf{R} = \sigma_{\ell}^{2} \mathbf{I}_{8 \times 8} \otimes \mathbf{1}_{2 \times 2}^{1'} + \sigma_{e}^{2} \mathbf{I}$$

Block Diagonal with blocks

$$egin{bmatrix} \sigma_\ell^2 + \sigma_e^2 & \sigma_\ell^2 \ \sigma_\ell^2 & \sigma_\ell^2 + \sigma_e^2 \end{bmatrix}$$

Thus, the covariance between two observations from the same litter is σ_ℓ^2 and the correlation is $\frac{\sigma_\ell^2}{\sigma_\ell^2 + \sigma_z^2}$.

These computations can also be done using the non-matrix expression of the model.

$$\forall i, j, \operatorname{Var}(y_{ijk}) = \operatorname{Var}(\mu + \alpha_i + \beta_j + \gamma_{ij} + \ell_{ik} + e_{ijk})$$

$$= \operatorname{Var}(\ell_{ik} + e_{ijk})$$

$$= \sigma_{\ell}^2 + \sigma_{e}^2.$$

$$Cov(y_{i1k}, y_{i2k}) = Cov(\mu + \alpha_i + \beta_1 + \gamma_{i1} + \ell_{ik} + e_{i1k}, \mu + \alpha_i + \beta_2 + \gamma_{i2} + \ell_{ik} + e_{i2k})$$

$$= Cov(\ell_{ik} + e_{i1k}, \ell_{ik} + e_{i2k})$$

$$= Cov(\ell_{ik}, \ell_{ik}) + Cov(\ell_{ik}, e_{i2k})$$

$$+ Cov(e_{i1k}, \ell_{ik}) + Cov(e_{i1k}, e_{i2k})$$

$$= Cov(\ell_{ik}, \ell_{ik}) + 0 + 0 + 0$$

$$= Var(\ell_{ik}) = \sigma_{\ell}^{2}.$$

Back to the Traditional Split-Plot Experimental Design



Block 1	G	eno	ype	С	G	eno	ype	Α	G	enot	ype	В
	0	100	150	50	50	100	150	0	150	100	50	0
Block 2	G	eno	type	В	G	eno	type	Α	G	enot	ype	С
	150	100	50	0	0	50	150	100	100	50	150	0
Block 3	G	eno	type	Α	G	enot	ype	В	G	enot	ype	С
	100	50	0	150	0	100	150	50	50	100	150	0
Block 4	G	enot	ype	В	G	enot	ype	С	G	enot	ype	Α

A Model for Data from the Traditional Split-Plot Experiment

Genotype i = 1, 2, 3, Fertilizer j = 1, 2, 3, 4, Block k = 1, 2, 3, 4

$$y_{ijk} = \mu_{ij} + b_k + w_{ik} + e_{ijk}$$

 $\mu_{ij} = \text{mean for Genotype } i$, Fertilizer j

 b_k = random effect for Block k

 w_{ik} = random effect for Genotype i whole plot in Block k

 e_{iik} random error effect for Genotype i, Fertilizer j, Block k

To express the model precisely in vector and matrix form as $y = X\beta + Zu + e$, we will sort the data first by Block, then Genotype, and then Fertilizer:

$$\mathbf{y} = [y_{111}, y_{121}, y_{131}, y_{141}, y_{211}, y_{221}, y_{231}, y_{241}, \dots, y_{314}, y_{324}, y_{334}, y_{344}]'$$

$$\mathbf{e} = [e_{111}, e_{121}, e_{131}, e_{141}, e_{211}, e_{221}, e_{231}, e_{241}, \dots, e_{314}, e_{324}, e_{334}, e_{344}]'$$

$$X = \underset{4\times 1}{\mathbf{1}} \otimes \underset{12\times 12}{I},$$

$$Z = \begin{bmatrix} I \otimes 1 & I_{2\times 1} & I_{2\times 12} \otimes 1 \\ I_{4\times 4} & I_{2\times 12} & I_{4\times 12} & I_{4\times 12} \end{bmatrix}$$

$$\boldsymbol{u} = \begin{bmatrix} \boldsymbol{b} \\ \boldsymbol{w} \end{bmatrix} = \begin{bmatrix} b_1 \\ \vdots \\ b_4 \\ w_{11} \\ w_{21} \\ \vdots \\ w_{34} \end{bmatrix} \sim N \left(\begin{bmatrix} \boldsymbol{0} \\ \boldsymbol{0} \end{bmatrix}, \begin{bmatrix} \sigma_b^2 \boldsymbol{I} & \boldsymbol{0} \\ \boldsymbol{0} & \sigma_w^2 \boldsymbol{I} \end{bmatrix} \right)$$

$$\begin{bmatrix} \boldsymbol{b} \\ \boldsymbol{w} \\ \boldsymbol{e} \end{bmatrix} \sim N \begin{pmatrix} \begin{bmatrix} \boldsymbol{0} \\ \boldsymbol{0} \\ \boldsymbol{0} \end{bmatrix}, \begin{bmatrix} \sigma_b^2 \boldsymbol{I} & \boldsymbol{0} & \boldsymbol{0} \\ \boldsymbol{0} & \sigma_w^2 \boldsymbol{I} & \boldsymbol{0} \\ \boldsymbol{0} & \boldsymbol{0} & \sigma_e^2 \boldsymbol{I} \end{bmatrix} \end{pmatrix}$$
$$\begin{bmatrix} \boldsymbol{u} \\ \boldsymbol{e} \end{bmatrix} \sim N \begin{pmatrix} \begin{bmatrix} \boldsymbol{0} \\ \boldsymbol{0} \end{bmatrix}, \begin{bmatrix} \boldsymbol{G} & \boldsymbol{0} \\ \boldsymbol{0} & \boldsymbol{R} \end{bmatrix} \end{pmatrix}$$