# Chapter II - Introduction to PDE and Modeling

John Cagnol, Pauline Lafitte

The Engineering Program of CentraleSupélec

Lecture 3 – January 7th 2020

Definition of a PDE The different types of PDE Vellposeness Boundary Conditions

## II.1. Definitions

Definition of a PDE The different types of PDE: Wellposeness Boundary Conditions

### II.1.1. Definition of a PDE

#### Definition II.1.1

A partial differential equation (PDE) is an equation that relates a function with its derivatives (with respect to d variables).

The unknown is a function.

#### Definition II.1.1

A partial differential equation (PDE) is an equation that relates a function with its derivatives (with respect to d variables).

The unknown is a function.

If d = 1, the differential equation is called **ordinary**. We have studied such equations in chapter I.

#### Definition II.1.1

A partial differential equation (PDE) is an equation that relates a function with its derivatives (with respect to d variables). The unknown is a function.

If d = 1, the differential equation is called **ordinary**. We have studied such equations in chapter I.

#### Definition II.1.2

The **order** or the PDE is determined by the term with the highest derivatives.

#### Definition II.1.1

A partial differential equation (PDE) is an equation that relates a function with its derivatives (with respect to d variables).

The unknown is a function.

If d = 1, the differential equation is called **ordinary**. We have studied such equations in chapter I.

#### Definition II.1.2

The **order** or the PDE is determined by the term with the highest derivatives.

#### Definition II.1.3

A PDE is **linear** if it is linear in the unknown function and its derivatives.

Definition of a PDE The different types of PDEs Wellposeness Boundary Conditions

II.1.2. The different types of PDEs

Second order linear partial differential equations (PDEs) can be classified in three categories:

- Elliptic
- Parabolic
- Hyperbolic

Second order linear partial differential equations (PDEs) can be classified in three categories:

- Elliptic
- Parabolic
- Hyperbolic

When d = 2, the PDEs car be written

$$A\frac{\partial^2 u}{\partial x_1^2} + B\frac{\partial^2 u}{\partial x_1 x_2} + C\frac{\partial^2 u}{\partial x_2^2} + D\frac{\partial u}{\partial x_1} + E\frac{\partial u}{\partial x_2} + Fu + G = 0$$

where A, B, C, D, E, F, and G are functions defined on  $\mathbb{R}^2$ .

Second order linear partial differential equations (PDEs) can be classified in three categories:

- Elliptic
- Parabolic
- Hyperbolic

When d = 2, the PDEs car be written

$$A\frac{\partial^2 u}{\partial x_1^2} + B\frac{\partial^2 u}{\partial x_1 x_2} + C\frac{\partial^2 u}{\partial x_2^2} + D\frac{\partial u}{\partial x_1} + E\frac{\partial u}{\partial x_2} + Fu + G = 0$$

where A, B, C, D, E, F, and G are functions defined on  $\mathbb{R}^2$ .

The PDE is said to be

- elliptic if  $B^2 4AC < 0$
- parabolic if  $B^2 4AC = 0$  and  $(A, B, C) \neq (0, 0, 0)$
- hyperbolic if  $B^2 4AC > 0$  or (A, B, C) = (0, 0, 0)

Definition of a PDE
The different types of PDEs
Wellposeness
Boundary Conditions

## Classification of PDEs

### Example

 $\Delta u = f$ 

### Example

$$\frac{\partial^2 u}{\partial x_1^2} + \frac{\partial^2 u}{\partial x_2^2} = f$$

Definition of a PDE The different types of PDEs Wellposeness Boundary Conditions

## Classification of PDEs

### Example

 $\Delta u = f$ 

### Example

 $\Delta u = f$  is an elliptic PDE.

### Example

 $\Delta u = f$  is an elliptic PDE.

The classification elliptic/parabolic/hyperbolic can be extended to higher order linear PDEs and non-linear PDEs.

 $\Delta u = f$  in dimension 3 is an elliptic PDE.

It is customary to use the variable t for time.

It is customary to use the variable t for time.

We use the term **evolution equation** when the PDE models the development (evolution) in time of a system.

On the contrary, we use the term **steady state** when the behavior of the system does not change over time.

It is customary to use the variable t for time.

We use the term **evolution equation** when the PDE models the development (evolution) in time of a system.

On the contrary, we use the term **steady state** when the behavior of the system does not change over time.

### Example

The propagation of a wave:

$$\frac{\partial^2 u}{\partial t^2} - \Delta_x u = t$$

is an hyperbolic PDE. It is an evolution equation.

It is customary to use the variable t for time.

We use the term **evolution equation** when the PDE models the development (evolution) in time of a system.

On the contrary, we use the term **steady state** when the behavior of the system does not change over time.

### Example

The propagation of a wave:

$$\frac{\partial^2 u}{\partial t^2} - \Delta u = f$$

is an hyperbolic PDE. It is an evolution equation.

Equation	Type name	Steady	Cls.
$\partial_t u = f(t, u)$	ODE	No	

Equation	Type name	Steady	Cls.
$\partial_t u = f(t, u)$	ODE	No	
$-\Delta u = f$	diffusion	Yes	Ε

Equation	Type name	Steady	Cls.
$\partial_t u = f(t, u)$	ODE	No	
$-\Delta u = f$	diffusion	Yes	Е
$\partial_t u - \Delta_{x} u = f$	diffusion	No	Р

Equation	Type name	Steady	Cls.
$\partial_t u = f(t, u)$	ODE	No	
$-\Delta u = f$	diffusion	Yes	Ε
$\partial_t u - \Delta_x u = f$	diffusion	No	Р
$\partial_t u + v \cdot \nabla_x(u) = f$	transport	No	Н

Equation	Type name	Steady	Cls.
$\partial_t u = f(t, u)$	ODE	No	
$-\Delta u = f$	diffusion	Yes	Е
$\partial_t u - \Delta_{X} u = f$	diffusion	No	Р
$\partial_t u + v \cdot \nabla_x(u) = f$	transport	No	Н
$\partial_t u + \vec{v} \cdot \nabla_{x}(u) - \Delta_{x} u = f$	transport-diffusion	No	Р

Equation	Type name	Steady	Cls.
$\partial_t u = f(t, u)$	ODE	No	
$-\Delta u = f$	diffusion	Yes	Е
$\partial_t u - \Delta_x u = f$	diffusion	No	Р
$\partial_t u + v \cdot \nabla_x(u) = f$	transport	No	Н
$\partial_t u + \vec{v} \cdot \nabla_x(u) - \Delta_x u = f$	transport-diffusion	No	Р
$\partial_{tt} u - c^2 \partial_{xx} u = f$	waves (1D)	No	Н

Definitions
Differential Calculus
The importance of PDEs in modeling
Outline of the work to be done

Definition of a PDE The different types of PDE: Wellposeness Boundary Conditions

II.1.3. Wellposeness

## Wellposedness

PDE: infinite number of solutions

**Problem**: PDE + conditions

- **boundary conditions:** value on  $\partial\Omega$  (e.g. Dirichlet)
- initial condition (Cauchy problem) for evolution equations: value at t = 0.

### Well-Posedness

#### Definition II.1.4

Let E and F be two spaces. Let  $f \in F$  be a data and  $A : E \to F$ . We are looking for solutions  $u \in E$  to A(u) = f (the PDE).

The PDE is well-posed in the sense of Hadamard if:

- a solution u exists,
- the solution u is unique,
- u changes "continuously" with respect tof.

A PDE that is not well-posed is said to be ill-posed

Definition of a PDE The different types of PDE: Wellposeness Boundary Conditions

II.1.4. Boundary Conditions

# Boundary

Let  $d \in \mathbb{N}^*$  and  $\Omega \subset \mathbb{R}^d$ .

Definition II.1.5 (Boundary)

We defined (CIP) the **boundary** of  $\Omega$  by  $\overline{\Omega} \setminus \mathring{\Omega}$ . It is denoted  $\partial \Omega$ 

# Boundary

Let  $d \in \mathbb{N}^*$  and  $\Omega \subset \mathbb{R}^d$ .

### Definition II.1.5 (Boundary)

We defined (CIP) the **boundary** of  $\Omega$  by  $\overline{\Omega} \setminus \mathring{\Omega}$ . It is denoted  $\partial \Omega$ 

### Example

d=1.

The boundary of ]a, b[ is  $\{a, b\}$ .

The boundary of [a, b] is  $\{a, b\}$ .

The boundary of  $]-\infty,b]$  is  $\{b\}$ .

The boundary of  $\mathbb{R}$  is  $\emptyset$ .

# Boundary

Let  $d \in \mathbb{N}^*$  and  $\Omega \subset \mathbb{R}^d$ .

### Definition II.1.5 (Boundary)

We defined (CIP) the **boundary** of  $\Omega$  by  $\overline{\Omega} \setminus \mathring{\Omega}$ . It is denoted  $\partial \Omega$ 

### Example

d=2.

The boundary of the disk is the circle.




# **Boundary Conditions**

### Definition II.1.6

Let  $\Omega \subset \mathbb{R}^d$  be a regular open set of class  $C^1$ .

Consider a PDE Au = f on  $\Omega$  where A is the differential operator, u is the unknown and f is the data.

The **Boundary Condition** (B.C.) is an equation that u must satisfy on  $\partial\Omega$  (or part of  $\partial\Omega$ ).



Definition of a PDE The different types of PDE Wellposeness Boundary Conditions

# **Boundary Conditions**

### Definition II.1.7

A Dirichlet boundary condition is u = g on  $\partial \Omega$  for a given g.

A Homogeneous Dirichlet boundary condition is u = 0 on  $\partial \Omega$ .

# **Boundary Conditions**

### Definition II.1.7

A Dirichlet boundary condition is u = g on  $\partial \Omega$  for a given g.

A Homogeneous Dirichlet boundary condition is u = 0 on  $\partial \Omega$ .

#### Example

$$\begin{cases} -\Delta u(x) = f(x) & x \in \Omega \\ u|_{\partial\Omega} = 0 \end{cases}$$

is an elliptic PDE with homogeneous Dirichlet boundary condition.

#### Definition II.1.7

A Dirichlet boundary condition is u = g on  $\partial \Omega$  for a given g.

A Homogeneous Dirichlet boundary condition is u = 0 on  $\partial \Omega$ .

### Example

$$\begin{cases} \frac{\partial^2 u}{\partial t^2}(t,x) - \Delta u(t,x) = f(t,x) & (t,x) \in ]0, T[\times \Omega \\ u|_{\partial\Omega}(t) = 0 & t \in ]0, T[ \\ u(0,x) = \phi(x) \text{ and } \frac{\partial u}{\partial t}(0,x) = \psi(x) & x \in \Omega \end{cases}$$

is an hyperbolic PDE with homogeneous Dirichlet boundary condition and with a given initial condition.

#### Definition II.1.7

A Dirichlet boundary condition is u = g on  $\partial \Omega$  for a given g.

A Homogeneous Dirichlet boundary condition is u = 0 on  $\partial \Omega$ .

### Example

$$\begin{cases} \frac{\partial^2 u}{\partial t^2}(t,x) - \Delta u(t,x) = f(t,x) & (t,x) \in ]0, T[\times \Omega \\ u(t,x) = 0 & (t,x) \in ]0, T[\times \partial \Omega \\ u(0,x) = \phi(x) \text{ and } \frac{\partial u}{\partial t}(0,x) = \psi(x) & x \in \Omega \end{cases}$$

is an hyperbolic PDE with homogeneous Dirichlet boundary condition and with a given initial condition.

#### Definition II.1.8

A Neumann boundary condition is  $\frac{\partial u}{\partial n} = g$  on  $\partial \Omega$  for a given g.

A Homogeneous Neumann B.C. is  $\frac{\partial u}{\partial n} = 0$  on  $\partial \Omega$ .

#### Definition II.1.8

A Neumann boundary condition is  $\frac{\partial u}{\partial n} = g$  on  $\partial \Omega$  for a given g.

A Homogeneous Neumann B.C. is  $\frac{\partial u}{\partial n} = 0$  on  $\partial \Omega$ .

### Example

$$\begin{cases} -\Delta u(x) = f(x) & in \ \Omega \\ \frac{\partial u}{\partial x} = 0 & on \ \partial \Omega \end{cases}$$

is an elliptic PDE with homogeneous Neumann boundary condition.

Outward Normal Vector Field Partial Derivatives Integration by Parts in Higher dimension

# II.2. Differential Calculus

Definitions
Differential Calculus
The importance of PDEs in modeling
Outline of the work to be done

Outward Normal Vector Field Partial Derivatives Integration by Parts in Higher dimension

II.2.1. Outward Normal Vector Field

An open set  $\Omega \subset \mathbb{R}^d$  is a regular open set of class  $C^1$  if for each point  $x_0 \in \partial \Omega$  there exist:

- $\bullet$  a radius r > 0 and
- a  $C^1$  function  $\gamma: \mathbb{R}^{d-1} \to \mathbb{R}$

such that

$$\Omega \cap B(x_0, r) = \{x \in B(x_0, r) : x_d > \gamma(x_1, \dots, x_{d-1})\}$$

(after reorienting the coordinates axes if necessary)

An open set  $\Omega \subset \mathbb{R}^d$  is a regular open set of class  $C^1$  if for each point  $x_0 \in \partial \Omega$  there exist:

- $\bullet$  a radius r > 0 and
- a  $C^1$  function  $\gamma: \mathbb{R}^{d-1} \to \mathbb{R}$

such that

$$\Omega \cap B(x_0, r) = \{x \in B(x_0, r) : x_d > \gamma(x_1, \dots, x_{d-1})\}$$

(after reorienting the coordinates axes if necessary)

A regular open set of class  $C^1$ :



An open set  $\Omega \subset \mathbb{R}^d$  is a regular open set of class  $C^1$  if for each point  $x_0 \in \partial \Omega$  there exist:

- $\bullet$  a radius r > 0 and
- a  $C^1$  function  $\gamma: \mathbb{R}^{d-1} \to \mathbb{R}$

such that

$$\Omega \cap B(x_0, r) = \{x \in B(x_0, r) : x_d > \gamma(x_1, \dots, x_{d-1})\}$$

(after reorienting the coordinates axes if necessary)

A regular open set of class  $C^1$ :



An open set  $\Omega \subset \mathbb{R}^d$  is a regular open set of class  $C^1$  if for each point  $x_0 \in \partial \Omega$  there exist:


- $\bullet$  a radius r > 0 and
- a  $C^1$  function  $\gamma: \mathbb{R}^{d-1} \to \mathbb{R}$

such that

$$\Omega \cap B(x_0, r) = \{x \in B(x_0, r) : x_d > \gamma(x_1, \dots, x_{d-1})\}$$

(after reorienting the coordinates axes if necessary)

A regular open set of class  $C^1$ :





An open set  $\Omega \subset \mathbb{R}^d$  is a regular open set of class  $C^1$  if for each point  $x_0 \in \partial \Omega$  there exist:

- $\bullet$  a radius r > 0 and
- a  $C^1$  function  $\gamma: \mathbb{R}^{d-1} \to \mathbb{R}$

such that

$$\Omega \cap B(x_0, r) = \{x \in B(x_0, r) : x_d > \gamma(x_1, \dots, x_{d-1})\}$$

(after reorienting the coordinates axes if necessary)

Not a regular open set of class  $C^1$ :



An open set  $\Omega \subset \mathbb{R}^d$  is a regular open set of class  $C^1$  if for each point  $x_0 \in \partial \Omega$  there exist:

- $\bullet$  a radius r > 0 and
- a  $C^1$  function  $\gamma: \mathbb{R}^{d-1} \to \mathbb{R}$

such that

$$\Omega \cap B(x_0, r) = \{x \in B(x_0, r) : x_d > \gamma(x_1, \dots, x_{d-1})\}$$

(after reorienting the coordinates axes if necessary)

Not a regular open set of class  $C^1$ :



An open set  $\Omega \subset \mathbb{R}^d$  is a regular open set of class  $C^1$  if for each point  $x_0 \in \partial \Omega$  there exist:

- $\bullet$  a radius r > 0 and
- a  $C^1$  function  $\gamma: \mathbb{R}^{d-1} \to \mathbb{R}$

such that

$$\Omega \cap B(x_0, r) = \{x \in B(x_0, r) : x_d > \gamma(x_1, \dots, x_{d-1})\}$$


(after reorienting the coordinates axes if necessary)

In other words, the boundary of  $\Omega$  is locally the graph of a  $C^1$  function.

### Definition II.2.1


Let  $\Omega$  will be a regular open set of class  $C^1$  bounded in one or more direction.

The outward unit normal vector field to  $\Omega$  is defined for each point of  $x \in \partial \Omega$  as the unit vector normal to the tangent plane to  $\Omega$  in x pointing towards the exterior.




It is usually denoted  $n(x) = [n_1(x), \dots, n_d(x)]^T$ .

Let d = 2 and  $\Omega$  be the open disk or radius 1 centered in (0,0).




Let d = 2 and  $\Omega$  be the open disk or radius 1 centered in (0,0).




$$\forall x = (x_1, x_2) \in \partial \Omega, \ n(x) = \begin{bmatrix} x_1 \\ x_2 \end{bmatrix}$$


Let d = 2 and  $\Omega$  be an open square.



Let d = 2 and  $\Omega$  be an open square.




Let d = 2 and  $\Omega$  be an open square.




$$\forall x = (x_1, x_2) \in \Gamma_1 \setminus \{A, B\}, \ n_1(x) = \begin{bmatrix} 1 \\ 0 \end{bmatrix}$$

Let d = 2 and  $\Omega$  be an open square.




$$\forall x \in \Gamma_1 \setminus \{A, B\}, \ n_1(x) = \begin{bmatrix} 1 \\ 0 \end{bmatrix}$$

Let d = 2 and  $\Omega$  be an open square.




Let d = 2 and  $\Omega$  be an open square.

Denote A, B, C, D its vertices and  $\Gamma_1$ ,  $\Gamma_2$ ,  $\Gamma_3$  and  $\Gamma_4$  its edges.  $\partial\Omega = \Gamma_1 \cup \Gamma_2 \cup \Gamma_3 \cup \Gamma_4$ .




Note:  $\Omega$  is not a regular open set and we cannot compute the unit outward normal vector field on the entire boundary (vertices)

Let 
$$d = 3$$
 and  $\Omega = \{(x, y, z) \in \mathbb{R}^3, z \leq \frac{1}{1 + x^2 + y^2}\}.$ 



Let 
$$d=3$$
 and  $\Omega=\left\{(x,y,z)\in\mathbb{R}^3,\ z\leq \frac{1}{1+x^2+y^2}\right\}$ .



Let 
$$f(x, y) = \frac{1}{1+x^2+y^2}$$
.

Can we characterize the normal field at (x, y)?

Definitions
Differential Calculus
The importance of PDEs in modeling
Outline of the work to be done

Outward Normal Vector Field Partial Derivatives Integration by Parts in Higher dimension

### II.2.2. Partial Derivatives

# Differentiability

Let  $d, N \in \mathbb{N}^*$  and  $U \subset \mathbb{R}^d$  be a non-empty open set.

### **Definition**

The function  $f: U \to \mathbb{R}^N$  is differentiable at  $x_0 \in U$  if there exists

- ullet a linear application  $L:\mathbb{R}^d o \mathbb{R}^N$  and
- a neighborhood  $V \in \mathcal{V}(x_0)$

such that

$$\forall x \in V, \quad f(x) - f(x_0) = L(x - x_0) + o(||x - x_0||).$$

# Partial Derivatives and Differential

## Definition (Partial Derivatives)

Let  $\mathbf{B} = (e_1, \dots, e_d)$  be a basis of  $\mathbb{R}^d$ . For  $i \in \{1, \dots, d\}$ , we note

$$\frac{\partial f}{\partial x_i}(x_0) = \lim_{s \in \mathbb{R}, s \to 0} \frac{f(x_0 + se_i) - f(x_0)}{h}.$$

It is the **partial derivative** of f with respect to  $x_i$  in  $x_0$ . It is also denoted  $\partial_{x_i} f(x_0)$ .

## Definition (Differential)

Differential of 
$$f = \begin{bmatrix} f_1 \\ \vdots \\ f_N \end{bmatrix}$$
 in  $x_0$ :  $D f(x_0) = \begin{bmatrix} \partial_{x_1} f_1(x_0) & \dots & \partial_{x_d} f_1(x_0) \\ \vdots & \ddots & \vdots \\ \partial_{x_1} f_N(x_0) & \dots & \partial_{x_d} f_N(x_0) \end{bmatrix}$ 

## Case N=1

If N=1 then

- f is a scalar valued function
- L is a linear form

#### Definition

The **gradient** of f at  $x_0$ , denoted  $\operatorname{grad} f(x_0)$  or  $\nabla f(x_0)$ , is the vector such that  $\forall h \in \mathbb{R}^d$ ,  $Lh = \langle \nabla f(x_0), h \rangle_{\mathbb{R}^d}$ 

$$\nabla f(x_0) = \begin{bmatrix} \partial_{x_1} f(x_0) \\ \vdots \\ \partial_{x_d} f(x_0) \end{bmatrix}$$
 in the basis **B**

The components of the gradient are the coefficients appearing in the equation of the tangent space to the graph, which, in turn gives the components of the normal vector field.

## Case N = d

If N = d, then L is an endomorphism of  $\mathbb{R}^d$ .

### Definition

We call **divergence** of f at  $x_0$ , denoted div  $f(x_0)$  or  $\nabla \cdot f(x_0)$  the trace of the matrix  $Df(x_0)$ .

$$\nabla \cdot f(x_0) = \sum_{1 \le i \le d} \frac{\partial f_i}{\partial x_i}(x_0)$$
 in the basis **B**

The divergence of a vector field is a scalar function that measures the tendency of a vector field's to close in toward a point or to repel from a point.

# Laplace Operator

### Definition

The Laplace operator or Laplacian is a differential operator defined by the divergence of the gradient. It is denoted  $\Delta$ .

Let  $f: U \subset \mathbb{R}^d \to \mathbb{R}$ . The Laplacian of f at  $x_0$  is

$$\Delta f(x_0) = div(\nabla f)(x_0) = \frac{\partial^2 f}{\partial x_1^2}(x_0) + \ldots + \frac{\partial^2 f}{\partial x_d^2}(x_0).$$

The notation  $\nabla^2$  can also be found to represent the Laplacian.

## The multi-index notation

### Definition

A d-dimensional **multi-index** is an element of  $\mathbb{N}^d$ .

It is an d-tuple  $\alpha = (\alpha_1, \alpha_2, \dots, \alpha_d)$  of non-negative integers.

## Example

(1,0,4) is a 3-dimensional multi-index.

# The multi-index notation

### **Definition**

Let  $\alpha = (\alpha_1, \alpha_2, \dots, \alpha_d)$  be a d-dimensional **multi-index**. The sum of components is denoted  $|\alpha| = \alpha_1 + \alpha_2 + \dots + \alpha_d$ .

## Definition (Higher-order partial derivative)

Let  $\alpha = (\alpha_1, \alpha_2, \dots, \alpha_d)$  be a d-dimensional multi-index.

$$D^{\alpha} = \frac{\partial^{|\alpha|}}{\partial x_1^{\alpha_1} \partial x_2^{\alpha_2} \dots \partial x_d^{\alpha_d}}$$

## Example

Let  $\alpha = (1,0,4)$  and  $f : \mathbb{R}^3 \to \mathbb{R}$  be a  $C^5$ -function.

$$D^{\alpha}f = \frac{\partial^5 f}{\partial x_1 \partial x_3^4}$$

er II PDE - Lecture 3

Definitions
Differential Calculus
The importance of PDEs in modeling
Outline of the work to be done

Outward Normal Vector Field Partial Derivatives Integration by Parts in Higher dimension

II.2.3. Integration by Parts in Higher dimension

# Support

### Definition II.2.2


Let f be a function defined from an open interval  $I \subset \mathbb{R}$  to  $\mathbb{R}$ . The **support** of f, denoted  $\operatorname{supp}(f)$ , is the closure of the set of points where f does not vanish:

$$\operatorname{supp}(f) = \overline{\{x \in I \mid f(x) \neq 0\}}$$

## Example

$$f: \mathbb{R} \to \mathbb{R}$$
 $x \mapsto \begin{cases} 1 - x^2 & \text{if } |x| < 1 \\ 0 & \text{if } |x| \ge 1 \end{cases}$ 

$$\mathrm{supp}(f) = [-1, 1]$$



# Support


### Definition II.2.3

Let f be a function defined on  $\Omega \subset \mathbb{R}^d$ .

The **support** of f, denoted supp(f), is the closure of the set of points where f does not vanish:

$$\operatorname{supp}(f) = \overline{\{x \in \Omega \mid f(x) \neq 0\}}$$

## Example



The support is the closed disk centered in (0,0) with radius 1.

# Integration

## Theorem II.2.4 (Green's Formula)

Let  $u \in C^1(\overline{\Omega})$  with compact support in  $\overline{\Omega}$ . Then

$$\forall i \in \{1,\ldots,d\}, \quad \int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ dx = \int_{\partial \Omega} u(s) n_i(s) \ ds.$$

### Theorem II.2.4 (Green's Formula)

Let  $u \in C^1(\overline{\Omega})$  with compact support in  $\overline{\Omega}$ . Then

$$\forall i \in \{1,\ldots,d\}, \quad \int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ dx = \int_{\partial \Omega} u(s) n_i(s) \ ds.$$

#### Remark

If d = 1 and  $\Omega = ]a, b[$  with a < b,

$$\int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ dx = \int_{\partial \Omega} u(s) n_i(s) \ ds$$

$$\int_{\Omega} \frac{du}{dx}(x) \ dx = \int_{\{a,b\}} u(s) n(s)$$

### Theorem II.2.4 (Green's Formula)

Let  $u \in C^1(\overline{\Omega})$  with compact support in  $\overline{\Omega}$ . Then

$$\forall i \in \{1,\ldots,d\}, \quad \int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ dx = \int_{\partial \Omega} u(s) n_i(s) \ ds.$$

#### Remark

If d = 1 and  $\Omega = ]a, b[$  with a < b,

$$\int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ dx = \int_{\partial \Omega} u(s) n_i(s) \ ds$$

$$\int_{\Omega} \frac{du}{dx}(x) \ dx = \sum_{s \in \{a,b\}} u(s) n(s)$$

### Theorem II.2.4 (Green's Formula)

Let  $u \in C^1(\overline{\Omega})$  with compact support in  $\overline{\Omega}$ . Then

$$\forall i \in \{1,\ldots,d\}, \quad \int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ dx = \int_{\partial \Omega} u(s) n_i(s) \ ds.$$

#### Remark

If d = 1 and  $\Omega = ]a, b[$  with a < b,

$$\int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ dx = \int_{\partial \Omega} u(s) n_i(s) \ ds$$

$$\int_{\Omega} \frac{du}{dx}(x) \ dx = u(a)n(a) + u(b)n(b)$$

### Theorem II.2.4 (Green's Formula)

Let  $u \in C^1(\overline{\Omega})$  with compact support in  $\overline{\Omega}$ . Then

$$\forall i \in \{1,\ldots,d\}, \quad \int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ dx = \int_{\partial \Omega} u(s) n_i(s) \ ds.$$

#### Remark

If d = 1 and  $\Omega = ]a, b[$  with a < b,

$$\int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ dx = \int_{\partial \Omega} u(s) n_i(s) \ ds$$

$$\int_{\Omega} \frac{du}{dx}(x) \ dx = u(b) - u(a)$$

# Integration by parts

### Corollary II.2.5 (IP 1)

Let  $u, v \in C^1(\overline{\Omega})$  with compact support in  $\overline{\Omega}$ . Then  $\forall i \in \{1, \dots, d\}$ ,

$$\int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ v(x) \ d\lambda^{(d)} = - \int_{\Omega} u(x) \ \frac{\partial v}{\partial x_i}(x) \ d\lambda^{(d)} + \int_{\partial \Omega} uv \ n_i \ d\sigma.$$

# Integration by parts

### Corollary II.2.5 (IP 1)

Let  $u, v \in C^1(\overline{\Omega})$  with compact support in  $\overline{\Omega}$ . Then  $\forall i \in \{1, ..., d\}$ ,

$$\int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ v(x) \ d\lambda^{(d)} = -\int_{\Omega} u(x) \ \frac{\partial v}{\partial x_i}(x) \ d\lambda^{(d)} + \int_{\partial \Omega} uv \ n_i \ d\sigma.$$

### Corollary II.2.6 (IP 2)

Let  $u \in C^2(\overline{\Omega})$  and  $v \in C^1(\overline{\Omega})$  with compact support in  $\overline{\Omega}$ . Then

$$\int_{\Omega} (\Delta u) \, v = - \int_{\Omega} \nabla u \cdot \nabla v + \int_{\partial \Omega} v \, \nabla u \cdot n$$

# Integration by parts

### Corollary II.2.5 (IP 1)

Let  $u, v \in C^1(\overline{\Omega})$  with compact support in  $\overline{\Omega}$ . Then  $\forall i \in \{1, ..., d\}$ ,

$$\int_{\Omega} \frac{\partial u}{\partial x_i}(x) \ v(x) \ d\lambda^{(d)} = -\int_{\Omega} u(x) \ \frac{\partial v}{\partial x_i}(x) \ d\lambda^{(d)} + \int_{\partial \Omega} uv \ n_i \ d\sigma.$$

### Corollary II.2.6 (IP 2)

Let  $u \in C^2(\overline{\Omega})$  and  $v \in C^1(\overline{\Omega})$  with compact support in  $\overline{\Omega}$ . Then

$$\int_{\Omega} (\Delta u) \, v = - \int_{\Omega} \nabla u \cdot \nabla v + \int_{\partial \Omega} v \, \frac{\partial u}{\partial n}$$

where  $\frac{\partial u}{\partial n} = \nabla u \cdot n$  is called the **normal derivative**.

# II.3. The importance of PDEs in modeling

Definitions
Differential Calculus
The importance of PDEs in modeling
Outline of the work to be done

Temperature in a Reactor Air Pollution / Traffic Floo Black and Scholes


II.3.1. Temperature in a Reactor




Credit: Rendermedia Ltd.




Credit: Rendermedia Ltd.





$$\begin{array}{ll} \text{Variables:} & t \in [0, +\infty[, \\ & x \in \Omega \\ \\ \text{Unknown:} & (t, x) \mapsto \theta(t, x) \\ \\ \text{Data:} & \rho \text{ (density),} \\ & u \text{ (velocity),} \\ & f \text{ (source)} \\ \\ \text{Parameters:} & x \mapsto c_v(x), \\ & x \mapsto \kappa(x) > 0 \end{array}$$

We are interested in the temperature in this reactor.




$$\begin{array}{ll} \text{Variables:} & t \in [0, +\infty[, \\ & x \in \Omega \\ \\ \text{Unknown:} & (t, x) \mapsto \theta(t, x) \\ \\ \text{Data:} & \rho \text{ (density)}, \\ & u \text{ (velocity)}, \\ & f \text{ (source)} \\ \\ \text{Parameters:} & x \mapsto c_v(x), \\ & x \mapsto \kappa(x) > 0 \\ \end{array}$$

### Heat Equation:

$$\rho c_V \partial_t \theta + \operatorname{div}_X (\rho c_V \theta u) - \operatorname{div}_X (\kappa \nabla_X (\theta)) = f \text{ in } ]0, +\infty[ \times \Omega.$$

We are interested in the temperature in this reactor.




$$\begin{array}{ll} \text{Variables:} & t \in [0, +\infty[, \\ & x \in \Omega \end{array} \\ \text{Unknown:} & (t, x) \mapsto \theta(t, x) \\ \text{Data:} & \rho \text{ (density)}, \\ & u \text{ (velocity)}, \\ & f \text{ (source)} \\ \\ \text{Parameters:} & x \mapsto c_v(x), \\ & x \mapsto \kappa(x) > 0 \end{array}$$

Heat Equation when the fluid does not move:

$$\rho c_v \partial_t \theta + \operatorname{div}_{\mathsf{X}}(\rho c_v \theta u) - \operatorname{div}_{\mathsf{X}}(\kappa \nabla_{\mathsf{X}}(\theta)) = f \text{ in } ]0, +\infty[\times \Omega.$$


We are interested in the temperature in this reactor.




$$\begin{array}{ll} \text{Variables:} & t \in [0, +\infty[, \\ & x \in \Omega \end{array} \\ \text{Unknown:} & (t, x) \mapsto \theta(t, x) \\ \text{Data:} & \rho \text{ (density)}, \\ & u \text{ (velocity)}, \\ & f \text{ (source)} \\ \\ \text{Parameters:} & x \mapsto c_v(x), \\ & x \mapsto \kappa(x) > 0 \end{array}$$


Let us establish the heat equation when the fluid does not move:

$$\rho c_v \partial_t \theta + \operatorname{div}_{\mathsf{x}}(\rho c_v \theta u) - \operatorname{div}_{\mathsf{x}}(\kappa \nabla_{\mathsf{x}}(\theta)) = f \text{ in } ]0, +\infty[\times \Omega.$$





Density of energy in V:  $(t,x) \mapsto \rho c_v(x) \theta(t,x)$ 




Density of energy in V:

$$(t,x)\mapsto \rho c_{\nu}(x)\theta(t,x)$$

Energy in V:

$$t \mapsto \iiint_{V} \rho c_{\nu}(x) \theta(t, x) \, dx$$



Density of energy in V:  $(t,x) \mapsto \rho c_v(x) \theta(t,x)$ 


$$(t,x)\mapsto \rho c_{\nu}(x)\theta(t,t)$$

Energy in V:

$$t \mapsto \iiint_V \rho c_v(x) \theta(t, x) dx$$

Energy flux through  $\partial V$ :

$$(t,s)\mapsto q(t,s)$$



Density of energy in V:

$$(t,x)\mapsto \rho c_v(x)\theta(t,x)$$

Energy in V:


$$t \mapsto \iiint_V \rho c_v(x) \theta(t,x) dx$$

Energy flux through  $\partial V$ :

$$(t,s)\mapsto q(t,s)$$

Energy sources/sinks in V:

$$(t,x)\mapsto f(t,x)$$



Density of energy in V:

$$(t,x)\mapsto \rho c_v(x)\theta(t,x)$$

Energy in V:

$$t \mapsto \iiint_V \rho c_v(x) \theta(t, x) \, dx$$

Energy flux through  $\partial V$ :

$$(t,s)\mapsto q(t,s)$$

Energy sources/sinks in V:

$$(t,x)\mapsto f(t,x)$$

$$\frac{d}{dt} \iiint_{V} \rho c_{V}(x) \theta(t,x) dx = - \iint_{\partial V} q(t,s) \cdot n(s) ds + \iiint_{V} f(t,x) dx$$

$$\frac{d}{dt} \iiint_{V} \rho c_{V}(x) \theta(t,x) dx = - \iint_{\partial V} q(t,s) \cdot n(s) ds + \iiint_{V} f(t,x) dx$$

$$\underbrace{\frac{d}{dt} \iiint_{V} \rho c_{v}(x) \theta(t,x) dx}_{=\iiint_{V} \partial_{t}(\rho c_{v} \theta)(t,x) dx} = -\iint_{\partial V} q(t,s) \cdot n(s) ds + \iiint_{V} f(t,x) dx$$

$$\iiint_{V} \partial_{t}(\rho c_{v}\theta)(t,x) dx = -\iint_{\partial V} q(t,s) \cdot n(s) ds + \iiint_{V} f(t,x) dx$$

$$\iiint_{V} \partial_{t}(\rho c_{v}\theta)(t,x) dx = -\iint_{\partial V} q(t,s) \cdot n(s) ds + \iiint_{V} f(t,x) dx$$

Green's formula (Theorem II.2.4) for  $w \in (C^1(\overline{\Omega}))^3$ :

$$\iint_{\partial V} w(s) \cdot n(s) ds = \iiint_{V} \operatorname{div}_{x}(w)(x) dx$$

$$\iiint_{V} \partial_{t}(\rho c_{v}\theta)(t,x) dx = -\iint_{\partial V} q(t,s) \cdot n(s) ds + \iiint_{V} f(t,x) dx$$

$$\iiint_{V} (\rho c_{v})(x) \partial_{t} \theta(t, x) dx + \iiint_{V} \operatorname{div}_{x}(q)(t, x) dx = \iiint_{V} f(t, x) dx$$

$$\iiint_{V} \partial_{t}(\rho c_{v}\theta)(t,x) dx = -\iint_{\partial V} q(t,s) \cdot n(s) ds + \iiint_{V} f(t,x) dx$$

$$\iiint_{V} (\rho c_{v})(x) \partial_{t} \theta(t, x) dx + \iiint_{V} \operatorname{div}_{x}(q)(t, x) dx = \iiint_{V} f(t, x) dx$$

This is true for all *V* thus

$$\forall t > 0, \ \forall x \in \Omega, \ (\rho c_v)(x) \, \partial_t \theta(t, x) + \operatorname{div}_x(q)(t, x) = f(t, x)$$

$$\forall t > 0, \ \forall x \in \Omega, \quad \rho c_{\nu}(x) \partial_t \theta(t, x) + \operatorname{div}_{x}(q)(t, x) = f(t, x)$$

This is not a PDE yet. We need to link q to  $\theta$ .

$$\forall t > 0, \ \forall x \in \Omega, \quad \rho c_v(x) \partial_t \theta(t, x) + \operatorname{div}_x(q)(t, x) = f(t, x)$$

This is not a PDE yet. We need to link q to  $\theta$ .

The Fourier law gives:  $q = -\kappa \nabla_{\mathsf{x}}(\theta)$ 

$$\forall t > 0, \ \forall x \in \Omega, \quad \rho c_v(x) \partial_t \theta(t, x) + \operatorname{div}_x(q)(t, x) = f(t, x)$$

This is not a PDE yet. We need to link q to  $\theta$ .

The Fourier law gives:  $q = -\kappa \nabla_x(\theta)$ We derive:

$$\rho c_{\mathsf{v}} \partial_t \theta - \mathsf{div}_{\mathsf{v}}(\kappa \nabla_{\mathsf{v}}(\theta)) = f \text{ in } \mathbb{R}^{+*} \times \Omega$$

# Initial conditions / Boundary conditions

- Initial Condition When t = 0:  $\theta^0$  is given. (Cauchy)
- Boundary Condition On  $\partial\Omega$  :
  - A set value:  $\theta|_{\partial\Omega} = g$  given. **Dirichlet**
  - A set flow:  $\nabla_x(\theta)|_{\partial\Omega} \cdot n = h$  given. **Neumann**
  - Both:  $\partial \Omega = \partial \Omega_D \sqcup \partial \Omega_N : \theta|_{\partial \Omega_D} = g$  and  $\nabla_x(\theta)|_{\partial \Omega_N} n = h$

# From Physics to Mathematics

In mathematics, the quantities are dimensionless. We need to go through a nondimensionalization.

Name	Variable	Unit	Nondimensionalization
Time (s)	t	Т	$t = Tt^*$
Length (m)	x	L	$x = Lx^*$
Temperature $(K)$	$\theta$	Θ	$\theta = \Theta \theta^*$
Velocity $(m.s^{-1})$	и	U	$u = Uu^*$
Th. Cond. $(W.m^{-1}.K^{-1})$	$\kappa$	$\mathcal{K}$	$\kappa = \mathcal{K}\kappa^*$
Source $(kg.m^2.s^{-3})$	f	F	$f = Ff^*$

# Nondimensionalized equation

$$\begin{cases} \partial_t \theta = \frac{1}{T} \partial_{t^*} \theta \\ \partial_{x_i} \theta = \frac{1}{L} \partial_{x_i^*} \theta \\ \operatorname{div}_x \theta = \frac{1}{L} \operatorname{div}_{x^*} \theta \end{cases}$$

# Nondimensionalized equation

$$\begin{cases} \partial_t \theta = \frac{1}{T} \partial_{t^*} \theta \\ \partial_{x_i} \theta = \frac{1}{L} \partial_{x_i^*} \theta \\ \operatorname{div}_x \theta = \frac{1}{L} \operatorname{div}_{x^*} \theta \end{cases}$$

In the equation

$$\frac{\rho c_v \Theta}{T} \partial_{t^*} \theta^* + \frac{\rho c_v \Theta U}{L} \text{div}_{x^*} (\theta^* u^*) - \frac{\Theta \mathcal{K}}{L^2} \Delta_{x^*} \theta^* = F f^*$$

## Nondimensionalized equation

$$\begin{cases} \partial_t \theta = \frac{1}{T} \partial_{t^*} \theta \\ \partial_{x_i} \theta = \frac{1}{L} \partial_{x_i^*} \theta \\ \operatorname{div}_x \theta = \frac{1}{L} \operatorname{div}_{x^*} \theta \end{cases}$$

Finally:

$$1 \, \partial_{t^*} \theta^* + \frac{T}{T_C} \mathsf{div}_{\mathsf{X}^*} (\theta^* \, u^*) - \frac{T}{T_D} \Delta_{\mathsf{X}^*} \theta^* = \frac{T}{T_S} f^*$$

With characteristic times

$$T_C = rac{L}{U}, \qquad T_D = rac{
ho c_v L^2}{\mathcal{K}} \qquad ext{et} \qquad T_S = rac{
ho c_v \Theta}{F}.$$

$$\partial_t \theta + \frac{T}{T_C} \operatorname{div}_X(\theta \, u) - \frac{T}{T_D} \Delta_X \theta = \frac{T}{T_S} f$$

Behavior	Equation	Туре

$$\partial_t \theta + \frac{T}{T_C} \operatorname{div}_X(\theta u) - \frac{T}{T_D} \Delta_X \theta = \frac{T}{T_S} f$$

Behavior	Equation	Туре
$T \ll T_D, T_C$	$\partial_t \theta = f$	ODE

$$\partial_t \theta + \frac{T}{T_C} \operatorname{div}_X(\theta u) - \frac{T}{T_D} \Delta_X \theta = \frac{T}{T_S} f$$

Behavior	Equation	Туре
$T \ll T_D, T_C$	$\partial_t \theta = f$	ODE
$T >> T_C >> T_D$	$-\Delta_{x}\theta=f$	diffusion (steady)

$$\partial_t \theta + \frac{T}{T_C} \operatorname{div}_X(\theta u) - \frac{T}{T_D} \Delta_X \theta = \frac{T}{T_S} f$$

Behavior	Equation	Туре
$T \ll T_D, T_C$	$\partial_t \theta = f$	ODE
$T >> T_C >> T_D$	$-\Delta_{\scriptscriptstyle X}  heta = f$	diffusion (steady)
$T \sim T_D << T_C$	$\partial_t \theta - \Delta_x \theta = f$	diffusion time-dep.
1		I

$$\partial_t \theta + \frac{T}{T_C} \operatorname{div}_X(\theta \, u) - \frac{T}{T_D} \Delta_X \theta = \frac{T}{T_S} f$$

Behavior	Equation	Туре
$T << T_D, T_C$	$\partial_t \theta = f$	ODE
$T >> T_C >> T_D$	$-\Delta_{x}  heta = f$	diffusion (steady)
$T \sim T_D << T_C$	$\partial_t \theta - \Delta_x \theta = f$	diffusion time-dep.
$T \sim T_C << T_D$	$\partial_t \theta + div_{x}(\theta u) = f$	transport
		l

$$\partial_t \theta + \frac{T}{T_C} \operatorname{div}_X(\theta \, u) - \frac{T}{T_D} \Delta_X \theta = \frac{T}{T_S} f$$

Behavior	Equation	Туре
$T \ll T_D, T_C$	$\partial_t \theta = f$	ODE
$T >> T_C >> T_D$	$-\Delta_{x}  heta = f$	diffusion (steady)
$T \sim T_D << T_C$	$\partial_t \theta - \Delta_x \theta = f$	diffusion time-dep.
$T \sim T_C << T_D$	$\partial_t \theta + div_x(\theta u) = f$	transport
$T_D \sim T \sim T_C$	$\partial_t \theta + \operatorname{div}_x(\theta u) - \Delta_x \theta = f$	transport-diffusion time-dep.

Definitions
Differential Calculus
The importance of PDEs in modeling
Outline of the work to be done

Temperature in a Reactor Air Pollution / Traffic Flow Black and Scholes

II.3.2. Air Pollution / Traffic Flow

# The Transport equation can be used to model air pollution

Consider the transport equation.

$$\begin{cases} \partial_t u + c \cdot \nabla_x u = f & \text{in } ]0, +\infty[\times \mathbb{R} \\ u(0, \cdot) = u_0 & \text{on } \mathbb{R} \end{cases}$$

where c > 0 is a constant and f is a given function.

It can be used to model the air pollution.

u represents the density of pollutant.

## The Transport equation can be used to model traffic flow

Consider the transport equation in one (space) dimension (note: d = 2).

$$\begin{cases} \partial_t u + c \, \partial_x u = f & \text{in } ]0, +\infty[\times \mathbb{R} \\ u(0, \cdot) = u_0 & \text{on } \mathbb{R} \end{cases}$$

where c > 0 is a constant and f is a given function.

It can be used to model the traffic flow.

*u* represents the density of vehicles.

Consider the transport equation in one dimension (note: d = 2).

$$\begin{cases} \partial_t u + c \, \partial_x u = 0 & \text{in } ]0, +\infty[\times \mathbb{R} \\ u(0, \cdot) = u_0 & \text{on } \mathbb{R} \end{cases}$$

where c > 0 is a constant.

#### **Characteristics:**

Find  $t \mapsto X(t)$  s.t.  $w : t \mapsto u(t, X(t))$  is constant.

Consider the transport equation in one dimension (note: d = 2).

$$\begin{cases} \partial_t u + c \, \partial_x u = 0 & \text{in } ]0, +\infty[\times \mathbb{R} \\ u(0, \cdot) = u_0 & \text{on } \mathbb{R} \end{cases}$$

where c > 0 is a constant.

#### **Characteristics:**

Find  $t \mapsto X(t)$  s.t.  $w : t \mapsto u(t, X(t))$  is constant.

$$\frac{dw}{dt} = \partial_t u + \frac{dX}{dt} \partial_x u$$

Consider the transport equation in one dimension (note: d = 2).

$$\begin{cases} \partial_t u + c \, \partial_x u = 0 & \text{in } ]0, +\infty[\times \mathbb{R} \\ u(0, \cdot) = u_0 & \text{on } \mathbb{R} \end{cases}$$

where c > 0 is a constant.

#### **Characteristics:**

Find  $t \mapsto X(t)$  s.t.  $w : t \mapsto u(t, X(t))$  is constant.

$$\frac{dw}{dt} = \partial_t u + \frac{dX}{dt} \partial_x u$$

If  $\frac{dX}{dt} = c$  then  $\frac{dw}{dt} = 0$  then w is constant.

Consider the transport equation in one dimension (note: d = 2).

$$\begin{cases} \partial_t u + c \, \partial_x u = 0 & \text{in } ]0, +\infty[\times \mathbb{R} \\ u(0, \cdot) = u_0 & \text{on } \mathbb{R} \end{cases}$$

where c > 0 is a constant.

#### **Characteristics:**

Find  $t \mapsto X(t)$  s.t.  $w : t \mapsto u(t, X(t))$  is constant.

$$\frac{dw}{dt} = \partial_t u + \frac{dX}{dt} \partial_x u$$

If 
$$\frac{dX}{dt} = c$$
 then  $\frac{dw}{dt} = 0$  then  $w$  is constant. Thus  $X(s) = cs + X(0)$ 

Consider the transport equation in one dimension (note: d = 2).

$$\begin{cases} \partial_t u + c \, \partial_x u = 0 & \text{in } ]0, +\infty[\times \mathbb{R} \\ u(0, \cdot) = u_0 & \text{on } \mathbb{R} \end{cases}$$

where c > 0 is a constant.

#### **Characteristics:**

Find  $t \mapsto X(t)$  s.t.  $w : t \mapsto u(t, X(t))$  is constant.

$$\frac{dw}{dt} = \partial_t u + \frac{dX}{dt} \partial_X u$$

If 
$$\frac{dX}{dt} = c$$
 then  $\frac{dw}{dt} = 0$  then  $w$  is constant. Thus  $X(s) = cs + X(0)$  therefore  $u(t, X(t)) = u^0(X(0))$ 

Definitions
Differential Calculus
The importance of PDEs in modeling
Outline of the work to be done

Temperature in a Reactor Air Pollution / Traffic Flo Black and Scholes

II.3.3. Black and Scholes

Consider a contract giving the right to buy or sell a stock at a date T at a strike price K.

Consider a contract giving the right to buy or sell a stock at a date T at a strike price K.

In finance, such a contract is called an option.

Consider a contract giving the right to buy or sell a stock at a date T at a strike price K.

In finance, such a contract is called an option.

In the 1970's, Robert C. Merton, Fischer Black and Myron Scholes showed that buying and selling in just the right way removes any risk.







source: wikipedia images

Consider a contract giving the right to buy or sell a stock at a date T at a strike price K.

In finance, such a contract is called an option.

In the 1970's, Robert C. Merton, Fischer Black and Myron Scholes showed that buying and selling in just the right way removes any risk. This implies there is a unique "right price" for the option.

Consider a contract giving the right to buy or sell a stock at a date T at a strike price K. With some hypotheses, we derive

$$\begin{cases} \frac{\partial u}{\partial t} - \frac{1}{2}\sigma^2 x^2 \frac{\partial^2 u}{\partial x^2} + rx \frac{\partial u}{\partial x} - ru = 0 \\ u(x, T) = \max(x - K, 0) \\ u(0, t) = 0 \text{ and } \lim_{x \to \infty} \frac{u(x, t)}{x} = 1 \end{cases}$$

#### where

- $t \in [0, T]$  is the time
- x(t) the price of the stock at time t,
- K the strike price
- u(x(t), t) is the price of the option
- r is the annualized risk-free interest rate
- $\bullet$   $\sigma$  is the standard deviation of the stock's returns.

Definitions
Differential Calculus
The importance of PDEs in modeling
Outline of the work to be done

II.4. Outline of the work to be done

(From the general introduction)

We would like wellposedness theorems for elliptic PDEs.

(From the general introduction)

We would like wellposedness theorems for elliptic PDEs.

#### We need:

- The theory of distributions: Chapter III. On Friday
- The variational formulation: Chapter IV. Next Week.

(From the general introduction)

We would like wellposedness theorems for elliptic PDEs.

#### We need:

- The theory of distributions: Chapter III. On Friday
- The variational formulation: Chapter IV. Next Week.

Then, we will approximate the solutions of the elliptic PDEs.

(From the general introduction)

We would like wellposedness theorems for elliptic PDEs.

#### We need:

- The theory of distributions: Chapter III. On Friday
- The variational formulation: Chapter IV. Next Week.

Then, we will approximate the solutions of the elliptic PDEs. After which, we will discuss parabolic PDEs.