Readers Writer Problem

Readers writer problem is another example of a classic synchronization problem. There are many variants of this problem, one of which is examined below.

The Problem Statement

There is a shared resource which should be accessed by multiple processes.

There are two types of processes in this context. They are **reader** and **writer**. Any number of **readers** can read from the shared resource simultaneously, but only one **writer** can write to the shared resource.

When a **writer** is writing data to the resource, no other process can access the resource. A **writer** cannot write to the resource if there are non-zero number of readers accessing the resource at that time.

The Solution

From the above problem statement, it is evident that readers have higher priority than writer.

If a writer wants to write to the resource, it must wait until there are no readers currently accessing that resource.

Here, we use one **mutex** m and a **semaphore** w. An integer variable **read_count** is used to maintain the number of readers currently accessing the resource.

The variable read_count is initialized to 0. A value of 1 is given initially to m and w.

Instead of having the process to acquire lock on the shared resource, we use the mutex m to make the process to acquire and release lock whenever it is updating the read_count variable.

The code for the **writer** process looks like this:

```
while(TRUE)
{
    wait(w);

    /* perform the write operation */
    signal(w);
}
```

And, the code for the **reader** process looks like this:

```
while (TRUE)
    //acquire lock
    wait(m);
    read count++;
    if(read count == 1)
        wait(w);
    //release lock
    signal(m);
    /* perform the reading operation */
    // acquire lock
    wait(m);
    read count--;
    if(read count == 0)
        signal(w);
    // release lock
    signal(m);
}
```

Here is the Code uncoded (explained)

- As seen above in the code for the writer, the writer just waits on the w semaphore until it gets a chance to write to the resource.
- After performing the write operation, it increments **w** so that the next writer can access the resource.
- On the other hand, in the code for the reader, the lock is acquired whenever the **read_count** is updated by a process.
- When a reader wants to access the resource, first it increments the **read_count** value, then accesses the resource and then decrements the **read_count** value.
- The semaphore **w** is used by the first reader which enters the critical section and the last reader which exits the critical section.
- The reason for this is, when the first readers enters the critical section, the writer is blocked from the resource. Only new readers can access the resource now.
- Similarly, when the last reader exits the critical section, it signals the writer using the w semaphore because there are zero readers now and a writer can have the chance to access the resource.