# Earth 121 Notes

# Contents

1	Cha	apter 1 Introduction	5
	1.1	The Science of Geology	5
	1.2	Geologic Time	5
	1.3	Early Evolution of Earth	5
	1.4	Plate Tectonics	6
	1.5	Planet of Shifting Plates	6
	1.6	Earth's Internal Structure	7
	1.7	Earth's Spheres	7
	1.8	The Face of Earth	8
	1.9	Rock Cycle	8
	1.9	TOOK Cycle	O
<b>2</b>	$\mathbf{C}\mathbf{h}$	12 (272-277): A Scientific Revolution Begins	8
_	2.1	Sea-floor Spreading Hypothesis	8
	2.2	Geomagnetic Reversals	8
	$\frac{2.2}{2.3}$	Last Puzzle Piece	8
	2.3	Last Fuzzie Fiece	0
3	Cha	apter 2 Minerals	8
J	3.1	Composition of Minerals	9
	3.2	Structure of Minerals	9
	3.3	Physical Properties of Minerals	9
	3.4	Mineral Classes	9
	3.5	Silicates	9
	3.6		10
	3.7	Nonsilicate Minerals	10
4	CI-	F (100 190)	11
4			$\frac{11}{11}$
	4.1		11
	4.2	8	11
	4.3		11
	4.4	8	11
	4.5	Rates of Weathering	12
_	~.		
5		0	12
	5.1		12
	5.2		12
	5.3	O I	13
	5.4	Igneous Texture	13
	5.5	Naming Igneous Rocks	14
		5.5.1 Felsic(Granitic)	14
		5.5.2 Intermediate	15
			16
			16
	5.6	·	16
	5.7		17
	5.8		17
	9.0	Daymontus	Τ1
6	Cha	apter 4: Volcanoes	17

	6.1	The Nature of Volcanic Eruptions	
	6.2	Materials Extruded Duraing Eruption	
	6.3	Volcanic Structures and Eruptive Styles	18
7		apter 6: Sedimentary Rocks	21
	7.1	What is a Sedimentary Rock	21
	7.2	Turning Sediment to Rock	21
	7.3	Environments	21
	7.4	Types of Sedimentary Rocks	22
	7.5	Detrital Sedimentary Rocks	22
		7.5.1 Mudrocks	22
		7.5.2 Sandstone	22
		7.5.3 Conglomerate and Breccia	23
	7.6	Chemical Sedimentary Rocks	23
		7.6.1 Limestone	23
		7.6.2 Dolostone	23
		7.6.3 Chert	23
		7.6.4 Evaporites	23
	7.7	Coal	$\frac{25}{24}$
	7.8	Classification of Sedimentary Rocks	24
	7.9	Sedimentary Stuctures	$\frac{24}{24}$
	1.10	Fossils	25
8	Cha	apter 7: Metamorphic Rock	25
G	8.1	Metamorphism	25
	8.2	Controlling Factors in Metamorphism	$\frac{25}{25}$
	0.2	•	
		8.2.1 Heat as a Metamorphic Agent	25
		8.2.2 Pressure as a Metamorphic Agent	25
	0.0	8.2.3 Chemically Active Fluids	26
	8.3	Metamorphic Grade and Index Minerals	26
	8.4	Burial Metamorphism	26
	8.5	Contact Metamorphism	26
	8.6	Regional Metamorphism	26
		8.6.1 Regional Metamorphism and Shale	26
		8.6.2 Regional Metamorphism and Basalt	27
		8.6.3 Upper Limit of Regional Metamorphism	27
		8.6.4 Regional Metamorphism and Nonfoliated Rocks	27
	8.7	Subduction Zone Metamorphism	27
	8.8	Metamorphic Facies and Plate Tectonics	28
	8.9	Ancient Metamorphic Environments	28
9	Cha	apter 8: Geologic Time	28
	9.1	Relative Dating	28
		9.1.1 Geologic Time	28
		9.1.2 Law of Superposition	28
		9.1.3 Principle of Original Horizontality	28
		9.1.4 Principle of Cross Cutting Relations	28
		9.1.5 Inclusion	28
		9.1.6 Unconformities	28
	9.2	Correlation of Rock Layers	29
	0.2	9.2.1 Correlation by Physical Criteria	29
		9.2.2 Fossils and Correlation	29
	9.3	Dating with Radioactivity	29
	ჟ.ა	· · · · · · · · · · · · · · · · · · ·	29 29
		v	
		9.3.2 Half Life	29
		9.3.3 Radiometric Dating	29
	0.4	9.3.4 Dating with Carbon-14	30
	9.4	Geologic Time Scale	30
		9.4.1 Structure of the Time Scale	30

9.5	Difficulties Dating the Geologic Time Scale	30
10 Cha	apter 9: Crustal Deformation	30
		30
		31
		31
10.3	*	31
10.0		31
	V I	31
10.4		31
		31
10.0		31
	1 1	32
	10.9.2 Strike Stip Tautos	02
11 Cha	apter 20: Minerals and Energy Resources	32
11.1	Metallic Minerals	32
	11.1.1 Magmatic Deposits	32
	11.1.2 Hydrothermal Deposits	32
		32
		33
		33
	v 1	33
	± ±	33
11.2	0 1	34
		34
	90 0	34
11.3		34
	90	34
		35
11.4		35
		35
		36
	30	36
	Ot a second seco	36
		36
		36
11.8		36
11.0		00
12 Cha	apter 10	<b>38</b>
12.1	1	38
	12.1.1 Earthquakes and Faults	38
	12.1.2 Elastic Rebound	38
	12.1.3 Foreshocks and Aftershocks	38
12.2	Seismology	38
12.3	Locating the Source of an Earthquake	38
	12.3.1 Earthquake Belts	38
12.4	Measuring the Size of Earthquakes	39
	12.4.1 Intensity Scales	39
		39
12.5	Earthquake Destruction	39
	•	39
		39
		40
		40
12.6		40
· ·		40
	· · · · · · · · · · · · · · · · · · ·	40
12.7		40
		40

	12.7.2 Seismic Waves and Earth's Structure	40
12.8	B Discovering Earth's Major Boundaries	41
	12.8.1 The Crust-Mantel Boundary	
	12.8.2 The Core-Mantle Boundary	
	12.8.3 Disovery of the Inner Core	
	·	
13 Cha	apter 14	41
13.1	Mass Wasting and Landform Development	41
	13.1.1 The Role of Mass Wasting	
	13.1.2 Slopes Change through Time	
13.2	Controls and Triggers	
	13.2.1 The Role of Water	
	13.2.2 Oversteepened Slopes	
	13.2.3 Removal of Vegetation	
	13.2.4 Earthquakes as Triggers	
	13.2.5 Liquefaction	
12 2	3 Classification of Mass Wasting	
10.0	13.3.1 Type of Motion	
	V.	
	13.3.2 Type of Material	
40.4	13.3.3 Rate of Movement	
	1 Slump	
	S Rock Slide	
13.6	6 Debris Flow	
	13.6.1 Lahars	
	Earthflow	
13.8	B Slow Movements	43
	13.8.1 Creep	43
	13.8.2 Solifluction	44
	13.8.3 Other Periglacial Features	44
~.		
	apter 15	44
	Hydrologic Cycle	44
14.1	Hydrologic Cycle	44
14.1 14.2	Hydrologic Cycle	44 44 44 44
14.1 14.2	Hydrologic Cycle	44 44 44 44 44
14.1 14.2	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  Basic Components of a Stream  Streamflow  14.3.1 Gradient and Channel Characteristics	44 44 44 44 44
14.1 14.2	Hydrologic Cycle	44 44 44 44 44
14.1 14.2 14.3	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  2 Basic Components of a Stream  3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream	44 44 44 44 44 45
14.1 14.2 14.3	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  Basic Components of a Stream  Streamflow  14.3.1 Gradient and Channel Characteristics	44 44 44 44 45 45
14.1 14.2 14.3	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  2 Basic Components of a Stream  3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  4 Stream Erosion	44 44 44 44 45 45 45
14.1 14.2 14.3	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  2 Basic Components of a Stream  3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  4 Stream Erosion  5 Transport of Sediment by Streams	44 44 44 44 45 45 45 45
14.1 14.2 14.3	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  Basic Components of a Stream  Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  Stream Erosion  Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load	44 44 44 45 45 45 45 45 45
14.1 14.2 14.3	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  Basic Components of a Stream  Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  Stream Erosion  Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load	44 44 44 45 45 45 45 45 45
14.1 14.2 14.3 14.4 14.5	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  Basic Components of a Stream  Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  Stream Erosion  Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence	44 44 44 44 45 45 45 45 45 45
14.1 14.2 14.3 14.4 14.5	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  Basic Components of a Stream  Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  Stream Erosion  Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence  Deposition of Sediment by Streams	44 44 44 45 45 45 45 45 45 45 45 45 45 4
14.1 14.2 14.3 14.4 14.5	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  2 Basic Components of a Stream  3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  4 Stream Erosion  5 Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence  5 Deposition of Sediment by Streams  14.6.1 Channel Deposits	44 44 44 45 45 45 45 45 45 45 45 45 45 4
14.1 14.2 14.3 14.4 14.5	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  Basic Components of a Stream  Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  Stream Erosion  Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence  Deposition of Sediment by Streams  14.6.1 Channel Deposits  14.6.2 Floodplain Deposites	44 44 44 45 45 45 45 45 45 45 45 45 45 4
14.1 14.2 14.3 14.4 14.5	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  2 Basic Components of a Stream  3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  4 Stream Erosion  5 Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence  5 Deposition of Sediment by Streams  14.6.1 Channel Deposits  14.6.2 Floodplain Deposites  7 The Graded Stream Concept and Base Level	44 44 44 45 45 45 45 45 45 45 45 46 46
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  2 Basic Components of a Stream  3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  4 Stream Erosion  5 Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence  5 Deposition of Sediment by Streams  14.6.1 Channel Deposits  14.6.2 Floodplain Deposites  7 The Graded Stream Concept and Base Level  8 Stream Valleys	44 44 44 45 45 45 45 45 45 45 45 46 46
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  2 Basic Components of a Stream  3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  4 Stream Erosion  5 Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence  5 Deposition of Sediment by Streams  14.6.1 Channel Deposits  14.6.2 Floodplain Deposites  7 The Graded Stream Concept and Base Level  8 Stream Valleys  9 Types of Stream Systems	44 44 44 45 45 45 45 45 45 45 45 45 46 46
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  2 Basic Components of a Stream  3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  4 Stream Erosion  5 Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence  5 Deposition of Sediment by Streams  14.6.1 Channel Deposits  14.6.2 Floodplain Deposites  7 The Graded Stream Concept and Base Level  8 Stream Valleys  1 Types of Stream Systems  14.9.1 Braided Streams	44 44 44 45 45 45 45 45 45 45 45 46 46 46
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow 2 Basic Components of a Stream 3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream 4 Stream Erosion 5 Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence 5 Deposition of Sediment by Streams  14.6.1 Channel Deposits  14.6.2 Floodplain Deposites  7 The Graded Stream Concept and Base Level 8 Stream Valleys  0 Types of Stream Systems  14.9.1 Braided Streams  14.9.2 Meandering Streams	44 44 44 45 45 45 45 45 45 45 45 45 46 46 46
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8 14.9	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow 2 Basic Components of a Stream 3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream 4 Stream Erosion 5 Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence 5 Deposition of Sediment by Streams  14.6.1 Channel Deposits  14.6.2 Floodplain Deposites  7 The Graded Stream Concept and Base Level 8 Stream Valleys  0 Types of Stream Systems  14.9.1 Braided Streams  14.9.2 Meandering Streams  14.9.3 Anastomosed Streams  14.9.3 Anastomosed Streams	44 44 44 45 45 45 45 45 45 45 45 46 46 46 46
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8 14.9	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  2 Basic Components of a Stream  3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  4 Stream Erosion  5 Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence  5 Deposition of Sediment by Streams  14.6.1 Channel Deposits  14.6.2 Floodplain Deposites  The Graded Stream Concept and Base Level  8 Stream Valleys  7 Types of Stream Systems  14.9.1 Braided Streams  14.9.2 Meandering Streams  14.9.3 Anastomosed Streams  10.0 Alluvial Fans and Deltas	44 44 44 45 45 45 45 45 45 45 46 46 46 46 46 47
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8 14.9	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow  2 Basic Components of a Stream  3 Streamflow  14.3.1 Gradient and Channel Characteristics  14.3.2 Discharge and Changes Downstream  4 Stream Erosion  5 Transport of Sediment by Streams  14.5.1 Dissolved Load  14.5.2 Suspended Load  14.5.3 Bed Load  14.5.4 Capacity and Competence  5 Deposition of Sediment by Streams  14.6.1 Channel Deposits  14.6.2 Floodplain Deposites  7 The Graded Stream Concept and Base Level  8 Stream Valleys  9 Types of Stream Systems  14.9.1 Braided Streams  14.9.2 Meandering Streams  14.9.3 Anastomosed Streams  10Alluvial Fans and Deltas  14.10.1 Alluvial Fans and Deltas	44 44 44 45 45 45 45 45 45 45 45 46 46 46 46 46 47
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8 14.9	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow 2 Basic Components of a Stream 3 Streamflow 14.3.1 Gradient and Channel Characteristics 14.3.2 Discharge and Changes Downstream 4 Stream Erosion 5 Transport of Sediment by Streams 14.5.1 Dissolved Load 14.5.2 Suspended Load 14.5.3 Bed Load 14.5.4 Capacity and Competence 5 Deposition of Sediment by Streams 14.6.1 Channel Deposits 14.6.2 Floodplain Deposites 7 The Graded Stream Concept and Base Level 8 Stream Valleys 0 Types of Stream Systems 14.9.1 Braided Streams 14.9.2 Meandering Streams 14.9.3 Anastomosed Streams 14.9.3 Anastomosed Streams 10.4lluvial Fans and Deltas 14.10.1 Alluvial Fans 14.10.2 Deltas	44 44 44 45 45 45 45 45 45 45 45 46 46 46 46 46 47 47
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8 14.9	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow 2 Basic Components of a Stream 3 Streamflow 14.3.1 Gradient and Channel Characteristics 14.3.2 Discharge and Changes Downstream 4 Stream Erosion 5 Transport of Sediment by Streams 14.5.1 Dissolved Load 14.5.2 Suspended Load 14.5.3 Bed Load 14.5.4 Capacity and Competence 5 Deposition of Sediment by Streams 14.6.1 Channel Deposits 14.6.2 Floodplain Deposites 7 The Graded Stream Concept and Base Level 8 Stream Valleys 9 Types of Stream Systems 14.9.1 Braided Streams 14.9.2 Meandering Streams 14.9.3 Anastomosed Streams 10Alluvial Fans and Deltas 14.10.2 Deltas 11Drainage Patterns	44 44 44 45 45 45 45 45 45 45 45 46 46 46 46 46 47 47 47
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8 14.9	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow 2 Basic Components of a Stream 3 Streamflow 14.3.1 Gradient and Channel Characteristics 14.3.2 Discharge and Changes Downstream 4 Stream Erosion 5 Transport of Sediment by Streams 14.5.1 Dissolved Load 14.5.2 Suspended Load 14.5.3 Bed Load 14.5.4 Capacity and Competence 6 Deposition of Sediment by Streams 14.6.1 Channel Deposits 14.6.2 Floodplain Deposites 7 The Graded Stream Concept and Base Level 8 Stream Valleys 9 Types of Stream Systems 14.9.1 Braided Streams 14.9.2 Meandering Streams 14.9.3 Anastomosed Streams 14.10.1 Alluvial Fans 14.10.2 Deltas 11Drainage Patterns 14.11.1 Headward Erosion and Stream Piracy	44 44 44 45 45 45 45 45 45 45 45 46 46 46 46 47 47 47
14.1 14.2 14.3 14.4 14.5 14.6 14.7 14.8 14.9	Hydrologic Cycle  14.1.1 From Sheet Flow to Channel Flow 2 Basic Components of a Stream 3 Streamflow 14.3.1 Gradient and Channel Characteristics 14.3.2 Discharge and Changes Downstream 4 Stream Erosion 5 Transport of Sediment by Streams 14.5.1 Dissolved Load 14.5.2 Suspended Load 14.5.3 Bed Load 14.5.4 Capacity and Competence 5 Deposition of Sediment by Streams 14.6.1 Channel Deposits 14.6.2 Floodplain Deposites 7 The Graded Stream Concept and Base Level 8 Stream Valleys 9 Types of Stream Systems 14.9.1 Braided Streams 14.9.2 Meandering Streams 14.9.3 Anastomosed Streams 10Alluvial Fans and Deltas 14.10.2 Deltas 11Drainage Patterns	44 44 44 45 45 45 45 45 45 45 45 46 46 46 46 47 47 47

# 1 Chapter 1 Introduction

### 1.1 The Science of Geology

Geo means earth and logos means discourse in greek which is where the name geology comes from. **Physical geology** examines composition of earth and **historical geology** looks for the origin of earth and its development. Most information about geology comes from **outcrops** where bedrock is exposed at the surface, but other times we dig down to get a good view.

**Sir William Logan** was a geologist the only reason we care is that he's canadian and evidently we've got nothing better to be learning about.

Geology effects people when it results in natural disasters or resource shortages. On the flip side people can effect geology (blah blah pollution, deforestation, so on).

Historical view of the nature of earth:

- Catastophism created by James Ussher (crazy christian that said the earth was 4000), said that earth's landscape had been created by great catastrophes (things like mountains and valleys were created suddenly be a force that no longer operates)
- Uniformitarianism created by James Hutton (scottish physician), says that the physical, chemical, and biologic laws that operate today operated in the geologic past so the stuff we see today have been shaping earth for a long time (small forces over a long time can make big changes)

### 1.2 Geologic Time

There was no good way to measure the age of earth until radioactivity was discovered. We now know its about **4.6** billion years old. Before radio active dating we used relative dating which relied on finding the order of events without knowing their dates. This was done with law of superposition which states that in layers of sedimentary rocks or lava flows the youngest layer is at the top. It used fossils with the priciple of fossil succession which states that fossil organisms succeed one another in a definite and determinable order and any time span can be recognized by its fossil content (this is why the ages are not consistently long).

The earth is old so relative terms must be reevaluated to account for this when describing geology.

### 1.3 Early Evolution of Earth

**Planet** The universe began with the big bang, duh. The **nebular theory** suggests that the bodies of our solar system evolved fro an enormous rotating cloud called the solar nebula. 5 billion years ago the solar nebula (a cloud of hydrogen, helium, and heavier elements) collapsed due to gravity when it reached equilibrium it formed a **protosun**.

Core When gravitational collapse stopped things cooled down and elements with higher melting points started to condense to form clumps (this is why the core of planets is often nickel and iron). These clumps started to orbit and collide forming larger clumps, eventually becoming the four inner planets. During this time the temperature increased from all the collisions and got hot enough to melt dense blobs that sank to core making it liquid.

Crust This heating of the plant also resulted in chemical differentiation which allowed lighter elements to melt and float to the surface to form the crust(usually oxygen and oxygen seeking elements). Some heavier elements were carried up with the bubble of lighter elements resulting in gold, and uranium being near the surface.

Mantle The heating of earth also created during the heating of earth so it became domibated by iron, magnesium, and oxygen seeking elements

**Atmosphere** During the heating of earth gasses were allowed to escape which formed a primitive atmosphere which would be used by the first life forms.

#### 1.4 Plate Tectonics

Alfred Wegener came up with the idea of continental drift (the idea that continents moved about the face of the planet) in the early twentieth century. The process that enables continental drift is called **plate tectonics**.

As world maps became more accurate we were able to see that certain continents fit together which was formalized by Wegener when he described **Pangaea**. This idea was first discounted because shorelines change continuously by erosion. When we look at the true outer boundary of continents, their **continental shelf** we can see where things fit together more concretely.

The biggest evidence of continental drift came from fossils of creatures that could not have crossed the ocean (namely a fern called Glossopteris) exiting in Africa and South America. It had large seeds that could not have blown far and no creature could carry it across. The plant also could only grow in certain climates but left fossils in locations they could never have grown.

We can see similar effects with mountain ranges (the Appalachians cross North America and fall off the edge beginning again under a different name in the British isles). These mountains are the same age and composition.

The last piece of evidence is the effects of past climates on the deposits in the area. Weathering in South America, Australia, and Africa shows the presence of past glaciers and coal deposits in North America and Europe show tropical climes in the past.

### 1.5 Planet of Shifting Plates

The **lithosphere** consists of the uppermost part of the mantle is broken into plates that move about on convection currents in the mantle

Seven Plates:

- North American
- South American
- Pacific
- African
- Eurasian
- Australian-Indian
- Antarctic

Some intermediary plates (Carribean, Nazca, Philippine, Arabian, Cocos, Juan de Fuca, and Scotia) and dozens of smaller ones have also been identified.

**Divergent Boundaries** are boundaries where the plates move apart. This occurs mainly at a **mid-ocean ridge** but can also occur under rift valley son the continents. New material rises up to form new sea floor called **sea-floor spreading**. This results in that part of the plate becoming older, cooler, and thicker.

Convergent Boundaries are boundaries where the plates move together causing the descent of oceanic lithosphere into the mantle, or the rise of continental margins (forming mountains). The leading edge of a converging plate is bent downwards to slide beneath the other in a subduction zone.

**Transform Fault Boundaries** are boundaries where the plates slide past each other without forming or consuming lithosphere. These cause tones of earthquakes.

### 1.6 Earth's Internal Structure

#### Crust:

- thin
  - oceanic averages 7km
  - continental averages 35km
- oceanic is homogenious
- continental
  - upper is similar granite
  - lower is similar to basalt
- continental density of  $2.7g/cm^3$
- continental is up to 4 billion years old
- oceanic density of  $3.0g/cm^3$
- oceanic less than 180 million years

#### Mantle:

- 82% of earths volume
- $\bullet$  depth of 2900km
- mainly peridotite
- density  $3.3q/cm^3$

#### Core:

- mostly iron-nickle alloy
- extreme pressure
- density  $11g/cm^3$

When you break up the earth based on physical properties you get five main layers.

Lithosphere is the outermost layer consisting of the crust and top of mantle that is cool and brittle.

Asthenosphere is the top layer of the mantle that is melty to allow the lithosphere to move about.

Mesosphere is a more rigid layer of the mantle than the asthenosphere, it still flow but much more slowly.

Outer core is the liquid layer that generates earth's magnetic field.

**Inner core** is the solid layer due to immense pressure.

# 1.7 Earth's Spheres

**Hydrosphere** is a dynamic mass of water cycling from sky to ocean and back. Covers 71% of earth. This includes underground water and glaciers as well.

**Atmosphere** is the gaseous envelope that surrounds earth.

**Biosphere** is all life on earth.

**Geosphere** is all the rocks and shit not in other spheres.

#### 1.8 The Face of Earth

The edge of a continent is the edge of its continental shelf, called **continental slope** which is the steel drop-off that extends from the outer edge of continental shelf to floor of deep ocean. There are two bands of young linear mountains, the cicum-Pacific belt (west americas and pacific island arcs) and the one that extends eastward from alps to himalayas. **Sheilds** are areas of continents that are relatively flat and composed of largely crystalline, granite-like rocks (some of the oldest rocks on earth are found there). The ocean basis contains the oceanic ridge system which si a 70 000km belt that winds around the globe consisting of layers of volcanic rock that have fractured and lifted. The ocean floor can also contain deep trenches

### 1.9 Rock Cycle

The **rock cycle** is the process by which one type of rock changes into another.

- 1. magma migrates upwards to crust where it cools and solidifies (called crystallization) resulting in **igneous rock**
- 2. igneous rock is weathered into dust and moved around by gravity, water, glaciers, wind, or waves to be deposited as **sediment**, this undergoes lithification where it is compacted by the layers above it into **sedimentary rock**
- 3. sedimentary rock is then barried deep in the earth and subjected to heat and pressure (from mountain building or magma) which turns it into **metamorphic rock**, this rock will eventually melt to complete the cycle

# 2 Ch 12 (272-277): A Scientific Revolution Begins

### 2.1 Sea-floor Spreading Hypothesis

Harry Hess came up with the theory of sea-floor spreading in the early 1960's. This was that ocean ridges are located above somes of upwelling in the mantle. This explained why rock from drilling into the ocean crust was all relatively young. He also explained that the sea floor was carried like a conveyer belt which would explain peices of the ocean floor that looked like they used to be islands. This proved that trenches are places where the crust is being consumed while it descends into the mantle.

### 2.2 Geomagnetic Reversals

A common occurrence is that the earth's magnetic field switches polarity, so rocks that are solidifying during that it will be magnetized opposite. Normal polarity is the direction of polarity of the current magnetic field and reverse polarity is the opposite. This was verified by examining lava flows from various ages. Scientists found trends of high and low intensity stripes of magnetism caused parallel to the ridge crest by using a magnetometer to measure magnetism of rocks. The alternate explanation (from Lawrence Morley) was that the high ridges were caused by normal polarity (rocks enhance the existing field) and low strips were formed during reverse polarity causing a weakening in the field there. Sea-floor spreading adds ocean floor at the middle of a stripe of magnetism maintaining the pattern as magnetism switches back and forth causing a mirror image to form on either side of the crack.

#### 2.3 Last Puzzle Piece

Tuzo Wilson combined the theory of sea-floor spreading, the theory of tectonic plates, and the theory of types of plate boundaries, into the theory of tectonics.

# 3 Chapter 2 Minerals

Minerals are any naturally occurring inorganic (usually) solids that posess an orderly internal structure and a definite chemical composition. A rock is any solid mass of mineral that occurs naturally. Some rocks are only one mineral but most are aggregates. Some rocks have nonmineral matter like volcanic rocks that have classy substances and coal which has organic matter.

### 3.1 Composition of Minerals

Earth has approximately 4660 minerals which are defined by their chemical composition and internal structure.

Atomic bonding happends due to interactions by valence electrons. An **ionic bond** is when one or more electrons are transferred between atoms. This creates an anion (negetively charged ion) and cation(positively charged ion). Ionic compounds consist of an orderly arrangement of oppositely charged ions assembled in a definite ratio to achieve net neutral charge. A **covalent bond** is when two atoms share electrons resulting in a bond stronger than ionic. Covalent bonds are more common.

#### 3.2 Structure of Minerals

The structure of ionic compounds is determined by the charges of the ions involved and their sizes. A positive ion will be surrounded by as many negative ions as it can while maintaining neutrality. Ex halite (table salt) forms cubes due to their orderly arrangement. **Polymorphs** are compounds that able to join in multiple geometries resulting in two minerals with same composition but different structures (ex graphite and diamonds). Polymorphs often happen due to temperature and pressure differences while they form.

### 3.3 Physical Properties of Minerals

Crystal Habit is the external expression of a mineral that reflects the orderly internal arrangement of atoms. Happens when a mineral forms without space restrictions, often crystals will compete for space resulting in a jumbled mess.

**Lustre** is the appearance or quality of light reflected from the surface of a mineral crystal. Lustre can be metallic (like pyrite) or non-metalic (like quartz). Other adjectives are vitreous (glassy), pearly, silky, resinous, or earthy.

Color is not of good indicator of mineral type a small impurities in minerals can drastically change their color (for example amethyst is just impure quartz).

**Streak** is the color of a mineral in its powdered form. This is found by rubbing the mineral across unglazed porcelain called a streak. This is a better indicator than color is.

Hardness is the minerals resistance to abrasion or scratching. It is determined by rubbing the mineral against one of known hardness and using the Mohs Scale of relative harness. This is 10 minerals arranged from softest to hardest.

Cleavage is the tendency of a mineral to break along planes of weak bonding, defined by amount and angle. Minerals with cleavage have smooth surfaces. For example micas have weak bonds in only one direction to sthey form thin flat sheets. Some, like quartz have no cleavage (note: cleavage is not habit, cleavage is how it breaks not forms).

**Fracture** is how the mineral breaks aside from cleavage. For example quartz breaks smoothly like glass or seashells which is called a conchoidal fracture, other minerals splinter or fibre. Most minerals fracture unevenly.

Specific gravity is a number representing the ration of the weight of a mineral to the weight of an equal volume of water

#### 3.4 Mineral Classes

Minerals that make up the earth's crust are classified as rock-forming minerals. The bulk of these are made of oxygen, silicon, aluminum, iron, calcium, sodium, potassium, and magnesium.

#### 3.5 Silicates

These are formed by the combination of oxygen and silicon. This fundimental building block is called the **silicon-oxygen tetrahedron** which has four oxygen ions surrounding a silicon ion. The tetrahedron can form single or double chains, or sheet structures by linking shared oxygen ions. Most common though is for the tetrahedron to become a jumbled 3D structure. We define these structures by their silicon to oxygen ratio. All of these structures have net negative charge so metal cations work as mortar to hold it together at the ends. You can swap out atoms that are about the same size without altering the mineral structure, this is denoted by parenthesis around an element list in the formula. The only anion available is oxygen so its always used, but silicon is the smallest of the cations so it bonds the strongest to it.

#### 3.6 Common Silicate Minerals

Feldspar (field-crystal) are the most common silicate minerals making up more than half the earths crust. Quartz is the second most common and only one made of pure silicon and oxygen. Silicates form when magma cools and solidifies. The environment when this happens determines what kind of silicate forms, this can be used to determine a minerals birth from inspection.

**Ferromagnesian Silicates**, sometimes called Dark Silicates, these are silicates containing iron or magnesium. The iron causes the silicate to be dark in color and have higher specific gravity.

Most common types:

- olivine: high temperature silicate that is black or olive green, glassy, with conchoidal fracture
  - part of mantle
  - individual silica tetrahedra linked to iron causing no consistent places of weakness so no cleavage
  - forms small rounded crystals
- proxenes: complex minerals important part of dark igneous rocks, single chain
  - most common is augite: dark, two cleavages meet at 90 degree, single chains bonded by iron, cleaves parallel
    to chain
- amphibole, double chain:
  - most common is hornblende: dark green to black, two cleavages meet at 60 and 90 degrees, double chain (wider chain means wider angle of cleavage),
- biotite: iron rich member of mica group, silica sheet form, sheet cleavage, shiny black,
- garnet: forms equidimensional crystals, often dark brown or red

**Nonferromagnesian silicates**, sometimes called light silicates, have a specific gravity of 2.7 due to not containing iron or magnesium.

Most common types:

- Muscovite: member of mica group, pearly, so thin its transparent (used for windows), very shiny
- Feldspar: most common mineral group, two cleavage at 90 degrees, about 6 on Mohs scale, glassy to pearly lustre
  - orthoclase: type that contains potassium, light creme to pink, no striations
  - plagioclase: type that contains sodium and calcium, white to grey to blue, has striations
- Quarz: only silicon and oxygen, perfect 2-1 ratio means no metals needed, 3D framework, strong bonds make it hard, conchoidal fracture, colored by impurities
- Clay: has sheet structure (not a mica), fine grained only studied at microscopic level, from chemical weathering of other silicates so very common in soil
  - kaolinite: most common, used in chinaware, and highgloss paper

#### 3.7 Nonsilicate Minerals

Carbonite A carbonate ion and cations. Calcite uses calcium and dolomite uses calcium-magnesium. These two are very similar, vitreous lustre, 3 hardness, rhobmic cleavage (three directions not at 90). You can tell them apart by dilute hydrochloric acid which dolomite reacts much more slowly to. These are often found in sedimentary rock limestone.

Sedementary rocks Halite (salt), sylvite (fertilizer), and gypsum (plaster) are found in thick layers that used to be ancient seas.

# 4 Ch 5 (109-120)

#### 4.1 Earth's External Processes

External processes are ones that happen near the surface (like weathering and erosion) and internal process are ones that derive their energy from earth's interior (like volcanos and mountains)

### 4.2 Weathering

Mechanical weathering is accomplished by physical forces that break rock into smaller eices without chaning its mineral composition. Chemical weathering is a chemical transformation of rock into new compounds.

### 4.3 Mechincal Weathering

This is just breaking rock into smaller and smaller pieces, there are three main ways to do this.

**Frost Wedging** is when liquid water seeps into cracks in rock then expands due to freezing which breaks the rock apart. This happens alot in mountains and polar regions were freezing and thawing happen alot. When these loose rocks tumple into large piles they are called **talus slopes** which you see at the base of steep outcrops. This fucks up roads in Canada (salt makes it worse).

**Sheeting** is when large masses of igneous rock are exposed by erosion causing concentric slabs to break loose making onion like layers. Weathering and erosion remove upper layers of rock decreasing the pressure on deeper igneous rock causing it to expand. More erosion makes these sheets flake of creating an **exfoliation dome**, When mining deep rocks have be known to explode due to released pressure.

Biologic Activity causes weathering when plants dig deep with their roots, often breaking up rock in the process, and their seeds settle into cracks and break them apart as they grow. Moss can event enhance chemical breakdown from the surface. Burrowing animals break down rock by moving it to the surface and dead animals produce acids that break things down chemically.

### 4.4 Chemical Weathering

Rocks decompose into elements that are stable in the environment, so if the rock's environment is stable chemical weathering doesn't happen. Water itself is a good solvent, but it can carry materials that speed up that process. There are three main processes.

**Dissolution** is the breakdown of materials that dissolve in water. This is due to the polar nature of water. Halite is a good example where the polarity of water disrupts the net neutral charge of the ions involved releasing the ions into water. Most minerals don't dissolve in pure water, but most water contains small amounts of acid that increase the corosive force of water. Once example is carbonic acid which forms when  $CO_2$  dissolves into rain drops. Calcite (limestone and marbel) is very susceptible to acid rain. The calcium carbonate in it is broken into calcium ions and bicarbonate. This forms the limestone caverns all over north america. This also bleeds calcium ions into the ground water making hard water that reacts with soap to become insoluble (can add a softener).

Oxidation is when iron rich minerals rust due to electrons being lost from one element during the reaction with oxygen. This forms hematite or limonite which gives iron rich minerals their dark coloration. The iron must first been freed from the silicate structure for this to happen (the process is called hydrolysis). Other silicates without iron can suffer from oxidation (pyrite breaks down into sulphuric acid and iron oxide) which can cause environmental issues. This is called mine acid because mining exposes the minerals to the moisture needed to form the acid.

**Hydrolysis** is the reaction of any substance with water. Ideally this is pure water but often it contains ions. This is the process that breaks down feldspar into clay resulting in is popularity in soil. In this the hydrogen ions in water replace the potassium ions breaking up the crystal structure and making the potassium available for plants to use. This also creates some silica that is carried to the ocean for critters to make their shells with. Clay minerals are very stable so they are usually the result of chemical weathering which makes them so common. Quartz is very resistant to chemical weathering.

Alerations Caused by Chemical Weathering Chemical weathering attacks corners and outcrops more readily due to their increased surface area causing rounded rocks in a process called **spheroidal weathering**.

### 4.5 Rates of Weathering

Weathering can be sped up by a number of factors:

- surface area
- rock composition (order of silicate mineral weathering is same as order of crystalization)
- climate (temperature and moisture effect chemicals present and vegetation)
- attributes of near by rocks (called **differential weathering**)

# 5 Ch 3: Igneous Rocks

### 5.1 Magma

Igneous rocks form when magma cools and solidifies. Magma is formed through a process called **partial melting** which occurs at various levels within the earth's crust. A body of magma rises towards the surface due to its lower density. If magma reaches the earth's surface it becomes **lava**, which happens through a volcanic eruption. Igneous rock that forms when magma solidifies at the surface is called **extrusive/volcanic**. If magma doesn't reach the surface and crystallizes at dept the rock that forms is called **intrusive/plutonic**. Bodies of this rock are called plutons which are only exposed when the crust is uplifted.

Formation of Magma Most magma originates in mantle causing most igneous rock to be at divergent plate boundaries. Lots of magma is also created at subduction zones. Some magma is even made in the earth's mantle due to temperature and pressure. The temperature increases by about 25°C per kilometer down called the **geothermal gradient**. At the edge of the crust and mantle rocks are super hot but still solid so any heat that is added will form magma (like at subduction zones with friction, or sinking at subduction points or rising up). Pressure also increases with depth raising the melting point for deeper rocks. When confining pressure drops enough **decompression melting** occurs (usually divergent boundaries). Water and gasses called **volatiles** can lower the melting point of rock. This happens at oceanic subduction zones where water seeps into the wedge.

Nature of Magma The liquid portion of magma is called **melt** and is made of mobile ions of silicon, oxygen, and lesser amounts of common metals. The solid portion are just bits that have already crystalized from the melt. Magma often has water, carbon dioxide, and sulphur dioxide volatiles in it. Volatiles stay dissolved due to pressure until the magma cools enough to crystallize and let them escape.

**Crystaline Rock** As magma cools its ions lose their mobility and arrange themselves into crystalline structures in a process called **crystalization**. Generally the silicon and oxygen atoms goind fist into tetrahedra which then join into embryonic crystal nuclei. Earlier crystals have more space to grow in and so develop better. This process is much more complicated due to temperature ranges .

### 5.2 How Magma Evolves

There are different kinds of lavas, sometimes from the same volcano.

Bowen's Reaction Series Magma crystalizes at a large range of temperatures so Bowen tested this in laboratory conditions. He found that minerals crystalize in a fashion relative to their melting points. Throughout this process the temperature and composition of the melt will alter. At about one third cooled the magma will be completely drained of fe, mg, and ca because those materials are used in the formation of the earliest melting compounds. This leaves the magma silica rich, it has evolved. There are many ways for magma to evolve.

Crystal setting is when earlier formed minerals sink as they are denser than the melt. The remaining melt will solidify into a very different rock from its parent magma called **magmatic differentiation**. If the solid crystals remain in contact with the melt they will evolved into the next mineral in the sequence called **Bowen's reaction series**. Minerals that form in the same temperature range in Bowen's series are found together in the same igenous rock.

As magma moves about it pulls in surrounding host rock in a process called **assimilation**. This happens when magma is moving up near the surface where rocks are brittle. The upward force of the magma causes cracks that can dislodge blocks of rock to mix into the magma. It can also happen deep down where the magma is hot enough to melt the surrounding rock.

Multiple magma bodies can intrude on each other which is called **magma mixing**. Convective flow mixes the magmas into a fluid of intermediate composition

**Partial Melting** Magma evolution also happens during melting, much the same way as it happens during cooling. If melting is complete the magma composition will resemble the rock it came from, but often melting is not complete. This results in melt that is enriched in ions from minerals with the lowest melting temperatures and a bunch of unmelted crystals.

Mafic magmas originate from the melting of peridotite (main thing in the upper mantle). When mafic magmas result for melting of mantle rock they are called primary magmas since they haven't evolved. Mafic magma often migrates upwards eventually erupting out.

Intermediate magmas and felsic magmas are found only at continental margins because they are the result of interactions between mafic magmas and silica rick components of the crust. Inbetween felsic and mafic magmas are **andiesitic composition** magmas. This can also form during magmatic differentiation of mafic magma which is why they are sometimes called secondary magmas. Felsic rocks are too common to be the result of differentiation of intermediary magma so they are likely the end product of cyrstallization of intermediate magma or the result of partial metlting of silica rich rock. Felsic magma is much thicker so doesnt erupt and forms large plutonic bodies.

### 5.3 Igenous Compositions

Felsic VS Mafic Most igneous rock can be divided into two groups based on the proportions of light and dark minerals. Igneous rocks dominant in light minerals (less than 10% dark) are called felsic. These are rich in silica and make up most of the crust. Since granite is the most common they are often referred to as having a granitic composition. Rocks that are dominated by dark minerals are called mafic. These are sometimes said to have basaltic compositions because basalt is the most common. Mafic rocks make up most of the ocean floor.

Other Groups Rocks between felsic and mafic (at leas 25 % dark) are called intermediate or andesitic composition. Rocks that are almost entirely dark minerals are called ultramafic. These are rare at the surface.

**Silica Content** Silica content is inversly related to the metal content in a mineral. Silica increases the viscousness of the magma. Silica also decreases the melting temperatures.

#### 5.4 Igneous Texture

**Texture** is the overall appearance of a rock based on the size, shape and arragement of crystals.

Crystal Size If magma cools slowly it forms larger but fewer crystals. If magma cools too quickly and results in rocks that consist of unordered ions it is called glass.

Types of Textures Aphanitic texture is used to describe rocks that form at the surface with rapid cooling resulting in a very fine grained texture. The crystals in them are so small that you need a microscope to tell them apart. This makes mineral identification impossible so they are characterized by color (light, medium, dark). These rocks often have cas bubbles where the lava solidified fast enough to catch gas, these are rocks are called **veicular texture**.

**Phaneritic** texture is used to describe rocks that form when large masses of magma cool slowly far below the surface resulting in a coarse grained texture. The crystals in these rocks can be identified by magnifying glass.

**Porphyritic** texture is used to describe rocks that have very large crystals in them as a result of deep magma growing crystals then suddenly changing environments. These rocks have large crystals, called **phenocrysts**, embedded in a matrix of smaller crystals called, **groundmass**.


Glassy texture is used to describe when molten rock is extruded into water or the air causing it to cool very rapidly resulting in unordered ions (no crystals formed). This can also happen when magma is very viscous (high in silica).

**Pyroclastic** texture is used to describe when igneous rock is formed from the consolidation of rock fragments. This is also sometimes called **fragmental texture**.

**Pegmatitic** texture is used to describe when rocks are composed of only large crystals called **pegmatites**. These are usually found on the edges of plutons. These form during the late stages of crystallization when there are lots of volatiles that enhance ion migration to speed up crystal formation. This is how the large number of large crystals exist.

### 5.5 Naming Igneous Rocks

Igneous rocks are classified by their mineral composition and texture.



### 5.5.1 Felsic(Granitic)

Granite:

- is the most well known due to its beauty and abundance.
- 20 % quartz, 65% feldspar (sodium and potassium rich)
  - quartz crystals irregular shape, glassy clear-grey color
  - feldspar crystals less glassy, grey-salmon color, rectangular shape
- can be porphyric texture (speckled) with feldspar crystals < 1cm
- by product of mountain building, resistant to weathering so gets left as a core
- granite also used to describe any rock that is intrusive coarse grained
- often found in large plutonic masses

#### Rhyolite:

- extrusive equivalent of granite
- full of light silicates (usually light grey or pink in color)
- aphanitic
- often contains glass or voids due to rapid cooling on surface
- if phenocrysts they are small (quartz or potassium feldspar)

#### Obsidian:

- dark, glassy
- formed when silica rich laval is quenched quickly
- unordered ions, due to quick cooling
- high silica concentration (despite dark color)
- excellent conchoidal fracture so it holds sharpness well

#### Pumice:

- forthy texture
- forms when large amounts of gass escape through lava (found near obsidian a lot)
- large number of voids
- sometimes will float
- flow lines can indicate movement during cooling

#### 5.5.2 Intermediate

#### Andesite:

- medium grey
- fine grained
- name comes from Andes mountains where they are commonly found
- ullet often has porphyritic texture
- if porphyritic pyrocysts are light, rectangular, plagioclase feldspar, or black, elongate amphibole crystals
- often looks like rhyolite
- very small amounts of quartz

#### Diorite:

- plutonic version of andesite
- coarse grained

- intrusive
- no visible quartz crystals
- high percentage of dark silicate minerals
- mostly sodium-calcium plagioclase felsdpar and amphibole giving it a salt and pepper look

#### 5.5.3 Mafic(basaltic) and Ultramafic

#### **Basalt**:

- very dark green-black
- mostly pyroxene and calcium plagiuclase feldspar with some olivine and amphibole
- contains light colored feldspar phenocrusts or glassly olvine phenocrysts
- most common extrusive igenous
- many volcanic islands and upper layers of oceanic crust are basalt

#### Gabbro:

- intrusive equivalent of basalt
- dark green to black
- proxyene and calcium rich plagioclase feldspar
- makes up lots of oceanic crust

#### Peridotite:

- most of the upper mantle is peridotite
- ultramafic
- olivine, proxene and calcium-rich plagioclase feldspar
- very rare, only make it to serfice as slivers in mountain building

#### 5.5.4 Pyrocastic Rocks

Tuff is most common pyrocastic rock and is composed of tiny ash-sized fragments that become cemented together. If these particles remain hot enough to fuse it is called **welded tuff**, which is mostly small glass shards with bits of pumice and other rock fragments. These are very common is volcanic areas. They formed millions of years ago when ash from volcanoes moved like avalanches. If the pyrocastic rocks are make of partivles alrger than ashe they are called colanic breccia and consist of streamlined fragments that solidified in air, or blocks broken from the walls of the volcanic vent.

### 5.6 Intrusive Igneous Bodies

Nature of Plutons Plutons occur when magma solidifies at depth. Plutons are classified according to shape as either tablular or massive and classified by their orientation relative to host rock. Discordant rocks are cut across existing rock and concordant rocks form parallel to sedimentary layers. The largest plutons are remnants of magma chambers that fed old volcanoes.

**Dykes** are tabular, discordant plutons formed when magma is injected into fractures. These are commonly found in groups with a non-observable parent pluton. Sometimes the force of the magma rising is enough to cause the cracks that the dyke eventually filled.

Sills are tabular concordant plutons which form when magma is injected along sedimentary bedding surfaces. Horizontal sills are the most common but they can occur at any orientation so long as there is sedimentary rock with that orientation. Sills tend to be the product of fluid mafic magmas in shallow environments. Sills often display **columnar joints** which form as igneous rocks cool and develop shrinkage fractures that produce elongate pillars which often gets sills confused for buried lava flows. The difference between sills and lava flows is that lava flows often have voids in their upper layers from gas escaping while sills often have particles of overlying rocks since they are forced in.

### 5.7 Laccoliths

**Laccoliths** are formed when viscous magma seeps between sedimentary layers resulting in blister-like masses that arch the overlying strata upward into domes that can sometimes be seen on the surface.

### 5.8 Batholiths

Batholiths are the larges intrusive igneous bodies which occur in groups that form massive belts. A plutonic body must have a surface exposure greater than 100 square kilometers to be called a batholith, else it is called a stock. Batholiths are usually mad of felisic to intermediate rocks. Some are the joining of multiple plutons. Some mountain cores are batholiths that get exposed by weathering and uplifting.

**Emplacement** Large granitic batholiths can form withing sedimentary and metamorphic rock with little deformation which confused scientists. They could not see how the magma body made it through several kilometers of solid rock or where the displaced rock went. At great depths magma is so boyant it can push aside solid rock to move upward and the rock that is pushed aside slides in behind it. The body may break up rocks above it and melt the peices changing its own composition, but eventually it cools enough to stop moving. Evidence for magma moving through solid rock is found in peices of unmelted host rock found in the pluton after is is exhumed by erosion called **xenoliths**.

# 6 Chapter 4: Volcanoes

### 6.1 The Nature of Volcanic Eruptions

The primary features that effect a volcano's behavior is the magnas composition, temperature, and the amount of dissolved gases it contains. Most of those factors effect the magna's viscosity.

**Viscosity** is directly proportional to the magma's silica content. This is due to silica structures linking together into long chains. So felsic lavas are much slower than mafic lavals.

Dissolved Gasses tend to decrease the viscosity and can even provide enough force during their escape to propel magma up through a vent or conduit. Before a volcano errupt its summit swells due to gases accumulating at the top. During an erruption the sudden decrease in pressure allows the gass to be released quickly. If the magma is mafic it can be propelled upward into a fountain. If the magma is feslic the gas expels jets of hot ash into buoyant plumes called eruption columns. Before this happens there is lots of differentiation letting iron rich crystals settle out leaving the upper part rich in silica and gases. This is how the gas contains small bits of ash due to little bits of magma being carried. Often the release of pressure allows lower layers of magma to build and erupt as well resulting in erruptions being a series of explosions. AFter the erruption phase is done the remaining de-gassed magma migrates upward slowly, There may be more gas build up after the initial eruption allowing more sporatic eruptions to happen.

### 6.2 Materials Extruded Duraing Eruption

**Lava Flows** Hot mafic lava is very fluid allowing it to flow in thin broad sheets or thin ribbons. These can move as fast as a walking person (some have been clocked at 30 km/h). This lava forms a skin like surface that wrinkles as it flows and are called **pahoehoe flows** (named in Hawaii where they are common). When lots of gas escape from the surface of the flowing lava it results in surface voids and a sharp jagged flow called **aa flow**. This flow continues to break as it goes

making it look like an advancing mass of rubble. When lava flows into the ocean, or originates in it the lava quickly forms an hardened skin due to the cooling nature of water. The rest of the lava usually cannot break through this skin resulting in round spherical shapes called **pillow lavas**. Often lava drains out of the tunnels it used to escape when pressure is not enough to push it through resulting in **lava tubes**. These allo fluid lavals to move great distances from their source

Gasses Volcanoes can emit so much gas that it effects the composition of the atmosphere. Gasses are also resposible for creating the passabeway that connects the magma chamber to the surface. The buoyant force of the rising magma makes cracks, but it is escaping gases that widen these cracks

Pyroclastic Materials Often volcanoes spit out little particles that can land near the mouth making that cone shape you see, or can be carried very far away. The little ash particles are formed when the gas disolved in the magma starts to rapidly expand creating a froth which is blown into the air to rapidly cool in to tiny flassy fragments which often fuse to become welded tuff. Particles that are nut sized ar called lapilli or cinders. Larger particles are called blocks if they are hardened or bombs if not. Bombs are often elongated because they cool as they fly through the air. Scoria is pyroclastic material that contains voids from mafic magma.

Nuee Ardente Pyroclastic flows are flows that consits of hot gases infused with incandescent ash and larger rocks. The most destructive of these are nuees ardentes as they can race down steep slopes at 100km/h to wipe out whole towns. The ground facing portion of the flow is rich in particles and suspended by buoyant jets of gas escaping. The flow moves quick enough to overtake air and trap it below heating it to provide buoyancy allowing the flow to move unhindered by friction and contain large rock fragments. They form from the collapse of eruption columns.

Lahars Steep sided volcanos can cause mudflows called lahars when volcanic debri becomes saturated with water to move rapidly down the slope. These can be triggered when large amounts of snow are melted by an eruption or even when there is heavy rain on volcanic deposites (volcano doesnt need to be erupting).

### 6.3 Volcanic Structures and Eruptive Styles

**Anatomy** The central conduit for lava is called the **pipe** which terminates in a vent. A volcano is built up through successive eruptions and coolings of lava. There is a small depression at the top of the vent called the **crater** which are built up as ejected fragments collect around the vent. Some volcanoes can have multiple craters or a single large one called a **caldera**. Side tunnels off the pipe can form and ejected materials form parasitic cones on the side of the volcano. When side vents only emit gas they are called **fumaroles**.

**Shield Volcanoes** These are volcanoes that form from the accumulation of fluid mafic lava resulting in broad domed structures (they look like a warrior's shield). Many grown up from the ocean floor to form islands. These have very large deep calderas that form when the roof of the volcano collapses, As they mature their magma thickens and eruptions become less frequent.

Cinder Cones These are ejected lava fragments that harden while in flight as a product of gas rich mafic magma. Occassionally these are made of ash and pumice if the magma is silica rich. They have a very regular shape that is formed due to gravity. They are sloped with a crater on one end and elongated on the uphill side. Cinder cones usually form as a result of the last eruption of a volcano after which it solidifies its pipe. Cinder cones are usually 30-300 meters in height.

Composite Volcanoes These are the pretties and deadliest volcanoes. Usually only found on the ring of fire. These are symetrical structures composed of lava and pyroclastic deposits as a product of gas rich magma having andesitic composition. These magmas are thick and travel short distances but also have explosive erruptions that spew great quantities. Composite volcanoes have very steep summit and gradually sloping sides due to larger pyroclastic ejecta gathering around the summit while smaller ejecta cover a larger area. In its early life lavas are more abundant and flow farther than latter on in life, also contributing to steep summit and sloping sides.

Huge mounds of volcanic debri around many cones can imply that a composite volcano had a massive landlist. Horseshoe shaped depression in summit imply an explosive eruption or landslide leaving a hole on one side of the summit.

Calderas These are collapsed depressions 1-10km in diameter firmed by the collapse of a large composite volcano summit followed by an explosion of pumice and ash, or the collapse of the top of a volcano caused by subteranian drainage, or the collapse of a large area without volcanic effect.

**Fissure Eruptions and Lava Plateaus** Fissures are cracks in the earth's crust allowing volcanic material through. Fissures can have many eruptions and this can lead to build up of basalt growing to thousands of meters in thickness. The lava escaping is very fluid allowing it to flow in sheets over great distances. **Flood basalt** is used to describe flows covering massive areas.

Lava Domes These are formed by maafic lavas that are squeezed out of the vent but dont really go anywhere resulting in a steep sided dome of congealed lava. Usually only the late stages of a mature, mainly andesitic composite volcano forms lava domes.

Volcanic Pipes and Necks Pipes are the conduits through which volcanoes are fed magma. Ultramafic magmas as migrate up through pipes so quickly they form prisine samples of the mantle giving deep pipes the nickname of "windows". These also often have diamonds and other high preasure minerals in them.

# MIDTERM 1

# 7 Chapter 6: Sedimentary Rocks

### 7.1 What is a Sedimentary Rock

Sedimentary rocks are formed from the raw materials produced by weathering. This sediment is diposited by settinling out of fluid or air. These piles of sediment accumulate until the layers near the bottle are compacted by pressure into rocks. While sedimentary rocks only make up about 5% of the crust they make up 75% of the outcrops we see. Because sedimentary rocks are only found near the surface we can use their layers to learn about past environments on the surface. This is often where fossils are found.

### 7.2 Turning Sediment to Rock

**Diagenesis** is the term for all of the changes that take place after sediments are deposited and before they become metamorphic rock. Diagenesis occurs in the upper portion of the earth's crust at about 150-200 degrees Celsius. At 200 degrees it starts metamorphism. One process in diagenesis is **re-crystalization** where more stable minerals are formed from less stable ones. Another is **lithification** where unconsolidated sediments are transformed into solid rocks by compaction and cementation.

Compaction This is the process where the weir of overlying material compresses the deeper layers. The deeper down, the more compacted sediment is. Compaction causes grains of sediment to get much closer together decreasing their **pore-space** and causes them to lose fluids. Due to this a significant percentage of volume is lost. The coarser the grain the less likely compaction will occur.

**Cementation** This is a chemical process through which dissolved minerals preciptate through grains of sediment to fill the pore space and join the grains. There are three main cementing materials with easy detection:

• calcite: bubbles when hydrochloric acid is introduced

• silica: forms hardest rocks

• iron oxide: has red orange color

Some sedimentary rocks start as masses of interlocking crystals rather than as sediment.

#### 7.3 Environments

Continental Environments These are dominated by erosion and movement caused by streams. Sometimes glaciers and winds are more common. Glaciers often result in a poorly sorted mix of particles picked up from all over that are deposited by the glacier's melting water resulting in straified, sorted accumulations. Streams work by eroding and carying sediment as they go. This agitates the existing sediment allowing it to sort as it resettles (heaviest at the bottom). This is why very turbulent waters have lots of pebbles and larger grained rocks in their sediment and calmer waters have finer grains. At places where waters change speed you get large sediment build ups. For example at the bottom of a mountain stream you get a aluvial fan. You also form plains of sediment where floods are periodic forming floodplains. Where wind dominates you get aelian deposits that are well sorted as wind can lift small grains quite high.

**Transitional Environments** These are characterized by low gradients or quiet waters where fine grained sediment may be deposited under shallow water or exposed to air. This results in tidal flats. At the other end we have shorelines with violent wave and current action to form a beach. Most deltas are a result of transitional environments as rivers experience a sudden drop in speed making them drop their load.

Marine Environments We divide these environments based on their depth, shallow (less than 200m deep) and deep (greater than 200m). In shallow environments huge amounts of land based sediment are deposited and the warm water allows for carbonate rich mud to form. The carbonate comes from organisms. In deep environments sediment usually remains suspended for a long period of time before it rains on the ocean floor, or it is deposited down an undersea slope by tubidity currents.

These different types of environment can occur near each other at the same time. We try to group these ingo **sedimentary** facies so that we can use all sediment in the same area from the same time to look back in history.

### 7.4 Types of Sedimentary Rocks

Sedimentary rocks made up of sediment formed through physical weathering are called **detrital sedimentary rocks** and those from chemical are called **chemical sedimentary rocks**. We can also have **organic sedimentary rocks** which are made from the remains of organisms.

### 7.5 Detrital Sedimentary Rocks

These are mostly made of silicate minerals clay and quartz resulting in these rocks often bein called siliciclastic sedimentary rocks. This is because clays is the most common product of chemical weathering of silicates and quartz is extremely durable (so it survives physical weathering). Fledspars and micas are also common becayse they are the source of sediment and dont get broken down completely.

We use particle size as a distinction for detrital rocks. The stronger the current carrying sediment, the larger the particles will be.

- Boulder greater than 256mm
- Cobble 64-256mm
- Pebble 4-64mm
- Granule 2-4mm
- Sand 0.062-2mm
- Silt 0.004-0.062mm
- Clay less than 0.004mm

#### 7.5.1 Mudrocks

These are sediemntary rocks that made of sediment whose grains are too small to see without magnification (clay-silt sized particles). Shale, mudstone, and siltstone are members of this group. Darker colored ones (like black shale) contain organic matter (carbon) from a low oxygen environment (else the organic material would have decayed).

At first the sediment forms thin layers called laminae with random orientation and large pore size, but compaction can cause particles to align in parallel sheets. This pushes out water so effectively that cementation becomes very hard (since minerals need to seep into pores via water). This results in rocks that are poorly cemented and thus very weak. This is also why mudrocks often form bariers in underground water movement (and petroleum) causing underground lakes.

Shale is a form of mudrock that can be split into thin lays called **fissility**. If it breaks into chunks it is called mudstone and if it crumbles it its siltstone.

#### 7.5.2 Sandstone

These are stones with primarily sand sized particles in them. The degree of similarity in particle size in a sedimentary rock is its **sorting**. Wind usually results in the best sorting and waves are usually better than streams. The longer the particles are carried for, the more time they have to sort themselves resulting in a better sorted rock.

The roundness of sand grains show the degree to which the corners have been ground down by colliding with other grains during transport. So rounder grains indicate longer travel time. Angular grains can also be caused by reworking (for example when a glacier crushes grains under it).

Through travel and weathering the less stable minerals get destroyed leaving behind only quartz and its tough friends.

Implications of lots of transport:

• quartz-rich

- round grains
- well-sorted

#### Variations:

- quartz sandstone primarily made of quartz
- arkose high quantities of feldspar (implies from granit, usually poor sorting and angular -; short travel and no chemical weathering due to dry climate)
- wacke lots of rock fragments held together by clay or silt called matrix (implies very short travel and reworking),
   associated with submarine deposits

#### 7.5.3 Conglomerate and Breccia

These are rocks make of pebbles and cobbles (though larger grains can exist) surrounded by sand or mud. The larger grains are usefull for idenifying the rock as they dont require magnification. Due to the abysmal sorting we know that these occur in places of turbulent action.

If the large particles are angular rather than rounded it is called **breccia**. These imply very short travel,

### 7.6 Chemical Sedimentary Rocks

#### 7.6.1 Limestone

This is the most abudant chemical sedimentary rock (about 10%), made primarily of calcite.

**Organic Limestones** Creatures in the ocean secrete calcareous skeletons to form massive structures called coral reefs. These are made up of limestone. Most limestone is actually organic limestone from coral reefs. Often limestone contains fossils of skeletal components that were not cemented properly.

Inorganic Limestone Baiscally this describes any instance where a chemical process resulted in calcium carbonate precipitating. When it happens in cages (ground water evaporates and disolves some of the carbondioxide to combine with salts) it results in **trivertine**. Limestone that contains small spheres formed when a seed particle is passed around and coated in calcium carbonate, is called **oolitic limestone** 

#### 7.6.2 Dolostone

This is composed on calcium-magnesium carbonate (mineral called dolomite). It forms when magnesium in water replaces half of the calcium in limestone. This takes a long time so dolomite only exists in anacient rocks. It doesn't dissolve as easily so it forms more rock outcrops.

#### 7.6.3 Chert

These are rocks composed of microcrystalline silica. This includes flint (darkened by organic matter), jasper (reddened from iron oxide), and agate (banded). Chert is often found in limestone or dolomite or as layers of rock. The silica composing chert can be deposited by precipitation from water resulting in tiny crystals, or (more often) it originated as biochemical sediment. Certain creatures extract silica from sea water to make exoskeletons from whose corpses chert is formed. Chert is also formed from the decomposition of volcanic ash.

#### 7.6.4 Evaporites

These are deposites of minerals as a result of the evaporation of the body of water they were dissolved in. As this happens the less soluble minerals precipitate first and sink to the bottom and so on as salinity increases (salt flats are a good example of this).

	Detrital Se	dimentary Rocks		
Clastic Texture Particle Size		Sediment Name	Rock Name	
Coarse (over 2 mm)	路路	Gravel (Rounded particles)	Conglomerate	
	知识	Gravel (Angular particles)	Breccia	
Medium (1/16 to 2 mm)		Sand (If abundant feldspar is present the rock is called Arkose)	Sandstone	
Fine (1/256 to 1/16 mm)		Silt	Siltstone	
Very fine (less than 1/256 mm)		Clay	Shale or mudstone	

Figure 6.18 Identification of sedimentary rocks. Sedimentary rocks are divided into two main groups, detrital and chemical, based on their source of sediment. The main criterion for naming detrital sedimentary rocks is particle size, whereas the primary criterion for naming chemical sedimentary rocks is their mineral composition. Note that the term "organic" in the chemical sedimentary rock category refers to the role of biological processes in the precipitation of minerals. This is distinct from the organic content of organic sedimentary rocks such as coal (altered, carbon-rich remains of once-living plant tissue).

Composition	Texture	Rock Name	
	Visible, similar- sized shells (and/or other skeletal components)	Coquina	stone
Calcite, CaCO <sub>3</sub>	Visible, variously sized shells (and/or other skeletal components) and calcareous mud	Fossiliferous Limestone	Organic Limestone
	Microscopic skeletal components	Chalk	
	Crystalline, may be banded and/or porous	Inorganic Limestone (e.g., Travertine)	
Dolomite, CaMg(CO <sub>3</sub> ) <sub>2</sub>	Variable (but commonly crystalline or laminated)	Dolostone  Chert  Rock Gypsum  Rock Salt	
Quartz, SiO <sub>2</sub>	Very fine crystalline		
Gypsum CaSO <sub>4</sub> • 2H <sub>2</sub> O	Fine to coarse crystalline		
Halite, NaCl	Fine to coarse crystalline		

### 7.7 Coal

Coal is the product of large amounts of plant material being burried for millions of years. This usually happens in a swamp since its water is oxygen deficient to prevent decay allowing the plants to be attacked by bacteria. This liberates oxygen and hydrogen from the plant material increasing the percentage of carbon. These bacteria evetually die due to lack of oxygen or acid from the plants.

At this point we have partial decomposition into a soft brown material called **peat**. With shallow burrial the peat becomes **lignite**, a soft brown coal. From there higher temperatures cause chemical reactions and yield water and organic gases, The pressure from above sediment pushes out the volitiles resulting in **bituminous**, soft black coal. Eventually metamorphism kicks in resulting in **anthracite**.

### 7.8 Classification of Sedimentary Rocks

First we divide into detrital and chemical rocks. Detrital are then divided by particle size and chemical are divided based on composition. Texture also plays a role, though there are only to main kinds. **Clastic** rocks have discrete fragments and particles taht re cemented and compacted together and **non-clastic** rocks have a pattern of interlocking crystals.

### 7.9 Sedimentary Stuctures

Sedimentary rocks usually form layers called **strata** of unique properties. Between each strata are **bedding planes** which are flat surfaces along which rocks separate or break. These are indicated by changes in grain size or composition of the rocks being deposited. These usually mark the end of a short-distance transport.

Usually strata are horizontal due to gravity but they ca be inclined due to **cross-bedding**, usually found in sand dunes or deltas. **Gradded beds** are when the particle type changes gradually usually due to currents rapidly slowing down (can also be caused by a storm).

You can get ripples anywhere the current often changes direction called oscillation ripples (these are symmetrical) or from regular currents crossing sediment piles resulting in a gentle side facing the current and steep side away.

Storms can form **hummocky cross-stratification** where we get low angle laminations with wavelike undulations (the strata bulge and are not just flat layers).

#### 7.10 Fossils

Fossils are very helpful in determining the age of rocks. They come in two forms, body fossils and trace fossiles. Very rarely do we get body fossils. To do so the remains must not get fucked with by other animals and microbes, usually caused by sudden entombment (like with tar or amber). The most famous example is the Burgess Shale in BC where organisms were rapidly burried by sediment at the foot of some submarine escarpment. There was little oxygen to support decomposition and the fossils were preserved carbonization (preservation as a carbon film on the loss of volitiles) and minerals precipitating on the tissue surface. Fossils can also be recorded as imprints (usually animals after the Paleozoic area that lacked exoskeletons).

We usually only get fossils of the hard parts since tissue doesn't preserve well. We can get these by **petrification** where minerals fill the pores of the remains (common for bone and wood). We can also preserve things through **replacement** where original material is replaced by another material (usually a sturdier material). Preservation can also occur by **moulding** where the surrounding material forms a mould of the fossil.

Trace fossils are not actual remains, but records of activities (like foot prints and burrows ans such).

# 8 Chapter 7: Metamorphic Rock

# 8.1 Metamorphism

This is the changes that take place when a rock is subjected to temperatures or pressures markedly different from those in which it originally formed.

### 8.2 Controlling Factors in Metamorphism

The composition of a metamorphic rock usually mimics that of its parent rock, but its texture and specific mineral makeup are determined by the process applied to it.

#### 8.2.1 Heat as a Metamorphic Agent

The primary role of heat in metamorphism is to change the chemical characteristics of rocks. Heat is what drives that basic chemical reactions that cause metamorphism and creates mobility and reactivity. Heat is first given off by an intrusive igneous body, or it can be given off by the earth's internal heat it the rocks are buried far enough. Different minerals metamorphose at different temperatures.

#### 8.2.2 Pressure as a Metamorphic Agent

The primary role of pressure in metamorphism is to change the physical properties of rocks. Pressure can influence heat so it does have a secondary role in determining the distribution of elements in rocks.

**Confining pressure** This is another name for uniform stress in which pressure is applied from all directions to squish the rock to its smallest possible volume. With this kind of pressure no deformation occurs.

**Directed Pressure** Also known as differential pressure, this is the unequal application of pressure which causes deformation, usually associated with tectonic activity. One type is **compressional stress** where the tectonic plate "shortens" resulting in rocks pushing together. A second type is **tensional stress** when a tectonic plate "lengthens" causing rocks to pull apart. The final type is **shear stress** where forces are parallel but opposite.

At places of low temperature rocks are brittle and tent to fracture under directed pressure. Higher temperature rocks are more malleable and deform under pressure causing their grains to flatten and elongate in the direction of least pressure. This effects the texture of the rocks. We call the layered texture that results **foliation**.

**Foliation** Foliation development is influenced by the rotation of grains, the changing shape of grains, and the recrystallization of minerals to form new grains. The rotation of grains only dominates in environments of low stress as it is a simple change that requires less force. Recrystallization happens when components are dissolved and transported to be reprecipitated on other grains. It usually flows from high stress zones to areas of less stress.

#### 8.2.3 Chemically Active Fluids

When magma cools it releases hot water into the surrounding rocks. Similarly rocks can contain water as they sink down and start to metamorphose releasing hot water into the area. Both of these conditions result in chemically active fluids at the sight of metamorphism which can carry ions from one site to another facilitating recrystallization. When the rocks surrounding a pluton are of different composition to the fluids being released there will be an exchange causing the host rock to have a different chemical composition in a process called **metasomatism**.

### 8.3 Metamorphic Grade and Index Minerals

Metamorphic grade is the intensity of metamorphism the rock has experienced. This is indicated by the sequential appearence of minerals due to different specific temperatures. We use some minerals as a **index materials** to evaluate against when determining the grade of metamorphic rock. Rocks that contain low grade minerals (ones that form at low temperatures) are low grade rocks. If a rock is heated without directed pressure being applied we have only the index materials to indicated metamorphic grade, otherwise we can use grain size and orientation to evaluate the rock.

### 8.4 Burial Metamorphism

**Burial Metamorphism** is the mild alteration of a rock by an increase in temperature and pressure due to being buried. Its basically one step past sediment diagenesis. Here geothermal heat is enough to recrystallize some minerals to form low grade metamorphic rock.

### 8.5 Contact Metamorphism

Contact Metamorphism is when ricks immediately surrounding an igneous body are cooked and altered. These define a zone of altered rock called **aureole**. These rocks tend to not be foliated as no pressure has been applied. This results in random crystal orientation. In the case of large grains we get a spotted appearance called **porphyroblastic texture**. As rocks get farther from the pluton their grade decreases.

### 8.6 Regional Metamorphism

Most metamorphic rocks are created by **regional metamorphism** which is metamorphism over a wide area due to pressures and temperatures at convergent plate boundaries. Here there is substantial confining pressure causing deformation. The section pushed down at the boundary sufferes the most heat and pressure causing intese metamorphism. This means that the cores of most mountains are metamorphic rock.

#### 8.6.1 Regional Metamorphism and Shale

Metamorphism is the process that turns shale into slate, phyllite, shist, and gneiss.

Slate This is a fine grained folliated rock composed of mica flakes produced by low grade metamorphism. You can tell it apart from shale because it doesnt have a earthy smell and rings when you flick it. Slate has very distinct **rock cleavage** (not the same as mineral cleavage or bedding).

**Phyllite** This is produced at slightly higher temperatures and pressures than slate. It also has rock cleavage, but is a wavy appearance rather than the straight lines of slate due to higher directed pressure on it.

**Schist** This has medium grains and is dominated by platy mica large enough to be see without aid. They have a distinctive foliation called **schistosity** that we use to define them.

**Gneiss** These are medium grain rocks dominated by elongate minerals of high metamorphic grade. The high metamorphism separates the light and dark components into layers giving it a stripy appearance called **gneissic texture**. It will often break along layers of platy minerals.

#### 8.6.2 Regional Metamorphism and Basalt

Basalt based rocks have a ahigher abudance of minerals with iron and magnesium than shale based rocks resulting in much less foliation. Instead of platy minerals it is dominated by elongated minerals which produce less pronounced foliation.

**Greenschist** At low grades of metamorphism feromagnesian minerals are hydrated to form different minerals like chlorite that provide foliation and a green color to the rock. Greenschist is equivalent to slate and phyllite.

**Amphibolite** At higher temperatures and pressures hydrated minerals lose water and are converted to amphiboles forming the rock called amphibolite. It is equivalent grade to schist. Amphibole crystals are very thin and needle-like resulting in a defined orientation taht produces less distinct foliation than greenschist.

**Granulite** At higher temperatures and pressures the amphibolite is dehydrated more to produce proxenes and garnets in a rock called granulite. It is equivalent grade to gneiss. The crystals in this type of rock are block shaped and coarse grained resulting in little elongation and little orientation.

### 8.6.3 Upper Limit of Regional Metamorphism

At the most extreme environments rocks begin to partially melt and start transforming into igneous rocks. The ambigous state in between has rocks called **migmatites** and have parts that are metamorphic and parts that are igneous. The lighter rocks tend to have the lowest melting temperatures resulting in them making up igneous bands while the darker minerals make up the metaphoric bands.

### 8.6.4 Regional Metamorphism and Nonfoliated Rocks

Sometimes the parent rock lacks the necessary elements to produce the platy or elongate mineral grains to create foliation in metamorphic rocks. In cases of pure quartzite or marbles (rocks made of quartz an calcite only) the metamorphic rocks formed from contact and regional metamorphism can look identical.

#### 8.7 Subduction Zone Metamorphism

**Subduction zone metamorphism** is a specific form of regional metamorphism that takes place in the region of a subducted slab. These are characterized by high pressure and low temperatures. In this environment a blue sodium rich amphibole forms called glaucophane. The rock that forms from this has foliation and is called **blueshist**. Further subduction pulls rocks into the mantle where it is transformed into **eclogite**.

### 8.8 Metamorphic Facies and Plate Tectonics

Metamorphic facies are defined by a distinctive assemblage of minerals used to designate a particular set of metamorphis environmental conditions recorded in rocks. This allows us to interpret rocks created by different types of metamorphism in a single context. The names of metamorphic facies refer to the basaltic parent rocks. Basically these are sections of a temperature by pressure graph that we label as resulting in similar rocks.

### 8.9 Ancient Metamorphic Environments

The oldest known rocks are found in large expanses of metamorphic rocks called **sheilds**. Great Bear Lake in Canada has the oldest known rocks at 4.03 billion years old. Shields are made up of rocks that resemble the cores of young mountains leading geologists to believe they are the remains of super old mountains that got weathered down to nothing.

## 9 Chapter 8: Geologic Time

### 9.1 Relative Dating

### 9.1.1 Geologic Time

**Relative Dating** is the notion that rocks are placed in their sequence of formation, It gives us the temporal order of events with no hard numbers associated.

#### 9.1.2 Law of Superposition

Nicolaus Steno first recognized a sequence of historical events in an outcrop of sedimentary rock and cam up with the law of superposition which states that in sedimentary rocks that have not been deformed a bed is older the than the one above it.

#### 9.1.3 Principle of Original Horizontality

The **principle of original horizontality** is also credited to Steno and states that layers of sediment are generally deposited in horizontal layers. This means that if we see a flat horizontal layer it has not been disturbed from its original shape.

#### 9.1.4 Principle of Cross Cutting Relations

The **principle of cross-cutting relations** states that when something cuts through layers(like a fault of intrusion) then we can assume that it is younger than the layers it is cutting through. A layer wouldn't form around a gap.

#### 9.1.5 Inclusion

**Inclusions** are fragments of one rock that trapped within another. We can say that the rock mass adjacent to the rock with the inclusion must have been there first inorder to donate the rock that ended up included.

#### 9.1.6 Unconformities

An **unconformity** is a gap in the record where depositing of sediment was interrupted or eroded away. These often represent significant events. There are three types.

**Angular Unconformity** This is the tilted or folded sedimentary rocks that are overlain by younger flat layers. It indicates a time between deposition where deformation occurred to tilt the current layers to a new angle.

**Disconformity** These are very hard to identify because the layers on either side of them are parallel and normal. Basically they are just gaps between layers that are not perfectly flat.

**Nonconformity** This is where the break separates much older rock from much younger rock. They are formed when periods of uplift or erosion bring deep rocks to the surface where younger layers can be built on them.

### 9.2 Correlation of Rock Layers

Correlation is that task of matching up rocks of similar age in different regions to develop a geologic time scale.

### 9.2.1 Correlation by Physical Criteria

When outcrops are near to each other we can not the position of a layer and correlate that layer to the one in the same position the near by outcrop. When the entire sequence is not visible we use the physical characteristics of the rock to find which layer matches it. This process doesn't work over large distances.

#### 9.2.2 Fossils and Correlation

We can know that layers that contain the same types of fossils must have formed within the lifetime of that species. This was discovered by **William Smith**. Further more we know that fossil organisms succeed each other allowing us to form a time line of fossils and corresponding layers. Fossils that are particularly widespread and thus more useful for correlation are called **index fossils**. If a index fossil is not present we can use a collection of fossils to find the overlapping time frame of the layer.

Fossils can also be used to give hints to the kind of environment in the area at the time they died and that layer was formed.

### 9.3 Dating with Radioactivity

This is the process by which we give dates numbers.

#### 9.3.1 Radioactivity

An unstable "parent" isotope decays into a more stable "daughter" isotope. By knowing the process and time this takes we can calculate dates for stuff. Decay rates can be precisely calculated and are unaffected by conditions deep in earth. We use the rate of decay with the amount of daughter isotope to calculate when the radioactive parent was first incorporated to that mineral.

#### 9.3.2 Half Life

The half life of a mineral is the time required for a sample to decay to half its mass (parent to daughter mass ratio of 1:1).

### 9.3.3 Radiometric Dating

In this version of dating we calculate based on the mass of daughter isotope only since we know that at the start of the clock (first crystalization of the rock) there was no daughter isotope present. Error can be introduced if anything influenced the amount of parent or daughter isotopes anywhere in the life time of the rock.

A common method is looking at the amount of argon-40 produced by the decay of potassium-40 since potassium is abundant and has only one common radio active isotope. Argon is unfortunatly a gas which means that some of the daughter isotope can escape and skew the radiometric date. To avoid this and other problems like it geologists use fresh unweathered rock when dating things.

#### 9.3.4 Dating with Carbon-14

Carbon-14 is used for **radiocarbon dating** since it has a much shorter half life (it can only be used for events ¡50 000 years ago). All organisms absorb carbon-14 as it is mixed into carbon dioxide (forms when cosmic ray bombardment warps carbon in carbon dioxide). While an organism is alive the decaying carbon-14 is replaced keeping it proportion constant, but when it dies it stops absorbing c14 allowing decay to begin.

### 9.4 Geologic Time Scale

The **geologic time scale** is the scale of time created in the nineteenth century using relative dating.

### 9.4.1 Structure of the Time Scale

The largest unit in the scale is eons, then eras, then periods, and finally epochs.

List of eons and eras

- Cambrian/Phanerozoic rocks containd abundant fossils
  - paleozoic ancient life
  - mesozoic middle life
  - cenozoic resent life
- precambrian time between birth of planet and first life
  - hadean
  - archean
  - proteozoic

### 9.5 Difficulties Dating the Geologic Time Scale

Radio metric dating begins when a mineral crystalizes which can lead to problems when different minerals crystalize at different times. Even worse is that the grains may not be the same age as the rock in which they occur. We attempt to date sedimentary rocks by relating strata to igneous masses.

# 10 Chapter 9: Crustal Deformation

#### 10.1 How Rocks Deform

Rocks usually deform by flowing/folding or fracturing/faulting. When stress if first applied rocks respond by deforming elastically (these changes are reversable) until a breaking point is reached.

Temperature and Confining Pressure Rocks at the surface have low temperatures and confining pressures resulting in rocks that fracture once their strength is exceeded. When this happens it is called **brittle fracture**. At depths where there are high temperatures and confining pressures rocks bend instead of breaking resulting **ductile deformation**. This can happen through gradual slippage and recrystallization along planes of weakness. This type of deformation makes the rock look like it was molded like putty.

**Rock Type** Rocks composed of hard minerals tend to fracture and rocks that are weakly cemented or containing zones of weakness (foliation) tend to bend.

Time Rocks respond mostly to small amounts of force over long periods of time making laboratory simulations impossible.

### 10.2 Mapping Geologic Structures

Rock structures are often massive and mostly hidden making mapping them very difficult.

#### 10.2.1 Strike and Drip

The **strike** of a rock is the compass direction of the line produced by the intersection of an inclined rock layer or fault with a horizontal plane. The **dip** of a rock is the angle of inclination of the surface of a rock unit measure for a horizontal plane. Geologist take these measurements all over the place and then use 3D rendering to map a much larger structure.

#### 10.3 Folds

Folds occur at zones of convergence where layers are forced upward and break (think of how mountains are formed). The **axis** of a fold is a virtical line through the center of the fold as determined by its peak and the **limbs** are the two sides of the fold.

#### 10.3.1 Types of Folds

An **anticline** is a standard upfolding fold where the center rises above the limbs (think mountain). A **syncline** is a standard downfolding fold where the center dips blow the limbs (think valley). When the limbs of a fold are mirrors across the axis the fold is **symmetric**. If a limb is tilted past a vertical line it is called a **overturned** fold.

Not all folds come as ripples, sometimes you get just one called a **monocline** as a result of a single fault sending some rock up to the surface causing a single fold in the above layers

#### 10.3.2 Domes and Basins

When a fold creates a single circular or elongate structure it is called a **dome**. If if warps downward it is a **basin**. This can be caused by broad warp ups of underlying rock or by the intrustion of magma in the form of lacoliths (also upward moving salt). Basins are thought to be the result of the lithosphere thinning or plume activity causing the crust to subside, also asteroids. Basins have their youngest rocks at the center and domes have the opposite.

### 10.4 Joints

Joints are fractures along which no appreciable displacement has occurred. The happen when rocks in the outermost crust are deformed and fail by brittle fracture. Here the rock just breaks into a couple of joints making regularly shaped blocks where weathering can begin.

#### 10.5 Faults

**Faults** are fractures along which displacement has occurred. These are the fuckers that cause tsunamis and earthquakes. The edges of faults are often areas of movement resulting in their edges being ground down and producing fault gouge.

#### 10.5.1 Dip-Slip Faults

**Dip-slip faults** are faults were the movement is primarily parallel to the inclination of the fault surface. Vertical movement results in long low cliffs with hanging walls (above the fault) and footwalls (below the fault).

**Normal Faults** These are dip-slip faults where the hanging wall block moves down relative to foot wall block (think of the top block sliding down along the fault). These are more common where plate spreading occurs and accommodates lengthening of the crust. The center block called a **graben** is surrounded by normal faults and drops as those plates separate. This produces a elongate valley bounded by uplifted structures called **horsts**.

Reverse and Thrust Faults These are dip-slip faults where the hanging wall block moves upwards relative to foot wall block (think of the foot wall subducting) with thrust faults having angle less than forty-five degrees. This occurs at places of convergence and accommodates shortening of the crust. Thrust faults are the most noticable as they lead to older rock on top of younger rock on a large scale

### 10.5.2 Strike-Slip Faults

Strike-slip faults are ones where displacement is mostly horizontal and parallel to the strike. These have a linear trace that is visible over a great distance. They often are actually a zone of many fractures. One of these fuckers caused the earthquake in California in 1906 (the San Andreas Fault). Some of these faults cut right though the lithosphere are called transform faults.

# 11 Chapter 20: Minerals and Energy Resources

Resources are materials that are useful to people. Renewable resources are replenished over a relatively short period of time and non-renewable resources are not.

### 11.1 Metallic Minerals

**Ores** are useful metallic minerals. If a rock no longer contains useful minerals it is no longer an ore. Nonmetallic minerals that are useful are called **industrial minerals**.

#### 11.1.1 Magmatic Deposits

**Gravitational Settling** This is the processes by which gravity causes minerals in a magmatic deposit to settle in layers based on their weight.

**Immiscibility** Certain magmatic deposits are separated by the liquids involved having non-mixing properties (think of water and oil).

**Pegmatites** As more parts of the magma crystallize the remaining melt becomes enricked in volatile components and rare elements resulting in odd crystals near the end. This melt is very fluid and easily injected into cracks which give the crystals much more room to grow. The rocks containing these odd, large crystals are called pegmatites.

#### 11.1.2 Hydrothermal Deposits

**Hydrothermal solutions** are the result of hot water from late stage magma coolings. This water is much better at dissolving metals due to its high salt concentration (called brines). This metal heavy brine water can travel great distances before it deposits the metals usually as sulphides. The sulphides left over from mining these metals are uber bad forms of pollution.

#### 11.1.3 Hydrothermal Deposits Associated with Igneous Activity

When water enters a zone of recent igneous activity it gets super heated allowing it to disolve minerals or even shoot up through the earth (see Yellow stone hot springs). This helps bring metal ores to the surface to be easily mined. This is especially true for sea water as salt is a good dislover resulting in gushes of particle rich clouds called **black smokers**.

**Vein Deposits** Some hydrothermic fluids escape through rock features (fault, fractures, etc) where they cool allowing minerals to precipitate. These minerals fill the crack creating vein deposits. Much of Canada's gold comes from here.

**Disseminated Deposits** When hydrothermic fluids cannot escape their magmatic body they form pockets in the body where their contained minerals can percolate into ores inside the pluton. The hydrothermic water on the outside of the pluton can shatter the surrounding rock creating tiny little veins that are filled with metal sulphides from the fluid. These are called **stockwork veinlets**.

Volcanogenic Massive Sulphide Deposits This is when a massive deposite of sulphides forms due to sea water leaches metals from the oceanic crust and transports them to mounds that surround volcanic vents.

#### 11.1.4 Sediment-Associated Hydrothermal Deposits

**Sedimentary Exhalative Deposits** These are thin layers of sulphides between sedimentary layers. This is thought to be from the mineral precipitation of fluids exhaled from vents on the sea floor where they settled as a minilayer in the currently building sedimentary rock of the area.

**Sediment-Hosted Stratiform Deposits** These are bodies of metallic minerals occurring in sedimentary units of ancient rift basins. Here ores occur as pore fillers. The current theory of this is metal rich brines moving over the ocean floor and hitting a section of oxygen poor sulpher rich mud where metal sulphides can form among the tiny minerals of clay.

Mississippi Valley-Type Deposits These are unusual hydrothermal deposits (seriously, the textbook forgot to actually say what they were) found all over the place (including mississippi).

#### 11.1.5 Sedimentary Deposits

**Banded Iron Formations** These are formed during Archean and Proterozoic and consist of alternating bands of iron oxides and chert. During this time lots of iron existed in a soluble ferrous state due to lack of oxygen in the atmosphere. Then comes photosynthesizing bacteria doing this weird thing of releasing lots of oxygen which oxidize the iron rich land in pulses. Resulting in bands of iron oxides and silica gell that eventually became chert.

**Placer Deposits** Minerals in running water get sorted by density allowing heavy minerals to form called placers. This is why the gold rushes of California took place in rivers.

### 11.1.6 Metamorphic Deposits

When rocks are metamorphosed they release hydrothermal solutions the density of minerals in that fluid is dependant on how much the initial rock is changed. Rocks like quartz that don't really change at all result in relatively clean water. The hot mineral rich fluids move around allowing chemical reactions to take place. These release carbon dioxide which allows the movement of metalic ions resulting in aureoles of metal-rich deposits called **skarns** around the edges of igneous plutons.

#### 11.1.7 Weathering Deposits

Weathering can concentrate minor amunts of rock into resources through secondary enrichment. This happens through chemical weathering allowing water to remove undesirable materials leaving the desirable on the surface.

**Bauxite** This is the principle ore of aluminum. Aluminum concentrations are usually tied up in silicate minerals and thus difficult to extract. Bauxite comes from hot wet climates where chemical weathering thrives resulting in deeply weathered soils called laterites. This weathering doesn't effect the aluminum as it is insoluble allowing it to concentrate into a hudrated aluminum oxide called bauxite.

Other Deposits As pyrite dissolves it generates sulphuric acid which mixes into water allowing it to break down ore minerals. These metals then migrate downward until they are precipitated. Precipitation happens when the fluid reaches the saturation zone (where all pore space is already filled) changing the chemistry of the fluid forcing it to drop its metals. This process is called enrichment.

#### 11.2 Non-Metallic Mineral Resources

Non-metallic mineral resources are materials that are not used for fuel or processed into metals.

#### 11.2.1 Aggregate and Stone

Aggregate and stone are fucking heavy and not worth much so they tend to only be used locally. Aggregate is usually make of crushed stone, sand, and gravel. It is used mainly in roads and buildings.

#### 11.2.2 Industrial Minerals

**Diamonds** Diamonds are hard (duh) which makes them most excellent as abrasive substances. Most diamonds come from a unique ultramafic igneous rock called **kimberlite** that is generated by a small amount of partial melting super deep. The diamonds don't crystallize in the kimberlite magma and are instead produced in the deep roots of the lithospheric mantle where temeratures and pressures are high but stable. The magma then rises and brings up the diamonds where they can be embedded as xenoliths.

Clays are a broad catagory that does a lot of different things making them valuble. Kaolinite is what bricks and pottery is made of (as well as a tooooooon of other stuff). Clays made out of volcanic ash called montmorillonites are used as absorbants and lubricants.

Carbonate Minerals Calcium carbonate is often found in limestone and one of the reasons that limestone is mined. Mostly calcite is used to make cements. Calcite, silica, clay, and iron oxide are crushed into powder and put into the top of a tower with a bunch of heating chambers. As the powder drops through the chambers it is heated and then its fed through a kiln which heats it even more. This makes clinker which is cooled, mixed with gypsum and powdered. The heating process is what forms calcium carbonate which when hydrated forms very strong bonds to be used in construction.

**Evaporite Salts** These are an important source of chloride and sulphate salts. They form when large wide basins periodically flood then allow all of the water to evaporate (hence the name). Minerals precipitate at different rates resulting in an order of appearance (calcite, gypsum, halite, and sylvite). Gypsum is the main source of plaster, halite (aka table salt) is used for food, deicing, and manufacturing of other chemicals. Sylvite is to rare to be commonly used on its own, instead it is used in potash (sylvite and carnallite) for fertilizer and deicer.

**Phosphate** Phosphates contain the mineral apatite which us used for phosphoric acid which is used in a ton of stuff. Phosphate occurs mostly in sedimentary rocks (geologists aren't quite sure why).

**Sulphur** Sulphur is used in sulphuric acid which is used in fertilizers and sulphur is used in gunpowder. Canada's main source of sulphur is natural gas (pulling it from there is also helpful to keep the atmosphere clean).

Other Industrial Mineral Deposits This paragraph is stupid. Pray its not on the test.

### 11.3 Non-Renewable Energy Resources

#### 11.3.1 Petroleum

How its Formed Most petroleum comes from algae and plankton in the ocean. These are often in shallow seas and lakes where fine grained deposits of shale form. These are called source rocks as they are organic rich. Microbes break

down the organic matter releasing lots of biogenic gas as they consume most of the oxygen, nitrogen, phospherous, and solphur leaving behind hydrocarbons. The organic matter then undergoes lithification where heat continues to break it down. It becomes a waxy substance called kerogen. At higher temperatures the carbon-carbon bonds break resulting in less complex hydrocarbons in the kerogen in a process called **cracking**. This peaks at one hundred degrees after which the kerogen is depleted of hydrocarbons and natrual gas is produced. This gas is called wet gas as it contains ethane, propane, and butane. At greater than one hundred and fifty degrees it become dry gas made only of methane. Land based organisms more readily become gas and marine sources become oil.

**Petroleum Migration** Oil and natural gas move around quite easily usually to rocks of higher permeability. The rocks around oil and gas source are often saturated with water it forces the oil and gas to move upward (since they are less dense).

**Petroleum Traps** This is an geologic structure that prevents the movement of petroleum. They are comprised of a **reservoir rock** that contains the petroleum and a **cap rock** that stops its movement. STructural traps are formed from structural deformation. An anticline is an example as oil and gas collect at the crest of the fold, another example is a fault trap which forms when a layer is displaced to form a cap rock, the final example is a salt dome which forms when salt at depths rises up it a column that forces everything above it up.

#### 11.3.2 Coal

Coal comes mostly from plants. In a swamp the decomposition of organic matter uses up most of the oxygen which stops further decomposition. This allows the organic matter to get buried and cooked into coal. Surface mining of coal can wreck the surroundings and underground mining is very dangerous for people. Coal is often impure with lots of sulphur in it that gets released into the atmosphere as sulphur oxide gases.

#### 11.4 Environmental Effects

Section skipped due to common sense

### 11.5 Unconventional Fossil Fuel Deposits

**Heavy Oil Sands** These are mixtures of sediment, water, and black tar bitumen. The hydrocarbons here are dense and imobile, they are mined from the surface and heated for mobility. It is then refined and hydrogen is added to make synthetic crude oil. Its a long intensive process where half the energy produced by the heavy oil sands is used refining it to a good enough state for use.

Oil Shale There are places where the shale containing organic matter was not heated enough to form oil and still holds it as kerogen. We can heat this kerogen to induce cracking. This process is not yet efficient enough to be used.

Methane Hydrate Methane hydrate forms when water molecules form cages surrounding molecules of methane. There are huge deposites of this in ice at the bottom of the sea floor (the pressure and temperatures there keep it stable). Currently no one even attempts this due to environmental concerns (leaking methane into the atmosphere is bad).

Coal-Bed Methane and Shale Gas Coal bed methane is a layer of methane gas trapped during the formation of coal between the coal and surrounding sedimentary rocks. It is trapped in pores making its extraction very difficult. It can be mined by pumping water into the coal seam Shale gas is natural gas trapped in the pres of shale. Shale gas can be mined by breaking apart rocks with pressurized water called hydrofracking.

### 11.6 Nuclear Energy

Canada mostly uses Canadian Deuterium Uranium nuclear reactors which use uranium-235 as fuel and deuterium oxide as a moderator and heat transport medium. Deuterium is also known as heavy water due to it being basically hydrogen plus a neutron. Most naturally occuring uranium is 99.7% unfissionable isotopes we need to refine them (reactors need at lease 3%). The size of a uranium atom prevents it from being incorperated into crystals.

**Obstacles** Building a power plant is very expensive and requires many safety features. People are often resistant to the idea for fear of meltdowns.

### 11.7 Renewable Energy Sources

#### 11.7.1 Geothermal

Water heated from geothermal gradient is puped to provide heating for industrial buildings. It usually focus on areas where ground water is heated by volcanic activity. Steam and super hot water can also be used to power turbines and generate electricity.

### 11.7.2 Organic-Based Sources

**Landfill Methane** Methane is produced by microbial decomposition of organic matter in landfills. If we harness this methane for fuel we can create a great loop of more people = more garbage = more methane = more energy.

**Biomass Energy** This is energy from the tissues of plants through photosynthesis. Basically you burn wood or dung (only really used in developing countries). Canada could use waste from the forestry industry to produce ethanol as a biomass fuel.

### 11.7.3 Hydroelectric Power

This is generated by dams which can have negative effects. The rivers the dam blocked was carrying sediment that is now dropped at the base of the dam. This can fill the reservoir in a couple decades.

#### 11.8 Other

Solar, wind, and tidal. They are as the name implies.

# MIDTERM 2

# 12 Chapter 10

# 12.1 What is an Earthquake

An **earthquake** is the vibration of Earth produced by the rapid release of energy. This happens primarily due to slippage along a fault. The energy radiates in all directions around the source, called the **hypocenter**. The surface location above the hypocenter is called the **epicenter**.

# 12.1.1 Earthquakes and Faults

Earthquakes are repetitive because the motion that caused the earthquake to happen doesn't stop once it is happened, that stress is still there it just gets momentarily alleviated.

#### 12.1.2 Elastic Rebound

The cause of earthquakes was determined by **H. F. Reid** when we inspected the results of the 1906 San Fransisco earthquake and found that displacement on the surface around the San Andreas fault showed that the Pacific Plate moved up to 9.7 meters adjacent to the North American Plate. When two plates at a transform boundary rub against each other stress builds as the plates deform, when their strength gives out they slip. The slippage travels along the fault building up stress as it goes until all of the built up stress is released. When the slip happens it allows the rock to snap back to its original shape called the **elastic rebound**, this is what causes the vibrations we feel.

#### 12.1.3 Foreshocks and Aftershocks

As things settle after a earthquake they can cause more shocks called **aftershocks**. Similarly there can be shocks before an earthquake called **foreshocks**. These can be used as a predictor for an earthquake.

# 12.2 Seismology

Seismology is the study of earthquake waves. The chinese worked on this over 2000 years ago with a pot. Inside the pot a weight was suspended and an earthquake would shake the pot causing the weight to knock small balls down tubes, the direction of tube pointed to where the epicenter of the earthquake is. While this wasn't too accurate, modern seismographs use a similar idea. A very heavy weight is suspended deep underground so that when the waves it it its initial inertia keeps it still. This way the movement of the earth relative to the weight is measured and recorded on seismograms. The waves that travel through earth are called body waves and waves on the surface are surface waves. Body waves can be primary waves or secondary waves. Primary waves are waves that "push" (think left right movement) and secondary waves "shake" (think up down movement). Primary waves move much faster, then come secondary waves, and finally surface waves. Surface waves have the highest amplitude and do the most damage while primary waves have the least. Surface waves have longer wavelengths as well leading them to often be referred to as long waves.

# 12.3 Locating the Source of an Earthquake

We can use the different speeds of primary and secondary waves to calculate the distance to the epicenter. There is a time travel graph that you use to find the distance to the epicenter to make things easier. To find the direction you use triangulation between three different measuring stations.

### 12.3.1 Earthquake Belts

Most of the earthquake activity in the world comes from the belt of seismic activity around the pacific plate. There are other belts running around the Mediterranean sea and through the Himalayas.

# 12.4 Measuring the Size of Earthquakes

Earthquakes are measured based on their intensity and magnitude. **Intensity** is the degree of shaking based on the amount of damage. This value is based on people estimating the worth of things. A more accurate measurement is the **magnitude** of the earthquake based on seismograph readings.

### 12.4.1 Intensity Scales

The first real standardized scale for earthquake intensity came from Giuseppe Mercalli in 1902 which used California buildings as its standard. The scale worked by assigning values based on how much damage the earthquake did to surface structures. This and any other intensity scale only really apply for earthquakes that effect the surface in populated areas.

## 12.4.2 Magnitude Scales

Richter Scale This was invented in 1935 by Charles Richter. It works by looking at the largest seismic wave recorded. The system accounts for differences in distance between the seismograph and epicenter. It doesn't account for different rock types altering the speed of the wave which resulted in different measuring stations having slightly different readings. Because of the wide variance in earthquake magnitude, the Richter scale uses a logarithmic scale. Each increase of 1 corresponds to a magnitude 10 times higher and roughly 32 times more energy released (no idea why 32 times).

Other Scales The Richter scale was only designed to study local earthquakes, but it was so convenient to be able to classify all earthquakes the same it became widely used. The Richter scale has been adapted for other uses, but none of them are good at measuring very large earthquakes.

Moment Magnitude This is the magnitude calculated by using average amount of displacement, area of rupture surface and shear strength of the faulted rock (along with many other factors). It attempts to measure the total energy released so it is better at measuring very large earthquakes.

### 12.5 Earthquake Destruction

Earthquakes fuck shit up.

#### 12.5.1 Destruction from Seismic Vibrations

The amount of damage done by an earthquake is determined by intensity, duration, material of building, and design of building. Much of what we know about this comes from studying an earthquake in Alaska in the 1960's since we could analyze the effect on modern buildings.

Amplification of Seismic Waves Soft sediments can amplify vibrations more than solid bedrock resulting in more destruction.

**Liquefaction** Areas with unconsolidated materials saturated with water are liquefied by earthquake vibrations causing what was stable soil to become fluid. This can cause underground structures (like sewer lines) to float to the surface and buildings to sink.

### 12.5.2 Tsunami

Tsunamis are big ass waves caused by vertical displacement along a fault line in the ocean. They move wicked fast (up to 800km/h) and get crazy tall (up to 30m) as the wave enter shallower coastal waters.

#### 12.5.3 Landslides and Ground Subsidence

Lots of the damage done by earthquakes is actually done by landslides. Earthquakes change the underlying rock which can cause sections of the surface so subside.

#### 12.5.4 Fire

Earthquakes often sever gas and electrical lines which can cause massive fires. The earthquake also fucks with water lines which make putting out said fires really hard. Luckily your house was fucked anyway.

# 12.6 Can Earthquakes be Predicted

## 12.6.1 Short-Range Predictions

We don't have a perfect way to predict earthquakes, but often look for precursors to provide warning. In California they are working on ways to measure the current stress in rocks near the fault. China and Japan are looking at animals that seem to know about earthquakes before they happen.

# 12.6.2 Long-Range Forecasts

These forecasts work on 30-100 year scales. They assume that earthquakes are cyclic and attempt to find historical patterns that they can extrapolate. Based on the known movement rate of plates scientists predicted that major earthquakes should occur every century or two. Places where the historical records show no earthquakes in that time frame are called **seismic gaps**.

# 12.7 Probing Earth's Interior

Waves of energy traveling through earth's interior (either from earthquakes or fucking huge explosions) tell us alot about the composition of it. To do this we need very accurate travel times for the primary and secondary waves for the earthquake (these times vary based on composition of the rocks they pass through) and very accurate measurements of the distance they traveled. The distance traveled is very hard to get because scientists need to know precisely where the epicenter was ad these are often in remote places. Scientists often just use nuclear explosions to generate waves for measurement since this is much more controlled. 0

#### 12.7.1 The Nature of Seismic Waves

- velocity depends on density and elasticity of rocks (more rigid rocks = faster waves)
- speed depends on depth because pressure makes rocks more elastic
- primary waves are faster than secondary waves in all materials
- shear waves cannot propagate through liquids
- the path of waves refracts when changing materials

Using the above listed properties scientists can tell alot about the rock that a seismic wave passed through.

## 12.7.2 Seismic Waves and Earth's Structure

Due to increased pressure, waves traveling through the interior of earth speed up and are refracted outwards. It is through observing these refractions that scientists found the earth to be composed of layers.

# 12.8 Discovering Earth's Major Boundaries

## 12.8.1 The Crust-Mantel Boundary


The **Mohorovicic Boundary** (dude was yugoslavian, had a weird name) is the break between crustal materials and the underlying mantle. It, unsurprisingly, is shortened to **Moho**. Seismograms taken more than 200km from an earthquake had much higher average travel velocities for primary waves. From this Mohorovici found that 50km below the surface a layer exists with very different properties that allow waves to speed up.

#### 12.8.2 The Core-Mantle Boundary

A german seismologist Ben Gutenberg found that primary waves die out 100 degrees from an earthquake and reappear at 140 degrees two minutes later than expected. This 40 degree belt of stealth primary waves is called the **P-wave shadow zone**. This is explained by earth containing a core that hinders primary waves and refracts them. Seconary waves do not go through this zone, so part of it must be liquid. This sudden drop in p wave velocity and abscense of s waves implies that there is a liquid layer below that of the mantle.

# 12.8.3 Disovery of the Inner Core

This was found in 1936 by Inge Lehmann by looking at a new area of seismic refraction. The size was calculated using underground nuclear explosions. P waves that pass through the inner core have higher velocities implying that it is solid.



# 13 Chapter 14

## 13.1 Mass Wasting and Landform Development

Sometimes, when gravity is feeling particularly bitchy, it decides to destroy your house, this is how it does it. **Mass** wasting is the downslope movement of rocks and shit due to gravity.

## 13.1.1 The Role of Mass Wasting

As weathering breaks things down rivers carry it away, this creates steram valleys. If streams created valleys without mass wasting they would be very narrow.

### 13.1.2 Slopes Change through Time

Volcanoes and mountains create peaks only for mass wasting to tear them down (vindictive little bitch that it is). Younger mountains are much more susceptible to mass wasting until they are worn down into gentler slopes.

## 13.2 Controls and Triggers

Gravity is the main cause of mass wasting, but many other factors weaken it before it falls.

#### 13.2.1 The Role of Water

Excessive water (either from rain or melting snow) can cause mass wasting. The pores in sediment become filled with water their cohesion fails allowing them to slip and slide about the place (like a drunk girl at a party) and then gravity can bring them crashing down (see previous metaphor).

## 13.2.2 Oversteepened Slopes

Particles assume a stable slope called the **angle of response** which is the steepest angle at which things are stable. Any angles past this are oversteepened slopes. Larger or more angular particles maintain steeper slopes. Oversteepened slopes are usually taken down by gravity.

# 13.2.3 Removal of Vegetation

Plants can add stability to slopes by using their roots to hold soil together. They can also prevent against damage due to rain and help remove water from saturated soils. If these plants are removed mass wasting often occurs.

# 13.2.4 Earthquakes as Triggers

Remember how I said earthquakes fuck shit up. Well this is one way. If you shake an unstable slope it falls.

# 13.2.5 Liquefaction

Liquefaction is a by product of earthquakes where saturated ground can become liquid. Liquids have non-existant stable slopes so they fail very easily.

### 13.3 Classification of Mass Wasting

Most types of mass wasting are classified by the type of motion displayed, type of material being moved, and the rate of movement.

### 13.3.1 Type of Motion

Motion tends to be a fall, slide, or flow.

**Fall** This is when detached particles drop through the air on their way down. This is common on very steep slopes. It is usually the result of freeze and thaw cycles or plants braking things down allowing gravity to pull them down. Talus slopes are created by these.

Slide This are when materials remain fairly coherent (don't break up too much) on the way down.

Flow This is when the material moves down the slope as a sort of viscous fluid. These tend to be saturated in water.

### 13.3.2 Type of Material

When soil or regolith fall they are referred to as debris and when bedrock breaks loose it is called rock.

#### 13.3.3 Rate of Movement

We group by those that slide, those that move viscously, and then those that creep. Not sure what the difference between this and Type of Motion.

## 13.4 Slump

**Slump** is the downward sliding of a mass of rock as a unit along a curved surface. It is common along river valleys eroded shorelines. This tends to happen to oversteepened slopes that were held in place by the layers below them when those layers are removed, or when the slope is overloaded. It is common for lower layers of the slope to flow.

#### 13.5 Rock Slide

Rock slides are when blocks of bedrock break loose and travel rapidly down a slope. These tend to occur where rock strata are inclined or where fractures run parallel to the surface. As rock at the base of the slope are cut the top layers relying on that slip loose and slide down rather quickly. Can also be caused by rain loosening the friction between rock strata (which is why they are common in spring).

### 13.6 Debris Flow

**Debris flow** is a rapid type of mass wasting that involves flow of soil and regolith containing a large amount of water. It is common on the sides of mountains and volcanoes and often follows river valley due to its liquid nature.

# 13.6.1 Lahars

When a debris flow is made up mostly of volcanic materials it is called a lahar.

#### 13.7 Earthflow

This is when water saturates the soil allowing materials to slump on a slope, the material at the bottom of the slope becomes viscous allowing it to flow

# 13.8 Slow Movements

### 13.8.1 Creep

Creep is a type of mass wasting that moves very gradually down hill. Freezing and thawing cycles contribute to the creation of creeps (also a traumatic childhood). Freezing raises particles perpendicular to the slope and thawing allows them to drop back down slightly farther down the hill. Anything else that disturbs soil also contributes to creep. Creep is very slow so you can't watch it in progress, but you can see it fuck up anything that requires straight lines.

#### 13.8.2 Solifluction

**Solifluction** is the process of slowly moving mass down a hill by turning it into a soggy mass that flows suuuuuuuper slowly. It is common anywhere water cannot escape the from the saturated top layer of soil. For instance, anywhere stuck above permafrost. The layer above is called the active layer. When the active layer thaws in the summer it cannot seep through the permafrost layer so it super saturates the soil allowing it to flow.

### 13.8.3 Other Periglacial Features

**Periglacial** refers to anything associated with permafrost. In coldland lakes can freeze so hard they form mounds with vegetation called **pingoes**. When the mounds are made of peat covered in ice (instead of pure ice) they are called **palsas**. When bedrock shatterns the shards cover the ground as **felsenmeer**. As water thaws and freezes it creates ice wedges that orient themselves in patterns leading to **patterned ground**. The cool thing is that rocks can be brought to the surface to be embedded into ground patterns. As things thaw they can form irregular features called **thermokarst** topography.

# 14 Chapter 15

# 14.1 Hydrologic Cycle

The **hydrologic cycle** is the circulation of water through earth. Water evaporates, wind moves it around, it rains back to earth, then rivers move it around some more. Some water soaks into the ground called **infiltration**. If more rain falls than can be absorbed there is run off. Water absorbed into the ground is released through evaporation or plants (called **transpiration**). Its impossible to tell how much water is transpired by plants so we group it with evaporated water in the term **evapotranspiration**.

#### 14.1.1 From Sheet Flow to Channel Flow

The amount of water than can be absorbed by the ground is its **infiltration capacity**. This is determined by the intesity and amount of rainfall, how wet it was before, the soil texture, the slope, and the amount of plants. If the ground is saturated run off moves as **sheet flow**. This happens for a short distance before tiny channels called **rills** form. Rills start to come together feeding large and larger channels. A stream can be any size but a river must be large.

## 14.2 Basic Components of a Stream

The **head** is at the source of the stream and the **mouth** is where it ends. Between them the path it follows is called its **course**. A segment of the stream along the course is called a **reach**. Bends or loops in the stream are called **meanders**. The bottom of a stream is called the **bed** and its sides are called **banks**. The areas around the banks of a river that are only submerged during floods are called **floodplains** and tend to be zones of sediment.

## 14.3 Streamflow

Laminar flow has water molecules in straight paths parallel to the channel. This occurs in relatively slow rivers with smooth channels. Turbulent flow has water moving in an chaotic (dare I say turbulent) fashion. Most streams move fast enough for turbulent flow which causes erosion.

# 14.3.1 Gradient and Channel Characteristics

The steeper the slope/gradient of the river the faster its water moves (duh). The cross-sectional shape of the river determines how much water is touching the channel and thus moving slower. Anywhere turbulent water makes it the surface **rapids** form.

## 14.3.2 Discharge and Changes Downstream

The **discharge** of a river is the mount of water flowing past a certain point in a given unit of time. The amount can change due to snow or rain and the speed can change due to erosion changing the channel shape. A stream flows much faster at its mouth due to erosion reducing friction along the channel causing increased speeds.

# 14.4 Stream Erosion

Streams erode their channel as they go, faster streams erode more and more eroded channels allow faster streams. Current can flow into cracks and lift rocks up, or sandblast them into smaller particles to carry away. **Potholes** occur when swirling eddies used abrasive particles to drill holes. As they drill they pick up more particles allowing very large potholes.

# 14.5 Transport of Sediment by Streams

Streams transport sediment in solution (called **disolved load**), in suspension (called **suspended load**), and along the bottom of the channel (called **bed load**).

#### 14.5.1 Dissolved Load

As water percolates through the ground it gains ions, eventually making it into a stream. The velocity of a stream does not effect how many ions it can carry. When the chemistry of the water changes these ions precipitate into sediment.

## 14.5.2 Suspended Load

This is the most common form of transport. The faster a stream moves, the more it can carry (and the larger its particles as well). The **settling velocity** of a grain is the speed at which particles fall through a stationary fluid. This effects how well a stream can carry that particle. The settling velocity is determined by the size, shape, and specific gravity of particles.

#### 14.5.3 Bed Load

These tend to be coarser particles. They move along the stream by rolling, sliding, and saltation. **Saltation** is where sediment jumps along the river bed as particles are pushed up by collisions and brought down by gravity. Bed load particles only move when the river is strong enough.

# 14.5.4 Capacity and Competence

Capacity is the maximum load of solid particles that a stream can transport per unit of time. Competence is the maximum particle size that it can transport. Competence increases as the square of its velocity.

# 14.6 Deposition of Sediment by Streams

Sediment that is deposited by streams is called **alluvium**.

### 14.6.1 Channel Deposits

Alluvium deposited in the channel forms **bars**, usually made of sand and gravel. If sediment accumulates in mounds on the channel bed it is called **intrachannel bars**. If sediment builds up inside a meander it is crescent shaped and called a **point bar**.

#### 14.6.2 Floodplain Deposites

Floodplains are areas that get flooded. **Natural levees** are ridges that flank a stream channel due to the sudden drop in a river's velocity when it goes over a floodplain causing it to drop large amounts of sediment.

# 14.7 The Graded Stream Concept and Base Level

Streams attempt to reach equilibrium between the outside influences. This is the stream having just enough energy to carry its load and not cause any erosion or deposition. Streams that reach this equilibrium are called **graded streams**. At its head the gradient is very steep to carry coarse grains and much less so at its mouth. Where the stream is higher energy than equilibrium it erodes thus gaining more sediment and where it is too low energy it deposits sediment in depressions. In this fashion the stream always aims to have just enough energy to carry its load. The **base level** is the lowest elevation to which a stream can erode its bed. A stream will have many different base levels throughout its course. Rocks that are too tough to be eroded will create waterfalls where it will maintain a steep slope. The water breaks down the layers under the tough layer until it eventually breaks off creating the crazy drop off of waterfalls. Sea level is called **ultimate base level** since it is the lowest elevation. As sea level changes streams react to balance out. The rising sea level causes rivers to deposit sediment raising its bed.

# 14.8 Stream Valleys

Most valleys are created by their streams slowly eroding them away, but some are very narrow because they were cut by glaciers and then streams formed.

# 14.9 Types of Stream Systems

#### 14.9.1 Braided Streams

Streams deposit sediment on their beds, these can build into bars that split the flow of the stream. This creates a complex set of flow courses as the stream diverges and converges called a **braided stream**. These streams tend to be dominated by coarse grained sediment.

## 14.9.2 Meandering Streams

Meanders are maintained because the current on the outer edge of its curves is moving much faster than the current on the inner edge causing sediment to be deposited on the inner edge and erosion on the outer allowing the meander to widen. The outside edge of a meander is where active erosion occurs so it is called the **cut bank**. The inner edge of the meander can record the various positions of the point bar (place sediment was deposited in a bar) through **lateral accretion surfaces**. These look a lot like cross bedding but are much larger in scale. Meanders can run into each other causing loops to form. The segment that joins them is called the **cutoff** and the bits that dry out because the stream takes a faster route is called the **oxbow lake**.

Meandering rivers tend to have natural levees, the area behind them is called a **back swamp** because it drains very poorly as it cannot get back over the levee. Streams that enter a valley with a meandering river travel through its back swamps before getting through a natural levee into the river, these are called **yazoo tributaries**.

#### 14.9.3 Anastomosed Streams

Anastomosed streams look like braided streams, but their flow is around very stable islands. These streams are actually many streams interwoven instead of one stream broken up, and are dominated by fine grained sediment. They occur at very low gradients so are very slow moving and have very wide floodplains with levees. When sediment is deposited in a anastomosed stream it doesn't move around it like a meandering stream, instead the sediment can build up and block the channel leaving it abandoned.

# 14.10 Alluvial Fans and Deltas

#### 14.10.1 Alluvial Fans

**Alluvial fans** form when a high-gradient stream suddenly slows down, at this point the stream rage quits and drops everything. It usually drops things in a fan-esque shape, hence the name.

#### 14.10.2 Deltas

Deltas form when a stream enters a large body of water. Like with alluvial fans, this causes a sudden decrease in stream velocity so it drops everything. First coarse grains, called foreset beds, are dropped to form the delta front at the mouth of the river. These are then covered by a thin layer of finer grains called the topset bed to form the delta plain. Very fine grains settle far out in horizontal layers called bottomset ds to form the prodelta. This sediment eventually chokes the river and it breaks into smaller streams called distributaries. These carry water away from the channel (unlike tributaries which carry water to it).

# 14.11 Drainage Patterns

A drainage basic is an area of land that contributes water to a stream, these are separated by areas of higher elevation called divides.

**Drainage Patterns** The most common drainage patter is the **dendritic pattern** which look a bit alike a tree with tons of random branches. It forms when bedrock is fairly uniform and resistant to erosion. A **radial pattern** is when streams all diverge out from a central area like spokes on a wheel. It forms on volcanic cones and domal uplifts. A **rectangular patter** has many right angles. It is found where the bedrock has lots of joints and faults that got eroded by streams. A **trellis pattern** has tributaries parallel to each other. This forms where there are parallel belts of reistant and less resistant rock.

#### 14.11.1 Headward Erosion and Stream Piracy

**Headward erosion** is the process of the stream extending itself by pushing its head upslope. **Stream piracy** is the diversion of the drainage of one stream because of the headward erosion of another. Basically one stream headbutts into another stream and breaks through its banks diverting its flow.

#### 14.12 Flood and Flood Control

Floods happen cyclically. The recurrence interval is the amount of time between floods of similar size.

## 14.12.1 Causes and Types of Floods

**Regional Floods** Most of these are seasonal due to melting of snow or heavy rains. This can be made worse if the ground is still frozen.

**Flash Floods** Basically these are floods that happen out of nowhere. This can be due to heavy rain or near by mountains funneling everything into very fast narrow streams. Urban areas are very susceptible because most of the ground is impermeable making lots of runoff.

Ice Jam Floods When frozen rivers flood they can break up the surface ice and carry it downstream. When these ice chunks hit an obstruction they can pile up and create a dam. This floods all areas upstream, when the ice dam fails the water will rush through causing a flash flood for the area downstream.

**Dam Failure Floods** These are floods that happen when dams fail (who would have guessed).

### 14.12.2 Flood Control

Artificial Levees These are mounds built on the banks of rivers to hold back flooding. When floods happen the river leaves some sediment in front of the levee meaning that the next flood will need less water to get over it. Due to this levees have to be frequently raised. They often fail as well.

**Flood Control Dams** These store flood water and control the rate of release. Dams are expensive and can fuck with the environment around them.

Channellization This is altering a stream channel to prevent it from reaching flood height. Often this is just clearing it of obstructions or widening it. We can even shorten a stream by creating cutoffs to encourage erosion and widening of the stream.

Non-Structural Approach Let shit flood, just make sure everyone who lives there knows its comming.