

Starter Edition Version 3.10

Notices



Important InformationNotices

Topics:

This section contains document notices.

- Legal Notices
- Document Information
- Service Support

Notices



Legal Notices

© 2018 HERE Global B.V. and its Affiliate(s). All rights reserved.

This material, including documentation and any related computer programs, is protected by copyright controlled by HERE. All rights are reserved. Copying, including reproducing, storing, adapting or translating, any or all of this material requires the prior written consent of HERE. This material also contains confidential information, which may not be disclosed to others without the prior written consent of HERE.

Trademark Acknowledgements

HERE is trademark or registered trademark of HERE Global B.V.

Other product and company names mentioned herein may be trademarks or trade names of their respective owners.

Disclaimer

This content is provided "as-is" and without warranties of any kind, either express or implied, including, but not limited to, the implied warranties of merchantability, fitness for a particular purpose, satisfactory quality and non-infringement. HERE does not warrant that the content is error free and HERE does not warrant or make any representations regarding the quality, correctness, accuracy, or reliability of the content. You should therefore verify any information contained in the content before acting on it.

To the furthest extent permitted by law, under no circumstances, including without limitation the negligence of HERE, shall HERE be liable for any damages, including, without limitation, direct, special, indirect, punitive, consequential, exemplary and/or incidental damages that result from the use or application of this content, even if HERE or an authorized representative has been advised of the possibility of such damages.



Document Information

Product	
Name:	HERE Android SDK
Version:	Starter Edition Version 3.10
Document	
Name:	HERE Android SDK Developer's Guide
ID:	0b506e1f-eca6-49e5-a1bc-2d9e252cd7ae
Status:	FINAL
Date:	2018-Dec-17, 17:21 (GMT)

Service Support

If you need assistance with this or any other HERE product, select one of the following options.

- If you have a HERE representative, contact them when you have questions/issues.
- If you manage your applications and accounts through *developer.here.com*, log into your account and check the pages on the SLA report or API Health. If this does not clarify the issue, then check *stackoverflow.com/questions/tagged/here-api*.
- If you have an evaluation plan, check stackoverflow.com/questions/tagged/here-api.
- If you have questions about billing or your account, Contact Us.
- If you have purchased your plan/product from a HERE reseller, contact your reseller.



Contents

Chapter 1: Overview	7
What is the HERE Android SDK?	8
Feature List	8
Legal Requirements	8
Chapter 2: Quick Start	10
Run the Sample Application	11
Create a Simple App Using the HERE SDK	13
Chapter 3: User Guide	19
System Requirements	20
Authenticating Applications	20
Examples on GitHub	21
Maps	21
Gestures	24
Map Schemes	27
MapEngine Class	29
Objects and Interaction	30
Custom Raster Tiles	34
Positioning	36
Basic Positioning	37
Directions	39
Route Calculation	40
Places	43
Geocoding and Reverse Geocoding	44
Search and Discovery	45
Chapter 4: Supplemental Information	52
Requesting Android Permissions	
Device and Emulator Support	
Adding a SupportManEragment at Duntime	

HERE Android SDK Developer's Guide Contents

	_		
_	$(\cap$	nte	ntc

de
Mr.

Development Tips	56
Chapter 5: Coverage Information	58

Overview



Chapter 1Overview

Topics:

- What is the HERE Android S...
- Feature List
- Legal Requirements

The articles that follow introduce the HERE Android SDK, explain essential concepts and describe the common use cases it supports.



What is the HFRF Android SDK?

The HERE Android SDK provides a set of programming interfaces that enable developers to build an immersive, geographically-aware Android applications by leveraging a powerful and flexible mapping platform. Through this SDK, developers can add rich location features such as routing, interactive maps, and global place search to their applications.

Feature List

The main features offered by the HERE Android SDK are listed below.

Note: The HERE Android SDK is designed for standalone Android APK development. If you plan to use the HERE SDK for platform-embedded app development (apps that ship with the device ROM), see Service Support on page 4 to contact us for more details.

Mapping:

- Dynamically download maps for more than 190 countries in over 60 languages
- Map styles: normal street map, satellite map, transit map, and more
- Touch gestures (including pan, flick, and pinch zoom)
- · Overlay objects on the map such as polylines, polygons, icons, and routes
- Overlay custom raster tiles on the map (for example, to display heat maps)
- · Ability to render raster tiles and map objects interleaved within different map layers

Search:

- Search through a broad set of geographical content across the globe, (including streets, address points, and categorized places)
- Search for a specific place or explore by categories
- Access rich details for a Point of Interest from third-party content sources (including images, ratings, reviews, and editorials)
- · Perform geocoding and reverse geocoding lookups

Directions:

- Online Car and Pedestrian Route Directions
- Specify preferred route type (fastest or shortest) and route options (such as avoiding toll roads, motorways, and parks)
- Alternate routes

Legal Requirements

In addition to the applicable *terms and conditions* under which you have licensed the SDK, the following shall apply.

► Overview



Components of the HERE SDK collect certain information from your application. Such information includes access credentials (App_Id and App_Code – see also Authenticating Applications on page 20) and the types of features utilized by your application when used by end users. The information does not identify an individual end user. However, your application's privacy policy must disclose to the end users that you have licensed products and services from HERE and that such information is collected from your application as it is being used by end users and that HERE collects and processes such information from the application.

Ouick Start



Chapter 2Quick Start

Topics:

- Run the Sample Application
- Create a Simple App Using ...

This section provides information to help you start using the HERE Android SDK.

Obtain the SDK

To obtain the HERE Android SDK, follow these steps:

- 1. Visit developer.here.com and click on Get Started for Free.
- 2. Register or sign in to your HERE Account.
- 3. Agree to the HERE Terms and Conditions.
- 4. On the Platform Activiation screen, find the section for HERE Android SDK Starter Edition and click on Generate App ID and App Code to obtain your app credentials and the SDK download link.
- **5.** Follow the link to download the HERE Android SDK as a Zip package.

After you have downloaded and extracted the Zip package, follow one of the next tutorials to begin using the SDK.



Run the Sample Application

This tutorial contains instructions on how to run the basic sample application to render a map on an Android device. This tutorial assumes that you are using the *Android Studio* development environment and a supported Android device. For more details, see *System Requirements* on page 20.

Development tasks for this basic application include:

- Open the sample project in Android Studio.
- Import the necessary resources into the project.
- Add HERE Credentials.

Open the Sample Project in Android Studio

The next task before running the sample HERE SDK project is to locate the project folder and open it in Android Studio as follows:

- In the Welcome to Android Studio dialogue box, select Open an existing Android Studio project.
- 2. In the Open File or Project dialogue box, select the BasicMapSolution folder from your file system and click OK. The BasicMapSolution folder is located at HERE-sdk.zip/HERE-sdk/tutorial/.
- 3. After completing these steps, the main Android Studio project window should appear with "Error: Failed to resolve: :HERE-sdk:" in the Messages pane.

Import the HERE SDK Android Archive

The HERE Android SDK library is shipped as an Android Archive (.AAR) file. You can import this library by doing the following:

- 1. On the View menu, click Tool Windows > Project.
- 2. A few tabs are available in this tool window. Select the **Project** tab to show a file system view of the application structure.
- Right-click on the app folder and select New > Directory to create a new folder. Use libs as the new folder name.
- 4. In your operating system's file system, navigate to the extracted HERE SDK directory. Copy the HERE-sdk.aar file and paste it into the newly created libs directory.
- 5. Open the build.gradle file under the app folder and ensure the following entries are present:

```
repositories {
    flatDir {
        dirs 'libs'
    }
}

dependencies {
    implementation(name:'HERE-sdk', ext:'aar')
    // Depending on your specific project configuration, you may have other entries here.
}
```


6. Optional: To enable quick Javadoc reference within your Android Studio environment, scroll down to the External Libraries section, right-click on HERE-sdk, and then select Library Properties. Click the + button and locate HERE-sdk-javadoc.jar from the HERE SDK package.

▶ Quick Start



Note: You can also import HERE-sdk.aar by using the menu, selecting File > Project Structure... and clicking the "+" button. If you use this method, ensure that HERE-sdk is listed properly under the app Module Dependencies.

Figure 1: Location of the .AAR file



Add Credentials

This sample application does not ship with a set of the required HERE SDK credentials. Typically, before developing a new HERE SDK application, you need to acquire a set of credentials by registering your application on http://developer.here.com. Each application requires a unique set of credentials. When you register your app, the registered bundle identifier must match the package name in your project.

Since this sample app has the package name com.here.android.tutorial by default, you can generate a set of app credentials on http://developer.here.com using the same package name and add them to the app.

You can add credentials to your app by opening the BasicMapSolution/app/src/main/AndroidManifest.xml file and modifying the following <meta-data> tags:

- <meta-data android:name="com.here.android.maps.appid"
 android:value="{YOUR_APP_ID}"/>
- · <meta-data android:name="com.here.android.maps.apptoken"
 android:value="{YOUR_APP_CODE}"/>

Run the Project

You can run your simple application by pressing the key combination **Shift + F10** (or **Ctrl + R** on macOS) from within Android Studio. The application renders a map retrieved from the HERE servers. When you are running your application on a device, make sure a data connection is enabled.

▶ Quick Start



Note: For detailed instructions on how to create a new HERE SDK app, see *Create a Simple App Using the HERE SDK* on page 13

Create a Simple App Using the HERE SDK

This tutorial provides instructions on how to create a simple application that uses the HERE Android SDK to render a map on an Android device.

This tutorial assumes that you are using the *Android Studio* development environment. Development tasks for this basic application include:

- Acquire HERE credentials for accessing map services.
- Create a new Android Studio project.
- · Add necessary resources, permissions, and a map fragment to the project.
- Modify AndroidManifest.xml
- Initialize the map fragment to create a map instance and associate this map with the map fragment for rendering on the client device.

Acquire HERE SDK Credentials

Typically, before developing a new HERE SDK application, you need to acquire a set of credentials by registering your application on http://developer.here.com. Each application requires a unique set of credentials. When you register your app, the registered bundle identifier must match the package name in your project.

Create a New Android Studio Project

The second stage of developing an application using the HERE SDK is to create a new project in Android Studio as follows:


- 1. From the Welcome to Android Studio dialogue box, select **Start a new Android Studio project** to open the Create New Project dialog.
- 2. In the New Android Application dialog, under Application name, specify an appropriate application name. The remainder of this tutorial uses BasicMapSolution as the application name.
- 3. Under Company Domain, specify an appropriate domain.

▶ Quick Start



4. Edit the package name by clicking the **Edit** link. The remainder of this tutorial uses com.here.android.tutorial as the package name.

Figure 2: Edit the Package Name



- 5. Under Project Location, specify an appropriate project location in the file system.
- 6. Click Next.
- 7. Select the form factors supported by your application. For the purpose of this tutorial, check Phone and Tablet.
- **8.** Under Minimum SDK, select the lowest version of the Android SDK you wish to support. For this sample application, use Android 4.1.x "Jelly Bean".
- 9. Click Next.
- **10.** You may be prompted to agree to a License Agreement. Click Accept, and then **Next** to install SDK components. After the installation is complete, click **Next** again.
- 11. In the "Add an activity to Mobile" dialog box, select Empty Activity and click Next.
- 12. In the "Configure Activity" dialog box, specify an appropriate activity name in Activity Name. This tutorial uses the name BasicMapActivity.
- 13. Under Layout Name, specify an appropriate layout name. (This tutorial uses activity_main.)
- 14. Click Finish.

Result: Andriod Studio creates the structure for your project and opens the development environment.

A few views are available in the Android Studio development environment. The Android view shows a flattened view of the application's structure, and the Project view shows a flattened view of the project's structure, including Gradle-related files.


The Android view provides quick access to key source files of your Android application. Selecting the activity_main.xml file in Android view opens the file in the Layout Editor and allows you to drag-and-drop widgets into your layout.

▶ Quick Start



The following image shows how to switch between Android and Project view.

Figure 3: Switching Views in Android Studio



Import the HERE SDK Android Archive

The HERE Android SDK library is shipped as an Android Archive (.AAR) file. You can import this library by doing the following:

- 1. On the View menu, click Tool Windows > Project.
- 2. A few tabs are available in this tool window. Select the **Project** tab to show a file system view of the application structure.
- 3. In your operating system's file system, navigate to the extracted HERE SDK directory. Copy the HERE-sdk.aar file and paste it into the app/libs/ directory under your application.
- 4. Optional: To enable quick Javadoc reference within your Android Studio environment, scroll down to the External Libraries section, right-click on HERE-sdk, and then select Library Properties. Click the + button and locate HERE-sdk-javadoc.jar from the HERE SDK package.

Modify build.gradle

After importing the .AAR file, modify build.gradle to add the file to your list of dependencies.

- From the Project view pane, locate the build.gradle file under the app folder and open it for editing.
- 2. In build.gradle, add the following line into the android { ... } section:

```
repositories {
   flatDir {
```

▶ Quick Start



```
dirs 'libs'
}
```

3. Next, add the following into the dependencies { ... } section:

```
implementation(name:'HERE-sdk', ext:'aar')
```

4. Optional: Add the JTS Topology Suite (version 1.15.0 or later) library, which is used for rendering complex polygons.

You can add this library by adding the following line into the dependencies $\{ \dots \}$ section of the build.gradle file:

```
implementation 'org.locationtech.jts:jts-core:1.15.0'
```

5. Optional: If you plan on extending this application with HERE Places or Routing functionality, add the GSON library to your project. You can add this library by adding the following line into the dependencies { ... } section:

```
implementation 'com.google.code.gson:gson:2.8.0'
```

Modify AndroidManifest.xml and Add HERE Credentials

- 1. Add the HERE credentials to AndroidManifest.xml. For instructions on how to edit this file, see *Authenticating Applications* on page 20.
- Modify the opening <application> by adding the android:hardwareAccelerated="true" attribute.

```
<application android:icon="@drawable/icon"
android:label="@string/app_name" android:hardwareAccelerated="true">
```

3. Add the following markup before the <application></application> tags:

```
<uses-permission android:name="android.permission.WRITE_EXTERNAL_STORAGE"/>
<uses-permission android:name="android.permission.ACCESS_NETWORK_STATE"/>
<uses-permission android:name="android.permission.INTERNET"/>
<uses-permission android:name="android.permission.ACCESS_WIFI_STATE"/>
```

- Note: If your app uses Android API level 23 (Android 6.0) or above, you must also add code to request for permissions during runtime. You can find more information in the *Request for Permissions* section.
- 4. Optional: To enable quick javadoc reference within your Android Studio environment, click on .idea/libraries/HERE_sdk.xml to edit it, and then add the following after </CLASSES> and before <SOURCES />:

```
<JAVADOC>
<root url="jar://$PROJECT_DIR$/app/libs/HERE-sdk-javadoc.jar!/" />
</JAVADOC>
```

Result: Your project is able to make use of APIs from the HERE SDK.

Edit activity_main.xml

Along with permissions and credentials, you must add an Android <fragment /> tag to set up the map fragment that your application activity is associated with. In this section, we add a text label (generated as part of the default new application) and a map as follows:

▶ Ouick Start



- From the Android View, under the res/layout/ folder of your project, double-click the activity_main.xml file to open it for editing.
- 2. Ensure that the XML file has <LinearLayout></LinearLayout> as its root element. Depending on your version of Android Studio, this may be a RelativeLayout instead. If that is the case, replace the contents of the file with the following:

```
<LinearLayout
    xmlns:android="http://schemas.android.com/apk/res/android"
    xmlns:tools="http://schemas.android.com/tools"
    android:layout_width="fill_parent"
    android:layout_height="fill_parent"
    android:orientation="vertical" >

    <TextView
        android:id="@+id/title"
        android:layout_width="wrap_content"
        android:layout_height="wrap_content"
        android:text="Hello World"
        tools:context=".BasicMapActivity" />

    </LinearLayout>
```

3. Add the following markup beneath the <TextView/> tag:

```
<!-- Map Fragment embedded with the map object -->
<fragment
class="com.here.android.mpa.mapping.SupportMapFragment"
android:id="@+id/mapfragment"
android:layout_width="match_parent"
android:layout_height="match_parent"/>
```

Result: When SupportMapFragment is initialized, your application's BasicMapActivity contains a SupportMapFragment UI element (with the ID mapfragment) that owns a Map object.

Initializing the Map Fragment

When you have defined the basic layout of the application and acquired necessary permissions, the final step is to initialize the instance of the SupportMapFragment class, thus creating and associating a Map with the SupportMapFragment declared in the activity_main.xml file:

- From the Android View, double-click the BasicMapActivity.java file under the java folder to open it for editing.
- Revise the import statements and functional logic of BasicMapActivity to look like the following:

```
package com.here.android.tutorial;
import android.app.Activity;
import android.os.Bundle;
import com.here.android.mpa.common.GeoCoordinate;
import com.here.android.mpa.common.OnEngineInitListener;
import com.here.android.mpa.mapping.Map;
import com.here.android.mpa.mapping.SupportMapFragment;
public class BasicMapActivity extends Activity {
   // map embedded in the map fragment
   private Map map = null;
   // map fragment embedded in this activity
```

▶ Quick Start



```
private SupportMapFragment mapFragment = null;
aOverride
public void onCreate(Bundle savedInstanceState) {
super.onCreate(savedInstanceState);
initialize();
private void initialize() {
setContentView(R.layout.activity_main);
 // Search for the map fragment to finish setup by calling init().
mapFragment = (SupportMapFragment) getFragmentManager().findFragmentById(R.id.mapfragment);
mapFragment.init(new OnEngineInitListener() {
 @Override
  public void onEngineInitializationCompleted(OnEngineInitListener.Error error) {
   if (error == OnEngineInitListener.Error.NONE) {
    // retrieve a reference of the map from the map fragment
   map = mapFragment.getMap();
   // Set the map center to the Vancouver region (no animation)
   map.setCenter(new GeoCoordinate(49.196261, -123.004773, 0.0),
      Map.Animation.NONE);
    // Set the zoom level to the average between min and max
   map.setZoomLevel((map.getMaxZoomLevel() + map.getMinZoomLevel()) / 2);
   } else {
   System.out.println("ERROR: Cannot initialize Map Fragment");
});
```

Request for Permissions

If your app supports Android 6.0 or above, your app needs to ask users to grant certain permissions at runtime. For more information about this requirement, see *Requesting Android Permissions* on page 53.

Run the Applciation

You can run your simple application by pressing the key combination **Shift + F10** (or **Ctrl + R** on Macs) from within Android Studio. The application renders a map retrieved from the HERE servers. When you are running your application on a device, make sure a data connection is enabled.

See the BasicMapSolution folder for a completed example. You need to add your own App_Id and App_Code for this completed example to work.

User Guide



Chapter 3User Guide

Topics:

- System Requirements
- Authenticating Application...
- Examples on GitHub
- Maps
- Positioning
- Directions
- Places

The articles in this section provide a guide to using the HERE Android SDK.

▶ User Guide



System Requirements

HERE Android SDK is designed and tested with Android phones and tablets in mind. SDK performance will vary between devices, since it is primarily determined by CPU, GPU, and display resolution. Currently, Nexus 5 is a suitable reference for a device which delivers acceptable SDK performance. If your target device is not a phone or tablet, see *Service Support* on page 4 to contact us for more details.

- Android 4.1.x "Jelly Bean" (API Level 16) or higher as the application Minimum API Level (android:minSdkVersion).
- Apps should be developed using Android Studio 2.3.2 or above
- 32MB of memory (RAM) available for foreground applications
- A minimum of 1MB per application should be made available for the storage of the HERE SDK libraries
- A minimum of 3.5MB should be made available for the storage of map data
- Data connectivity (WiFi or Cellular) is required to download map data.
- Note: HERE Android SDK does not support x86 Android and x86_64 devices. x86 and x86_64 emulators are supported. It is recommended that app testing is performed on ARM and ARM64 devices.

Authenticating Applications

Developers using the HERE SDK with their app are required to register for a set of HERE credentials and to specify these credentials (App_Id and App_Code) in their app's Android manifest XML file. Failure to do so results in blocked access to certain features and degradation in the quality of other services.

To obtain these credentials, visit the developer portal at https://developer.here.com/plans and register for a license. Once your project is created, you can generate these credentials on your Project Details page. If you already have a plan, you can also retrieve these credentials from your Project Details page.

Note: Credentials are unique to your account and your application's package namespace. Avoid reusing credentials across multiple applications.

Adding Credentials to the Manifest

You can add your HERE credentials as <meta-data/> attributes to the AndroidManifest.xml file as follows:

- 1. In your development environment, double-click your project's AndroidManifest.xml file and ensure that you are viewing the file in text editor mode.
- 2. Within the <application></application> block of tags, add the following markup:

```
<meta-data android:name="com.here.android.maps.appid" android:value="YOUR_APP_ID"/>
<meta-data android:name="com.here.android.maps.apptoken" android:value="YOUR_APP_CODE"/>
```

Replace the {YOUR_APP_ID} and {YOUR_APP_CODE} strings with appropriate credentials for your application.

▶ User Guide



Examples on GitHub

You can find more HERE SDK sample projects on GitHub: https://www.github.com/heremaps

Maps

The core feature of the HERE Android SDK is Maps. The key concepts covered in this section include adding a map to an Android application, changing the location displayed by the map and its various properties. The classes covered include SupportMapFragment and Map. SupportMapFragment and Map are parts of a Model-View-Controller (MVC) pattern where the Model is the Map, and the View is the SupportMapFragment. The SupportMapFragment is a standard Android Fragment derived component. You can create a controller class to coordinate all interactions using custom logic.

The first step to integrate a map into an application is to insert a SupportMapFragment to the view layout of the application. This is accomplished by adding com.here.android.mpa.mapping.SupportMapFragment to the Android XML layout file as follows.

```
<!-- Example fragment. This can be integrated and annotated
like any other android Fragment or View widget -->
<fragment
class="com.here.android.mpa.mapping.SupportMapFragment"
android:id="@+id/mapfragment"
android:layout_width="fill_parent"
android:layout_height="fill_parent"/>
```

The SupportMapFragment class handles all user interactions such as panning, tapping or pinching, as well as other standard HERE SDK touch gestures documented in *MapGestures*.

Initializing SupportMapFragment

After adding the SupportMapFragment to the layout, the fragment must be initialized. The SupportMapFragment initialization is processed asynchronously. During initialization, the MapEngine is initialized to create an instance of Map that is associated with the SupportMapFragment. The SupportMapFragment.init(OnEngineInitListener) method takes in an OnEngineInitListener input parameter to signal the caller when initialization is completed and if it was successful. The SupportMapFragment also initializes a MapEngine instance and creates a Map object associated with the SupportMapFragment. The following code illustrates the basic initialization flow when an Activity is created.

```
@Override
public void onCreate(Bundle savedInstanceState) {
   super.onCreate(savedInstanceState);
   setContentView(R.layout.activity_main);
   // Search for the Map Fragment
   final SupportMapFragment mapFragment = (SupportMapFragment)
    getFragmentManager().findFragmentById(R.id.mapfragment);
   // initialize the Map Fragment and
```

▶ User Guide



```
// retrieve the map that is associated to the fragment
mapFragment.init(new OnEngineInitListener() {
    @Override
    public void onEngineInitializationCompleted(
        OnEngineInitListener.Error error) {
        if (error == OnEngineInitListener.Error.NONE) {
            // now the map is ready to be used
            Map map = mapFragment.getMap();
            // ...
        } else {
            System.out.println("ERROR: Cannot initialize SupportMapFragment");
        }
      }
    }
});
}
```

Note: For performance reasons, com.here.android.mpa.mapping.SupportMapFragment has set Fragment.setRetainInstance(boolean) to true, and therefore onCreate(Bundle) is not called again when Activity is re-created (for example, after a zoom-level change).

Working with Map

Once the SupportMapFragment is initialized, you get the Map associated with the SupportMapFragment through SupportMapFragment.getMap(). The Map class represents the virtual model of the world in a digital format. Key attributes of the Map include the center GeoCoordinate and zoom level. For example, the following code snippet illustrates how to use Map.setCenter(GeoCoordinate, Map.Animation) to render the Map at Vancouver, Canada.

In the preceding code:

- The GeoCoordinate for the map center is created by a call to the new GeoCoordinate(double, double) constructor.
- When setting the center of a map, there is an option either to animate the change or to suppress animation by passing the constant Map. Animation. NONE as the relevant parameter.

Map Center and Zoom

Here are examples of setting and getting Map attributes:

Map Center

The center of the Map is a GeoCoordinate location that your Map is focused on. You can move a Map by redefining its center GeoCoordinate:

```
// Move the map to London.
map.setCenter(new GeoCoordinate(51.51,-0.11),
   Map.Animation.NONE );
```

▶ User Guide



```
// Get the current center of the Map
GeoCoordinate = map.getCenter();
```

Zoom Level

The size of the geographical area displayed by Map can be controlled by changing the zoom level. The zoom level ranges from getMinZoomLevel() to getMaxZoomLevel(), with the minimum value displaying the entire world. The following code sets the zoom level to the median zoom level.

```
// Get the maximum,minimum zoom level.
double maxZoom = map.getMaxZoomLevel();
double minZoom = map.getMinZoomLevel();

// Set the zoom level to the median (10).
map.setZoomLevel((maxZoom + minZoom)/2);

// Get the zoom level back
double zoom = map.getZoomLevel();
```

Animations

The map supports three types of animations when changing attributes:

- Map.Animation.NONE
- Map.Animation.LINEAR

```
// Move to Vancouver using bow animation
map.setCenter(new GeoCoordinate(49.0,-123.0),
   Map.Animation.LINEAR);
```

Note: If the map changes size or the app comes to the foreground while Map.Animation.LINEAR is being used in a Map attribute setter method, then the animation aborts, and the transition appears to fail. To avoid this behavior, use the Map.Animation.NONE animation type or wait until the map is stable before performing the transition operation.

MapState and Listening for Map Transform Events

MapState is an object that is a composite of the zoom level and center map attributes. Your application can listen for updates to the MapState by using an OnTransformListener.

Map transform events are triggered by any operation that causes the MapState to change. These operations include user interaction (for example, map gestures) as well as programmatic calls to the Map (for example, map.setCenter(GeoCoordinate, MapAnimation)). The onMapTransformStart() method is called before MapState begins to change, while the onMapTransformEnd(MapState) method is called after the MapState returns to a steady value. Because of this, there can be a significant amount of time between the two callbacks in cases such as animated map movement events and continuous user interaction.

The following code is an example of registering an OnTransformListener to listen for map transform events:

```
map.addTransformListener(new OnTransformListener() {
     @Override
    public void onMapTransformStart() {
          // map transform is about to start
     }
     @Override
    public void onMapTransformEnd(MapState mapState) {
          // map transform has come to an end
```

▶ User Guide



});

If you need to update UI widgets as the MapState changes between these two callbacks, the recommended approach is to trigger a Runnable when onMapTransformStart() is called, which periodically checks (at no more than 30 frames per second) the current map state via map.getMapState() and updates the UI widgets accordingly. This Runnable can then be canceled upon a call to onMapTransformEnd(MapState). An Android Handler can be used to trigger these Runnable objects.

■ Note: Do not update UI widgets in MapRenderListener.onPostDraw(boolean, long), as this method is frequently called.

Map Gestures

The MapGesture interface encapsulates all user interactions and touch gestures supported by the HERE Android SDK. The MapGesture associated with a particular fragment can be retrieved from SupportMapFragment.getMapGesture(). The default behavior of the map for each gesture type may be used as-is, supplemented, or replaced entirely. The following table is a summary of the available gestures and their default behavior.



To zoom the map in a fixed amount, tap the screen twice with one finger



To zoom out a fixed amount, tap the screen with two fingers



To move the map, press and hold one finger to the screen, and move it in any direction.



To pan the map with momentum, press and swipe one finger on the screen. The map continues to move in the same direction, and gradually slows to a stop.



To zoom in or out continuously, press and hold two fingers to the screen, and increase or decrease the distance between them

► User Guide





Tap the screen with one finger. This gesture does not have a predefined map action.



Press and hold one finger to the screen. This gesture does not have a predefined map action.

The OnGestureListener Interface

The OnGestureListener interface represents a listener to provide notification upon completion of a Map gesture event such as a single tap on a map.

For example, you can create a new OnGestureListener(), as illustrated below.

```
// Map gesture listener
private class MyOnGestureListener implements OnGestureListener {
@Override
public void onPanStart() {
a0verride
public void onPanEnd() {
a0verride
public void onMultiFingerManipulationStart() {
aOverride
public void onMultiFingerManipulationEnd() {
a0verride
public boolean onMapObjectsSelected(List<ViewObject> objects) {
    return false;
ეეე verride
public boolean onTapEvent(PointF p) {
     return false;
@Override
public boolean onDoubleTapEvent(PointF p) {
    return false;
aOverride
public void onPinchLocked() {
aOverride
public boolean onPinchZoomEvent(float scaleFactor, PointF p) {
```

▶ User Guide



```
return false;
}
∩Override
public void onRotateLocked() {
aOverride
public boolean onRotateEvent(float rotateAngle) {
     return false;
a0verride
public boolean onTiltEvent(float angle) {
     return false;
public boolean onLongPressEvent(PointF p) {
     return false;
ล0verride
public void onLongPressRelease() {
ეOverride
public boolean onTwoFingerTapEvent(PointF p) {
     return false;
}
```

Note: The OnGestureListener methods that mention "rotate" and "tilt", such as onRotateEvent(float), are not supported. They are only defined here to maintain compatibility with the Premium Edition of the HERE SDK.

To add the listener to your map, include a call to addOnGestureListener(OnGestureListener) after the map fragment has been successfully initialized as follows:

Note: After you add an OnGestureListener to an application, remember to call removeOnGestureListener(OnGestureListener) when you no longer need to listen for map events to free up application resources.

The default implementation of a OnGestureListener does not affect any of the standard HERE SDK touch gestures. Each method within the MyOnGestureListener class returns a value of false, which stipulates that the application should not override the underlying action that a device performs upon detecting a particular gesture.

If you want to customize an action that your application performs upon detection of a particular gesture, you must include appropriate commands within a relevant method of the MyOnGestureListener

▶ User Guide



class and return a value of true to override the default action, as illustrated below with revisions to the onTwoFingerTapEvent(PointF) method.

```
@Override
public boolean onTwoFingerTapEvent(PointF p) {
    // Reset the map view
    double level = map.getMinZoomLevel() + map.getMaxZoomLevel() / 2;
    map.setCenter(new GeoCoordinate(49.196261, -123.004773),
        Map.Animation.NONE);
    map.setZoomLevel(level);
    return true;
}
```

Note: Since the onTapEvent(PointF) event is always triggered before the onMapObjectsSelected(List<ViewObject>) event, you can leverage this behavior to implement your own object selection logic. While implementing object selection, it is recommended that you use both Map.getSelectedObject(PointF) and Map.getSelectedObject(ViewRect) and combine the results, so that the user's tap input is interpreted over a larger area, rather than only a single point.

After the revision, the basic application responds to each two-finger tap gesture by returning to its initial view (the view displayed upon application launch). Other touch gestures continue to trigger standard HERE SDK actions.

Map Schemes

The HERE Android SDK provides a variety of map appearances for your application to choose from, these appearances are otherwise known as *map schemes*.

Map. Scheme defines visualization types that the HERE map service supports. There is a variety of map schemes available that can be used, based on the specific use case:

- Normal
- Terrain
- Satellite
- Day or Night Time

You can set a desired scheme by making a call to the Map.setMapScheme(String) method.



Examples of Map Scheme

All available schemes are defined as constant strings in the Map. Scheme class. The following are examples of string values that you can use to set the map scheme in your application:

Figure 4: Scheme.NORMAL_DAY



Figure 5: Scheme.SATELLITE_DAY





Figure 6: Scheme.HYBRID_DAY



Figure 7: Scheme.TERRAIN_DAY



Setting a Map Scheme

The following example demonstrates how to retrieve available map schemes and change the current map scheme:

```
// Array containing string values of all available map schemes
List<String> schemes = map.getMapSchemes();
// Assume to select the 2nd map scheme in the available list
map.setMapScheme(schemes.get(1));
```

► User Guide



Listening for MapScheme Change Events

Applications can listen for map scheme change events by way of the Map.OnSchemeChangedListener:

MapEngine Class

MapEngine is a singleton class used to manage active mapping resources for use in applications developed with the HERE SDK. MapEngine must be initialized before Map and map-related objects, such as MapMarker and Places, can be instantiated and retrieved from the API. A runtime exception occurs if MapEngine is not properly initialized before map-related objects are used.

Initialization

MapEngine must be initialized before it can be used and should be done in the main thread.

MapEngine is automatically initialized for your application by using SupportMapFragment.

SupportMapFragment is a fragment class that applications can use as an UI module in an activity for map display. However, if your application does not use SupportMapFragment classes, then the application should initialize the MapEngine directly before using any HERE APIs. You can do this by calling MapEngine.init(ApplicationContext, OnEngineInitListener) as shown below:

If map engine initialization is in progress or has failed, calling any other HERE SDK APIs fails because invalid objects cannot be created. To avoid this problem, check for MapEngine.isInitialized() in your app lifecycle callbacks. For example, the following example avoids problems with using the PositionManager before an instance can be properly created:

```
public void onDestroy()
{
  //Set initComplete using MapEngine.isInitialized()
  if (initComplete) {
    PositioningManager.getInstance().removeListener(this);
  }
  super.onDestroy();
}
```

▶ User Guide



For examples of typical scenarios using the SupportMapFragment that automatically initializes the MapEngine, see *Maps* on page 21.

Objects and Interaction

You can select ViewObject objects by using a single tap gesture. To enable this in your code, create an OnGestureListener object and pass it to

SupportMapFragment.getMapGesture().addOnGestureListener(OnGestureListener). When a single tap occurs, the listener receives the onTapEvent(PointF) callback, and if that event is not handled, then the listener receives the onMapObjectsSelected(List<ViewObject>) callback. The application can then define what to do with the selected ViewObject.

Types of ViewObject objects that are selectable are defined within the ViewObject. Type enumeration, which includes:

- USER_OBJECT an object that the application adds to a map with a MapObject base class (MapPolygon for example).
- UNKNOWN_OBJECT a selectable map object that is not a USER_OBJECT

The ViewObject Abstract Class

The ViewObject abstract class represents the base implementation for all objects that are selectable on a MapView or SupportMapFragment. The SupportMapFragment features user-selectable objects.

Sub-classes of the ViewObject class include MapObject.

MapObject and Geo Objects

MapObject represents an abstract class for all map-related objects that can be added on a Map. The subclasses of this abstract class include:

- MapContainer
- MapCircle
- MapPolyline
- MapPolygon
- MapRoute
- MapMarker

These objects can be created by calling the appropriate constructor methods. In some cases, a geo object is required in the constructor. Geo objects (for example, GeoPolyline and GeoPolygon) are geographical data representations that act as models to MapObjects, which act as views. Unlike map objects, geo objects cannot be added directly to a Map. For more information on geo objects and creating map objects, see the API Reference.

The following code snippet demonstrates how to create a MapPolyline and a GeoPolyline object:

```
List<GeoCoordinate> testPoints = new ArrayList<GeoCoordinate>();
testPoints.add(new GeoCoordinate(49.163, -123.137766, 10));
testPoints.add(new GeoCoordinate(59.163, -123.137766, 10));
testPoints.add(new GeoCoordinate(60.163, -123.137766, 10));
GeoPolyline polyline = new GeoPolyline(testPoints);
MapPolyline mapPolyline = new MapPolyline(polyline);
```

► User Guide



To add a MapObject to the map, use Map.addMapObject(MapObject) or Map.addMapObjects(List<MapObject>).

MapContainer


You can use MapContainer as a container for other MapObject instances. Map containers determine the stacking order of objects displayed on a map. To add a map object, call the MapContainer.addMapObject(MapObject) method.

■ Note: MapRoute and MapContainer cannot be added to a MapContainer.

MapCircle

A MapCircle represents a type of MapObject in the shape of a circle, with an assigned radius distance and a GeoCoordinate center. It can be created by calling the constructor MapCircle(double radius, GeoCoordinate center).

Figure 8: A MapCircle object



MapPolyline


A MapPolyline is a MapObject in the shape of a polyline with anchor points at any number of GeoCoordinate points. It can be created via a GeoPolyline object, which can be created by calling the GeoPolyline(List<GeoCoordinate> points) constructor.

► User Guide



■ **Note:** A MapPolyline or MapPolygon can only contain up to 65536 vertices.

Figure 9: A MapPolyline object



MapPolygon

A MapPolygon is a MapObject in the shape of a polygon. In contrast with a MapPolyline, it is assumed that the last coordinate in the line's path is connected to the first coordinate, thereby constructing an enclosed geometry. A MapPolygon may define separate border and fill colors. To create a MapPolygon, use the constructor MapPolygon (GeoPolygon polygon). A GeoPolygon can be created by calling GeoPolygon(List<GeoCoordinate> points).

Figure 10: A MapPolygon object



MapRoute

A MapRoute is a MapObject that displays a calculated route on a map. For more information on MapRoute, see *Routing*.


► User Guide



MapMarker


A MapMarker is a MapObject that displays an icon at a geographical position on a map. You can create a MapMarker with your own custom icon by calling MapMarker(GeoCoordinate, Image).

Figure 11: A MapMarker object



MapMarker instances are always placed on top of other map objects. Refer to the diagram below for more information about z-index ordering for multiple map markers.

Figure 12: MapMarker order



You can set MapMarker to be draggable by using the MapMarker.setDraggable(true) method. To listen for drag events, such as marker position changes, use MapMarker.OnDragListener.

User Interactions with MapObject

This section provides an example on handling MapObject tap events. In the following code:

- addMapObject() adds the object on the Map.
- List<ViewObject> holds the objects that have been selected in this tap event. By looping through this list of objects, your code can find the MapObject that should respond to this tap event.

► User Guide



Note: The onMapObjectsSelected(List) callback is triggered after the onTapEvent(PointF) callback. For more information on this, refer to Map Gestures on page 24

```
// Create a custom marker image
com.here.android.mpa.common.Image myImage =
new com.here.android.mpa.common.Image();
try {
myImage.setImageResource(R.drawable.my png);
} catch (IOException e) {
finish();
// Create the MapMarker
MapMarker myMapMarker =
new MapMarker(new GeoCoordinate(LAT, LNG), myImage);
map.addMapObject(myMapMarker);
// Create a gesture listener and add it to the SupportMapFragment
MapGesture.OnGestureListener listener =
new MapGesture.OnGestureListener.OnGestureListenerAdapter() {
 a0verride
 public boolean onMapObjectsSelected(List<ViewObject> objects) {
   for (ViewObject viewObj : objects) {
   if (viewObj.getBaseType() == ViewObject.Type.USER_OBJECT) {
    if (((MapObject)viewObj).getType() == MapObject.Type.MARKER) {
     // At this point we have the originally added
      // map marker, so we can do something with it
     // (like change the visibility, or more
      // marker-specific actions)
      ((MapObject)viewObj).setVisible(false);
    }
   // return false to allow the map to handle this callback also
   return false;
  }
};
```

Custom Raster Tiles

You can use the HERE Android SDK to enhance maps with custom raster tiles. Custom raster tiles are tile images that you can add to a map to customize it with enhanced information. For example, you may wish to use this feature to add heat maps over a map of New York City. You can store custom raster tile images locally or on a remote server for users to access when they navigate in a map. If the application is set to display custom raster tiles, then tiles are displayed when users view a designated geographical area at a specified zoom level or range of zoom levels.

Dividing a Map and Tile Lookup

To use your own custom raster tile images, you need to have a scheme for dividing your map according to the zoom level and map coordinates, and then provide map tiles according to this scheme. Your application must then use this scheme in the implementation of one of the following classes:

▶ User Guide



- MapRasterTileSource Implement this class if you plan to fetch local tile images, create dynamic images, or if you would like to provide your own method of retrieving images from a remote server.
- UrlMapRasterTileSourceBase This is a convenience child class of MapRasterTileSource. Implement this if you plan to fetch tile images from a remote server using a URL over HTTP.
- **Note:** Raster tiles can be one of the following supported image types:
 - PNG
 - JPEG
 - BMP

Once a tile source has been implemented, you can toggle its display by adding or removing it to the map using Map.addRasterTileSource(MapRasterTileSource) or Map.removeRasterTileSource(MapRasterTileSource).

The MapRasterTileSource Abstract Class

MapRasterTileSource is the common way for you to define your raster tile source. If your application uses local tile images or remote images that require custom server authentication, then you should implement this class by defining the hasTile() and getTileWithError() methods. For example:

```
public class MyTileSource extends MapRasterTileSource {
    @Override
    public boolean hasTile(int x, int y, int zoomLevel) {
        return true;
    }
    @Override
    public TileResult getTileWithError(int x, int y, int zoomLevel) {
        byte[] myImageData = null;
        // perform tile retrieval logic such as server authentication
        // also translate the x, y, and zoomlevel to address an image
        TileResult result = new TileResult(Error.NONE, myImageData);
        return result;
    }
}
```

Note: Ensure that getTileWithError() returns within a reasonable amount of time. If your operation takes a longer period of time, launch an asynchronous operation and return the TileResult.Error.NOT_READY error code while the operation is in progress.

The UrlMapRasterTileSourceBase Abstract Class

UrlMapRasterTileSourceBase is a child abstract class of MapRasterTileSource that you can use if you plan to fetch tile images from a remote server using image URLs. The following is a sample implementation of UrlMapRasterTileSourceBase. In this example, we use the MapRasterTileSource.MapTileSystemHelper.tileXYToQuadKey() method to address our map tiles. This helper method assumes that we are using a quadtree/quadkey scheme, where the map is divided into a quadtree (a tree data structure where each node has exactly four children) with 20 levels. Each level of this map quadtree has $(2^x)^2$ tiles, where x represents the floor function value of the current zoom level. So for level 0, there is 1 x 1 = 1 tile, level 1 has 2 x 2 = 4 tiles, level 2 has 4 x 4 = 16 tiles, and level 3.7 has 8 x 8 = 64 tiles—since the floor value of 3.7 is 3.

► User Guide



For more information about the quadkey/quadtree division scheme, see the tileXYToQuadKey() API reference.

```
public class LiveMapRasterTileSource extends UrlMapRasterTileSourceBase {
private final static String URL_FORMAT =
   "http://1.communitymaptiles.example.org/tilehub/live/map/png/%s";
public LiveMapRasterTileSource() {
  // We don't want the tiles visible between these zoom levels
 hideAtZoomRange(12, 20);
 // Do not cache tiles
 setCachingEnabled(false);
}
// Implementation of UrlMapRasterTileSourceBase
public String getUrl(int x, int y, int zoomLevel) {
 String url = null;
 // Utility to map the x, y coordinates easily into an equivalent
  // quadkey at a specified zoomLevel
  String quadKey =
   MapTileSystemHelper.tileXYToQuadKey(x, y, zoomLevel);
  // Append the quadkey to the URL template to get a real URL
  url = String.format(URL_FORMAT, quadKey);
  } catch (Exception ex) {
   ex.printStackTrace();
  return url;
}
```

The example above generates a quadkey from the x, y coordinates and the zoom level and appends it to the URL. However, this is server-specific and the method of converting x, y and zoom level to a URL can be done in many ways. Also, it is worth noting that tiles can be cached with setCachingEnabled(true).

Caching Tiles

Tiles can be cached to the disk by calling the following:

```
// Give the tile source a custom prefix so it can be cached on the disk
MapRasterTileSource.setCachePrefix(String cache)

// Give each raster tile file an expiration time in seconds.
MapRasterTileSource.setCacheExpiration( int seconds )
```

If no expiration time is set, then the raster tiles remains on the device. We recommend that both a cache prefix and an expiration time be set.

Positioning

▶ User Guide



Basic Positioning

The HERE Android SDK provides the following interfaces for users to retrieve location updates and to display their current location on a map:

- PositioningManager
- OnPositionChangedListener
- PositionIndicator
- Note: The Android permission android.permission.ACCESS_FINE_LOCATION is required when your app calls PositioningManager.start(LocationMethod). Otherwise, the method returns false. In addition, to ensure that the app receives location updates, the user needs to have the Location permission enabled (toggled to "on") during runtime.

PositioningManager Class

A PositioningManager class provides information related to the device's geographical location, like the current position and the average speed. Applications can register to receive position updates using one of the positioning mechanisms described in the LocationMethod:

- GPS positioning using the real GPS available on the device.
- GPS_NETWORK positioning is provided using a wireless network or the real GPS available on the device
- NETWORK positioning using a wireless network.

The current status of a particular location method is represented by the LocationStatus value returned from the PositioningManager.getLocationStatus(LocationMethod) method.

PositioningManager can be accessed by calling PositioningManager.getInstance(). An application can start receiving real time positioning updates by calling PositioningManager.start(LocationMethod) with one of the location methods listed above and can stop the positioning updates by calling PositioningManager.stop(). While position updates are being received, an application can retrieve the current position of the client device via the PositioningManager.getPosition() method.

OnPositionChangedListener Interface

In addition to the PositioningManager's getPosition() method, applications can subscribe to position update notifications from the PositioningManager through the PositioningManager.OnPositionChangedListener interface. To add or remove OnPositionChangedListener, applications can use the following methods:

PositioningManager.addListener(WeakReference<OnPositionChangedListener>)

Positioning Manager.remove Listener (On Position Changed Listener)

The positioning manager enhances your application with the current position of the user's device. The registration of the positioning listener should be performed after the SupportMapFragment, MapView, or MapEngine is initialized as described in the following code snippet.

```
// Define positioning listener
private OnPositionChangedListener positionListener = new
```

▶ User Guide



In order to avoid unnecessary position updates while the activity is in the background, you need to start or stop the PositioningManager within your activity's onResume() and onPause() methods.

```
// Set this to PositioningManager.getInstance() upon Engine Initialization
private PositioningManager posManager;
// Resume positioning listener on wake up
public void onResume() {
super.onResume();
paused = false;
if (posManager != null) {
 posManager.start(
    PositioningManager.LocationMethod.GPS_NETWORK);
}
// To pause positioning listener
public void onPause() -
if (posManager != null) {
 posManager.stop();
super.onPause();
paused = true;
// To remove the positioning listener
public void onDestroy() {
if (posManager != null) {
 // Cleanup
 posManager.removeListener(
   positionListener);
map = null;
super.onDestroy();
```

PositionIndicator Class

PositionIndicator is a special map marker object that allows the current client device position to be shown on a map. Every HERE SDK Map object has an integrated position indicator, set to invisible, by

▶ User Guide




default. The indicator can be retrieved and set to visible by calling Map.getPositionIndicator() and PositionIndicator.setVisible(), as follows:

```
// map fragment has been successfully initialized,
// now the map is ready to be used
map = mapFragment.getMap();

// Display position indicator
map.getPositionIndicator().setVisible(true);
```

By default, the position indicator is rendered as a marker surrounded by a circle, the diameter of which illustrates the accuracy of the indicated position. You can change this marker by calling PositionIndicator.setMarker(Image).

Figure 13: A PositionIndicator



- Note: For the position indicator to stay in the center of the map and illustrate real-time updates of the device's position, it is necessary to update the map's center whenever a new location update is received.
- **Note:** PositionIndicator only works if the application has started the PositioningManager.

Directions

This section provides an overview of the Directions feature in the HERE SDK. The Directions feature allows developers to define and display routes between a start and a destination point within their application. It supports many navigation options such as toll road preference and transport type.

▶ User Guide



Route Calculation for Walking or Driving

The HERE Android SDK supports route calculation with multiple waypoints, optimized for walking or driving.

A route describes a path between at least two waypoints, the starting point and the destination, with optional intermediate waypoints in between. Applications can provide route information to users in two ways:

- A line rendered on a map that displays a connecting path between all waypoints
- Turn-by-turn directions in text format

Note:

- To use this feature, your application must include the **Gson** library (release 2.2.4 or a compatible version) on its class path.
- To support routes that are greater than 5000 km, add the largeHeap attribute in the <application> section of AndroidManifest.xml. For more information, see this article on managing your app memory.

Route Calculation Classes

This section introduces the following classes that are used for route calculations:

- RouteManager
- RoutePlan
- RouteOptions

The RouteManager class is responsible for calculating a route. An application can initiate a route calculation by calling the RouteManager.calculateRoute(RoutePlan, Listener) method, providing options and waypoints through RoutePlan, and receive progress updates through the RouteManager.Listener instance.

RoutePlan is a waypoint container that is used for route calculation. A RoutePlan object is comprised of a list of waypoint objects and an optional RouteOptions. If RouteOptions is not specified, default values are used. You can add an individual waypoint to a RoutePlan by using a GeoCoordinate.

The RouteOptions class is a model of the parameters required to calculate one route. It encapsulates "building block" parameters for a route such as:

- The desired number of routes
- · The direction of travel that the route should start in
- The routing type, such as fastest travel time or shortest distance
- The mode of transportation, such as by walking or driving
- The departure time
- The allowed types of route segments, such as dirt roads, highways, or ferries
- **Note:** Routing type describes different optimizations that can be applied during the route calculation:
 - Fastest route calculation from start to destination optimized by travel time. In some cases, the
 route returned by the fastest mode may not be the route with the shortest possible travel time.
 For example, it may favor a route that remains on a highway, even if a shorter travel time can be
 achieved by taking a detour or shortcut through a side road.
 - Shortest route calculation from start to destination disregarding any speed information. In this mode, the distance of the route is minimized, while keeping the route sensible. This includes,

▶ User Guide



for example, penalizing turns. Because of that, the resulting route will not necessarily be the one with minimal distance.

 Balanced - route calculation from start to destination optimizing based on combination of travel time and distance.

The HERE SDK supports alternate routes between two waypoints. The alternate route feature allows more than one route to be returned after a route calculation. You can use the RouteOptions class to set the desired number of routes, and the HERE SDK then returns different routes according to this limit. Note that the first element of the returned list of RouteResult is the main route, and the rest of the returned routes are not listed in any specific order.

RouteResult and Route

The RouteResult class represents a route calculation result. Applications can retrieve a Route object and the corresponding set of violated routing conditions. *Violated routing options* are the conditions that a routing result was unable to adhere to. For example, after specifying a route calculation that avoids tolls and ferries, you may get a RouteResult that contains a Route object along with RouteResult.ViolatedOption.AVOID_TOLL_ROADS. This indicates that although a route was found, this route goes through at least one toll road—violating a condition of your route request.

The Route class is a distinct calculated path connecting two or more waypoints, consisting of a list of maneuvers and route links. By using RouteManager.calculateRoute(RoutePlan, Listener) to trigger a route calculation, your application can use the RouteManager.Listener to monitor the calculation and trigger callback methods. These callback methods have parameters that include a list of the calculated RouteResult objects. Using these RouteResult objects, you can call getRoute() to retrieve the routes.

The MapRoute Class


The MapRoute class is a type of MapObject that displays a calculated route on a map. Typically, an application creates a MapRoute after a route calculation, passing the relevant Route object as a parameter to the MapRoute(Route) constructor before adding the MapRoute to the map by calling Map.addMapObject(MapRoute).

► User Guide



For example, if you want to render a route that connects two waypoints (start and destination), you can add the following application logic:

Figure 14: Calculate Route



1. Declare a RouteManager instance.

```
// Declare the rm variable (the RouteManager)
RouteManager rm = new RouteManager();
```

2. Create a RoutePlan and add two GeoCoordinate waypoints.

```
// Create the RoutePlan and add two waypoints
RoutePlan routePlan = new RoutePlan();
routePlan.addWaypoint(new GeoCoordinate(49.1966286, -123.0053635));
routePlan.addWaypoint(new GeoCoordinate(49.1947289, -123.1762924));
```

3. Create a new RouteOptions object, set its Type and TransportMode values by calling appropriate RouteOptions methods, and then add it to RoutePlan.

```
// Create the RouteOptions and set its transport mode & routing type
RouteOptions routeOptions = new RouteOptions();
routeOptions.setTransportMode(RouteOptions.TransportMode.CAR);
routeOptions.setRouteType(RouteOptions.Type.FASTEST);
routePlan.setRouteOptions(routeOptions);
```

4. To make sure route calculation can handle returning a Route object that in turn can be used to create a MapRoute instance for rendering on the map, add an inner class by implementing RouteManager.Listener in the appropriate activity class.

```
private class RouteListener implements RouteManager.Listener {
```

▶ User Guide



```
// Method defined in Listener
public void onProgress(int percentage) {
    // Display a message indicating calculation progress
}

// Method defined in Listener
public void onCalculateRouteFinished(RouteManager.Error error, List<RouteResult> routeResult) {
    // If the route was calculated successfully
    if (error == RouteManager.Error.NONE) {
        // Render the route on the map
        MapRoute mapRoute = new MapRoute(routeResult.get(0).getRoute());
        map.addMapObject(mapRoute);
    }
    else {
        // Display a message indicating route calculation failure
    }
}
```

 After adding the inner listener class (named RouteListener for this example), calculate the route by calling RouteManager.calculateRoute(RoutePlan, Listener) (making use of an instantiated RouteListener object).

```
// Calculate the route
rm.calculateRoute(routePlan, new RouteListener());
```

Note: Routes with more than 100 waypoints may require significant calculation time.

Routing-related Enumerations

Route calculations make use of HERE SDK enumerations that include:

- The Route.TrafficPenaltyMode enum represents values describing how the RouteManager should handle traffic events in a route calculation, such as DISABLED, AVOID_LONG_TERM_CLOSURES, or OPTIMAL.
- The RouteOptions.Type enum represents values describing different routing types, such as FASTEST, SHORTEST, or ECONOMIC
- The RouteOptions.TransportMode enum represents values describing different transport modes, such as CAR or PEDESTRIAN
- The RouteManager.Error enum represents values describing possible route calculation errors, such as NONE or VIOLATES OPTIONS
- The RouteResult.ViolatedOption enum represents values describing possible route option violations, such as AVOID HIGHWAYS or AVOID FERRIES

Places

This section provides an overview of the Places feature in the HERE SDK. The Places feature enables developers to build rich, location-aware applications by adding point of interest search, discovery, interaction, and information retrieval.

For example, when an application submits a place discovery request using this API, the application receives a response that contains a list of links to places resources (among other information). By accessing one of the linked Place resources, the application can get detailed information about that place, including ratings, images, reviews, editorials, and owner content. This detailed place response also contains references to

▶ User Guide



other related places, allowing the application's users to discover other places relevant or related to their original search.

Geocoding and Reverse Geocoding

Geocoding and reverse geocoding APIs from the HERE Android SDK allow application developers to offer search functionality for requesting location information and structured addresses. Geocoding APIs resolve to a GeoCoordinate from a text query, while reverse geocoding APIs resolve to a geographic data, such as Address, from a GeoCoordinate. Address provides textual address information, which includes house number, street name, city, country, and district. It encompasses everything about an address or a point on the map. Location represents a physical point on the map where additional attributes can be retrieved. These additional attributes include a unique identifier, label, Address, GeoCoordinate positions, and GeoBoundingBox for the Location.

The GeocodeRequest2 Class

GeocodeRequest2 represents an extended Request. GeocodeRequest2 can be created using a one-box (free-formatted text) search using a combination of a text query string and geographical area arguments. The following shows the method used to create a one-box request:

```
GeocodeRequest2 request = new GeocodeRequest2(String).setSearchArea(GeoCoordinate, int)
```

The preceding method returns a GeocodeRequest2 object. To begin the search, call GeocodeRequest2.execute(). This method requires a ResultListener as an argument. When the search is completed, the ResultListener.onCompleted() method is called with a result status and a list of found locations.

After a request is invoked, it can be canceled using the GeocodeRequest2.cancel() method, which returns true if the request was cancelled successfully. For GeocodeRequest2, a list of Location objects are expected at the completion of the request.

The following code example demonstrates how to perform a GeocodeRequest2:

▶ User Guide

}



The ReverseGeocodeRequest Class

The ReverseGeocodeRequest class represents an extended Request used to retrieve Address data. The request is created using a GeoCoordinate as shown below:

```
new ReverseGeocodeRequest(GeoCoordinate)
```

The above method returns a ReverseGeocodeRequest object. To invoke the request, you can then call the execute() method of the returned ReverseGeocodeRequest object and pass in a ResultListener to retrieve the information about the completion of the request. Once a request is invoked, the request can be cancelled via the ReverseGeocodeRequest.cancel() method. cancel() returns true if the request was cancelled successfully. For ReverseGeocodeRequest, a structured Address is expected at the completion of the request.

The following is an example of creating ReverseGeocodeRequest using new ReverseGeocodeRequest(GeoCoordinate):

```
// Implementation of ResultListener
class ReverseGeocodeListener implements ResultListener<Address> {
aOverride
public void onCompleted(Address data, ErrorCode error) {
 if (error != ErrorCode.NONE) {
  // Handle error
 } else {
  // Process result data
// Instantiate a GeoCoordinate object
GeoCoordinate vancouver = new GeoCoordinate( 49.2849, - 123.1252);
// Example code for creating ReverseGeocodeRequest
ResultListener<Address> listener = new ReverseGeocodeListener();
ReverseGeocodeRequest request = new ReverseGeocodeRequest(vancouver);
if (request.execute(listener) != ErrorCode.NONE) {
// Handle request error
}
```

Search and Discovery

The HERE Android SDK provides application developers the Places API, which allows places discovery and information retrieval.

Steps for performing a search

- Implement the ResultListener interface to handle the completion of the search
- 2. Create a request and apply request options
- Invoke the request by calling Request.execute(ResultListener)
- 4. The ResultListener.onCompleted() callback is triggered when the request is finished

► User Guide



- **Note:** Applications that use the Places API must honor the following prescribed workflow:
 - 1. Search
 - 2. Request for Details
 - 3. Perform Actions

Do not preload results linked from a response to improve performance, as doing so violates HERE's guidelines. For more information about usage restrictions, consult the API Implementation Check List in the REST HERE Places API documentation.

The Place Class

The Place class represents a detailed set of data about a physical place, acting as a container for various attributes, collections of media about a place, and key-value pairs of related places. A Place object can belong to a specific Category, and has attributes such as:

- A unique identifier (ID)
- A name
- A Location object representing the physical location of the place, including access locations
- A List of Category objects that link to the categories assigned to the place
- A URL to the icon that best represents the place
- Optional information, such as related places, user ratings, reviews, and other editorial media.

For more information, please see the API Reference.

Discovery Requests

The HERE Places Search API supports the following discovery requests:

Request	HERE SDK class	Purpose
Search	SearchRequest	Finds places that match user-provided search terms.
Explore	ExploreRequest	Finds interesting places nearby, or in the map viewport, sorted by popularity. Use this type of request if you are trying to answer the question "What are the interesting places near here?" The results may be optionally restricted to a given set of categories, which acts as a filter in terms of what places get returned.
Here	HereRequest	Helps users identify places at the given location by finding places of interest near a given point, sorted by distance. Use this type of request if you are trying to answer the question "What is near this location?" or "Where am I?" You can use this endpoint to implement features like "check-in" (by identifying places at the user's current position) or "tap to get more information about this place of interest".
		Note: Normally, the closest known places are returned with the Here Discovery request, but if the uncertainty in the given position is high, then some nearer places are excluded from the result in favor of more popular places in the area of uncertainty.

The following code example demonstrates how to perform a search discovery request:

```
// Example Search request listener
class SearchRequestListener implements ResultListener<DiscoveryResultPage> {
    @Override
    public void onCompleted(DiscoveryResultPage data, ErrorCode error) {
```

▶ User Guide



```
if (error != ErrorCode.NONE) {
  // Handle error
  } else {
  // Process result data
 }
}
// Create a request to search for restaurants in Seattle
GeoCoordinate seattle
  = new GeoCoordinate(47.592229, -122.315147);
DiscoveryRequest request =
 new SearchRequest("restaurant").setSearchCenter(seattle);
// limit number of items in each result page to 10
request.setCollectionSize(10);
ErrorCode error = request.execute(new SearchRequestListener());
if( error != ErrorCode.NONE ) {
 // Handle request error
} catch (IllegalArgumentException ex) {
// Handle invalid create search request parameters
```

The result of a discovery request is a DiscoveryResultPage. The DiscoveryResultPage represents a paginated collection of items from which the following can be retrieved:

- Next page and previous page requests discovery requests used to retrieve additional pages of search items
- Items for the current page a List of DiscoveryResult

When additional pages of search results are needed, retrieve and invoke the DiscoveryRequest returned by DiscoveryResultPage.getNextPageRequest(). If the next page request is null, no additional results are available.

The following is an example:

```
DiscoveryResultPage mResultPage = null;

// Example Search request listener
class SearchRequestListener implements ResultListener<DiscoveryResultPage> {

@Override
public void onCompleted(DiscoveryResultPage data, ErrorCode error) {
    if (error != ErrorCode.NONE) {
        // Handle error
        ...
    } else {
        // Store the last DiscoveryResultPage for later processing
        mResultPage = data;
        ...
    }
}

// When the next page of results is needed...
```

▶ User Guide



```
DiscoveryRequest nextPageRequest = mResultPage.getNextPageRequest();

if (nextPageRequest != null) {
    // More data is available if the nextPageRequest is not null
    ErrorCode error = nextPageRequest.execute(new SearchRequestListener());
    if( error != ErrorCode.NONE ) {
        // Handle request error
        ...
    }
}
```

Calling DiscoveryResultPage.getItems(), returns a List containing one of the following types of objects, which are DiscoveryResult instances. DiscoveryResult is a collection of Link subtypes.

- PlaceLink Represents discovery information about a Place. The PlaceLink contains a brief summary about a place. Details about a place are available from the Place that the PlaceLink references.
- DiscoveryLink Represents a discovery-related API link used to retrieve additional
 DiscoveryResultPage. This type of Link can be a result item in an Explore or Here type of search.
 The DiscoveryLink references refined discovery requests resulting in more specific results. For
 example, the DiscoveryLink may link to a discovery request to search for 'Eat & Drink', 'Going Out',
 'Accommodation', and so on.

Since there may be new types of Link items in the future, it is recommended that each type of DiscoveryResult be checked before it is used (as shown in the following code snippet). In the following example, it is shown how a Place is retrieved through a PlaceLink:

```
// Implement a search result listener
ResultListener<DiscoveryResultPage> searchListener = new ResultListener<DiscoveryResultPage>() {
aOverride
public void onCompleted(DiscoveryResultPage results, ErrorCode error) {
  if (error == ErrorCode.NONE) {
  // The results is a DiscoveryResultPage which represents a
  // paginated collection of items.
  List<DiscoveryResult> items = results.getItems();
  // Iterate through the found place items.
  for (DiscoveryResult item : items) {
   // A Item can either be a PlaceLink (meta information
   // about a Place) or a DiscoveryLink (which is a reference
   // to another refined search that is related to the
   // original search; for example, a search for
   // "Leisure & Outdoor").
   if (item.getResultType() == ResultType.PLACE) {
    PlaceLink placeLink = (PlaceLink) item;
     // PlaceLink should be presented to the user, so the link can be
     // selected in order to retrieve additional details about a place
    // of interest.
   } else if (item.getResultType() == ResultType.DISCOVERY) {
    DiscoveryLink discoveryLink = (DiscoveryLink) item;
     // DiscoveryLink can also be presented to the user.
    // When a DiscoveryLink is selected, another search request should be
     // performed to retrieve results for a specific category.
   }
  }
  } else {
  // Handle search request error.
```

▶ User Guide



```
}
};
// Implement a Place listener for handling user interaction with a displayed PlaceLink
class PlaceListener implements ResultListener<Place> {
@Override
public void onCompleted(Place data, ErrorCode error) {
  if (error != ErrorCode.NONE) {
  // Handle error
 } else {
  // Present the place details to the user.
  String placeName = data.getName();
  List<Category> placeCategories = data.getCategories();
}
// Retrieve the place details when the user selects a displayed PlaceLink.
private void onPlaceLinkSelected(PlaceLink placeLink) {
PlaceRequest placeRequest = placeLink.getDetailsRequest();
if( placeRequest.execute(new PlaceListener()) == ErrorCode.NONE ) {
 // Request successful. Additional work can be done here, however, place details will
 // be returned in PlaceListener.onCompleted().
} else {
 // Handle the error
}
```

Text AutoSuggestion Requests

The HERE Places Search API also supports text autosuggestion requests. This type of request is used for retrieveing a list of suggested search terms (AutoSuggestQuery), instant results (AutoSuggestPlace), and refined search links (AutoSuggestSearch) that are related to a specified location context and a partial search term. For example, if you make a request with the String "rest" in Berlin, the results contain search terms such as "Restaurant", "Rest area", and "Restorf, Höhbeck, Germany".

To use text suggestions, implement a listener to handle a list of AutoSuggest objects and call new TextAutoSuggestionRequest(String) as follows:

▶ User Guide



```
}
}
}
```

You can retrieve the results of a TextAutoSuggestionRequest by first checking the autosuggest object type, as shown in the following example. Note that it is possible for AutoSuggestSearch to contain additional paginated results through the DiscoveryRequest object. If the object is AutoSuggestPlace, you can request for more details through its PlaceRequest object. AutoSuggestQuery contains additional results through its TextAutoSuggestionRequest object.

```
//assume autoSuggestList contains the list of results
try {
   AutoSuggest autoSuggest = autoSuggestList.get(index);
   // set title
   String title = autoSuggest.getTitle();
   // get highlightedTitle
   String highlightedTitle = Html.fromHtml(autoSuggest.getHighlightedTitle()).toString();
   if (autoSuggest instanceof AutoSuggestPlace) {
        AutoSuggestPlace autoSuggestPlace = (AutoSuggestPlace)autoSuggest;
        // vicinity
       if (autoSuggestPlace.getVicinity() != null) {
            String vicinity = autoSuggestPlace.getVicinity();
        // set category
       if (autoSuggestPlace.getCategory() != null) {
            String category = autoSuggestPlace.getCategory();
        // set position
       if (autoSuggestPlace.getPosition() != null) {
            String position = autoSuggestPlace.getPosition().toString();
        // set boundaryBox
       if (((AutoSuggestPlace)autoSuggest).getBoundingBox() != null) {
            String boundingBox = ((AutoSuggestPlace)autoSuggest).getBoundingBox().toString();
    } else if (autoSuggest instanceof AutoSuggestSearch) {
       AutoSuggestSearch autoSuggestSearch = (AutoSuggestSearch)autoSuggest;
        // set category
       if (autoSuggestSearch.getCategory() != null) {
            String category = autoSuggestSearch.getCategory();
        // set position
       if (autoSuggestSearch.getPosition() != null) {
            String position = autoSuggestSearch.getPosition().toString();
        // set boundaryBox
       if (autoSuggestSearch.getBoundingBox() != null) {
            String boundingBox = autoSuggestSearch.getBoundingBox().toString();
        DiscoveryRequest myDiscoveryRequest = autoSuggestSearch.getSuggestedSearchRequest();
       myDiscoveryRequest.execute(myDiscoveryResultPagelistener);
```

► User Guide



```
} else if (autoSuggest instanceof AutoSuggestQuery) {
    AutoSuggestQuery autoSuggestQuery = (AutoSuggestQuery)autoSuggest;

    // set completion
    if (autoSuggestQuery.getQueryCompletion() != null) {
        String completion = autoSuggestQuery.getQueryCompletion();
    }

    TextAutoSuggestionRequest myAutoSuggestionRequest = autoSuggestQuery.getRequest();
    myAutoSuggestionRequest.execute(myAutoSuggestionResultPagelistener);
}

} catch (Exception e) {
    Log.e("ERROR: ", e.getMessage());
}
```

► Supplemental Information



Chapter 4Supplemental Information

Topics:

- Requesting Android Permiss...
- Device and Emulator Suppor...
- Adding a SupportMapFragmen...
- Development Tips

This section provides supplemental information for using the HERE Android SDK.

► Supplemental Information



Requesting Android Permissions

If your application supports Android 6.0 or above, add the following code in your activity file to ask the application users to grant Android permissions at runtime. For more information about this requirement, see the *Android Developer documentation*.

Figure 15: Request Location Permission





Figure 16: Request File Access Permission



1. Add the following import statements to the beginning of the file:

```
import android.content.pm.PackageManager;
import android.support.annotation.NonNull;
import android.support.v4.app.ActivityCompat;
import android.support.v4.content.ContextCompat;
import android.Manifest;
import android.widget.Toast;
import java.util.ArrayList;
import java.util.Arrays;
import java.util.List;
```

Add these static variables to the BasicMapActivity class:

```
/**
* permissions request code
```

► Supplemental Information



```
*/
private final static int REQUEST_CODE_ASK_PERMISSIONS = 1;

/**
 * Permissions that need to be explicitly requested from end user.
 */
private static final String[] REQUIRED_SDK_PERMISSIONS = new String[] {
    Manifest.permission.ACCESS_FINE_LOCATION, Manifest.permission.WRITE_EXTERNAL_STORAGE };
```

- Note: android.permission.ACCESS_FINE_LOCATION is not required to initialize or use the SDK. However, this Android permission is required if you use PositioningManager.
- Add the following methods to the BasicMapActivity class:

```
* Checks the dynamically-controlled permissions and requests missing permissions from end user.
protected void checkPermissions() {
    final List<String> missingPermissions = new ArrayList<String>();
    // check all required dynamic permissions
    for (final String permission : REQUIRED_SDK_PERMISSIONS) {
        final int result = ContextCompat.checkSelfPermission(this, permission);
        if (result != PackageManager.PERMISSION_GRANTED) {
            missingPermissions.add(permission);
    if (!missingPermissions.isEmpty()) {
        // request all missing permissions
        final String[] permissions = missingPermissions
                .toArray(new String[missingPermissions.size()]);
        ActivityCompat.requestPermissions(this, permissions, REQUEST_CODE_ASK_PERMISSIONS);
        final int[] grantResults = new int[REQUIRED_SDK_PERMISSIONS.length];
        Arrays.fill(grantResults, PackageManager.PERMISSION_GRANTED);
        onRequestPermissionsResult(REQUEST_CODE_ASK_PERMISSIONS, REQUIRED_SDK_PERMISSIONS,
                grantResults);
}
@Override
public void onRequestPermissionsResult(int requestCode, @NonNull String permissions[],
        aNonNull int[] grantResults) {
    switch (requestCode) {
        case REQUEST_CODE_ASK_PERMISSIONS:
            for (int index = permissions.length - 1; index >= 0; --index) {
                if (grantResults[index] != PackageManager.PERMISSION_GRANTED) {
                    // exit the app if one permission is not granted
                    Toast.makeText(this, "Required permission '" + permissions[index]
                            + "' not granted, exiting", Toast.LENGTH_LONG).show();
                    finish();
                    return;
                }
            }
            // all permissions were granted
            initialize();
            break;
```

4. Finally, change the method call in onCreate(Bundle) from initialize() to checkPermissions() instead:

```
@Override
public void onCreate(Bundle savedInstanceState) {
  super.onCreate(savedInstanceState);
  checkPermissions();
```

► Supplemental Information



}

Device and Emulator Support

HERE Android SDK includes support for the x86 and x86_64 Application Binary Interface (ABI). The x86 ABIs enables you to run apps with x86 or x86_64 Android Virtual Devices (AVD).

For more information on ABIs, see https://developer.android.com/ndk/guides/abis.html.

For more information on how to create AVDs, see https://developer.android.com/studio/run/managing-avds.html.

Note: To get the best possible performance on an AVD, install and enable Intel HAXM by following these instructions: https://developer.android.com/studio/run/emulator-acceleration.html.

By default, you do not need to make any changes to your development environment to include x86 or x86_64 native libraries. However, any .apk file that you build with the HERE SDK will be larger, since it contains more native libraries. Optionally, you can follow *this guide* to create multiple .apk files, with each containing native libraries for a specific ABI, and thus reducing application sizes.

Adding a SupportMapFragment at Runtime

Earlier tutorials in this document featured adding a SupportMapFragment to an activity by editing the layout XML file. You can also add a SupportMapFragment to an activity dynamically, during runtime, by performing the following steps in the Activity class:

1. Create a layout container:

```
final int CONTAINER_ID = 1234567;
LinearLayout layoutContainer = new LinearLayout(this);
layoutContainer.setOrientation(LinearLayout.HORIZONTAL);
layoutContainer.setId(CONTAINER_ID);
```

2. Define a map tag:

```
final String MAP_TAG = "map_tag";
```

3. Create a map fragment and add it using the fragment manager:

```
mapFragment = new SupportMapFragment();
getFragmentManager().beginTransaction().add(layoutContainer.getId(), mapFragment,
MAP_TAG).commit();
```

4. Initialize the map fragment by implementing OnEngineInitListener:

```
MyOnEngineInitListener onEngineInitListener = new MyOnEngineInitListener();
ApplicationContext context = new ApplicationContext(this);
mapFragment.init(context, onEngineInitListener);
```

► Supplemental Information



5. Finally, show the content view:

```
setContentView(layoutContainer);
```

For more information on adding a fragment at runtime, see this article: https://developer.android.com/training/basics/fragments/fragment-ui.html#AddAtRuntime.

Development Tips

This section provides tips on building your application using the HERE Android SDK.

Upgrading from Older Versions of HERE SDK

The HERE Android SDK is now packaged as an Android archive (AAR) file instead of separate JAR, native library and proguard components. If you are upgrading from an older HERE SDK release, the old components should be cleaned up before integrating the AAR version of the HERE SDK. To do so, follow these steps:

 Ensure the HERE-sdk.jar file is removed from your project and the compile entry is removed from your build.gradle file. The JAR may be located at app/libs/HERE-sdk.jar and included in your build.gradle file one of the following:

```
compile files('libs/HERE-sdk.jar')
compile fileTree(dir: 'libs', include: ['*.jar'])
```

Note that if you were previously using the Google GSON library or the JTS Topology Suite library with the HERE SDK, it is still required to be included separately.

2. Remove the HERE SDK proguard file and the proguard entry specific to the HERE SDK from the build.gradle file. The file to remove is named proguard-here-sdk.txt, and the entry of the same name should also be removed from the proguardFiles property in your build.gradle file. The proguard instructions for newer versions of the HERE SDK are now applied automatically and are included in the AAR.

You can find further info on integrating the AAR version of the HERE SDK into your app in the *Run the Sample Application* on page 11 section of the User Guide and the associated HERE-sdk/tutorial/BasicMapSolution/app/build.gradle file.

Lapsed Listeners and Garbage Collection

The HERE SDK provides a number of listener interfaces, such as Map.OnSchemeChangedListener, Map.OnTransformListener, and MapGesture.OnGestureListener. To use these listeners, you are required to implement and create a listener instance, then register it with another object (using a method such as addSchemeChangedListener()) to receive event notifications. Unfortunately, this coding pattern can also lead to the *lapsed listener problem*, where available memory is consumed by listener objects that are not explicitly unregistered and not garbage collected.

To mitigate this problem, the HERE SDK, in some cases, accepts listener objects in WeakReference containers. This has the advantage of avoiding lapsed listeners, but it also means that you must be aware of registered listeners becoming garbage collected. To avoid any unintended issues with this coding pattern, be sure to retain a strong reference to your listener instances (for example, by assigning it to a class variable) if

► Supplemental Information



you would like to manage its garbage collection lifecycle. Listener objects are not garbage collected as long as a strong reference exists.

Working with Getters

Classes in the HERE SDK return copies of objects in its getters. For example, MapPolyline.getPolyline() does not return the same GeoPolyline instance that was used to construct the MapPolyline object; instead, a copy of the GeoPolyline is returned. Since this returned object is a copy, you cannot dynamically modify the MapPolyline instance by modifying this object. If you would like to make changes to MapPolyline, you must call setGeoPolyline(GeoPolyline) instead.

Map Object Limitations

The HERE SDK does not limit the number of map markers, polygons, and polylines that can be added to a map. However, rendering a large number of map objects can cause performance degradation in your application. It is recommended that you use techniques such as viewport clipping to avoid these issues.

Doze and App Standby

If you are using Android 6.0 (API level 23) or above, be aware that the *Doze* and *App Standby* features may impact your HERE SDK app by disabling network access when the device is unplugged, stationary, and has the screen off for a period of time. While the HERE Android SDK has the ability to work offline, you should design your app with these operating system features in mind.

For more information about Doze and App Standby, including how to use notifications and whitelisting to ensure your app functions properly, see the Android article, "Optimizing for Doze and App Standby".

Native Libraries and ABI Splits

Your app may encounter an error if it also *includes other dependencies that have unsupported ABIs*. To get around this issue, enable ABI splits to build for the armeabi-v7a, arm64-v8a, or both architectures explicitly by modifying your app's build.gradle file:

```
android {
  (...)
  splits {
   abi {
    enable true
    reset()
    include 'armeabi-v7a', 'arm64-v8a' // or choose one of them
    universalApk false
   }
} (...)
}
```

For more information about the splits Gradle block, see *Configure multiple APKs for ABIs* in the Android Studio User Guide.

► Coverage Information



Chapter 5Coverage Information

The following list provides coverage information for HERE Android SDK features. Feature support in the HERE SDK may differ depending on the language and locale.

- Satellite Imagery
- Public Transit
- Routing
- Point Address (such as house numbers)
- Online Geocoding / Reverse Geocoding
- Online Places and Search