Modules and Locations a11y.text Modules and Locations Almost all of your interaction with Metasploit will be through its many modules, which it looks for in two locations. The first is the primary module store under /usr/share/metasploit-framework/modules/ and the second, which is where you will store custom modules, is under your home directory at ~/.msf4/modules/. root@kali: ~ # Is /usr/share/metasploit-framework/modules/ auxiliary encoders exploits nops payloads post All Metasploit modules are organized into separate directories, according to their purpose. A basic overview of the various types of Metasploit modules is shown below. Exploits a11y.text Exploits In the Metasploit Framework, exploit modules are defined as modules that use payloads. root@kali: ~ # Is /usr/share/metasploit-framework/modules/exploits/ aix bsdi firefox irix multi solaris

android dialup freebsd linux netware unix

apple_ios example.rb hpux mainframe osx windows Auxiliary a11y.text Auxiliary Auxiliary

modules include port scanners, fuzzers, sniffers, and more. root@kali: ~ # Is

/usr/share/metasploit-framework/modules/auxiliary/ admin client dos gather scanner spoof

vsploit

analyze crawler example.rb parser server sqli

bnat docx fuzzers pdf sniffer voip Payloads, Encoders, Nops a11y.text Payloads, Encoders, Nops Payloads consist of code that runs remotely, while encoders ensure that payloads make it to their destination intact. Nops keep the payload sizes consistent across exploit attempts. root@kali: ~ # ls /usr/share/metasploit-framework/modules/payloads/ singles stagers stages root@kali: ~ # ls /usr/share/metasploit-framework/modules/encoders/ cmd generic mipsbe mipsle php ppc ruby sparc x64 x86 root@kali: ~ # ls /usr/share/metasploit-framework/modules/nops/ aarch64 armle mipsbe php ppc sparc tty x64 x86 Loading Additional Module Trees a11y.text Loading Additional Module Trees Metasploit gives you the option to load modules either at runtime or after msfconsole has already been started. Pass the -m option when running msfconsole to load additional modules at runtime: root@kali: ~ # msfconsole -m ~/secret-modules/ If you need to load

additional modules from with msfconsole, use the loadpath command: msf > loadpath
Usage: loadpath </path/to/modules>

Loads modules from the given directory which should contain subdirectories for module types, e.g. /path/to/modules/exploits

msf > loadpath /usr/share/metasploit-framework/modules/

Loaded 399 modules:

399 payloads Next Metasploit Object Model Prev Filesystem And Libraries