# Chapter 3: Transport Layer – Part 2

Instructor: Zhuozhao Li

Lab: Qing Wang

Department of Computer Science and Engineering

#### Miscellaneous

■ HW2 deadline in a week

#### Quick review

- Multiplexing and demultiplexing
  - UDP, DEMUX using only port number
  - TCP, 四元组, DEMUX using 4-tuple
- UDP
  - Connectionless
  - MUX and DEMUX
  - Checksum
- Design principles of reliable data transfer (RDT) protocol
  - RDT 1.0
  - RDT 2.0
  - RDT 3.0

#### rdt3.0: channels with errors and loss

Approach: sender waits "reasonable" amount of time for ACK

- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
  - retransmission will be duplicate, but seq #s already handles this!
  - receiver must specify seq # of packet being ACKed
- use countdown timer to interrupt after "reasonable" amount of time

timeout

## Performance of rdt3.0 (stop-and-wait)




### Performance of rdt3.0 (stop-and-wait)

- *U* <sub>sender</sub>: *utilization* fraction of time sender busy sending
- example: 1 Gbps link, 15 ms prop. delay, 8000 bit packet
  - time to transmit packet into channel:

$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$

## rdt3.0: stop-and-wait operation



### rdt3.0: stop-and-wait operation

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R}$$

$$= \frac{.008}{30.008}$$


$$= 0.00027$$

- rdt 3.0 protocol performance stinks!
- Protocol limits performance of underlying infrastructure (channel)

## rdt3.0: pipelined protocols operation

pipelining: sender allows multiple, "in-flight", yet-to-be-acknowledged packets

- range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

## rdt3.0: pipelined protocols operation

pipelining: sender allows multiple, "in-flight", yet-to-be-acknowledged packets


- range of sequence numbers must be increased
- buffering at sender and/or receiver



## rdt3.0: pipelined protocols operation




## Pipelining: increased utilization



## Go-Back-N (回退N步):sender

- sender: "window" of up to N, consecutive transmitted but unACKed pkts
  - k-bit seq # in pkt header




- cumulative ACK: ACK(n): ACKs all packets up to, including seq # n
  - on receiving ACK(n): move window forward to begin at n+1
- timer for oldest in-flight packet
- timeout(n): retransmit packet n and all higher seq # packets in window

#### Go-Back-N: receiver

- ACK-only: always send ACK for correctly-received packet so far, with highest in-order seq #
  - may generate duplicate ACKs
  - need only remember rcv base
  - on receipt of out-of-order packet:
    - can discard (don't buffer) or buffer: an implementation decision
    - re-ACK pkt with highest in-order seq #

Receiver view of sequence number space:




received and ACKed

Out-of-order: received but not ACKed

Not received


#### Go-Back-N in action




# Selective repeat (选择重传)

- receiver individually acknowledges all correctly received packets
  - buffers packets, as needed, for eventual in-order delivery to upper layer
- sender times-out/retransmits individually for unACKed packets
  - sender maintains timer for each unACKed pkt
- sender window
  - N consecutive seq #s
  - limits seq #s of sent, unACKed packets

## Selective repeat: sender, receiver windows



## Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

## Selective repeat: sender and receiver

#### sender

#### data from above:

if next available seq # in window, send packet

#### timeout(*n*):

resend packet n, restart timer

#### ACK(n) in [sendbase,sendbase+N]:

- mark packet n as received
- if n is smallest unACKed packet, advance window base to next unACKed seq #

#### receiver

#### packet n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order packets), advance window to next not-yetreceived packet


#### packet n in [rcvbase-N,rcvbase-1]

ACK(n)

#### otherwise:

ignore

## Selective Repeat in action




### Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- Principles of congestion control
- TCP congestion control



### **TCP: overview** RFCs: 793,1122, 2018, 5681, 7323

- point-to-point:
  - one sender, one receiver
- reliable, in-order byte steam:
  - no "message boundaries"
- full duplex (全双工) data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size



### **TCP: overview** RFCs: 793,1122, 2018, 5681, 7323


- point-to-point:
  - one sender, one receiver
- reliable, in-order byte steam:
  - no "message boundaries"
- full duplex (全双工) data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size

- cumulative ACKs
- pipelining:
  - TCP congestion and flow control set window size
- connection-oriented:
  - handshaking (exchange of control messages) initializes sender, receiver state before data exchange
- flow controlled:
  - sender will not overwhelm receiver

### TCP segment structure

32 bits dest port # source port # segment seq #: counting ACK: seq # of next expected bytes of data into bytestream sequence number byte; A bit: this is an ACK (not segments!) acknowledgement number length (of TCP header) receive window len used CE flow control: # bytes Internet checksum receiver willing to accept checksum Urg data pointer options (variable length) C, E: congestion notification TCP options application data sent by RST, SYN, FIN: connection data application into management (variable length) TCP socket

## TCP segment structure



The MSS is typically set by first determining the length of the largest link-layer frame that can be sent by the local sending host (the so called maximum transmission unit, MTU)

Ethernet and PPP link-layer protocols MTU: 1,500 bytes.

A typical value of MSS: 1460 bytes

## TCP sequence numbers, ACKs

#### Sequence numbers:


 byte stream "number" of first byte in segment's data

#### Acknowledgements:


- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-oforder segments

 A: TCP spec doesn't say, - up to implementor



## TCP sequence numbers, ACKs



simple telnet scenario

## TCP round trip time, timeout

- Q: how to set TCP timeout value?
- longer than RTT, but RTT varies!
- too short: premature timeout, unnecessary retransmissions
- too long: slow reaction to segment loss


#### Q: how to estimate RTT?

- SampleRTT: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
  - average several recent measurements, not just current SampleRTT

## TCP round trip time, timeout


EstimatedRTT =  $(1-\alpha)$ \*EstimatedRTT +  $\alpha$ \*SampleRTT

- <u>e</u>xponential <u>w</u>eighted <u>m</u>oving <u>a</u>verage (EWMA)
- influence of past sample decreases exponentially fast
- typical value:  $\alpha$  = 0.125



## TCP round trip time, timeout

- timeout interval: EstimatedRTT plus "safety margin"
  - large variation in EstimatedRTT: want a larger safety margin



DevRTT: EWMA of SampleRTT deviation from EstimatedRTT:

DevRTT = 
$$(1-\beta)$$
\*DevRTT +  $\beta$ \*|SampleRTT-EstimatedRTT|

(typically,  $\beta = 0.25$ )

<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose\_ross/interactive/

### TCP Sender (simplified)

# event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
  - think of timer as for oldest unACKed segment
  - expiration interval:TimeOutInterval


#### event: timeout

- retransmit segment that caused timeout
- restart timer

#### event: ACK received

- if ACK acknowledges previously unACKed segments
  - update what is known to be ACKed
  - start timer if there are still unACKed segments


### TCP Receiver: ACK generation [RFC 5681]




## TCP Receiver: ACK generation [RFC 5681]

Event at receiver	TCP receiver action
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment, send ACK
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send <i>duplicate ACK</i> , indicating seq. # of next expected byte

#### TCP: retransmission scenarios



#### TCP: retransmission scenarios




#### TCP fast retransmit

#### TCP fast retransmit

if sender receives 3 additional ACKs for same data ("triple duplicate ACKs"), resend unACKed segment with smallest seq #

 likely that unACKed segment lost, so don't wait for timeout

Receipt of three duplicate ACKs indicates 3 segments received after a missing segment – lost segment is likely. So retransmit!




### Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- Principles of congestion control
- TCP congestion control



# TCP flow control (流量控制)


**Q**: What happens if network layer delivers data faster than application layer removes data from socket buffers?



receiver protocol stack

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?






Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?


#### -flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast



receiver protocol stack


- TCP receiver "advertises" free buffer space in rwnd field in TCP header
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust
     RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow



TCP receiver-side buffering

- TCP receiver "advertises" free buffer space in rwnd field in TCP header
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust
     RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow

flow control: # bytes receiver willing to accept




TCP segment format

### TCP connection management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)



```
Socket clientSocket =
  newSocket("hostname", "port number");
```

```
application


connection state: ESTAB
connection Variables:
  seq # client-to-server
      server-to-client
  rcvBuffer size
  at server,client


network
```

```
Socket connectionSocket =
  welcomeSocket.accept();
```

### Agreeing to establish a connection

#### 2-way handshake:






Q: will 2-way handshake always work in network?


- variable delays
- retransmitted messages (e.g. req\_conn(x)) due to message loss
- message reordering
- can't "see" other side

# 2-way handshake scenarios






### 2-way handshake scenarios



# 2-way handshake scenarios



accepted!

# TCP 3-way handshake (三次握手)


#### Client state

serverSocket.listen(1) clientSocket = socket(AF INET, SOCK STREAM) LISTEN clientSocket.connect((serverName, serverPort) choose init seq num, x send TCP SYN msq **SYNSFNT** SYNbit=1, Seq=x choose init seq num, y send TCP SYNACK msg, acking SYN SYNbit=1, Seq=y ACKbit=1; ACKnum=x+1 received SYNACK(x) indicates server is live; **ESTAB** send ACK for SYNACK; this segment may contain ACKbit=1, ACKnum=y+1 client-to-server data received ACK(y) indicates client is live **ESTAB** 


#### Server state

serverSocket = socket(AF INET, SOCK STREAM) serverSocket.bind(('', serverPort)) connectionSocket, addr = serverSocket.accept() LISTEN SYN RCVD

# A human 3-way handshake protocol



### TCP: closing a connection



### Closing a TCP connection

- 4-way handshake (四次挥手)
- client, server each close their side of connection
  - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

### Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



### Principles of congestion control

#### Congestion:

• informally: "too many sources sending too much data too fast for network to handle"

- manifestations:
  - long delays (queueing in router buffers)
  - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!




congestion control:
too many senders,

sending too fast


flow control: one sender too fast for one receiver

# Principles of congestion control




#### Simplest scenario:


- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed



Q: What happens as arrival rate  $\lambda_{in}$  approaches R/2?




maximum per-connection throughput: R/2




large delays as arrival rate  $\lambda_{in}$  approaches capacity


- one router, finite buffers
- sender retransmits lost, timed-out packet
  - application-layer input = application-layer output:  $\lambda_{in} = \lambda_{out}$
  - transport-layer input includes retransmissions :  $\lambda'_{in} \ge \lambda_{in}$



#### Idealization: perfect knowledge


sender sends only when router buffers available






#### Idealization: some perfect knowledge


- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost



#### Idealization: some perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost







R/2

#### Realistic scenario: *un-needed duplicates*


- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered





#### Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered




#### "costs" of congestion:


- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
  - decreasing maximum achievable throughput

- four senders
- multi-hop paths
- timeout/retransmit

 $\underline{Q}$ : what happens as  $\lambda_{in}$  and  $\lambda_{in}$  increase?

A: as red  $\lambda_{in}$  increases, all arriving blue pkts at upper queue are dropped, blue throughput  $\rightarrow$  0







#### another "cost" of congestion:


when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!


# Causes/costs of congestion: insights


- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream












### Approaches towards congestion control

#### End-end congestion control:


- no explicit feedback from network
- congestion inferred from observed loss, delay
- approach taken by TCP



## Approaches towards congestion control

# Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



### Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



### TCP congestion control: AIMD

 approach: senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

#### Additive Increase <u>Multiplicative Decrease</u> increase sending rate by 1 cut sending rate in half at maximum segment size every each loss event RTT until loss detected Sending rate **AIMD** sawtooth behavior: probing TCP sender for bandwidth

time

### TCP AIMD: more


#### Multiplicative decrease detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

#### Why AIMD?

- AIMD a distributed, asynchronous algorithm has been shown to:
  - optimize congested flow rates network wide!
  - have desirable stability properties

### TCP congestion control: details



#### TCP sending behavior:


 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

TCP rate 
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

- TCP sender limits transmission: LastByteSent- LastByteAcked < cwnd
- cwnd is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

### TCP slow start

- when connection begins, increase rate exponentially until first loss event:
  - initially cwnd = 1 MSS
  - double cwnd every RTT
  - done by incrementing cwnd for every ACK received
- summary: initial rate is slow, but ramps up exponentially fast




# TCP: from slow start to congestion avoidance

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.


#### Implementation:

- variable ssthresh
- on loss event, ssthresh is set to
   1/2 of cwnd just before loss event




<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose\_ross/interactive/

### Summary: TCP congestion control




### TCP CUBIC

- Is there a better way than AIMD to "probe" for usable bandwidth?
- Insight/intuition:
  - W<sub>max</sub>: sending rate at which congestion loss was detected
  - congestion state of bottleneck link probably (?) hasn't changed much
  - after cutting rate/window in half on loss, initially ramp to to  $W_{max}$  faster, but then approach  $W_{max}$  more slowly




### TCP CUBIC

- K: point in time when TCP window size will reach W<sub>max</sub>
  - K itself is tuneable
- increase W as a function of the cube of the distance between current time and K
  - larger increases when further away from K
  - smaller increases (cautious) when nearer K
- TCP CUBIC default in Linux, most popular TCP for popular Web servers




## TCP and the congested "bottleneck link"

 TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link




## TCP and the congested "bottleneck link"

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link
- understanding congestion: useful to focus on congested bottleneck link



### Delay-based TCP congestion control

Keeping sender-to-receiver pipe "just full enough, but no fuller": keep bottleneck link busy transmitting, but avoid high delays/buffering



#### Delay-based approach:

- RTT<sub>min</sub> minimum observed RTT (uncongested path)
- uncongested throughput with congestion window cwnd is cwnd/RTT<sub>min</sub>

```
if measured throughput "very close" to uncongested throughput increase cwnd linearly /* since path not congested */ else if measured throughput "far below" uncongested throughout decrease cwnd linearly /* since path is congested */
```


### Delay-based TCP congestion control

- congestion control without inducing/forcing loss
- maximizing throughout ("keeping the just pipe full...") while keeping delay low ("...but not fuller")
- a number of deployed TCPs take a delay-based approach
  - BBR deployed on Google's (internal) backbone network

### Explicit congestion notification (ECN)


TCP deployments often implement *network-assisted* congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
  - policy to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)



### TCP fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



### Q: is TCP Fair?

#### Example: two competing TCP sessions:

- additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



#### Is TCP fair?

A: Yes, under idealized assumptions:

- same RTT
- fixed number of sessions only in congestion avoidance

### Fairness: must all network apps be "fair"?

#### Fairness and UDP

- multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- instead use UDP:
  - send audio/video at constant rate, tolerate packet loss
- there is no "Internet police" policing use of congestion control

# Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this, e.g., link of rate R with 9 existing connections:
  - new app asks for 1 TCP, gets rate R/10
  - new app asks for 11 TCPs, gets R/2