NASM: data and bss (inverted)

ICS312
Machine-Level and
Systems Programming

Henri Casanova (henric@hawaii.edu)



NASM Program Structure

data segment

bss segment

text segment

initialized data

uninitialized data

statically allocated data that is allocated for the duration of program execution



code

100

The data and bss segments

- Both segments contains data directives that declare preallocated zones of memory
- There are two kinds of data directives

DX directives: initialized data (D = "defined")

□ **RESX directives**: uninitialized data (RES = "reserved")

■ The "X" above refers to the data size:

Unit	Letter(X)	Size in bytes
byte	В	1
word	W	2
double word	D	4
quad word	Q	8
ten bytes	Т	10



The DX data directives

- One declares a zone of initialized memory using three elements:
 - Label: the name used in the program to refer to that zone of memory
 - A pointer to the zone of memory, i.e., an address
 - DX, where X is the appropriate letter for the size of the data being declared
 - Initial value, with encoding information
 - default: decimal
 - b: binary
 - h: hexadecimal
 - o: octal
 - quoted: ASCII

100

DX Examples

- L1 db 0
 - □ 1 byte, named L1, initialized to 0
- **L**2 dw 1000
 - 2-byte word, named L2, initialized to 1000
- L3 db 110101b
 - □ 1 byte, named L3, initialized to 110101 in binary
- L4 db **0**A2h
 - 1 byte, named L4, initialized to A2 in hex (note the '0')
- **L**5 db 170
 - □ 1 byte, named L5, initialized to 17 in octal (1*8+7=15 in decimal)
- L6 dd **0**FFFF1A92h (note the '**0**')
 - 4-byte double word, named L6, initialized to FFF1A92 in hex
- L7 db "A"
 - □ 1 byte, named L7, initialized to the ASCII code for "A" (65d)



ASCII Code

- Associates 1-byte numerical codes to characters
 - Unicode, proposed much later, uses 2 bytes and thus can encode 2⁸ times more characters (room for all languages, Chinese, Japanese, accents, etc.)
- A few values to know:
 - 'A' is 65d, 'B' is 66d, etc.
 - □ 'a' is 97d, 'b' is 98d, etc.
 - □ ''is 32d

70

DX for multiple elements

- L8 db 0, 1, 2, 3
 - □ Defines 4 bytes, initialized to 0, 1, 2 and 3
 - L8 is a pointer to the first byte
- L9 db "w", "o", 'r', 'd', **0**
 - □ Defines a **null-terminated** string, initialized to "word\0"
 - L9 is a pointer to the beginning of the string
- L10 db "word", 0
 - Equivalent to the above, more convenient to write



DX with the times qualifier


- Say you want to declare 100 bytes all initialized to 0
- NASM provides a nice shortcut to do this, the "times" qualifier
- L11 times 100 db 0
 - Equivalent to L11 db 0,0,0,....,0 (100 times)

7

Data segment example

```
tmp dd -1
pixels db 0FFh, 0FEh, 0FDh, 0FCh
i dw 0
message db "H", "e", "llo", 0
buffer times 8 db 0
max dd 254
```








Data segment example

```
-1
          dd
tmp
pixels
               OFFh, OFEh, OFDh, OFCh
          db
i
          dw
               0
               "H", "e", "llo", 0
          db
message
buffer times 8 db 0
               254
          dd
max
```


28 bytes




×

Endianness?

max dd 254





- In the previous slide we showed the above 4-byte memory content for a double-word that contains 254 = 000000FEh
- While this seems to make sense, it turns out that Intel processors do not do this!
 - Yes, the last 4 bytes shown in the previous slide are wrong
- The scheme shown above (i.e., bytes in memory follow the "natural" order): Big Endian
- Instead, Intel processors use Little Endian:





mov eax, 0AABBCCDDh mov [M1], eax mov ebx, [M1]








mov eax, 0AABBCCDDh mov [M1], eax mov ebx, [M1]

Registers

eax AA BB CC DD

ebx





mov eax, 0AABBCCDDh mov [M1], eax mov ebx, [M1]

Registers

eax AA BB CC DD

ebx

Memory

[M1] DD CC BB AA



mov eax, 0AABBCCDDh mov [M1], eax mov ebx, [M1]

Registers

eax AA BB CC DD

ebx AA BB CC DD

Memory

[M1] DD CC BB AA

mov eax, 0AABBCCDDh mov [M1], eax mov ebx, [M1]

Registers

eax AA BB CC DD

ebx AA BB CC DD

Memory

[M1] DD CC BB AA

In-register byte order and in-memory byte order, within a single multi-byte value, are different!



Little/Big Endian

- Motorola and IBM processors use(d) Big Endian
- Intel/AMD uses Little Endian (used in this class)
- When writing code in a high-level language one rarely cares
 - Although in C one can definitely expose the Endianness of the computer
 - And thus one can write C code that's not portable between an IBM and an Intel!!!
- This only matters when writing multi-byte quantities to memory and reading them differently (e.g., byte per byte)
- When writing assembly code one often does not care, but we'll see several examples when it matters, so it's important to know this inside out
- Some processors are configurable (either in hardware or in software) to use either type of endianness (e.g., MIPS processor)



```
      pixels
      times
      4
      db
      0FDh

      x
      dd
      00010111001101100001010111010011b

      blurb
      db
      "ad", "b", "h", 0

      buffer
      times
      10
      db
      14o

      min
      dw
      -19
```

- What is the layout and the content of the data memory segment on a Little Endian machine?
 - Byte per byte, in hex




```
        pixels
        times
        4
        db
        0FDh

        x
        dd
        00010111001101100001010111010011b

        blurb
        db
        "ad", "b", "h", 0

        buffer
        times
        10
        db
        14o

        min
        dw
        -19
```





Uninitialized Data

- The RESX directive is very similar to the DX directive, but always specifies the number of memory elements
- L20 resw 100
 - □ 100 uninitialized 2-byte words
 - L20 is a pointer to the first word
- L21 resb 1
 - 1 uninitialized byte named L21



Our first instructions

- At this point we need to introduce a few assembly instructions
 - adding integers
 - subtracting integers
 - moving data between registers / memory locations / constants

7

Simple arithmetic and operands

- Assembly instructions can have operands, and it's important to know what kind of operands are possible
- Register: specifies one of the registers
 - □ add eax, ebx
 - □ means eax = eax + ebx
- Memory: specifies an address in memory.
 - add eax, [ebx]
 - means eax = eax + content of memory at address ebx
- Immediate: specifies a fixed value (i.e., a number)
 - □ add eax, 2
 - □ means eax = eax + 2
- Implied: not actually encoded in the instruction
 - inc eax
 - □ means eax = eax + 1



Additions, subtractions

Additions

- \square add eax, 4 ; eax = eax + 4
- \square add al, ah ; al = al + ah

Subtractions

- □ sub bx, 10 ; bx = bx 10
- □ sub ebx, edi ; ebx = ebx edi

Increment, Decrement

- □ inc ecx ; ecx++ (a 4-byte operation)
- □ dec dl ; dl-- (a 1-byte operation)

-

The move instruction

- This instruction moves data from one location to another mov dest, src
- Destination goes first, and the source goes second
- At most one of the operands can be a memory operand
 - □ mov eax, [ebx] ; OK
 - mov [eax], ebx ; OK
 - mov [eax], [ebx] ; NOT OK
- Both operands must be exactly the same size
 - For instance, AX cannot be stored into BL
- Examples:
 - mov ax, ebx ; NOT OK
 - □ mov bx, ax ; OK
- This type of "exceptions to the common case" make programming languages difficult to learn and assembly may be the worst offender
 - □ By contrast, Lisp is known for being very consistent (ICS313)



Use of Labels

- It is important to constantly be aware that when using a label in a program, the label is a pointer, not a value
- Therefore, a common use of the label in the code is as a memory operand, in between square brackets '[' ']'
- mov AL, [L1]
 - Move the data at address L1 into register AL
- Question: how does the assembler know how many bits to move?
- Answer: it's up to the programmer to do the right thing, that is load into appropriately sized registers
- Labels do not have a type!
- So although it's tempting to think of them as variables, they are much more limited: just pointers to a byte somewhere in memory



Moving to/from a register

- Say we have the following data segment
 - L db 0F0h, 0F1h, 0F2h, 0F3h
- Example: mov AL, [L]
 - □ AL: Lowest bits of AX, i.e., 1 byte
 - Therefore, value F0 is moved into AL
- Example: mov [L], AX
 - Moves 2 bytes into L, overwriting the first two bytes
- Example: mov [L], EAX
 - Moves 4 bytes into L, overwriting all four bytes
- Example: mov AX, [L]
 - AX: 2 bytes
 - □ Therefore value F1F0 is moved into AX
 - Note that this is reversed because of Little Endian!!



More About Little Endian

Consider the following data segment

L1 db 0AAh, 0BBh, 0CCh, 0DDh

L2 dd 0AABBCCDDh

- The instruction: mov eax, [L1] puts DDCCBBAA into eax
 - □ Note that we're loading 4x1 bytes as a 4-byte quantity
- The instruction: mov eax, [L2] puts AABBCCDD into eax!!!
 - Meaning that the memory content was DDCCBBAA
- When declaring a value in the data segment, that value is declared as it would be appearing in registers when loaded "whole"
 - It would be confusing to write numbers in little endian in the program
 - So all numerical values you write are in register-order not memory-order



Data segment:

```
L1 db 0AAh, 0BBh
L2 dw 0CCDDh
L3 db 0EEh, 0FFh
```

Program:

```
mov eax, [L2]
mov ax, [L3]
mov [L1], eax
```

What's the memory content?



Solution

Data segment:

L1 db 0AAh, 0BBh

L2 dw 0CCDDh

L3 db 0EEh, 0FFh

L1 L2 L3

AA BB DD CC EE FF



Solution

```
L1 L2 L3

AA BB DD CC EE FF
```

```
mov eax, [L2]; eax = FF EE CC DD
```

```
mov ax, [L3]; eax = FF EE FF EE
```

mov [L1], eax ; L1 points to EE FF EE FF

L1 L2 L3

EE FF EE FF Final memory content

100

Moving immediate values

- Consider the instruction: mov [L], 1
- The assembler will give us an error: "operation size not specified"!
- This is because the assembler has no idea whether we mean for "1" to be 01h, 0001h, 00000001h, etc.
 - Labels have no type (they're NOT variables)
- Therefore the assembler must provide us with a way to specify the size of immediate operands
- mov dword [L], 1
 - 4-byte double-word
- 5 size specifiers: byte, word, dword, qword, tword



Size Specifier Examples

mov [L1], 1 ; Error

mov byte [L1], 1 ; 1 byte

mov word [L1], 1 ; 2 bytes

mov dword [L1], 1 ; 4 bytes

mov [L1], eax ; 4 bytes

mov [L1], ax ; 2 bytes

■ mov [L1], al ; 1 byte

mov eax, [L1] ; 4 bytes

■ mov ax, [L1] ; 2 bytes

■ mov ax, 12 ; 2 bytes

-

Brackets or no Brackets

- mov eax, [L]
 - Puts the content at address L into eax
 - Puts 32 bits of content, because eax is a 32-bit register
- mov eax, L
 - Puts the address L into eax
 - □ Puts the 32-bit address L into eax
- mov ebx, [eax]
 - Puts the content at address eax (= L) into ebx
- inc eax
 - Increase eax by one
- mov ebx, [eax]
 - □ Puts the content at address eax (= L + 1) into ebx



```
first db 00h, 04Fh, 012h, 0A4h second dw 165 third db "adf"
```


```
mov eax, first
inc eax
mov ebx, [eax]
mov [second], ebx
mov byte [third], 11o
```

What is the content of "data" memory after the code executes on a Little Endian Machine?



```
first db 00h, 04Fh, 012h, 0A4h second dw 165 third db "adf"
```

```
mov eax, first
inc eax
mov ebx, [eax]
mov [second], ebx
mov byte [third], 11o
```






```
first db 00h, 04Fh, 012h, 0A4h second dw 165 third db "adf"
```

```
mov eax, first
inc eax
mov ebx, [eax]
mov [second], ebx
mov byte [third], 11o
```


Put an **address** into eax (addresses are 32-bit)





```
first db 00h, 04Fh, 012h, 0A4h second dw 165 third db "adf"
```

```
mov eax, first
inc eax
mov ebx, [eax]
mov [second], ebx
mov byte [third], 11o
```





```
first db 00h, 04Fh, 012h, 0A4h second dw 165 third db "adf"
```


```
mov eax, first
inc eax
mov ebx, [eax]
mov [second], ebx
mov byte [third], 11o
```

```
00 4F 12 A4 A5 00 61 64 66

first second third
(4) (2) (3)
```


```
first db 00h, 04Fh, 012h, 0A4h second dw 165 third db "adf"
```


```
mov eax, first
inc eax
mov ebx, [eax]
mov [second], ebx
mov byte [third], 11o
```



```
first db 00h, 04Fh, 012h, 0A4h second dw 165 third db "adf"
```

```
mov eax, first
inc eax
mov ebx, [eax]
mov [second], ebx
mov byte [third], 11o
```








Assembly is Dangerous

- The previous example is really a terrible program
- But it's a good demonstration of why the assembly programmer must be really careful
- For instance, we were able to store 4 bytes into a 2-byte label, thus overwriting the first 2 characters of a string that merely happened to be stored in memory next to that 2-byte label
- Playing such tricks can lead to very clever programs that do things that would be impossible (or very cumbersome) to do with many high-level programming language (e.g., in Java)
- But you really must know what you're doing
- Typically such behaviors are bugs

20

x86 Assembly is Dangerous

- Another dangerous thing we did in our assembly program was the use of unaligned memory accesses
 - We stored a 4-byte quantity at some address
 - We incremented the address by 1
 - We read a 4-byte quantity from the incremented address!
 - This really removes all notion of a structured memory
- Some architectures only allow aligned accesses
 - Accessing an X-byte quantity can only be done for an address that's a multiple of X!





Conclusion

It's important to understand the memory layout