

Installing Ubuntu 26.04.1 LTS

Dual-Boot Installation with Windows 11 / 10

Lab 01
Module: SE1

Ferhat Abbas University Sétif 1

2026



Outline

- 1 Introduction
- 2 Prerequisites
- 3 Install Ubuntu 26.04.1 LTS in Dual Boot
 - Step 1: Create the Ubuntu installation USB
 - Step 2: Prepare free disk space
 - Step 3: Start the Ubuntu installer
 - Step 4: Configure the dual-boot disk layout
 - Step 5: Complete the installation
 - Step 6: Select the operating system at startup
 - Step 7: First start and verification

Introduction

Objective

- This practical session explains how to install **Ubuntu 26.04.1 LTS (Resolute Raccoon)** on a computer that already runs Windows.
- The result is a **dual-boot Windows/Ubuntu** configuration in which both operating systems coexist on the same computer.
- At startup, you can select the operating system you want to use.
- Back up all important files before changing disk partitions or installing another operating system.

Check UEFI and Secure Boot

Recommended configuration


- Use **UEFI mode** rather than Legacy/CSM mode whenever possible.
- Ubuntu supports **UEFI Secure Boot**; therefore, Secure Boot normally **does not need to be disabled**.
- Only change Secure Boot settings if your specific hardware, firmware, or driver configuration requires it.
- If you use BitLocker or device encryption in Windows, save the recovery key before modifying boot or firmware settings.

Disable Windows Fast Startup

Press **WIN+R** to open the Run dialog.

Run the following command:

```
%windir%\system32\control.exe /name  
Microsoft.PowerOptions /page pageGlobalSettings
```



Options d'alimentation

← → ↕ ↑ > Panneau de configuration > Matériel et audio > Options d'alimentation

Page d'accueil du panneau de configuration

Choisir l'action des boutons d'alimentation

Choisir l'action qui suit la fermeture du capot

Créer un mode de gestion de l'alimentation

Choisir quand éteindre l'écran

Modifier les conditions de mise en veille de l'ordinateur

Choisir ou personnaliser un mode de gestion de l'alimentation

Un mode de gestion de l'alimentation est un ensemble de paramètres matériels et système (comme la luminosité de l'écran, le mode veille, etc.) qui définit comment votre ordinateur utilise l'alimentation en énergie. [Informations sur les modes de gestion de l'alimentation](#)

Mode de gestion de l'alimentation sélectionné


Utilisation normale (recommandé) [Modifier les paramètres du mode](#)

Équilibre automatiquement les performances et la consommation d'énergie sur les matériels compatibles.

Disable Windows Fast Startup


Open:

Control Panel > Hardware and Sound > Power Options > Choose what the power buttons do




Disable Windows Fast Startup

Click **Change settings that are currently unavailable.**



Disable Windows Fast Startup

Clear the checkbox **Turn on fast startup**, then save the changes.



Check BitLocker / Device Encryption

Before resizing or installing


- Check whether the Windows system drive is protected by **BitLocker** or **Device Encryption**.
- Keep the recovery key in a safe place.
- Ubuntu 26.04 includes improved dual-boot handling, but if the installer reports that Windows cannot be safely accessed or resized, return to Windows and disable BitLocker before continuing.
- Do not erase or reformat the Windows EFI, recovery, or system partitions.

We're making space for Ubuntu without deleting Windows or its important system partitions

Create a Bootable Ubuntu USB


- 1 Download the latest **Ubuntu 26.04.1 LTS Desktop** ISO from the official Ubuntu website:
<https://ubuntu.com/download/desktop>
- 2 Use an **8 GB or larger** USB flash drive.
- 3 Create the bootable USB with Rufus, balenaEtcher, or another trusted image-writing tool.
- 4 If Rufus asks for a partition scheme on a modern Windows PC, use **GPT / UEFI** unless your hardware requires otherwise.

IWT: A program that copies an ISO image to a USB drive in a special way so the computer can boot from the USB.



Open Windows Disk Management


Press **WIN+R**, type `diskmgmt.msc`, and press **Enter**.



`.msc` is a Windows file extension used for Microsoft Management Console tools.

Shrink the Windows Partition

- 1 Identify the main Windows partition, usually the **C:** partition.
- 2 Right-click it and select **Shrink Volume**.
- 3 Do not modify EFI System, Microsoft Reserved, or Windows Recovery partitions.




Choose the Space for Ubuntu

Enter the amount of space to shrink, then click **Shrink**.


Suggested capacity

Ubuntu Desktop requires about **25 GB of free storage** for a comfortable installation. For coursework and software development, allocating **40–60 GB or more** is preferable when disk capacity allows.




Verify the Unallocated Space

After shrinking the Windows partition, leave the new area as **Unallocated space**. Do not create or format a Windows volume in that space.



Boot from the USB Drive

- 1 Insert the Ubuntu 26.04.1 LTS installation USB.
- 2 Restart the computer.
- 3 Open the firmware boot menu (commonly **F12**, **F10**, **F2**, or **Esc**).
- 4 Select the **UEFI USB** entry.



Installer: Language and Accessibility


- Select the installation language.
- Configure any required accessibility options.
- Select the correct keyboard layout.
- Connect to the network if you want the installer to download updates and drivers.

Note

The Ubuntu 26.04 installer interface differs from older Ubuntu 22.04 screenshots, but the installation workflow remains similar.

Try or Install Ubuntu


- Choose **Try Ubuntu** if you want to test hardware compatibility before making disk changes.
- Choose **Install Ubuntu** when you are ready to continue.
- If the installer reports **Intel RST** as unsupported, stop the installation and reconfigure Windows/firmware for AHCI according to Ubuntu's official instructions.



RST and AHCI are two different ways for the operating system to communicate with the storage controller.


Installation Options

- Select the standard/default installation appropriate for your course work.
- Allow updates to be downloaded during installation when a stable Internet connection is available.
- Enable third-party software if you need proprietary graphics, Wi-Fi, or media support and accept the associated license terms.



Install Ubuntu Alongside Windows

- When available, select **Install Ubuntu alongside Windows Boot Manager**.
- Confirm that the correct physical drive is selected.
- Allocate the previously prepared free space to Ubuntu.
- Carefully review the summary before writing changes to disk.



Manual Partitioning (Advanced)

Use **Manual partitioning** only if the guided dual-boot option is unavailable or if a custom layout is required.

- Reuse the existing EFI System Partition; do not format it unless you fully understand the consequences.
- Create the Ubuntu partitions only inside the unallocated space.
- A single Linux root partition (/) is sufficient for a basic installation; advanced layouts may use separate partitions or encrypted LVM.

Location and User Account

- Select your time zone or location.
- Enter your full name, computer name, username, and password.
- Use a strong password and keep it secure.

The screenshot shows the 'Installation' window titled 'Qui êtes-vous ?'. It contains the following fields and options:

- Votre nom :** A text box containing 'Samir' with a green checkmark icon to its right.
- Le nom de votre ordinateur :** A text box containing 'samir-pc' with a green checkmark icon to its right. Below this box is the text: 'Le nom qu'il utilise pour communiquer avec d'autres ordinateurs.'
- Choisir un nom d'utilisateur :** A text box containing 'samir' with a green checkmark icon to its right.
- Choisir un mot de passe :** A password field with 10 black dots, a strength indicator icon (a circle with a checkmark), and the text 'Mot de passe sûr' in green.
- Confirmez votre mot de passe :** A password field with 10 black dots and a green checkmark icon to its right.
- Options:**
 - ☐ Ouvrir la session automatiquement
 - ☒ Demander mon mot de passe pour ouvrir une session
 - ☐ Utiliser Active Directory

Below the options is the text: 'Vous saisissez le domaine et d'autres détails à l'étape suivante.'

At the bottom right are two buttons: 'Précédent' and 'Continuer'.


At the very bottom of the window, there is a progress bar consisting of seven dots, with the fifth dot from the left being filled orange, indicating the current step.

Install Ubuntu

The installer now copies the system files and configures Ubuntu 26.04.1 LTS.


Important

Do not power off the computer or remove the USB drive while the installation is in progress.




Restart the Computer

When the installation completes, click **Restart Now**.



Remove the Installation Media


When prompted, remove the USB flash drive and press **Enter**.



GRUB Boot Menu


Normally, Ubuntu configures a UEFI boot entry and the **GRUB** boot manager automatically.

- Select **Ubuntu** to start Ubuntu.
- Select **Windows Boot Manager** to start Windows.
- If GRUB does not appear, check the UEFI boot order and place the Ubuntu boot entry before Windows Boot Manager.



First Ubuntu Startup

- Start Ubuntu from the boot menu.
- Sign in with the account created during installation.
- Complete the initial welcome screens and privacy preferences.
- Install available system updates after the first login.




Verify the Dual-Boot Configuration

- Restart and confirm that both **Ubuntu** and **Windows Boot Manager** are available.
- Boot once into Windows and verify that Windows starts normally.
- Boot again into Ubuntu and verify networking, audio, graphics, storage, and other required hardware.
- If BitLocker was disabled, review your Windows encryption settings only after confirming that the dual-boot setup works correctly.

Ubuntu 26.04.1 LTS Installed

Result

Your computer is now configured with a Windows / Ubuntu dual-boot environment using the latest Ubuntu 26.04 LTS series.



Thank you!