

Chapter 6: Synchronization Tools






Outline

- Background
- The Critical-Section Problem
- Peterson's Solution
- Hardware Support for Synchronization
- Mutex Locks
- Semaphores
- Monitors
- Liveness






Objectives


- Describe the critical-section problem and illustrate a race condition
- Illustrate hardware solutions to the criticalsection problem using memory barriers, compare-and-swap operations, and atomic variables
- Demonstrate how mutex locks, semaphores, monitors, and condition variables can be used to solve the critical section problem






Background

- Processes can execute concurrently
 - May be interrupted at any time, partially completing execution
- Concurrent access to shared data may result in data inconsistency
- Maintaining data consistency requires mechanisms to ensure the orderly execution of cooperating processes
- We illustrated the problem in Chapter 4 when we considered the Bounded Buffer problem with use of a counter that is updated concurrently by the producer and consumer, which leads to race condition




Race Condition

- Processes P₀ and P₁ are creating child processes using the fork() system call
- Race condition on kernel variable next_available_pid which represents the next available process identifier (pid)




• Unless there is a mechanism to prevent P₀ and P₁ from accessing the variable next_available_pid the same pid could be assigned to two different processes!



Critical Section Problem

- Consider system of n processes $\{p_0, p_1, \dots p_{n-1}\}$
- Each process has critical section segment of code
 - Process may be changing common variables, updating table, writing file, etc.
 - When one process in critical section, no other may be in its critical section
- Critical section problem is to design protocol to solve this
 - Each process must ask permission to enter critical section in entry section, may follow critical section with exit section, then remainder section



Critical Section

• General structure of process P_i

```
do {
     entry section
          critical section
     exit section
          remainder section
} while (true);
```






Critical-Section Problem (Cont.)

Requirements for solution to critical-section problem


- 1. Mutual Exclusion If process P_i is executing in its critical section, then no other processes can be executing in their critical sections
- 2. Progress If no process is executing in its critical section and there exist some processes that wish to enter their critical section, then the selection of the process that will enter the critical section next cannot be postponed indefinitely
- 3. Bounded Waiting A bound must exist on the number of times that other processes are allowed to enter their critical sections after a process has made a request to enter its critical section and before that request is granted
 - Assume that each process executes at a nonzero speed
 - No assumption concerning relative speed of the n processes



Interrupt-based Solution

- Entry section: disable interrupts
- Exit section: enable interrupts
- Will this solve the problem?
 - What if the critical section is code that runs for an hour?
 - Can some processes starve never enter their critical section
 - What if there are two CPUs?





Software Solution 1

- Two-process solution
- Assume that the load and store machine-language instructions are atomic; that is, cannot be interrupted
- The two processes share one variable:
 - int turn;
- The variable turn indicates whose turn it is to enter the critical section






Algorithm for Process P_i


```
while (true) {
     turn = i;
     while (turn == j)
     /* critical section */
     turn = j;
     /* remainder section */
```





Algorithm for Process P_i and P_j

```
while (true)
                        while (true)
  turn = i;
                          turn = j;
 while (turn == j)
                          while (turn == i)
                          /* critical section
  /* critical section
  * /
                          turn = i;
  turn = j;
                          /* remainder
  /* remainder
  section */
                          section */
```



Correctness of the Software Solution

Mutual exclusion is preserved

P_i enters critical section only if:

turn = i

and turn cannot be both 0 and 1 at the same time


- What about the Progress requirement?
 - E.g. consider the case when Pj is faster than Pi
 - While Pi is waiting in the loop, Pj could be leaving (by setting turn=i) and then entering again (by setting turn=j) before Pi could proceed
- What about the Bounded-waiting requirement?





Peterson's Solution


- Two-process solution
- Assume that the load and store machinelanguage instructions are atomic; that is, cannot be interrupted
- The two processes share two variables:
 - int turn;
 - boolean flag[2]
- The variable turn indicates whose turn it is to enter the critical section
- The flag array is used to indicate if a process is ready to enter the critical section
 - flag[i] = true implies that process P_i is ready!



Algorithm for Process P_i


```
while (true) {
      flag[i] = true;
      turn = j;
      while (flag[j] && turn == j)
      /* critical section */
      flag[i] = false;
      /* remainder section */
```





Algorithm for Process P_i and P_j


```
while (true)
                           while (true)
                              flag[j] = true;
  flag[i] = true;
  turn = j;
                              turn = i;
                              while (flag[i] && turn
  while (flag[j] && turn
                                  == i)
      == j)
   /* critical section */
                            /* critical section */
  flag[i] = false;
                              flag[j] = false;
  /* remainder section */ /* remainder section */
```



Correctness of Peterson's Solution

- Provable that the three CS requirements are met:
 - 1. Mutual exclusion is preserved
 - **P**_i enters CS only if:
 - either flag[j]=false or turn=i
 - 2. Progress requirement is satisfied
 - 3. Bounded-waiting requirement is met





Peterson's Solution and Modern Architecture

- Although useful for demonstrating an algorithm,
 Peterson's Solution is not guaranteed to work on modern architectures
 - To improve performance, processors and/or compilers may reorder operations that have no dependencies
- Understanding why it will not work is useful for better understanding race conditions
 - For single-threaded this is ok as the result will always be the same
 - For multithreaded the reordering may produce inconsistent or unexpected results!



Modern Architecture Example

Two threads share the data:

```
boolean flag = false; int x = 0;
```

Thread 1 performs

```
while (!flag)
;
print x
```


Thread 2 performs

$$x = 100;$$
 flag = true

What is the expected output?

100





Modern Architecture Example (Cont.)


However, since the variables flag and x are independent of each other, the instructions:

```
flag = true; x = 100;
```

for Thread 2 may be reordered


If this occurs, the output may be 0!





Peterson's Solution Revisited


 The effects of instruction reordering in Peterson's Solution



- This allows both processes to be in their critical section at the same time!
- To ensure that Peterson's solution will work correctly on modern computer architecture we must use
 Memory Barrier

Effect of Instruction Reordering on Peterson's Solution

```
while (true)
                            while (true)
  turn = 1;
                              turn = 0;
  flag[0] = true;
                              flag[1] = true;
  while (flag[1] && turn
                              while (flag[0] && turn
                                  == 0)
      == 1)
   /* critical section */
                            /* critical section */
                              flag[1] = false;
  flag[0] = false;
  /* remainder section */ /* remainder section */
```



Memory Barrier


- Memory model are the memory guarantees a computer architecture makes to application programs
- Memory models may be either:
 - Strongly ordered where a memory modification of one processor is immediately visible to all other processors
 - Weakly ordered where a memory modification of one processor may not be immediately visible to all other processors
- A memory barrier is an instruction that forces any change in memory to be propagated (made visible) to all other processors



Memory Barrier Instructions

- When a memory barrier instruction is performed, the system ensures that all loads and stores are completed before any subsequent load or store operations are performed
- Therefore, even if instructions were reordered, the memory barrier ensures that the store operations are completed in memory and visible to other processors before future load or store operations are performed





Memory Barrier Example

- Returning to the example of slides 6.17 6.18
- We could add a memory barrier to the following instructions to ensure Thread 1 outputs 100:
- Thread 1 now performs


```
while (!flag)
  memory_barrier();
print x
```

Thread 2 now performs

```
x = 100;
memory_barrier();
flag = true
```

- For Thread 1, we are guaranteed that the value of flag is loaded before the value of x
- For Thread 2, we ensure that the assignment to x occurs before the assignment flag






Synchronization Hardware

- Many systems provide hardware support for implementing the critical section code
- Uniprocessors could disable interrupts
 - Currently running code would execute without preemption
 - Generally too inefficient on multiprocessor systems
 - Operating systems using this not broadly scalable
- We will look at two forms of hardware support:
 - 1. Hardware instructions
 - 2. Atomic variables






Hardware Instructions

- Special hardware instructions that allow us to either test-and-modify the content of a word, or to swap the contents of two words atomically (uninterruptedly)
 - Test-and-Set instruction
 - Compare-and-Swap instruction






The test_and_set Instruction

Definition

```
boolean test_and_set (boolean *target)
{
    boolean rv = *target;
    *target = true;
    return rv:
}
```

- Properties
 - Executed atomically
 - Returns the original value of passed parameter
 - Set the new value of passed parameter to true





Solution Using test_and_set()

- Shared boolean variable lock, initialized to false
- Solution:

```
do {
    while (test_and_set(&lock))
        ; /* do nothing */

    /* critical section */

    lock = false;
    /* remainder section */
} while (true);
```

Does it solve the critical-section problem?





The compare_and_swap Instruction

Definition

```
int compare_and_swap(int *value, int expected, int
new_value)
{
   int temp = *value;
   if (*value == expected) *value = new_value;
   return temp;
}
```

- Properties
 - Executed atomically
 - Returns the original value of passed parameter value
 - Set the variable value the value of the passed parameter
 new_value but only if *value == expected is true
 - That is, the swap takes place only under this condition



Solution using compare_and_swap

- Shared integer lock initialized to 0;
- Solution:

```
while (true)
{
    while (compare_and_swap(&lock, 0, 1) != 0)
        ; /* do nothing */


    /* critical section */

    lock = 0;

    /* remainder section */
}
```

Does it solve the critical-section problem?






Bounded-waiting with compare-and-swap

```
while (true) {
   waiting[i] = true;
   key = 1;
   while (waiting[i] && key == 1)
      key = compare and swap(&lock,0,1);
   waiting[i] = false;
   /* critical section */
   j = (i + 1) % n;
   while ((j != i) && !waiting[j])
      j = (j + 1) % n;
   if (j == i)
      lock = 0;
   else
      waiting[j] = false;
   /* remainder section */
```






Atomic Variables

- Typically, instructions such as compare-and-swap are used as building blocks for other synchronization tools
- One tool is an atomic variable that provides atomic (uninterruptible) updates on basic data types such as integers and booleans
- For example:
 - Let sequence be an atomic variable
 - Let increment() be operation on the atomic variable sequence
 - The Command:

increment(&sequence);

ensures **sequence** is incremented without interruption




Atomic Variables

The increment() function can be implemented as follows:

```
void increment(atomic int *v)
   int temp;
   do {
        temp = *v;
   while (temp !=
(compare and swap(v,temp,temp+1))
```






Mutex Locks

- Previous solutions are complicated and generally inaccessible to application programmers
- OS designers build software tools to solve critical section problem
- Simplest is mutex lock
 - Boolean variable indicating if lock is available or not
- Protect a critical section by
 - First acquire() a lock
 - Then release() the lock
- Calls to acquire() and release() must be atomic
 - Usually implemented via hardware atomic instructions such as compare-and-swap
- But this solution requires busy waiting
 - This lock therefore called a spinlock





Solution to CS Problem Using Mutex Locks

```
while (true) {
    acquire lock
        critical section

    release lock
    remainder section
}
```





Semaphore

- Synchronization tool that provides more sophisticated ways (than Mutex locks) for processes to synchronize their activities
 - Semaphore S integer variable
- Can only be accessed via two indivisible (atomic) operations
 - wait() and signal()
 - Originally called P() and V()
- Definition of the wait() operation

```
wait(S) {
    while (S <= 0)
        ; // busy wait
    S--;
}</pre>
```

Definition of the signal() operation

```
signal(S) {
    S++;
}
```






Semaphore (Cont.)

- Counting semaphore integer value can range over an unrestricted domain
- Binary semaphore integer value can range only between 0 and 1
 - Same as a mutex lock
- Can implement a counting semaphore S as a binary semaphore
- With semaphores we can solve various synchronization problems





Semaphore Usage Example

- Solution to the CS Problem
 - Create a semaphore "mutex" initialized to 1
 wait (mutex);


CS

```
signal(mutex);
```

- Consider P_1 and P_2 that with two statements S_1 and S_2 and the requirement that S_1 to happen before S_2
 - Create a semaphore "synch" initialized to 0

```
P1:
S<sub>1</sub>;
signal(synch);
P2:
wait(synch);
S<sub>2</sub>;
```






Semaphore Implementation

- Must guarantee that no two processes can execute the wait() and signal() on the same semaphore at the same time
- Thus, the implementation becomes the critical section problem where the wait and signal code are placed in the critical section
- Could now have busy waiting in critical section implementation
 - But implementation code is short
 - Little busy waiting if critical section rarely occupied
- Note that applications may spend lots of time in critical sections and therefore this is not a good solution





Semaphore Implementation with no Busy waiting

- With each semaphore there is an associated waiting queue
- Each entry in a waiting queue has two data items:
 - Value (of type integer)
 - Pointer to next record in the list
- Two operations:
 - block place the process invoking the operation on the appropriate waiting queue
 - wakeup remove one of processes in the waiting queue and place it in the ready queue






Implementation with no Busy waiting (Cont.)

Waiting queue

```
typedef struct {
  int value;
  struct process *list;
} semaphore;
```






Implementation with no Busy waiting (Cont.)

```
wait(semaphore *S) {
   S->value--;
   if (S->value < 0) {
      add this process to S->list;
      block();
signal(semaphore *S) {
   S->value++;
   if (S->value <= 0) {
      remove a process P from S->list;
      wakeup(P);
```






Problems with Semaphores

- Incorrect use of semaphore operations:
 - signal(mutex) ... wait(mutex)
 - wait(mutex) ... wait(mutex)
 - Omitting of wait (mutex) and/or signal (mutex)

 These – and others – are examples of what can occur when semaphores and other synchronization tools are used incorrectly





Monitors


- A high-level abstraction that provides a convenient and effective mechanism for process synchronization
 - Abstract data type, internal variables only accessible by code within the procedure
 - Only one process may be active within the monitor at a time
- Pseudocode syntax of a monitor:

```
monitor monitor-name
{
    // shared variable declarations
    procedure P1 (...) { ... }
    procedure P2 (...) { ... }
    procedure Pn (...) { ... }
    initialization code (...) { ... }
}
```





Schematic view of a Monitor







Monitor Implementation Using Semaphores

Variables


```
semaphore mutex;
mutex = 1;
```

Each procedure P is replaced by

```
wait(mutex);
...
// body of P;
...
signal(mutex);
```

Mutual exclusion within a monitor is ensured






Condition Variables

- condition x, y;
- Two operations are allowed on a condition variable:
 - x.wait() a process that invokes the operation is suspended until x.signal()
 - x.signal() resumes one of processes (if any) that invoked x.wait()
 - If no x.wait() on the variable, then it has no effect on the variable





Monitor with Condition Variables





Usage of Condition Variable Example

- Consider P_1 and P_2 that that need to execute two statements S_1 and S_2 and the requirement that S_1 to happen before S_2
 - Create a monitor with two procedures F₁ and F₂ that are invoked by P₁ and P₂ respectively
 - One condition variable "x" initialized to 0
 - One Boolean variable "done"





Monitor Implementation Using Semaphores

Variables


```
semaphore mutex; // (initially = 1)
semaphore next; // (initially = 0)
int next_count = 0; // number of processes
waiting inside the monitor
```

Each function P will be replaced by

```
wait(mutex);
...
    // body of P;
...
if (next_count > 0)
    signal(next);
else
    signal(mutex);
```

Mutual exclusion within a monitor is ensured





Implementation - Condition Variables


• For each condition variable **x**, we have:

```
semaphore x_sem; // (initially = 0)
int x_count = 0;
```

The operation x.wait() can be implemented as:

```
x_count++;
if (next_count > 0)
    signal(next);
else
    signal(mutex);
wait(x_sem);
x count--;
```





Implementation (Cont.)

The operation x.signal() can be implemented as:

```
if (x_count > 0) {
  next_count++;
  signal(x_sem);
  wait(next);
  next_count--;
}
```





Resuming Processes within a Monitor

- If several processes queued on condition variable x, and x.signal() is executed, which process should be resumed?
- FCFS frequently not adequate
- Use the conditional-wait construct of the form

where:

- c is an integer (called the priority number)
- The process with lowest number (highest priority) is scheduled next






Single Resource allocation

- Allocate a single resource among competing processes using priority numbers that specifies the maximum time a process plans to use the resource
 - The process with the shortest time is allocated the resource first
- Let R is an instance of type ResourceAllocator (next slide)
- Access to ResourceAllocator is done via:

```
R.acquire(t);
...
// access the resource;
...
R.release();
```

Where t is the maximum time a process plans to use the resource





A Monitor to Allocate Single Resource

```
monitor ResourceAllocator
  boolean busy;
  condition x;
  void acquire(int time) {
          if (busy)
             x.wait(time);
          busy = true;
  void release() {
          busy = false;
          x.signal();
   initialization code() {
     busy = false;
```






Single Resource Monitor (Cont.)

Usage:

```
acquire()
...
release()
```

- Incorrect use of monitor operations
 - release() ... acquire()
 - acquire() ... acquire()
 - Omitting of acquire() and/or release()






Liveness

- Processes may have to wait indefinitely while trying to acquire a synchronization tool such as a mutex lock or semaphore
- Waiting indefinitely violates the progress and bounded-waiting criteria discussed at the beginning of this chapter
- Liveness refers to a set of properties that a system must satisfy to ensure processes make progress
- Indefinite waiting is an example of a liveness failure






Liveness

- Deadlock two or more processes are waiting indefinitely for an event that can be caused by only one of the waiting processes
- Let S and Q be two semaphores initialized to 1

```
P_0 P_1 wait(S); wait(Q); wait(Q); wait(S); ... signal(S); signal(Q); signal(S);
```

- Consider if P₀ executes wait(S) and P₁ wait(Q). When P₀ executes wait(Q), it must wait until P₁ executes signal(Q)
- However, P_1 is waiting until P_0 execute signal(S)
- Since these signal() operations will never be executed, P₀ and P₁ are deadlocked





Liveness

- Other forms of deadlock:
- Starvation indefinite blocking
 - A process may never be removed from the semaphore queue in which it is suspended
- Priority Inversion Scheduling problem when lower-priority process holds a lock needed by higher-priority process
 - Solved via priority-inheritance protocol



End of Chapter 6





Priority Inheritance Protocol

- Consider the scenario with three processes P1, P2, and P3.
 - P1 has the highest priority, P2 the next highest, and P3 the lowest.
- Assume that P3 is holding semaphore S and that P1 is waiting to S to be released
- Assume that P2 is assigned the CPU and preempts P3
 - P3 is still holding semaphore S
 - P1 is waiting to S to be released
- What has happened is that P2 a process with a lower priority than
 P1 has indirectly prevented P3 from gaining access to the resource.
- To prevent this from occurring, a priority inheritance protocol is used. This simply allows the priority of the highest thread waiting to access a shared resource to be assigned to the thread currently using the resource. Thus, the current owner of the resource is assigned the priority of the highest priority thread wishing to acquire the resource.





Usage of Condition Variable Example

- Consider P_1 and P_2 that that need to execute two statements S_1 and S_2 and the requirement that S_1 to happen before S_2
 - Create a monitor with two procedures F₁ and F₂ that are invoked by P₁ and P₂ respectively
 - One condition variable "x" initialized to 0
 - One Boolean variable "done"

