Chapter 3: Processes

Outline

- Process Concept
- Process Scheduling
- Operations on Processes
- Interprocess Communication
  - IPC in Shared-Memory Systems
  - IPC in Message-Passing Systems
  - Examples of IPC Systems
- Communication in Client-Server Systems

Objectives

- Identify the separate components of a process and illustrate how they are represented and scheduled in an OS
- Describe how processes are created and terminated in an operating system, including developing programs using the appropriate system calls that perform these operations
- Describe and contrast interprocess communication using shared memory and message passing
- Design programs that use pipes and POSIX shared memory to perform interprocess communication
- Describe client-server communication using sockets and remote procedure calls
- Design kernel modules that interact with the Linux OS

Process Concept

- An OS executes a variety of programs that run as a process
- **Process** – a program in execution; process execution must progress in sequential fashion. No parallel execution of instructions of a single process
- Multiple parts
  - The program code, also called **text section**
  - Current activity including **program counter**, processor registers
  - **Stack** containing temporary data
    - Function parameters, return addresses, local variables
  - **Data section** containing global variables
  - **Heap** containing memory dynamically allocated during run time

Process Concept (Cont.)

- Program is **passive** entity stored on disk (**executable file**); process is **active**
  - Program becomes process when an executable file is loaded into memory
- Execution of program started via GUI mouse clicks, command line entry of its name, etc.
- One program can be several processes
  - Consider multiple users executing the same program

Process in Memory



Memory Layout of a C Program



Process State

- As a process executes, it changes **state**
  - **New**: The process is being created
  - **Running**: Instructions are being executed
  - **Waiting**: The process is waiting for some event to occur
  - **Ready**: The process is waiting to be assigned to a processor
  - **Terminated**: The process has finished execution

Diagram of Process State



Process Control Block (PCB)

Information associated with each process (also called **task control block**)

- Process state – running, waiting, etc.
- Program counter – location of instruction to next execute
- CPU registers – contents of all process-centric registers
- CPU scheduling information - priorities, scheduling queue pointers
- Memory-management information – memory allocated to the process
- Accounting information – CPU used, clock time elapsed since start, time limits
- I/O status information – I/O devices allocated to process, list of open files



Threads

- So far, process has a single thread of execution
- Consider having multiple program counters per process
  - Multiple locations can execute at once
    - Multiple threads of control -> **threads**
  - Must then have storage for thread details, multiple program counters in PCB
- Explore in detail in Chapter 4

Process Representation in Linux

Represented by the C structure `task_struct`

```
pid t_pid;                    /* process identifier */
long state;                   /* state of the process */
unsigned int time_slice       /* scheduling information */
struct task_struct *parent;/* this process's parent */
struct list_head children; /* this process's children */
struct files_struct *files;/* list of open files */
struct mm_struct *mm;         /* address space of this
process */
```



Process Scheduling

- **Process scheduler** selects among available processes for next execution on CPU core
- Goal -- Maximize CPU use, quickly switch processes onto CPU core
- Maintains **scheduling queues** of processes
  - **Ready queue** – set of all processes residing in main memory, ready and waiting to execute
  - **Wait queues** – set of processes waiting for an event (i.e., I/O)
  - Processes migrate among the various queues

Ready and Wait Queues



Representation of Process Scheduling



CPU Switch From Process to Process

A **context switch** occurs when the CPU switches from one process to another



Context Switch

- When CPU switches to another process, the system must **save the state** of the old process and load the **saved state** for the new process via a **context switch**
- **Context** of a process represented in the PCB
- Context-switch time is pure overhead; the system does no useful work while switching
  - The more complex the OS and the PCB ➔ the longer the context switch
- Time dependent on hardware support
  - Some hardware provides multiple sets of registers per CPU ➔ multiple contexts loaded at once

Multitasking in Mobile Systems

- Some mobile systems (e.g., early version of iOS) allow only one process to run, others suspended
- Due to screen real estate, user interface limits, iOS provides
  - Single **foreground** process- controlled via user interface
  - Multiple **background** processes– in memory, running, but not on the display, and with limits
  - Limits include single, short task, receiving notification of events, specific long-running tasks like audio playback
- Android runs foreground and background, with fewer limits
  - Background process uses a **service** to perform tasks
  - Service can keep running even if background process is suspended
  - Service has no user interface, small memory use

Operations on Processes

- System must provide mechanisms for:
  - Process creation
  - Process termination

Process Creation

- **Parent** process create **children** processes, which, in turn create other processes, forming a **tree** of processes
- Generally, process identified and managed via a **process identifier** (**pid**)
- Resource sharing options
  - Parent and children share all resources
  - Children share subset of parent's resources
  - Parent and child share no resources
- Execution options
  - Parent and children execute concurrently
  - Parent waits until children terminate

A Tree of Processes in Linux



Process Creation (Cont.)

- Address space
  - Child duplicate of parent
  - Child has a program loaded into it
- UNIX examples
  - **`fork()`** system call creates new process
  - **`exec()`** system call used after a **`fork()`** to replace the process' memory space with a new program
  - Parent process calls **`wait()`** waiting for the child to terminate



C Program Forking Separate Process

```c
#include <sys/types.h>
#include <stdio.h>
#include <unistd.h>

int main()
{
pid_t pid;

    /* fork a child process */
    pid = fork();

    if (pid < 0) { /* error occurred */
      fprintf(stderr, "Fork Failed");
      return 1;
    }
    else if (pid == 0) { /* child process */
      execlp("/bin/ls","ls",NULL);
    }
    else { /* parent process */
      /* parent will wait for the child to complete */
      wait(NULL);
      printf("Child Complete");
    }

    return 0;
}
```

Creating a Separate Process via Windows API

```
#include <stdio.h>
#include <windows.h>

int main(VOID)
{
STARTUPINFO si;
PROCESS_INFORMATION pi;

   /* allocate memory */
   ZeroMemory(&si, sizeof(si));
   si.cb = sizeof(si);
   ZeroMemory(&pi, sizeof(pi));

   /* create child process */
   if (!CreateProcess(NULL, /* use command line */
    "C:\\WINDOWS\\system32\\mspaint.exe", /* command */
    NULL, /* don't inherit process handle */
    NULL, /* don't inherit thread handle */
    FALSE, /* disable handle inheritance */
    0, /* no creation flags */
    NULL, /* use parent's environment block */
    NULL, /* use parent's existing directory */
    &si,
    &pi))
   {
     fprintf(stderr, "Create Process Failed");
     return -1;
   }
   /* parent will wait for the child to complete */
   WaitForSingleObject(pi.hProcess, INFINITE);
   printf("Child Complete");

   /* close handles */
   CloseHandle(pi.hProcess);
   CloseHandle(pi.hThread);
}
```

Process Termination

- Process executes last statement and then asks the OS to delete it using the **`exit()`** system call
  - Returns status data from child to parent (via **`wait()`**)
  - Process' resources are released by OS
- Parent may terminate the execution of children processes using the **`abort()`** system call. Some reasons for doing so:
  - Child has exceeded allocated resources
  - Task assigned to child is no longer required
  - The parent is exiting, and the OS does not allow a child to continue if its parent terminates

Process Termination

- Some OS do not allow child to exist if its parent has terminated. If a process terminates, then all its children must also be terminated
  - **cascading termination.** All children, grandchildren, etc., are terminated
  - The termination is initiated by the OS
- The parent process may wait for termination of a child process by using the **`wait()`** system call. The call returns status information and the pid of the terminated process

```
pid = wait(&status);
```

  - If no parent waiting (did not invoke **`wait()`**) process is a **zombie**
  - If parent terminated without invoking **`wait()`**, process is an **orphan**

Android Process Importance Hierarchy

- Mobile OS often have to terminate processes to reclaim system resources such as memory. From **most** to **least** important:
  - Foreground process
  - Visible process
  - Service process
  - Background process
  - Empty process
- Android will begin terminating processes that are least important

Multiprocess Architecture – Chrome Browser

- Many web browsers ran as single process (some still do)
  - If one web site causes trouble, entire browser can hang or crash
- Google Chrome Browser is multiprocess with 3 different types of processes:
  - **Browser** process manages user interface, disk and network I/O
  - **Renderer** process renders web pages, deals with HTML, Javascript. A new renderer created for each website opened
    - Runs in **sandbox** restricting disk and network I/O, minimizing effect of security exploits
  - **Plug-in** process for each type of plug-in



Each tab represents a separate process.

Interprocess Communication

- Processes within a system may be ***independent*** or ***cooperating***
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
  - Information sharing
  - Computation speedup
  - Modularity
  - Convenience
- Cooperating processes need **interprocess communication** (**IPC**)
- Two models of IPC
  - **Shared memory**
  - **Message passing**

Communications Models

(a) Shared memory (b) Message passing



Producer-Consumer Problem

- Paradigm for cooperating processes:
  - *producer* process produces information that is consumed by a *consumer* process
- Two variations:
  - **unbounded-buffer** places no practical limit on the size of the buffer:
    - Producer never waits
    - Consumer waits if there is no buffer to consume
  - **bounded-buffer** assumes that there is a fixed buffer size
    - Producer must wait if all buffers are full
    - Consumer waits if there is no buffer to consume

IPC – Shared Memory

- An area of memory shared among the processes that wish to communicate
- The communication is under the control of the user processes not the OS
- Major issue is to provide mechanism that will allow the user processes to synchronize their actions when they access shared memory
- Synchronization is discussed in great details in Chapters 6 & 7

Bounded-Buffer – Shared-Memory Solution

- Shared data

```
#define BUFFER_SIZE 10
typedef struct {
  . . .
} item;

item buffer[BUFFER_SIZE];
int in = 0;
int out = 0;
```

- Solution is correct, but can only use **BUFFER_SIZE-1** elements

Producer Process – Shared Memory

```
item next_produced;

while (true) {
   /* produce an item in next_produced */
   while (((in + 1) % BUFFER_SIZE) == out)
        ; /* do nothing */
   buffer[in] = next_produced;
   in = (in + 1) % BUFFER_SIZE;
}
```

Consumer Process – Shared Memory

```
item next_consumed;

while (true) {
      while (in == out)
            ; /* do nothing */
      next_consumed = buffer[out];
      out = (out + 1) % BUFFER_SIZE;

      /* consume the item in next_consumed */
}
```

What about Filling all the Buffers?

- Suppose that we wanted to provide a solution to the consumer-producer problem that fills **all** the buffers
- We can do so by having an integer **`counter`** that keeps track of the number of full buffers
- Initially, **`counter`** is set to 0
- The integer **`counter`** is incremented by the producer after it produces a new buffer
- The integer **`counter`** is decremented by the consumer after it consumes a buffer

Producer

```
while (true) {
      /* produce an item in next_produced
*/


      while (counter == BUFFER_SIZE)
            ; /* do nothing */
      buffer[in] = next_produced;
      in = (in + 1) % BUFFER_SIZE;
      counter++;
}
```

Consumer

```
while (true) {
      while (counter == 0)
            ; /* do nothing */
      next_consumed = buffer[out];
      out = (out + 1) % BUFFER_SIZE;
      counter--;
      /* consume the item in next_consumed
*/
}
```

Race Condition

- **`counter++`** could be implemented as

```
register1 = counter
register1 = register1 + 1
counter = register1
```

- **`counter--`** could be implemented as

```
register2 = counter
register2 = register2 - 1
counter = register2
```

- Consider this execution interleaving with "count = 5" initially:

S0: producer execute **`register1 = counter`** {register1 = 5}
S1: producer execute **`register1 = register1 + 1`** {register1 = 6}
S2: consumer execute **`register2 = counter`** {register2 = 5}
S3: consumer execute **`register2 = register2 - 1`** {register2 = 4}
S4: producer execute **`counter = register1`** {counter = 6 }
S5: consumer execute **`counter = register2`** {counter = 4}

Race Condition (Cont.)

- **Question – why was there no race condition in the first solution where at most (N – 1) buffers can be filled?**
- **More in Chapter 6**

IPC – Message Passing

- Processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
  - **`send`**(*message*)
  - **`receive`**(*message*)
- The *message* size is either fixed or variable

Message Passing (Cont.)

- If processes *P* and *Q* wish to communicate, they need to:
  - Establish a ***communication link*** between them
  - Exchange messages via send/receive
- Implementation issues:
  - How are links established?
  - Can a link be associated with more than two processes?
  - How many links can there be between every pair of communicating processes?
  - What is the capacity of a link?
  - Is the size of a message that the link can accommodate fixed or variable?
  - Is a link unidirectional or bi-directional?

Implementation of Communication Link

- Physical:
  - Shared memory
  - Hardware bus
  - Network
- Logical:
  - Direct or indirect
  - Synchronous or asynchronous
  - Automatic or explicit buffering

Direct Communication

- Processes must name each other explicitly:
  - **`send`** (*P*, *message*) – send a message to process P
  - **`receive`**(*Q*, *message*) – receive a message from process Q
- Properties of communication link
  - Links are established automatically
  - A link is associated with exactly one pair of communicating processes
  - Between each pair there exists exactly one link
  - The link may be unidirectional, but is usually bi-directional

Indirect Communication

- Messages are directed and received from mailboxes (also referred to as ports)
  - Each mailbox has a unique id
  - Processes can communicate only if they share a mailbox
- Properties of communication link
  - Link established only if processes share a common mailbox
  - A link may be associated with many processes
  - Each pair of processes may share several communication links
  - Link may be unidirectional or bi-directional

Indirect Communication (Cont.)

- Operations
  - Create a new mailbox (port)
  - Send and receive messages through mailbox
  - Delete a mailbox
- Primitives are defined as:
  - **`send`**(*A, message*) – send a message to mailbox A
  - **`receive`**(*A, message*) – receive a message from mailbox A

Indirect Communication (Cont.)

- Mailbox sharing
  - P_1, P_2, and P_3 share mailbox A
  - P_1, sends; P_2 and P_3 receive
  - Who gets the message?
- Solutions
  - Allow a link to be associated with at most two processes
  - Allow only one process at a time to execute a receive operation
  - Allow the system to select arbitrarily the receiver. Sender is notified who the receiver was

Synchronization

Message passing may be either blocking or non-blocking

- **Blocking** is considered **synchronous**
  - **Blocking send** -- the sender is blocked until the message is received
  - **Blocking receive** -- the receiver is blocked until a message is available
- **Non-blocking** is considered **asynchronous**
  - **Non-blocking send** -- the sender sends the message and continue
  - **Non-blocking receive** -- the receiver receives:
    - A valid message, or
    - Null message
- Different combinations possible
  - If both send and receive are blocking, we have a **rendezvous**

Buffering

- Queue of messages attached to the link
- Implemented in one of three ways
  1. Zero capacity – no messages are queued on a link
     Sender must wait for receiver (rendezvous)
  2. Bounded capacity – finite length of *n* messages
     Sender must wait if link full
  3. Unbounded capacity – infinite length
     Sender never waits

Producer-Consumer: Message Passing

- Producer

```
message next_produced;
while (true) {
 /* produce an item in next_produced */

 send(next_produced);
}
```

- Consumer

```
message next_consumed;
while (true) {
  receive(next_consumed)

 /* consume the item in next_consumed */
}
```

Examples of IPC Systems - POSIX

- POSIX Shared Memory
  - Process first creates shared memory segment
    `shm_fd = shm_open(name, O CREAT | O RDWR, 0666);`
    - Also used to open an existing segment
  - Set the size of the object

    ```
    ftruncate(shm_fd, 4096);
    ```

  - Use **`mmap()`** to memory-map a file pointer to the shared memory object
  - Reading and writing to shared memory is done by using the pointer returned by **`mmap()`**

IPC POSIX Producer

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>

int main()
{
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* strings written to shared memory */
const char *message_0 = "Hello";
const char *message_1 = "World!";

/* shared memory file descriptor */
int shm_fd;
/* pointer to shared memory obect */
void *ptr;

   /* create the shared memory object */
   shm_fd = shm_open(name, O_CREAT | O_RDWR, 0666);

   /* configure the size of the shared memory object */
   ftruncate(shm_fd, SIZE);

   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_WRITE, MAP_SHARED, shm_fd, 0);

   /* write to the shared memory object */
   sprintf(ptr,"%s",message_0);
   ptr += strlen(message_0);
   sprintf(ptr,"%s",message_1);
   ptr += strlen(message_1);

   return 0;
}
```

IPC POSIX Consumer

```
#include <stdio.h>
#include <stdlib.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>

int main()
{
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* shared memory file descriptor */
int shm_fd;
/* pointer to shared memory obect */
void *ptr;

   /* open the shared memory object */
   shm_fd = shm_open(name, O_RDONLY, 0666);

   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_READ, MAP_SHARED, shm_fd, 0);

   /* read from the shared memory object */
   printf("%s",(char *)ptr);

   /* remove the shared memory object */
   shm_unlink(name);

   return 0;
}
```

Examples of IPC Systems - Mach

- Mach communication is message based
  - Even system calls are messages
  - Each task gets two ports at creation - Kernel and Notify
  - Messages are sent and received using the **`mach_msg()`** function
  - Ports needed for communication, created via

    `mach_port_allocate()`
  - Send and receive are flexible; for example four options if mailbox full:
    - Wait indefinitely
    - Wait at most n milliseconds
    - Return immediately
    - Temporarily cache a message

Mach Messages

```
#include<mach/mach.h>

struct message {
      mach_msg_header_t header;
      int data;
};

mach port t client;
mach port t server;
```

Mach Message Passing - Client

```
/* Client Code */

struct message message;

// construct the header
message.header.msgh_size = sizeof(message);
message.header.msgh_remote_port = server;
message.header.msgh_local_port = client;

// send the message
mach_msg(&message.header, // message header
  MACH_SEND_MSG, // sending a message
  sizeof(message), // size of message sent
  0, // maximum size of received message - unnecessary
  MACH_PORT_NULL, // name of receive port - unnecessary
  MACH_MSG_TIMEOUT_NONE, // no time outs
  MACH_PORT_NULL // no notify port
);
```

Mach Message Passing - Server

```
/* Server Code */

struct message message;

// receive the message
mach_msg(&message.header, // message header
   MACH_RCV_MSG, // sending a message
   0, // size of message sent
   sizeof(message), // maximum size of received message
   server, // name of receive port
   MACH_MSG_TIMEOUT_NONE, // no time outs
   MACH_PORT_NULL // no notify port
);
```

Examples of IPC Systems – Windows

- Message-passing centric via **advanced local procedure call** **(LPC)** facility
  - Only works between processes on the same system
  - Uses ports (like mailboxes) to establish and maintain communication channels
  - Communication works as follows:
    - The client opens a handle to the subsystem's **connection port** object
    - The client sends a connection request
    - The server creates two private **communication ports** and returns the handle to one of them to the client
    - The client and server use the corresponding port handle to send messages or callbacks and to listen for replies

Local Procedure Calls in Windows



Pipes

- Acts as a conduit allowing two processes to communicate
- Issues:
  - Is communication unidirectional or bidirectional?
  - In the case of two-way communication, is it half or full-duplex?
  - Must there exist a relationship (i.e., ***parent-child***) between the communicating processes?
  - Can the pipes be used over a network?
- **Ordinary pipes** – cannot be accessed from outside the process that created it. Typically, a parent process creates a pipe and uses it to communicate with a child process that it created
- **Named pipes** – can be accessed without a parent-child relationship

Ordinary Pipes

- Ordinary Pipes allow communication in standard producer-consumer style
- Producer writes to one end (the **write-end** of the pipe)
- Consumer reads from the other end (the **read-end** of the pipe)
- Ordinary pipes are therefore unidirectional
- Require parent-child relationship between communicating processes



- Windows calls these **anonymous pipes**

Examples of Pipes in UNIX and Windows

- Ordinary Pipes in UNIX
  - fork(), read(), write(), wait(), close()
  - (See Fig. 3.25 & 3.26)
- Windows anonymous pipe – parent & child process
  - CreateProcess(), WriteFile(), ReadFile(), WaitForSingleObject(), CloseHandle()
  - (See Fig. 3.27, 3.28, & 3.29)

```
#include <sys/types.h>
#include <stdio.h>
#include <string.h>
#include <unistd.h>

#define BUFFER_SIZE 25
#define READ_END 0
#define WRITE_END 1

int main(void)
{
char write_msg[BUFFER_SIZE] = "Greetings";
char read_msg[BUFFER_SIZE];
int fd[2];
pid_t pid;

      /* Program continues in  Figure 3.26 */
```

Figure 3.25 Ordinary pipe in UNIX.

```
    /* create the pipe */
    if (pipe(fd) == -1) {
      fprintf(stderr,"Pipe failed");
      return 1;
    }

    /* fork a child process */
    pid = fork();

    if (pid < 0) { /* error occurred */
      fprintf(stderr, "Fork Failed");
      return 1;
    }

    if (pid > 0) { /* parent process */
      /* close the unused end of the pipe */
      close(fd[READ_END]);

      /* write to the pipe */
      write(fd[WRITE_END], write_msg, strlen(write_msg)+1);

      /* close the write end of the pipe */
      close(fd[WRITE_END]);
    }
    else { /* child process */
      /* close the unused end of the pipe */
      close(fd[WRITE_END]);

      /* read from the pipe */
      read(fd[READ_END], read_msg, BUFFER_SIZE);
      printf("read %s",read_msg);

      /* close the write end of the pipe */
      close(fd[READ_END]);
    }

    return 0;
}
```

Figure 3.26 Figure 3.25, continued.

```
#include <stdio.h>
#include <stdlib.h>
#include <windows.h>

#define BUFFER_SIZE 25

int main(VOID)
{
HANDLE ReadHandle, WriteHandle;
STARTUPINFO si;
PROCESS_INFORMATION pi;
char message[BUFFER_SIZE] = "Greetings";
DWORD written;

      /* Program continues in  Figure 3.28 */
```

Figure 3.27 Windows anonymous pipe — parent process.

```
/* set up security attributes allowing pipes to be inherited */
SECURITY_ATTRIBUTES sa = {sizeof(SECURITY_ATTRIBUTES),NULL,TRUE};
/* allocate memory */
ZeroMemory(&pi, sizeof(pi));

/* create the pipe */
if (!CreatePipe(&ReadHandle, &WriteHandle, &sa, 0)) {
  fprintf(stderr, "Create Pipe Failed");
  return 1;
}

/* establish the START_INFO structure for the child process */
GetStartupInfo(&si);
si.hStdOutput = GetStdHandle(STD_OUTPUT_HANDLE);

/* redirect standard input to the read end of the pipe */
si.hStdInput = ReadHandle;
si.dwFlags = STARTF_USESTDHANDLES;

/* don't allow the child to inherit the write end of pipe */
SetHandleInformation(WriteHandle, HANDLE_FLAG_INHERIT, 0);

/* create the child process */
CreateProcess(NULL, "child.exe", NULL, NULL,
 TRUE, /* inherit handles */
 0, NULL, NULL, &si, &pi);

/* close the unused end of the pipe */
CloseHandle(ReadHandle);

/* the parent writes to the pipe */
if (!WriteFile(WriteHandle, message,BUFFER_SIZE,&written,NULL))
  fprintf(stderr, "Error writing to pipe.");

/* close the write end of the pipe */
CloseHandle(WriteHandle);

/* wait for the child to exit */
WaitForSingleObject(pi.hProcess, INFINITE);
CloseHandle(pi.hProcess);
CloseHandle(pi.hThread);
return 0;
}
```

Figure 3.28 Figure 3.27, continued.

```
#include <stdio.h>
#include <windows.h>

#define BUFFER_SIZE 25

int main(VOID)
{
HANDLE Readhandle;
CHAR buffer[BUFFER_SIZE];
DWORD read;

   /* get the read handle of the pipe */
   ReadHandle = GetStdHandle(STD_INPUT_HANDLE);

   /* the child reads from the pipe */
   if (ReadFile(ReadHandle, buffer, BUFFER_SIZE, &read, NULL))
     printf("child read %s",buffer);
   else
     fprintf(stderr, "Error reading from pipe");

   return 0;
}
```

Figure 3.29 Windows anonymous pipes — child process.

Named Pipes

- Named Pipes are more powerful than ordinary pipes
- Communication is bidirectional
- No parent-child relationship is necessary between the communicating processes
- Several processes can use the named pipe for communication
- Provided on both UNIX and Windows systems

Communications in Client-Server Systems

- Sockets
- Remote Procedure Calls

Sockets

- A **socket** is defined as an endpoint for communication
- Concatenation of IP address and **port** – a number included at start of message packet to differentiate network services on a host
- The socket **161.25.19.8:1625** refers to port **1625** on host **161.25.19.8**
- Communication consists between a pair of sockets
- All ports below 1024 are ***well known***, used for standard services
- Special IP address 127.0.0.1 (**loopback**) to refer to system on which process is running

Socket Communication



Berkeley Socket API (in C)

- An Example of TCP Socket

[Source: https://en.wikipedia.org/wiki/Berkeley_sockets]



Sockets in Java

- Three types of sockets
  - **Connection-oriented** (**TCP**)
  - **Connectionless** (**UDP**)
  - **`MulticastSocket`** class – data can be sent to multiple recipients
- Consider this "Date" server in Java:

```
import java.net.*;
import java.io.*;

public class DateServer
{
   public static void main(String[] args) {
      try {
         ServerSocket sock = new ServerSocket(6013);

         /* now listen for connections */
         while (true) {
            Socket client = sock.accept();

            PrintWriter pout = new
             PrintWriter(client.getOutputStream(), true);

            /* write the Date to the socket */
            pout.println(new java.util.Date().toString());

            /* close the socket and resume */
            /* listening for connections */
            client.close();
         }
      }
      catch (IOException ioe) {
         System.err.println(ioe);
      }
   }
}
```

Sockets in Java

The equivalent Date client

```
import java.net.*;
import java.io.*;

public class DateClient
{
   public static void main(String[] args) {
      try {
         /* make connection to server socket */
         Socket sock = new Socket("127.0.0.1",6013);

         InputStream in = sock.getInputStream();
         BufferedReader bin = new
            BufferedReader(new InputStreamReader(in));

         /* read the date from the socket */
         String line;
         while ( (line = bin.readLine()) != null)
            System.out.println(line);

         /* close the socket connection*/
         sock.close();
      }
      catch (IOException ioe) {
         System.err.println(ioe);
      }
   }
}
```

Remote Procedure Calls

- Remote procedure call (RPC) abstracts procedure calls between processes on networked systems
  - Again uses ports for service differentiation
- **Stubs** – client-side proxy for the actual procedure on the server
- The client-side stub locates the server and **marshalls** the parameters
- The server-side stub receives this message, unpacks the marshalled parameters, and performs the procedure on the server
- On Windows, stub code compile from specification written in **Microsoft Interface Definition Language** (**MIDL**)

Remote Procedure Calls (Cont.)

- Data representation handled via **External Data Representation** (**XDL**) format to account for different architectures
  - **Big-endian** and **little-endian**
- Remote communication has more failure scenarios than local
  - Messages can be delivered ***exactly once*** rather than ***at most once***
- OS typically provides a rendezvous (or **matchmaker**) service to connect client and server

Execution of RPC



Portmapper (or rpcbind): port 111

RPC Flow

- Check RFC 5531 for more details



Remote Procedure Call Flow

[Source: https://www.ibm.com/support/knowledgecenter/en/ssw_aix_71/commprogramming/rpc_mod.html]

End of Chapter 3



Producer-Consumer Problem

- Paradigm for cooperating processes:
  - *producer* process produces information that is consumed by a *consumer* process
- Two variations:
  - **unbounded-buffer** places no practical limit on the size of the buffer:
    - Producer never waits
    - Consumer waits if there is no buffer to consume
  - **bounded-buffer** assumes that there is a fixed buffer size
    - Producer must wait if all buffers are full
    - Consumer waits if there is no buffer to consume

Cooperating Processes

- ***Independent*** process cannot affect or be affected by the execution of another process
- ***Cooperating*** process can affect or be affected by the execution of another process
- Advantages of process cooperation
  - Information sharing
  - Computation speed-up
  - Modularity
  - Convenience

Synchronization

- Message passing may be either blocking or non-blocking
  - **Blocking** is considered **synchronous**
    - **Blocking send** -- the sender is blocked until the message is received
    - **Blocking receive** -- the receiver is blocked until a message is available
  - **Non-blocking** is considered **asynchronous**
    - **Non-blocking send** -- the sender sends the message and continue
    - **Non-blocking receive** -- the receiver receives:
    - A valid message, or
    - Null message
  - Different combinations possible
    - If both send and receive are blocking, we have a **rendezvous**