NSD NETWORK DAY03

- 1. 案例1: 动态路由
- 2. <u>案例2</u>: <u>基本ACL的配置</u> (1) 3. <u>案例3</u>: <u>基本ACL的配置</u> (2)
- 4. 案例4: 高级ACL

1案例1: 动态路由

1.1 问题

通过配置静态路由协议ospf实现全网互通




图-1

1.2 步骤

S3700交换机配置

```
01.
       [Huawei]vlan batch 2 3
                                    //创建VLAN2、3
02.
       [Huawei]interface Ethernet0/0/2
03.
       [Huawei-Ethernet0/0/2]port default vlan 2
04.
       [Huawei]interface Ethernet0/0/3
05.
       [Huawei-Ethernet0/0/3]port default vlan 3
06.
       [Huawei]interface Ethernet0/0/22
07.
       [Huawei-Ethernet0/0/22]port link-type trunk
08.
       [Huawei-Ethernet0/0/22]port trunk allow-pass vlan all
```

S5700交换机配置

Top

```
02.
       [Huawei]interface Vlanif 1
       [Huawei-Vlanif4]ip address 192.168.1.254 24
03.
04.
       [Huawei]interface Vlanif 2
       [Huawei-Vlanif4]ip address 192.168.2.254 24
05.
06.
       [Huawei]interface Vlanif 3
07.
       [Huawei-Vlanif4]ip address 192.168.3.254 24
08.
       [Huawei]interface Vlanif 4
09.
       [Huawei-Vlanif4]ip address 192.168.4.1 24
10.
11.
       [Huawei]interface GigabitEthernet 0/0/1
12.
       [Huawei-GigabitEthernet0/0/1] port link-type trunk
13.
       [Huawei-GigabitEthernet0/0/1] port trunk allow-pass vlan all
       [Huawei]interface GigabitEthernet 0/0/2
14.
15.
       [Huawei-GigabitEthernet0/0/2] port link-type access
       [Huawei-GigabitEthernet0/0/2] port default vlan 4
16.
17.
       [Huawei]ospf 1
18.
       [Huawei-ospf-1]area 0
19.
       [Huawei-ospf-1-area-0.0.0.0]network 192.168.1.0 0.0.0.255
20.
       [Huawei-ospf-1-area-0.0.0.0]network 192.168.2.0 0.0.0.255
21.
       [Huawei-ospf-1-area-0.0.0.0]network 192.168.3.0 0.0.0.255
       [Huawei-ospf-1-area-0.0.0.0]network 192.168.4.0 0.0.0.255
22.
23.
       [Huawei]ip route-static 0.0.0.0 0.0.0.0 192.168.4.2
```

路由器配置

O1. [Huawei]interface GigabitEthernet 0/0/0
O2. [Huawei-GigabitEthernet0/0/0] ip address 192.168.4.2 24
O3. [Huawei]interface GigabitEthernet 0/0/1
O4. [Huawei-GigabitEthernet0/0/0] ip address 192.168.5.254 24
O5. [Huawei]ospf 1
O6. [Huawei-ospf-1]area 0
O7. [Huawei-ospf-1-area-0.0.0.0]network 192.168.4.0 0.0.0.255

2 案例2:基本ACL的配置 (1)

2.1 问题

按照图-2所示拓扑结构,禁止主机pc2与pc1通信,而允许所有其他流量




图-2

2.2 步骤

1,为路由器g0/0/0接口配置ip 192.168.1.254,为路由器g0/0/1接口配置ip 192.168.2.254

- 01. [Huawei]interface GigabitEthernet 0/0/0
- 02. [Huawei-GigabitEthernet0/0/0] ip address 192.168.1.254 24
- 03. [Huawei]acl 2000
- 04. [Huawei-acl-basic-2000]rule deny source 192.168.2.1 0
- 05. [Huawei]interface GigabitEthernet 0/0/1
- 06. [Huawei-GigabitEthernet0/0/1]ip address 192.168.2.254 24
- 07. [Huawei-GigabitEthernet0/0/1]traffic-filter inbound acl 2000

3 案例3:基本ACL的配置 (2)

3.1 问题

按照图-3所示拓扑结构,允许主机pc2与pc1互通,而禁止其他设备访问pc1




图-3

3.2 步骤

注:此案例需要提前配置好所有设备的ip地址

- 01. [Huawei]acl 2001
- 02. [Huawei-acl-basic-2001]rule permit source 192.168.2.1 0
- 03. [Huawei-acl-basic-2001]rule deny source any
- 04. [Huawei]interface GigabitEthernet 0/0/1
- 05. [Huawei-GigabitEthernet0/0/1]undo traffic-filter inbound acl 2000
- 06. [Huawei-GigabitEthernet0/0/1] traffic-filter inbound acl 2001

4 案例4: 高级ACL

4.1 问题

按照图-4所示拓扑结构,禁止pc2访问pc1的ftp服务,禁止pc3访问pc1的www服务,所有主机的 其他服务不受限制




图-4

4.2 步骤

注:此案例需要提前配置好所有设备的ip地址

- 01. [Huawei]acl 3000
- 02. [Huawei-acl-adv-3000]rule deny tcp source 192.168.2.1 0 destination 192.168.1.1
- 03. 0 destination-port eq 21
- 04. [Huawei-acl-adv-3000]rule deny tcp source 192.168.2.2 0 destination 192.168.1.1
- 05. 0 destination-port eq 80
- 06. [Huawei]interface g0/0/1
- 07. [Huawei-GigabitEthernet0/0/1]traffic-filter inbound acl 3000 //在接口中应用acl