⚡ CRYPTO SCALP SCANNER

Complete User Guide & Reference — v9

- ▸ Real-time Binance scanner for sub-$1 coins with multi-indicator scoring
- ▸ Live trade journal with auto SL/TP detection and equity curve
- ▸ Multi-channel alerts: Sound · Desktop · Telegram · WhatsApp (PicoClaw)
- ▸ No API key required — Binance public endpoints only
- ▸ Runs on Linux · Windows · macOS

Python 3.10+ PyQt6 Arch Linux Windows macOS

Table of Contents

1. Installation
2. Tab 1 — Scanner
3. Tab 2 — Top Picks
4. Tab 3 — Config
5. Tab 4 — Alerts
6. Tab 5 — Trades
7. How Scoring Works
8. Full Workflow Example
9. Keyboard & Mouse Shortcuts

1 — Installation

Step 1: Install Python dependencies

On Arch Linux, add --break-system-packages to the pip command.

```
pip install PyQt6 requests
```

Step 2: Run the application

The app uses only Binance public REST endpoints — no account or API key needed.

```
python crypto_scanner_v9.py
```

Step 3: Optional: install a monospace font for crisp text

Arch: sudo pacman -S ttf-jetbrains-mono · Windows: Consolas is built-in · macOS: Menlo is built-in

> 💡 No API key needed. The scanner uses Binance public REST endpoints only — no account, no login, no rate-limit concerns for normal usage.

2 — Tab 1: Scanner

The Scanner table is the engine room. After hitting ⚡ SCAN, every qualifying coin appears as a row with all its indicator values. Click any column header to sort. Double-click a row to open the full detail popup. Right-click to enter a trade.



#	SYMBOL	PRICE	24H%	RSI	STRSI	MACD	BB%	VOL 24H	SIGNAL	POT%	EXP%	L/S	PATTERN	CHART	AGE	CONF	1H
1	PIXEL	$0.01509	+168.…	37.6	0.0	▲	-3%	$62.4M	STRONG BUY	81%	10.…	L8/S2	Neutral		–	–	↑
2	XAI	$0.01356	+43.7%	39.2	7.0	▲	12%	$22.4M	STRONG BUY	72%	7.3%	L6/S2	Neutral		–	–	↑
3	OPN	$0.29780	-12.0%	50.1	29.4	▲	40%	$23.5M	STRONG BUY	52%	1.1%	L6/S0	Neutral		–	–	↓
4	HUMA	$0.02149	+28.4%	72.7	100.0	▼	95%	$13.6M	STRONG SELL	97%	6.2%	L2/S11	Vol Spike ↑		–	–	↑
5	WIF	$0.16800	-1.8%	67.2	81.5	▼	77%	$9.8M	STRONG SELL	100%	2.9%	L0/S10	Doji		–	–	↓
6	RESOLV	$0.11250	-12.6%	65.5	100.0	▼	111%	$9.9M	STRONG SELL	82%	2.4%	L1/S11	Neutral		–	–	↓
7	ROBO	$0.03988	-14.6%	58.9	86.3	▼	88%	$16.3M	STRONG SELL	72%	1.7%	L3/S7	Bullish Engulf…		–	–	↓
8	WLD	$0.35890	-3.9%	60.5	54.2	▼	69%	$17.2M	STRONG SELL	58%	1.2%	L0/S6	Neutral		–	–	↓
9	SUI	$0.96050	-1.4%	61.0	69.3	▼	77%	$49.5M	STRONG SELL	60%	1.1%	L0/S8	Neutral		–	–	↑
10	ADA	$0.26120	-1.4%	62.3	61.0	▼	73%	$48.5M	STRONG SELL	59%	1.1%	L0/S7	Neutral		–	–	→
11	VIRTUAL	$0.69830	-2.2%	60.9	93.0	▼	85%	$10.4M	STRONG SELL	71%	1.1%	L0/S9	Neutral		–	–	↑
12	HBAR	$0.09430	-2.6%	59.4	67.2	▼	74%	$9.1M	STRONG SELL	59%	0.7%	L0/S6	Neutral		–	–	↓
13	FET	$0.16130	+8.3%	46.0	0.0	▲	10%	$13.3M	BUY	53%	1.1%	L5/S3	Downtrend ↓		–	–	↑
14	FLOW	$0.05807	-10.0%	54.1	52.3	▼	79%	$16.7M	SELL	46%	1.8%	L0/S3	Neutral		–	–	↑
15	FIL	$0.90000	-3.5%	56.8	31.6	▼	64%	$28.8M	SELL	42%	1.6%	L1/S5	Neutral		–	–	↓
16	SHIB	$0.00001	-1.2%	64.5	25.2	▼	–	$16.1M	SELL	48%	1.2%	L1/S5	Doji		–	–	↑
17	XPL	$0.09970	+4.3%	53.9	54.0	▼	67%	$16.8M	SELL	38%	1.2%	L0/S4	Neutral		–	–	↑
18	ENA	$0.10340	-0.5%	59.9	35.9	▼	67%	$10.9M	SELL	43%	1.1%	L1/S3	Doji		–	–	↑

Figure 1 — Scanner tab showing 18 coins after a scan, sorted by Pot% descending.

Column Reference

Column	Description
Symbol	Trading pair name. Double-click any row to open the full detail popup with candlestick chart and pre-calculated trade setup.
Price	Current last price in USDT from Binance live ticker.
24h%	Price change over last 24 hours. Green = up, Red = down. Strong negative = potential LONG bounce. Strong positive = SHORT candidate.
RSI	14-period RSI shown as mini bar + number. Below 40 = oversold → LONG signal. Above 60 = overbought → SHORT signal.
StRSI	Stochastic RSI — faster oscillator. Below 20 = strongly oversold. Above 80 = strongly overbought. More sensitive than regular RSI.
MACD ▲▼	▲ = MACD histogram positive (bullish momentum). ▼ = negative (bearish). Fresh crossovers score 3×, stale ones only 1×.
BB%	Bollinger Band position. 0% = price at lower band (LONG setup). 100% = at upper band (SHORT setup).
Vol 24h	24-hour volume in USDT. Must exceed Min Volume filter (default $1M) to appear in results.
Signal	STRONG BUY / BUY / STRONG SELL / SELL / NEUTRAL — based on multi-indicator scoring. See Section 7.
Pot%	Profit Potential composite score 0–100%. Green ≥70%, Yellow 40–69%. Sort by this to rank best opportunities.
Exp%	Expected price move based on ATR + volume. Higher = bigger expected swing.
L/S	Long/Short raw score e.g. L8/S2. The higher side wins. Maximum theoretical score ~13.
Pattern	Candlestick pattern: Hammer, Shooting Star, Bullish/Bearish Engulf, Vol Spike ↑↓, Doji, Squeeze, Uptrend, Downtrend.
Sparkline	Mini price chart of last 50 candles. Green line = up. Red line = down. Instant visual of recent momentum.
Age / Conf / 1H	Age: time since signal appeared (green <30s, yellow <5m, red = stale). Conf: confirmation count. 1H: 1-hour trend arrow ↑↓→.

Right-click Context Menu

Right-click any row in the Scanner to enter a trade or open the coin on Binance. The signal-matching side (LONG for BUY signals, SHORT for SELL signals) is highlighted with ★.

> How to enter a trade: Right-click the coin → select LONG or SHORT → review the confirm dialog with pre-filled Entry, SL, TP → set your USDT quantity → Confirm. The app switches to the Trades tab automatically.

Double-click: Full Detail Popup

Double-clicking any row opens a floating detail panel with a mini candlestick chart, full indicator readouts, support/resistance levels, and the complete pre-calculated trade setup. Press Esc or click outside to close the popup (Esc does NOT close the main app).

3 — Tab 2: Top Picks

Top Picks filters out NEUTRAL coins and presents only BUY and SELL candidates as rich cards. Fully scrollable — all qualifying coins are shown. Each card contains everything needed to make an entry decision without switching tabs.



Figure 2 — Top Picks tab showing LONG candidates (PIXEL, XAI, OPN, FET) and SHORT candidates below.

Card Layout — Row by Row

Row	Content
Row 1 — Header	Symbol name · Signal badge (STRONG BUY / BUY / etc.) · ⚡ Pot% score (green ≥70%) · Expected move % · 24h% change right-aligned
Row 2 — Quality bars	Score bar filled to winning-side pts/10 · RSI bar (green if <40, red if >60) · BB% bar (green near 0, red near 100) · Conf count right-aligned
Row 3 — Trade setup	Entry price · SL (red) · TP1 (green) · TP2 · R/R ratio · Sup% (distance to support) · Res% (distance to resistance)
Row 4 — Extras	MACD ▲/▼ direction + raw value · StRSI number · 1H timeframe trend arrow · Volume multiplier · Candlestick pattern name

> Sup / Res explained: Sup −1.0% = support is 1% below entry — price is sitting right on support, tight risk. Res +18.7% = resistance is 18.7% above — well beyond TP1 and TP2, room to run without being blocked.

4 — Tab 3: Config

All scan parameters, risk settings and UI preferences live here. Changes take effect when you click ✓ Apply Settings.



Figure 3 — Config tab with Scan Filters, Risk Management, UI Appearance, Alerts toggle and Export.

Settings Reference

Setting	Default	Description
Max Price ($)	$1.00	Only scan coins below this price. Keeps focus on sub-$1 high-momentum coins.
Min Volume (USDT)	$1,000,000	Minimum 24h USDT volume. Filters illiquid coins that are hard to exit quickly.
Interval	5m	Candle timeframe for all indicators. 5m = optimal for scalping. 1m = noisier, 15m = slower signals.
Top N Coins	30	How many coins to analyse per scan. More = slower but wider coverage of the market.
Candles to Fetch	50	Lookback window for all indicator calculations. Minimum 30 recommended.
Stop Loss %	3.0%	SL distance from entry. Used in all pre-calculated trade setups in Top Picks and detail popup.

Take Profit %	5.0%	TP1 distance. R/R = TP ÷ SL. Default 5÷3 = 1.67×. Always aim for R/R ≥ 1.5.
TP2 % (extended)	10.0%	Extended target for runners. Move SL to breakeven after TP1 is hit.
R/R Ratio	1.67× (auto)	Auto-calculated live as you change SL% or TP%. Read-only display.
Font Size	16px	Resize all UI text. Resize the window after changing to reflow column widths.

> 💡 R/R updates live as you change SL% or TP%. Never take trades below 1.0× R/R — the math works against you long-term. The default 1.67× means each winner recovers 1.67 losers.

Alerts Master Toggle & Export

The Alerts section contains a single ON/OFF toggle button. When green, all alert channels are active. Click to disable all alerts at once without changing individual channel settings.

The Export section lets you save the last scan results to a timestamped JSON file. Useful for offline analysis or logging.

5 — Tab 4: Alerts

Enable auto-scan so the app monitors Binance in the background while you do other things. Configure which signal types trigger notifications and which delivery channels are active.



Figure 4 — Alerts tab showing auto-scan config, notification channels and alert history log.

Auto-Scan Trigger Settings

Setting	Default	Description
Enable auto-scan	Off	Check to start background scanning. The status bar shows scan progress.
Scan interval	30s	How often to scan. 30–60s is practical. Shorter = more API calls.
Minimum signal	STRONG BUY	Only alert when a signal meets or exceeds this threshold.
Min Potential %	40%	Ignore signals below this Pot% score. Filters weak setups.
Min Exp Move %	5.0%	Ignore coins with low expected volatility. Filters illiquid, flat coins.

Notification Channels

Channel	Status	Notes
Sound alert	✓ On by default	Different tones for LONG vs SHORT via ffplay (Linux/macOS) or Windows audio.

Desktop notification	✓ On by default	System tray notification via notify-send. Critical urgency for STRONG signals.
Telegram bot	Off by default	Formatted message to your Telegram bot. Requires Bot Token + Chat ID from @BotFather.
WhatsApp via PicoClaw	Off by default	Routes via local PicoClaw bridge (Telegram→WhatsApp). Scan QR once, alerts forever.

Setting Up Telegram Alerts

Step 1: Create a Telegram bot

Open Telegram → message @BotFather → send /newbot → follow prompts → copy the Bot Token.

Step 2: Get your Chat ID

Message @userinfobot on Telegram → it replies with your numeric Chat ID.

Step 3: Enter credentials in the Alerts tab

Paste Bot Token + Chat ID into the Telegram fields → Apply Alert Settings → Test Alerts Now to verify.

> Visual alerts always fire regardless of channel settings: • Strong signal popup — floating panel with full trade setup appears over the app • Window flash — app background flashes green (BUY) or red (SELL) • Title bar flash — window title alternates signal + symbol for ~10 seconds • Alert log entry — every alert is appended to the history log in this tab

6 — Tab 5: Trades

Every trade you enter is tracked here with live unrealised P&L for open positions and cumulative statistics plus an equity curve for closed ones. All trades persist across sessions in ~/.crypto_scanner_trades.json



Figure 5 — Trades tab with one open SHORT trade (PIXEL), statistics panel and equity curve area.

How to Enter a Trade

Step 1: Find a signal in the Scanner tab

Look for STRONG BUY or STRONG SELL with Pot% ≥70% and a fresh Age (green).

Step 2: Right-click the coin → LONG or SHORT

The signal-matching side is highlighted with ★ in the context menu.

Step 3: Review the confirm dialog

Entry price, SL, TP1, and TP2 are pre-filled from config. Set your USDT quantity. The dialog shows estimated cost and risk in USDT.

Step 4: Confirm — app switches to Trades tab automatically

The trade is saved immediately to ~/.crypto_scanner_trades.json.

Trades Table Columns

Column	Description
Opened	Timestamp when the trade was entered.
Symbol	Trading pair (e.g. PIXELUSDT).
Side	LONG (green) or SHORT (red).
Entry $	Entry price at time of trade creation.
Qty	Position size in USDT.
SL $	Stop loss price level.
TP $	Take profit 1 price level.
Exit $	Live current price (~) for open trades, actual exit for closed.
P&L	Live unrealised P&L for open trades. Realised P&L for closed. Shown as % and USDT.
Status	OPEN (green badge) or CLOSED (dim). Closed trades show WIN/LOSS reason.

Auto SL/TP Hit Detection

> ⚡ After every scan cycle (manual or auto), current prices are checked against all open trade SL/TP levels. • Price crosses Stop Loss → trade auto-closed as LOSS. Critical desktop notification + SL sound fires. • Price crosses Take Profit → trade auto-closed as WIN. TP notification + sound fires. Set your levels and let auto-scan run. You will be alerted when levels are hit.

Action Buttons

Button	Action
✓ **Close Selected**	Close the selected trade at current market price. Records exit price and calculates final P&L.
✏️ **Edit Selected**	Edit entry price, stop loss, or take profit levels post-entry (e.g. move SL to breakeven after TP1).
× **Delete**	Remove the trade record entirely — does not affect any actual positions on Binance.
↓ **Export CSV**	Save all trade records to a timestamped CSV file for external analysis.

Trade Statistics Panel

The left panel shows live stats: Total trades · Open · Wins · Losses · Win rate · Avg win · Avg loss · Best trade · Worst trade · Profit Factor · Total P&L.

Profit Factor = total wins ÷ total losses. A value above 1.5 indicates a healthy edge. The equity curve on the right plots cumulative P&L across all closed trades.

7 — How Scoring Works

Every coin is scored independently for LONG and SHORT. The higher-scoring side wins and determines the signal — provided it clears a minimum margin over the other side. No machine learning, no black box — pure deterministic rules you can read in the source code.

Indicator Scoring Table

Indicator	LONG Points	SHORT Points	Max
RSI (14)	<25→+5 · <30→+4 · <35→+3 · <40→+2 · <45→+1	>75→+5 · >70→+4 · >65→+3 · >60→+2 · >55→+1	±5
Stoch RSI	<20→+2 · <40→+1	>80→+2 · >60→+1	±2
MACD	Positive + rising→+3 · Positive stale→+1	Negative + falling→+3 · Negative stale→+1	±3
Bollinger Band	pos<10%→+3 · <25%→+2 · <40%→+1	pos>90%→+3 · >75%→+2 · >60%→+1	±3
Pattern	Bullish pattern→+2 · Bearish pattern→−1 penalty	Bearish pattern→+2 · Bullish pattern→−1 penalty	±2
24h Momentum	24h<−10%→+1 (bounce candidate)	24h>15%→+2 · >8%→+1	±2

Signal Thresholds

Signal	Condition
STRONG BUY	Long score ≥ 6 AND margin over Short score ≥ 3
BUY	Long score ≥ 3 AND margin over Short score ≥ 2
STRONG SELL	Short score ≥ 6 AND margin over Long score ≥ 3
SELL	Short score ≥ 3 AND margin over Long score ≥ 2
NEUTRAL	Neither side clears the threshold — skip this coin

> 💡 MACD freshness is the key improvement introduced in v3 of the scanner. A freshly rising MACD histogram scores +3 — three times more than a stale positive one (+1). This eliminates signals that look good on paper but are based on old, fading momentum.

BB% Width Penalty

When the Bollinger Band width exceeds 12% (very high volatility, bands are wide apart), the BB% score contribution is halved. This prevents false signals during explosive moves where price can ride the

band for extended periods without a meaningful reversal.

8 — Full Workflow Example

A complete end-to-end example from opening the app to monitoring an active trade.

Step 1: First time: Configure your filters (Config tab)

Set Max Price ($1.00), Min Volume ($1,000,000), Interval (5m), SL% (3), TP% (5). Click Apply Settings. These settings persist across restarts in ~/.crypto_scanner_settings.ini.

Step 2: Enable auto-scan (Alerts tab)

Tick 'Enable auto-scan alerts', set interval to 30–120 seconds, set Minimum signal to STRONG BUY. Click Apply Alert Settings. The scanner now runs in the background.

Step 3: Hit ⚡ SCAN for an immediate scan

Watch the status bar fill with progress. Takes approximately 10–30 seconds depending on Top N setting. Results populate the Scanner table sorted by Pot% descending.

Step 4: Review the Top Picks tab

Look for cards with: Score bar ≥7/10 · Fresh Age (green) · RSI deeply extreme · BB% near 0 for LONG or near 100 for SHORT · Sup% distance small · Res% bigger than your TP%.

Step 5: Right-click the coin in Scanner → LONG or SHORT

The signal-matching side is highlighted with ★. Review the confirm dialog — entry, SL, TP1, TP2 are pre-filled. Set your USDT quantity. Check the live cost/risk hint. Click Confirm.

Step 6: Monitor in the Trades tab

The app auto-closes your trade when SL or TP is hit on the next scan cycle. You receive a notification. Or manually close anytime via right-click → Close at current price.

Step 7: Review your statistics

After several trades, check Win Rate and Profit Factor in the stats panel. Profit Factor above 1.5 = healthy edge. The equity curve shows your cumulative P&L trend.

> ⚠️ Decision-support tool, not a trading bot. Trades are recorded manually by you. SL/TP hit detection is informational — execute actual trades on Binance yourself. Always manage your own risk. Past signal quality does not guarantee future results.

9 — Keyboard & Mouse Shortcuts

Key / Action	Effect
Q	Close the application
Ctrl + Q	Close the application
Esc	Close the detail popup only — does NOT close the main app
Double-click row (Scanner)	Open full detail popup (chart + all indicators + trade setup)
Right-click row (Scanner)	Context menu: LONG / SHORT / Open on Binance / View Details
Right-click row (Trades)	Context menu: Close at market / Edit levels / Open on Binance / Delete
Click column header	Sort ascending; click again to reverse to descending
Drag column edge	Resize column — column locks to your manual width after dragging
⚙ Cols button (top bar)	Reset all column widths back to automatic proportional sizing
Mouse wheel (Top Picks tab)	Scroll through candidate cards

File Locations

File	Location & Purpose
Settings	~/.crypto_scanner_settings.ini — all Config and Alert settings, saved on app close
Trades	~/.crypto_scanner_trades.json — all trade records, loaded automatically on startup
Alert log	In-memory only — clears when app closes. Export individual alerts from the Alerts tab.
Scan export	Timestamped JSON file in your current directory when using Export Last Scan to JSON.
Trade CSV	Timestamped CSV file in your current directory when using Export CSV button.

> Crypto Scalp Scanner v9 · Binance Spot Public API · PyQt6 · Python 3.10+ · No API key required