#### 张向宇 18281059 安全1801

- 一、安装和配置Docker
  - 1) 安装Docker
  - 2) 配置阿里云加速
  - 3) 配置Docker图形化界面 portainer
  - 4) 常用配置和工具命令
  - 5) 配置Ubuntu Docker
- 二、安装和配置Telnet
- 三、安装和配置VNC
- 四、安装和配置内网穿透服务
  - 1) 购买并配置具有公网的VPS
  - 2) 在VPS部署FRP服务
- 五、编写并测试WWW服务器
  - 1) 编写代码
  - 2) 本地测试
  - 3) 使用内网穿透变成公网可访问服务器
- 六、遇到的问题和解决方案
  - 1) Docker daemon socket权限不足
  - 2) Docker中Ubuntu更换清华源镜像信任出错

## 一、安装和配置Docker

脚本安装是最推荐的方式,只需要输入下面的命令,等待自动安装好即可

## 1) 安装Docker

先安装 curl 工具

```
sudo apt install curl
```

然后获取脚本并通过管道工具直接执行

```
sudo curl -sSL https://get.docker.com | sh
```

然后测试Docker

```
sudo docker run hello-world
```

获取到如下信息则说明Docker安装成功

```
zxy@ubuntu:~/Desktop/QTL/ZXYCalc/ZXY_Caculator$ sudo docker run hello-world
Unable to find image 'hello-world:latest' locally
latest: Pulling from library/hello-world
0e03bdcc26d7: Pull complete
Digest: sha256:d58e752213a51785838f9eed2b7a498ffa1cb3aa7f946dda11af39286c3db9a9
Status: Downloaded newer image for hello-world:latest
Hello from Docker!
This message shows that your installation appears to be working correctly.
```

```
    To generate this message, Docker took the following steps:

            The Docker client contacted the Docker daemon.
            The Docker daemon pulled the "hello-world" image from the Docker Hub. (amd64)
            The Docker daemon created a new container from that image which runs the executable that produces the output you are currently reading.
            The Docker daemon streamed that output to the Docker client, which sent it to your terminal.

    To try something more ambitious, you can run an Ubuntu container with:

            docker run -it ubuntu bash

    Share images, automate workflows, and more with a free Docker ID:

            https://hub.docker.com/

    For more examples and ideas, visit:

            https://docs.docker.com/get-started/
```

### 2) 配置阿里云加速

- 进入阿里云镜像加速页面: <a href="https://cr.console.aliyun.com/#/accelerator">https://cr.console.aliyun.com/#/accelerator</a>
- 修改/etc/docker/daemon.json文件配置,没有则新建:

```
o {
    "registry-mirrors": ["加速器地址"]
}
```

- 重启daemon: systemctl daemon-reload
- 重启docker服务: systemctl restart docker

### 3) 配置Docker图形化界面 portainer

- 下载portainer: sudo docker pull portainer/portainer
- 创建portainer容器: sudo docker volume create portainer\_data
- 运行portainer: sudo docker run -d -p 9000:9000 --name portainer --restart always -v /var/run/docker.sock:/var/run/docker.sock -v portainer\_data:/data portainer/portainer
- 之后查询本机IP地址,通过URL = IP: 9000 进入图形化管理界面

### 4) 常用配置和工具命令

```
#查看 Docker 版本
docker -v
sudo docker pull 仓库/镜像:版本(留空的话默认为 latest)
sudo docker run 加参数,用来创建容器
#查看运行容器
sudo docker ps
#查看所有下载的镜像
sudo docker images
#进入容器终端
sudo docker exec -i -t ha /bin/bash
#实时查看10行的 ha 日志
sudo docker logs -f -t --tail 10 ha
#重启 systemctl 守护进程
sudo systemctl daemon-reload
```

```
#设置 Docker 开机启动
sudo systemctl enable docker
#开启 Docker 服务
sudo systemctl start docker
#搜索镜像
docker search [option] keyword
```

## 5) 配置Ubuntu Docker

#### • 搜索镜像

O zxy@ubuntu:/etc/docker\$ sudo docker search ubuntu
[sudo] password for zxy:

NAME DESCRIPTION

STARS OFFICIAL

AUTOMATED

ubuntu Ubuntu is a
Debian-based Linux operating sys... 11089 [OK]

#### • 下载镜像

zxy@ubuntu:/etc/docker\$ docker pull ubuntu
Using default tag: latest
latest: Pulling from library/ubuntu
692c352adcf2: Pull complete
97058a342707: Pull complete
2821b8e766f4: Pull complete
4e643cc37772: Pull complete
Digest:
sha256:55cd38b70425947db71112eb5dddfa3aa3e3ce307754a3df2269069d2278ce47
Status: Downloaded newer image for ubuntu:latest
docker.io/library/ubuntu:latest

### • 运行容器

zxy@ubuntu:/etc/docker\$ docker images REPOSITORY TAG IMAGE ID CREATED SIZE ubuntu latest adafef2e596e 27 hours 73.9MB portainer/portainer latest cd645f5a4769 5 weeks 79.1MB ago hello-world bf756fb1ae65 6 months latest 13.3kB zxy@ubuntu:/etc/docker\$ docker run -it ubuntu /bin/bash root@d880c4a6adf1:/#

# 二、安装和配置Telnet

• 安装客户端: sudo apt install telnet

• 安装服务程序: sudo apt-get install xinetd

• 测试命令: netstat -a | grep telnet

LISTEN

- 重启机器或重启网络服务: sudo /etc/init.d/xinetd restart
- 查看本虚拟机IP地址

```
zxy@ubuntu:/etc/docker$ ifconfig
docker0: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
       inet 172.17.0.1 netmask 255.255.0.0 broadcast 172.17.255.255
       inet6 fe80::42:ccff:fe77:39fc prefixlen 64 scopeid 0x20<link>
       ether 02:42:cc:77:39:fc txqueuelen 0 (Ethernet)
       RX packets 10955 bytes 5423270 (5.4 MB)
       RX errors 0 dropped 0 overruns 0 frame 0
       TX packets 15122 bytes 45547780 (45.5 MB)
       TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
ens33: flags=4163<UP, BROADCAST, RUNNING, MULTICAST> mtu 1500
       inet 192.168.159.132 netmask 255.255.255.0 broadcast
192.168.159.255
       inet6 fe80::1d49:cffb:d73b:cd58 prefixlen 64 scopeid
0x20<1ink>
       ether 00:0c:29:c9:48:cd txqueuelen 1000 (Ethernet)
        RX packets 1113264 bytes 1535931210 (1.5 GB)
       RX errors 0 dropped 0 overruns 0 frame 0
       TX packets 310101 bytes 26061308 (26.0 MB)
       TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
10: flags=73<UP,LOOPBACK,RUNNING> mtu 65536
       inet 127.0.0.1 netmask 255.0.0.0
        inet6 ::1 prefixlen 128 scopeid 0x10<host>
       loop txqueuelen 1000 (Local Loopback)
       RX packets 6956 bytes 779881 (779.8 KB)
       RX errors 0 dropped 0 overruns 0 frame 0
       TX packets 6956 bytes 779881 (779.8 KB)
       TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
veth7f64c72: flags=4163<UP, BROADCAST, RUNNING, MULTICAST> mtu 1500
       inet6 fe80::9421:8eff:fe47:ad45 prefixlen 64 scopeid
0x20<1ink>
       ether 96:21:8e:47:ad:45 txqueuelen 0 (Ethernet)
       RX packets 1398 bytes 5024914 (5.0 MB)
       RX errors 0 dropped 0 overruns 0 frame 0
       TX packets 2747 bytes 691877 (691.8 KB)
       TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

- Windows下测试Telnet成功:
  - o telnet 192.168.159.132

```
O Ubuntu 20.04 LTS
ubuntu login: zxy

Password:

Welcome to Ubuntu 20.04 LTS (GNU/Linux 5.4.0-40-generic x86_64)
```

# 三、安装和配置VNC

• 因为貌似Ubuntu的桌面环境Gnome与VNC存在兼容性问题,安装桌面环境Xfce


- o sudo apt-get install xfce4 xfce4-goodies
- 安装VNC服务端
  - sudo apt-get install tightvncserver
- 设置VNC连接密码设置以及生成配置文件
  - 。 首先执行 vncserver 命令来设置 VNC 连接密码以及生成 VNC 配置文件

```
You will require a password to access your desktops.
Password:
Verify:
```

- 配置文件在下面目录里面: /home/your\_username/.vnc/
- 第一次运行 vncserver 命令会自动启动VNC实例,分配到:1上,对应端口为5901 (端口5901=5900+1,如果是:2,则端口为5902,以此类推)。由于要配置VNC,所以先要关闭VNC实例
  - vncserver -kill :1
- 配置VNC
  - 。 要配置的文件为 xstartup, 该文件在 \$HOME/.vnc 里面
  - 首先备份原始配置文件: mv ~/.vnc/xstartup ~/.vnc/xstartup.bak
  - o 然后创建新的配置文件: touch ~/.vnc/xstartup
  - 。 编辑该文件,添加以下内容:
    - #!/bin/sh # Uncomment the following two lines for normal desktop: unset SESSION MANAGER unset DBUS\_SESSION\_BUS\_ADDRESS # exec /etc/X11/xinit/xinitrc [ -x /etc/vnc/xstartup ] && exec /etc/vnc/xstartup [ -r \$HOME/.Xresources ] && xrdb \$HOME/.Xresources xsetroot -solid grey vncconfig -iconic & x-terminal-emulator -geometry 80x24+10+10 -ls -title "\$VNCDESKTOP Desktop" & #x-window-manager & #gnome-session & x-session-manager & xfdesktop & xfce4-panel & xfce4-menu-plugin & xfsettingsd & xfconfd & xfwm4 &
  - o 为了保证VNC配置文件能够生效,赋予该文件执行权限: chmod +x ~/.vnc/xstartup
- VNC连接

启动VNC实例: vncserver查看端口开启情况: ss -1tn

。 使用VNC Viewer连接成功



# 四、安装和配置内网穿透服务

由于我家使用的互联网运营商是中国电信,没有直接给我分配公网IP,我需要进行内网穿透才能让配合的同学访问我的主机,我在这里选用的内网穿透软件是FRP

## 1) 购买并配置具有公网的VPS

这里我选择腾讯云的广州区EPYC云服务器



### 2) 在VPS部署FRP服务

- 下载地址: https://github.com/fatedier/frp/releases
- 配置服务端 (公网服务器) ,首先删掉frpc、frpc.ini两个文件,然后再进行配置, vi ./frps.ini

- 保存然后启动服务./frps -c ./frps.ini,这是前台启动,后台启动命令为nohup ./frps -c ./frps.ini &
- 配置客户端(内网服务器),首先删掉frps、frps.ini两个文件,然后再进行配置, vi./frpc.ini

```
common]
    server_addr = 42.194.197.68
    server_port = 5443
    token = nA9rqFk76s8lusqH

[ssh]
    type = tcp
    local_ip = 127.0.0.1
    local_port = 22
    remote_port = 6000
```

- 测试SSH服务
  - 。 测试环境: 手机目前使用的是移动网络, 与虚拟机不在同一网段内, 属于外网环境



○ 配置SSH参数,使用的IP是中间代理服务器的IP,端口是之前设置的映射端口

	类型:	SSH	~
	地址:	42.194.197.68	
•	认证:	syc	~
	高级设置		
	端口:	6000	

。 连接成功,说明内网穿透实验成功

```
Welcome to Ubuntu 20.04 LTS (GNU/Linux 5.4.0-40-generic x86_64)

* Documentation: https://help.ubuntu.com

* Management: https://landscape.canonical.com

* Support: https://lubuntu.com/advantage

* "If you've been waiting for the perfect Kubernetes dev solution for macOS, the wait is over. Learn how to install Microk8s on macOS."

https://www.techrepublic.com/article/how-to-install-microk8s-on-macos/
1 update can be installed immediately.
1 of these updates is a security update.
To see these additional updates run: apt list --upgradable

Your Hardware Enablement Stack (HME) is supported until April 2025.
Last login: Med Jul 8 06:39:48 2020 from 127.0.0.1

syc@ubuntu:-$ ||
```

• 配置Telnet和VNC端口映射服务

```
[common]
server\_addr = 42.194.197.68
server_port = 5443
token = nA9rqFk76s8lusqH
[ssh]
type = tcp
local_ip = 127.0.0.1
local_port = 22
remote_port = 6000
[telnet]
type = tcp
local_ip = 127.0.0.1
local_port = 23
remote_port = 6003
[vnc]
type = tcp
local_ip = 127.0.0.1
local_port = 5901
remote_port = 6002
```

- 与同学一同测试Telnet服务
  - o PS C:\Users\syc> telnet 42.194.197.68:6003

```
O Ubuntu 20.04 LTS ubuntu login: zxy


Password:

Welcome to Ubuntu 20.04 LTS (GNU/Linux 5.4.0-40-generic x86_64)
```


• 使用 netstat -a 查看连接情况


```
tcp 0 0 0.0.0.0:ssh 0.0.0.0:* LISTEN
tcp 0 0 0 W-0-15-ubuntu:47964 169.254.0.55:5574 ESTABLISHED
tcp 0 0 WW-0-15-ubuntu:59h 125.73.91.199:24259 ESTABLISHED
tcp 0 0 WW-0-15-ubuntu:59h 125.73.91.199:24259 ESTABLISHED
tcp 0 0 WW-0-15-ubuntu:59h 125.73.91.199:24259 ESTABLISHED
tcp6 0 0 [::]:6443 [::]:* LISTEN
tcp6 0 0 [::]:xl11 [::]:* LISTEN
tcp6 0 0 [::]:xl12-2 [::]:* LISTEN
tcp6 0 0 [::]:xl15-5 [::]:xl15-5 [::]:* LISTEN
tcp6 0 0 [::]:xl15-5 [::]:xl15-5 [::]:* LISTEN
tcp6 0 0 [::]:xl15-5 [::]:xl15-5 [::]
```

- o 获得同学的IP: 116.11.152.252, 经过验证同样是同学的IP
- 。 同学终端切换成功:



• 与同学一同测试VNC服务





# 五、编写并测试WWW服务器

### 1) 编写代码

我使用的是用Go语言编写的轻量级HTTP服务程序,源代码:

```
package main

import (
    "fmt"
    "net/http"
    "path/filepath"
)


func main() {
    p, _ := filepath.Abs(filepath.Dir("./Resource"))//是获取当前可执行程序所在的绝对

路径
    http.Handle("/", http.FileServer(http.Dir(p)))//是开启一个文件服务器,使用当前可执

f文件所在的路径
    err := http.ListenAndServe(":8080", nil)//是监听8080端口并开启文件服务器
    if err != nil {
        fmt.Println(err)
    }
}
```

## 2) 本地测试

在Linux虚拟机运行本地测试:



# 3) 使用内网穿透变成公网可访问服务器


配置FRP文件:

```
[common]
server\_addr = 42.194.197.68
server_port = 5443
token = nA9rqFk76s8lusqH
[ssh]
type = tcp
local_ip = 127.0.0.1
local_port = 22
remote\_port = 6000
[telnet]
type = tcp
local_ip = 127.0.0.1
local_port = 23
remote_port = 6003
[vnc]
type = tcp
local_ip = 127.0.0.1
local_port = 5901
remote\_port = 6002
[MYHTTP]
type = tcp
local_ip = 127.0.0.1
local\_port = 8080
remote\_port = 6005
```

### 外网成功:



下载成功:



# 六、遇到的问题和解决方案

## 1) Docker daemon socket权限不足

运行docker出现以下报错:

```
docker: Got permission denied while trying to connect to the Docker daemon socket at unix:///var/run/docker.sock: Post http://%2Fvar%2Frun%2Fdocker.sock/v1.38/containers/create: dial unix /var/run/docker.sock: connect: permission denied.
```

### 出现上面问题是因为:

```
Manage Docker as a non-root user
即: 管理Docker的不是root用户
```

方案一:使用sudo获取管理员权限,运行docker命令方案二:添加docker group组,将用户添加进去

```
zxy@ubuntu:~$ sudo groupadd docker #添加docker用户组 groupadd: "docker"组已存在 zxy@ubuntu:~$ sudo gpasswd -a $USER docker #将登陆用户加入到docker用户组中 正在将用户"syc"加入到"docker"组中 zxy@ubuntu:~$ newgrp docker #更新用户组 zxy@ubuntu:~$ docker ps #测试当前用户是否可以正常使用docker命令 CONTAINER ID IMAGE COMMAND CREATED STATUS PORTS NAMES
```

## 2) Docker中Ubuntu更换清华源镜像信任出错

There was a problem with the certificates installed in this base image. I managed to fix it by install ca-certificates:

```
sudo apt install ca-certificates
```