# COMP2310/COMP6310 Systems, Networks, & Concurrency


Convener: Prof John Taylor

# **Today**

- Address spaces
- VM as a tool for caching
- VM as a tool for memory management
- VM as a tool for memory protection
- Address translation


**Acknowledgement of material:** With changes suited to ANU needs, the slides are obtained from Carnegie Mellon University: https://www.cs.cmu.edu/~213/

## A System Using Physical Addressing



 Used in "simple" systems like embedded microcontrollers in devices like cars, elevators, and digital picture frames

# A System Using Virtual Addressing



- Used in all modern servers, laptops, and smart phones
- One of the great ideas in computer science

## **Address Spaces**

■ Linear address space: Ordered set of contiguous non-negative integer addresses:

$$\{0, 1, 2, 3 \dots \}$$

- Virtual address space: Set of  $N = 2^n$  virtual addresses  $\{0, 1, 2, 3, ..., N-1\}$
- Physical address space: Set of  $M = 2^m$  physical addresses  $\{0, 1, 2, 3, ..., M-1\}$

# Why Virtual Memory (VM)?

#### Uses main memory efficiently

Use DRAM as a cache for parts of a virtual address space

#### Simplifies memory management


Each process gets the same uniform linear address space

#### Isolates address spaces

- One process can't interfere with another's memory
- User program cannot access privileged kernel information and code


# **Today**

- Address spaces
- VM as a tool for caching
- VM as a tool for memory management
- VM as a tool for memory protection
- Address translation



## VM as a Tool for Caching

- Conceptually, virtual memory is an array of N contiguous bytes stored on disk.
- The contents of the array on disk are cached in physical memory (DRAM cache)
  - These cache blocks are called pages (size is P = 2<sup>p</sup> bytes)



#### **DRAM Cache Organization**


- DRAM cache organization driven by the enormous miss penalty
  - DRAM is about 10x slower than SRAM
  - Disk is about 10,000x slower than DRAM

#### Consequences

- Large page (block) size: typically 4 KB, sometimes 4 MB
- Fully associative
  - Any VP can be placed in any PP
  - Requires a "large" mapping function different from cache memories
- Highly sophisticated, expensive replacement algorithms
  - Too complicated and open-ended to be implemented in hardware
- Write-back rather than write-through


# **Enabling Data Structure: Page Table**

- A page table is an array of page table entries (PTEs) that maps virtual pages to physical pages.
  - Per-process kernel data structure in DRAM




#### Page Hit

Page hit: reference to VM word that is in physical memory (DRAM cache hit)




#### Page Fault


Page fault: reference to VM word that is not in physical memory (DRAM cache miss)




Page miss causes page fault (an exception)




- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)



- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)




- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)
- Offending instruction is restarted: page hit!



#### **Allocating Pages**

Allocating a new page (VP 5) of virtual memory.



## Locality to the Rescue Again!


- Virtual memory seems terribly inefficient, but it works because of locality.
- At any point in time, programs tend to access a set of active virtual pages called the working set
  - Programs with better temporal locality will have smaller working sets
- If (working set size < main memory size)</p>
  - Good performance for one process after compulsory misses
- If (SUM(working set sizes) > main memory size)
  - Thrashing: Performance meltdown where pages are swapped (copied) in and out continuously

# **Today**

- Address spaces
- VM as a tool for caching
- VM as a tool for memory management
- VM as a tool for memory protection
- Address translation


#### VM as a Tool for Memory Management

- Key idea: each process has its own virtual address space
  - It can view memory as a simple linear array
  - Mapping function scatters addresses through physical memory
    - Well-chosen mappings can improve locality



# VM as a Tool for Memory Management

- Simplifying memory allocation
  - Each virtual page can be mapped to any physical page
  - A virtual page can be stored in different physical pages at different times
- Sharing code and data among processes
  - Map virtual pages to the same physical page (here: PP 6)




# Simplifying Linking and Loading

#### Linking

- Each program has similar virtual address space
- Code, data, and heap always start at the same addresses – they are set by the compiler.

#### Loading

- execve allocates virtual pages for .text and .data sections & creates PTFs marked as invalid
- The .text and .data sections are copied, page by page, on demand by the virtual memory system




# **Today**

- Address spaces
- VM as a tool for caching
- VM as a tool for memory management
- VM as a tool for memory protection
- Address translation

#### VM as a Tool for Memory Protection

- Extend PTEs with permission bits
- MMU checks these bits on each access



# **Today**

- Address spaces
- VM as a tool for caching
- VM as a tool for memory management
- VM as a tool for memory protection
- Address translation

#### **VM Address Translation**

- Virtual Address Space
  - $V = \{0, 1, ..., N-1\}$
- Physical Address Space
  - $P = \{0, 1, ..., M-1\}$
- Address Translation
  - MAP:  $V \rightarrow P \cup \{\emptyset\}$
  - For virtual address a:
    - MAP(a) = a' if data at virtual address a is at physical address a' in P
    - $MAP(a) = \emptyset$  if data at virtual address a is not in physical memory
      - Either invalid or stored on disk

# **Summary of Address Translation Symbols**

#### Basic Parameters

- N = 2<sup>n</sup>: Number of addresses in virtual address space
- M = 2<sup>m</sup>: Number of addresses in physical address space
- P = 2<sup>p</sup> : Page size (bytes)


#### Components of the virtual address (VA)

- TLBI: TLB index
- **TLBT**: TLB tag
- VPO: Virtual page offset
- VPN: Virtual page number


#### Components of the physical address (PA)

- PPO: Physical page offset (same as VPO)
- PPN: Physical page number

# Address Translation With a Page Table




#### **Address Translation: Page Hit**




- 1) Processor sends virtual address to MMU
- 2-3) MMU fetches PTE from page table in memory
- 4) MMU sends physical address to cache/memory
- 5) Cache/memory sends data word to processor

## **Address Translation: Page Fault**



- 1) Processor sends virtual address to MMU
- 2-3) MMU fetches PTE from page table in memory
- 4) Valid bit is zero, so MMU triggers page fault exception
- 5) Handler identifies victim (and, if dirty, pages it out to disk)
- 6) Handler pages in new page and updates PTE in memory
- 7) Handler returns to original process, restarting faulting instruction

### **Integrating VM and Cache**




VA: virtual address, PA: physical address, PTE: page table entry, PTEA = PTE address

# Speeding up Translation with a TLB


- Page table entries (PTEs) are cached in L1 like any other memory word
  - PTEs may be evicted by other data references
  - PTE hit still requires a small L1 delay
- Solution: Translation Lookaside Buffer (TLB)
  - Small set-associative hardware cache in MMU
  - Maps virtual page numbers to physical page numbers
  - Contains complete page table entries for small number of pages

# Accessing the TLB

MMU uses the VPN portion of the virtual address to access the TLB:




#### **TLB Hit**



#### A TLB hit eliminates a memory access

#### **TLB Miss**



#### A TLB miss incurs an additional memory access (the PTE)

Fortunately, TLB misses are rare. Why?


## **Multi-Level Page Tables**

#### Suppose:

4KB (2<sup>12</sup>) page size, 48-bit address space, 8-byte PTE


#### Problem:

- Would need a 512 GB page table!
  - $2^{48} * 2^{-12} * 2^3 = 2^{39}$  bytes
- Common solution: Multi-level page table
- Example: 2-level page table
  - Level 1 table: each PTE points to a page table (always memory resident)
  - Level 2 table: each PTE points to a page (paged in and out like any other data)




Level 2

#### A Two-Level Page Table Hierarchy



# **Translating with a k-level Page Table**



#### **Summary**

#### Programmer's view of virtual memory

- Each process has its own private linear address space
- Cannot be corrupted by other processes

#### System view of virtual memory

- Uses memory efficiently by caching virtual memory pages
  - Efficient only because of locality
- Simplifies memory management and programming
- Simplifies protection by providing a convenient interpositioning point to check permissions