# CSCI 3753 Operating Systems

## **Memory Management**Working Set and Memory-Mapped Files

Chapters 8 and 9

Lecture Notes By
Shivakant Mishra
Computer Science, CU-Boulder

**Last Update: 04/03/14** 

#### Allocation of Memory Frames

- How many frames does each process get allocated? How many frames does the OS get allocated versus user processes?
- Variety of policies:
  - based on number of frames
  - based on whether frames are allocated locally or globally

#### **Allocation Policies**

#### 1. Equal allocation

- split m frames equally among n process
- m/n frames per process
- problem: doesn't account for size of processes,
   e.g. a large database process versus a small client process whose size is << m/n</li>
- needs to be adaptive as new process enter and the value of n fluctuates

#### 2. Proportional allocation

- allocate the number of frames relative to the size of each process
- Let  $S_i$  = size of process  $P_i$
- S =  $\Sigma$  S<sub>i</sub>
- Allocate  $a_i = (S_i/S) * m$  frames to process  $P_i$
- proportion a<sub>i</sub> can vary as new processes start and existing processes finish
- Also, if size is based on the code size, or address space size, then that is not necessarily the number of pages that will be used by a process

#### 3. Minimum # frames:

- determine the minimum # of frames to allocate to each process to run. Ideally, this is just one page, i.e. the page in which the program counter is currently executing.
- In practice, some CPUs support complex instructions.
  - multi-address instructions. Each address could belong to a different page.
  - Also, there can be multiple levels of indirection in the addressing, i.e. pointers. Each such level of indirection could result in a different page being accessed in order to execute the current instruction. Up to N levels of indirection may be supported, which means may need up to N pages as the minimum.

## Working Set Model

- Multiprogramming Environment
  - All processes share the limited number of page frames available.
  - Multiprogramming vs CPU throughput
    - Increase in the degree of multiprogramming  $\rightarrow$  Increase in CPU utilization.
    - Increase in the degree of multiprogramming → Less number of page frames per process → Increase in the number of page faults → Decrease in CPU utilization.

#### Thrashing

• Most of the CPU time is spent in swapping processes between disk and main memory.

<*Figure*>

• How can we maximize CPU utilization, but avoid thrashing?

- How much memory (number of page frames) should be allocated to a process?
  - Fault rate must be "tolerable"
  - Will change according to the phase of process
- Contemporary models are based on working set

## Working Set

- Working set of a process is the set of pages that the process is currently using
  - Determined by principle of locality of reference.
- To reduce the # of page faults, preload the working set of a process before a process runs.
  - Prepaging as opposed to demand paging.

## Working Set

- w(t, t-T): set of pages accessed in past T time units.
- T is adjusted dynamically to keep the # of page faults between a low and a high thresholds
  - − # of page faults exceed the high threshold: increase T
     → decrease the degree of multiprogramming.
  - − # of page faults fall below the low threshold: decrease
     T → increase the degree of multiprogramming.

## Working Set Principle

A process runs only if its working set is in memory.

## Thrashing

- Instead of using a working set model, just directly measure the page fault frequency (PFF)
  - When PFF > upper threshold, then increase the # frames allocated to this process
  - When PFF < lower threshold, then decrease the # frames allocated to this process (it doesn't need so many frames)
  - Windows NT used a version of this approach

#### Memory-Mapped Files

- Map some parts of a file on disk to pages of virtual memory
  - normally, each read/write from/to a file requires a system call plus file manager involvement plus reading/writing from/to disk
  - programmer can improve performance by copying part of or entire file into a local buffer, manipulating it, then writing it back to disk
    - this requires manual action on the part of the programmer
  - instead, it would be faster and simpler if the file could be loaded into memory (almost) transparently so that reads/writes take place from/ to RAM
  - use the virtual memory mechanism to map (parts of) files on disk to pages in the logical address space

#### Steps for memory-mapping a file

- 1. Obtain a handle to a file by creating or opening it
- 2. Reserve virtual addresses for the file in your logical address space
- 3. Declare a (portion of a) file to be memory mapped by establishing a mapping between the file and your virtual A.S. using an OS function like mmap()
  - void \* mmap(void \*start, size\_t length, int prot, int flags, int fd, off\_t offset)
    - map length bytes beginning at offset into file fd, preferably at address start (hint only), prot = R/W/X/no access, flags = maps\_fixed, map\_shared, map\_private
    - returns pointer to mmap'ed area
- 4. When file is first accessed, it's demand paged into physical memory
- 5. Subsequent read/write accesses to (that portion of) the file are served by physical memory

Memory-Mapped Files P2's P1's address space address space P2's P1's page table page table F F wdate F Disk F

#### Advantages of Memory-Mapped Files

- After the first access, all subsequent reads/ writes from/to a file (in memory) are fast
- Multiple processes can map the same file concurrently and share efficiently, as shown in the previous figure
  - In Windows, this mapping mechanism is also used to create shared memory between processes and is the preferred memory for sharing information among address spaces
  - on Linux, have separate mmap() and shared memory calls, e.g. shmget() and shmat()

#### Memory-Mapped I/O (vs. Files)

- Similar behavior to memory-mapped files
- Memory-mapped I/O maps device registers (instead of file pages) to memory locations
  - reads/writes from/to these memory addresses are easy and are automatically caught by the MMU (just as for mem-mapped files), causing the data to be automatically sent from/to the I/O devices
  - e.g. writing to a display's memory-mapped frame buffer, or reading from a memory-mapped serial port

#### Memory Management System Calls

- Two important system calls for memory allocation
  - brk( ) and mmap ()
- brk() sets the end of the data segment, which is also the end of heap
- sbrk() adds a displacement
- Both brk() and sbrk() extend heap
- mmap() creates a new mapping in the virtual address space of the calling process
  - Typically used for mapping files or devices in memory

#### malloc()

- Calls sbrk() to get the memory to allocate in the heap
- malloc is more efficient than allocating memory using brk() or sbrk()
  - malloc() does buffering
  - A malloc ( ) call does not always invoke sbrk( )
  - When it calls sbrk() it calls it with a large number

#### Virtual Memory

- getconf PAGESIZE
- getpagesize()
- pmap command: memory map of a process
- getrlimit() and setrlimit()
  - Process virtual memory size limit
  - Max CPU time
  - Max data segment size
  - Max file size

**—** ...