- Samba គឺជា Service មួយមានដែលអាចអនុញ្ញាត្តិអោយ Window ធ្វើការទំនាក់ទំនងមកកាន់ Linux បានហើយមានតួនាទីជាច្រើនដូចជា File Server, Print Server, Domain Controller, និងជា Member of Window...ជាដើម។
- Samba Domain Controller ជាចំនុចកណ្តាលមួយដែលវាធ្វើការគ្រប់គ្រង់ទៅលើធនធានផ្សេងៗដូចជា User, Computer, Contact, OU, Group, Group Policy...
- Samba File Sharing: យើងអាចធ្វើការចែករំលែកទិន្នន័យទៅម៉ាស៊ីន Client អាចប្រើប្រាស់បានដូច ជាFile Sharing, Printer Sharing....
- ដើម្បីធ្វើក្រូវតំលើង Package ឈ្មោះ Samba ដោយប្រើនូវដូចខាងក្រោម

Scenario

In this tutorial, we use two systems as described below

Samba server:

Operating system : CentOS 6.x

Hostname: CentosServer

IP Address: 192.168.1.50/24

Samba client:

Operating system: Windows 7 Professional

Hostname: client

IP Address: 192.168.1.51/24

1- Install Package

#yum install samba samba-client samba-common

2- Create sharing folder

#mkdir -p /home/samba/share

#chmod –R 777 /home/samba/share

3- Backup file smb.conf before edit

#cp /etc/samba/smb.conf /etc/samba/smb.conf.backup

4- Edit file smb.conf

```
#vim /etc/samba/smb.conf
workgroup = WORKGROUP
[sharename]
        comment = Insert a comment here
       path = /Samba/Share/
        browsable = yes #show ShareName
        guest ok = yes #allow anonymous
       read only = no
        create mask = 0777
        directory mask = 0777
```

5- Start samba service

#service smb start

6- To start samba service automatically while booting

#chkconfig smb on

7- To check service samba

#service smb status

8- Samba Testing

#testparm

9- Disable SELINUX

#vim /etc/sysconfig/selinux

SELINUX=disabled

10 – In casse Selinux not disable

#chcon -Rt samba_share_t/home/samba/anyone/

11 - Disable firewall

Type the following command as the root user to disable firewall for IPv4:

service iptables save

service iptables stop

chkconfig iptables off

#service iptables status

12- Testing

Window client: click start → Run and enter the samba server IP

របៀបកំឡើង Samba File Server (Configure a authenticated share

1- Configure file smb.conf

#vim /etc/samba/smb.conf

[public]	[ADMIN-Dept]	[ACCOUNT-Dept]
path = /home/samba/public	path = /home/samba/admins	path = /home/samba/accounts
browsable = yes	browsable = yes	browsable = yes
guest ok =yes	guest ok = no	guest ok = no
writable = yes	writable = yes	writable = yes
create mask = 0644	create mask = 0660	create mask = 0660
directory mask = 0755	directory mask = 0770	directory mask = 0770
	force group = +admin	force group = +account

```
របៀបកំឡើង Samba File Server (Configure a authenticated share
```

2- Create Sharing folder

#mkdir /home/samba/public

#chmod 777 /home/samba/pubic

#mkdir /home/samba/admin

#chmod 777 /home/samba/admin

#mkdir /home/samba/account

#chmod 777 /home/samba/account

```
របៀបកំឡើង Samba File Server (Configure a authenticated share
```

3- Create group and user

#groupadd public

#groupadd admin

#groupadd account

#useradd -m pany -g public

#useradd -m ada -g admin

#useradd -m aca -g account

```
របៀបតំឡើង Samba File Server (Configure a authenticated share
```

4- Add user into samba

#smbpasswd -a pany

type: new password

#smbpasswd -a ada

type: new password

#smbpasswd -a aca

type: new password

5- Start samba service

#service smb start

6- To start samba service automatically while booting

#chkconfig smb on

7- To check service samba

#service smb status

8- Samba Testing

#testparm

9- Disable SELINUX

#vim /etc/sysconfig/selinux

SELINUX=disabled

10 – In casse Selinux not disable

#chcon -Rt samba_share_t/home/samba/anyone/

11 - Disable firewall

Type the following command as the root user to disable firewall for IPv4:

service iptables save

service iptables stop

chkconfig iptables off

#service iptables status

12- Testing

Window client: click start → Run and enter the samba server IP