

Red Hat Enterprise Linux 9

Using Ansible to install and manage Identity Management

Using Ansible to maintain an IdM environment

Last Updated: 2025-06-10

Red Hat Enterprise Linux 9 Using Ansible to install and manage Identity Management

Using Ansible to maintain an IdM environment

Legal Notice

Copyright © 2025 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java [®] is a registered trademark of Oracle and/or its affiliates.

XFS [®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack [®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

Red Hat provides the ansible-freeipa package to enable administrators to run Red Hat Identity Management (IdM) by using Ansible. You can use playbooks to install IdM and manage users, groups, hosts, access control, and configuration settings.

Table of Contents

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION	. 9
CHAPTER 1. ANSIBLE TERMINOLOGY	10
CHAPTER 2. INSTALLING AN IDENTITY MANAGEMENT SERVER USING AN ANSIBLE PLAYBOOK	. 11
2.1. ANSIBLE AND ITS ADVANTAGES FOR INSTALLING IDM	11
Advantages of using Ansible to install IdM	11
2.2. INSTALLING THE ANSIBLE-FREEIPA PACKAGE	11
2.3. ANSIBLE ROLES LOCATION IN THE FILE SYSTEM	12
2.4. SETTING THE PARAMETERS FOR A DEPLOYMENT WITH AN INTEGRATED DNS AND AN INTEGRATED CA AS THE ROOT CA	13
2.5. SETTING THE PARAMETERS FOR A DEPLOYMENT WITH EXTERNAL DNS AND AN INTEGRATED CA A THE ROOT CA	\S 16
2.6. DEPLOYING AN IDM SERVER WITH AN INTEGRATED CA AS THE ROOT CA USING AN ANSIBLE	10
PLAYBOOK	18
2.7. SETTING THE PARAMETERS FOR A DEPLOYMENT WITH AN INTEGRATED DNS AND AN EXTERNAL C	
AS THE ROOT CA	.A 19
2.8. SETTING THE PARAMETERS FOR A DEPLOYMENT WITH EXTERNAL DNS AND AN EXTERNAL CA AS ROOT CA	22
2.9. DEPLOYING AN IDM SERVER WITH AN EXTERNAL CA AS THE ROOT CA USING AN ANSIBLE PLAYBO	OK 25
2.10. UNINSTALLING AN IDM SERVER USING AN ANSIBLE PLAYBOOK	26
2.11. USING AN ANSIBLE PLAYBOOK TO UNINSTALL AN IDM SERVER EVEN IF THIS LEADS TO A	
DISCONNECTED TOPOLOGY	27
CHAPTER 3. INSTALLING AN IDENTITY MANAGEMENT REPLICA USING AN ANSIBLE PLAYBOOK	30
3.1. SPECIFYING THE BASE, SERVER AND CLIENT VARIABLES FOR INSTALLING THE IDM REPLICA	30
3.2. SPECIFYING THE CREDENTIALS FOR INSTALLING THE IDM REPLICA USING AN ANSIBLE PLAYBOOK	
3.2. OF ECH THIS THE CREDENTIALEST CHARGE TREATMENT FIRE EIGHT COMPONITION TO BE EXCHANGED FOR THE STATE OF T	34
3.3. DEPLOYING AN IDM REPLICA USING AN ANSIBLE PLAYBOOK	35
3.4. UNINSTALLING AN IDM REPLICA USING AN ANSIBLE PLAYBOOK	36
5.4. ONING FALLING AN IDM NEI EIGA GOING AN ANGIDEET EATBOOK	50
CHAPTER 4. INSTALLING AN IDENTITY MANAGEMENT CLIENT USING AN ANSIBLE PLAYBOOK	37
4.1. SETTING THE PARAMETERS OF THE INVENTORY FILE FOR THE AUTODISCOVERY CLIENT	
INSTALLATION MODE	37
4.2. SETTING THE PARAMETERS OF THE INVENTORY FILE WHEN AUTODISCOVERY IS NOT POSSIBLE	
DURING CLIENT INSTALLATION	39
4.3. AUTHORIZATION OPTIONS FOR IDM CLIENT ENROLLMENT USING AN ANSIBLE PLAYBOOK	42
4.4. DEPLOYING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK	43
4.5. USING THE ONE-TIME PASSWORD METHOD IN ANSIBLE TO INSTALL AN IDM CLIENT	44
4.6. TESTING AN IDENTITY MANAGEMENT CLIENT AFTER ANSIBLE INSTALLATION	46
4.7. UNINSTALLING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK	46
CHAPTER 5. PREPARING YOUR ENVIRONMENT FOR MANAGING IDM USING ANSIBLE PLAYBOOKS .	48
5.1. PREPARING A CONTROL NODE AND MANAGED NODES FOR MANAGING IDM USING ANSIBLE	
PLAYBOOKS	48
5.2. DIFFERENT METHODS TO PROVIDE THE CREDENTIALS REQUIRED FOR ANSIBLE-FREEIPA	
PLAYBOOKS	50
5.3. THE INVENTORY PLUGIN IN ANSIBLE-FREEIPA	52
S.S. THE HAVERTONE I LOOK WANTED BEEF THEER A	J2
CHAPTER 6. CONFIGURING GLOBAL IDM SETTINGS USING ANSIBLE PLAYBOOKS	54
6.1. RETRIEVING IDM CONFIGURATION USING AN ANSIBLE PLAYBOOK	54
6.2. CONFIGURING THE IDM CA RENEWAL SERVER USING AN ANSIBLE PLAYBOOK	56
6.3. CONFIGURING THE DEFAULT SHELL FOR IDM USERS USING AN ANSIBLE PLAYBOOK	57

6.4. CONFIGURING A NETBIOS NAME FOR AN IDM DOMAIN BY USING ANSIBLE6.5. ENSURING THAT IDM USERS AND GROUPS HAVE SIDS BY USING ANSIBLE6.6. ADDITIONAL RESOURCES	59 60 62
CHAPTER 7. MANAGING USER ACCOUNTS USING ANSIBLE PLAYBOOKS	63
7.2. ENSURING THE PRESENCE OF AN IDM USER USING AN ANSIBLE PLAYBOOK	64
7.3. ENSURING THE PRESENCE OF MULTIPLE IDM USERS USING ANSIBLE PLAYBOOKS 7.4. ENSURING THE PRESENCE OF MULTIPLE IDM USERS FROM A JSON FILE USING ANSIBLE	66
PLAYBOOKS	68
7.5. ENSURING THE ABSENCE OF USERS USING ANSIBLE PLAYBOOKS 7.6. ADDITIONAL RESOURCES	69 71
CHAPTER 8. MANAGING USER GROUPS USING ANSIBLE PLAYBOOKS	72
8.1. THE DIFFERENT GROUP TYPES IN IDM	72
8.2. DIRECT AND INDIRECT GROUP MEMBERS	73
8.3. ENSURING THE PRESENCE OF IDM GROUPS AND GROUP MEMBERS USING ANSIBLE PLAYBOOKS	73
8.4. USING ANSIBLE TO ADD MULTIPLE IDM GROUPS IN A SINGLE TASK	75 75
8.5. USING ANSIBLE TO ENABLE AD USERS TO ADMINISTER IDM	75 76
8.6. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE	, 0
PLAYBOOKS	78
8.7. ENSURING THE ABSENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS	80
CHAPTER 9. USING ANSIBLE TO AUTOMATE GROUP MEMBERSHIP IN IDM	82
9.1. USING ANSIBLE TO ENSURE THAT AN AUTOMEMBER RULE FOR AN IDM USER GROUP IS PRESENT	82
9.2. USING ANSIBLE TO ENSURE THAT A SPECIFIED CONDITION IS PRESENT IN AN IDM USER GROUP AUTOMEMBER RULE	83
9.3. USING ANSIBLE TO ENSURE THAT A CONDITION IS ABSENT FROM AN IDM USER GROUP AUTOMEMBER RULE	85
9.4. USING ANSIBLE TO ENSURE THAT AN AUTOMEMBER RULE FOR AN IDM USER GROUP IS ABSENT	87
9.5. USING ANSIBLE TO ENSURE THAT A CONDITION IS PRESENT IN AN IDM HOST GROUP AUTOMEMB RULE	BER 89
CHAPTER 10. USING ANSIBLE PLAYBOOKS TO MANAGE SELF-SERVICE RULES IN IDM	92
10.1. SELF-SERVICE ACCESS CONTROL IN IDM	92
10.2. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS PRESENT	92
10.3. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS ABSENT	94
10.4. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE HAS SPECIFIC ATTRIBUTES	95
10.5. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE DOES NOT HAVE SPECIFIC ATTRIBUTES	96
	30
CHAPTER 11. DELEGATING PERMISSIONS TO USER GROUPS TO MANAGE USERS USING ANSIBLE PLAYBOOKS	99
11.1. DELEGATION RULES	99
11.2. CREATING AN ANSIBLE INVENTORY FILE FOR IDM	99
11.3. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS PRESENT	100
11.4. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS ABSENT	102
11.5. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE HAS SPECIFIC ATTRIBUTES	103
11.6. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE DOES NOT HAVE SPECIFIC ATTRIBUTES	105
CHAPTER 12. USING ANSIBLE PLAYBOOKS TO MANAGE ROLE-BASED ACCESS CONTROL IN IDM	107
12.1. PERMISSIONS IN IDM	107
12.2. DEFAULT MANAGED PERMISSIONS	108
12.3. PRIVILEGES IN IDM	109

12.4. ROLES IN IDM	110
12.5. PREDEFINED ROLES IN IDENTITY MANAGEMENT	110
12.6. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE WITH PRIVILEGES IS PRESENT	111
12.7. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE IS ABSENT	113
12.8. USING ANSIBLE TO ENSURE THAT A GROUP OF USERS IS ASSIGNED TO AN IDM RBAC ROLE	114
12.9. USING ANSIBLE TO ENSURE THAT SPECIFIC USERS ARE NOT ASSIGNED TO AN IDM RBAC ROLE	116
12.10. USING ANSIBLE TO ENSURE A SERVICE IS A MEMBER OF AN IDM RBAC ROLE	117
12.11. USING ANSIBLE TO ENSURE A HOST IS A MEMBER OF AN IDM RBAC ROLE	119
12.12. USING ANSIBLE TO ENSURE A HOST GROUP IS A MEMBER OF AN IDM RBAC ROLE	120
CHAPTER 13. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PRIVILEGES	
13.1. USING ANSIBLE TO ENSURE A CUSTOM IDM RBAC PRIVILEGE IS PRESENT	123
13.2. USING ANSIBLE TO ENSURE MEMBER PERMISSIONS ARE PRESENT IN A CUSTOM IDM RBAC PRIVILEGE	124
13.3. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE DOES NOT INCLUDE A PERMISSION	126
13.4. USING ANSIBLE TO RENAME A CUSTOM IDM RBAC PRIVILEGE	128
13.5. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE IS ABSENT	129
13.6. ADDITIONAL RESOURCES	131
CHAPTER 14. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PERMISSIONS IN IDM	
14.1. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS PRESENT	132
14.2. USING ANSIBLE TO ENSURE AN RBAC PERMISSION WITH AN ATTRIBUTE IS PRESENT	134
14.3. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS A MEMBER OF AN IDM PRAC PERMISSION.	136
14.4. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS A MEMBER OF AN IDM RBAC PERMISSION	137
14.5. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS NOT A MEMBER OF AN IDM RBAC PERMISSION	139 140
14.6. USING ANSIBLE TO RENAME AN IDM RBAC PERMISSION 14.7. ADDITIONAL RESOURCES	140
CHARTER 15 LIGING ANGIRLE TO MANAGE THE REPUBLICATION TOROL OCYUNIDM	1.40
CHAPTER 15. USING ANSIBLE TO MANAGE THE REPLICATION TOPOLOGY IN IDM	
15.1. USING ANSIBLE TO ENSURE A REPLICATION AGREEMENT EXISTS IN IDM	143
15.2. USING ANSIBLE TO ENSURE REPLICATION AGREEMENTS EXIST BETWEEN MULTIPLE IDM REPLI	JAS 145
15.3. USING ANSIBLE TO CHECK IF A REPLICATION AGREEMENT EXISTS BETWEEN TWO REPLICAS	147
15.4. USING ANSIBLE TO VERIFY THAT A TOPOLOGY SUFFIX EXISTS IN IDM	149
15.5. USING ANSIBLE TO REINITIALIZE AN IDM REPLICA	150
15.6. USING ANSIBLE TO ENSURE A REPLICATION AGREEMENT IS ABSENT IN IDM	152
15.7. ADDITIONAL RESOURCES	154
CHAPTER 16. MANAGING IDM SERVERS BY USING ANSIBLE	. 155
16.1. CHECKING THAT AN IDM SERVER IS PRESENT BY USING ANSIBLE	155
16.2. ENSURING THAT AN IDM SERVER IS ABSENT FROM AN IDM TOPOLOGY BY USING ANSIBLE	156
16.3. ENSURING THE ABSENCE OF AN IDM SERVER DESPITE HOSTING A LAST IDM SERVER ROLE	158
16.4. ENSURING THAT AN IDM SERVER IS ABSENT BUT NOT NECESSARILY DISCONNECTED FROM OT	HER
IDM SERVERS	160
16.5. ENSURING THAT AN EXISTING IDM SERVER IS HIDDEN USING AN ANSIBLE PLAYBOOK	161
16.6. ENSURING THAT AN EXISTING IDM SERVER IS VISIBLE BY USING AN ANSIBLE PLAYBOOK	163
16.7. ENSURING THAT AN EXISTING IDM SERVER HAS AN IDM DNS LOCATION ASSIGNED	164
16.8. ENSURING THAT AN EXISTING IDM SERVER HAS NO IDM DNS LOCATION ASSIGNED	166
CHAPTER 17. MANAGING HOSTS USING ANSIBLE PLAYBOOKS	. 168
17.1. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH FQDN USING ANSIBLE PLAYBOOKS	168
17.2. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH DNS INFORMATION USING ANSIBLE	
PLAYBOOKS 17.3. ENSURING THE PRESENCE OF MULTIPLE IDM HOST ENTRIES WITH RANDOM PASSWORDS USING	169

17.4. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH MULTIPLE IP ADDRESSES USING ANSI	BLE
PLAYBOOKS	173
17.5. ENSURING THE ABSENCE OF AN IDM HOST ENTRY USING ANSIBLE PLAYBOOKS	175
17.6. ADDITIONAL RESOURCES	177
CHAPTER 18. MANAGING HOST GROUPS USING ANSIBLE PLAYBOOKS	178
18.1. HOST GROUPS IN IDM	178
18.2. ENSURING THE PRESENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	178
18.3. ENSURING THE PRESENCE OF HOSTS IN IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	180
18.4. NESTING IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	181
18.5. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM HOST GROUPS USING ANSIBLE	
PLAYBOOKS	183
18.6. ENSURING THE ABSENCE OF HOSTS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	185
18.7. ENSURING THE ABSENCE OF NESTED HOST GROUPS FROM IDM HOST GROUPS USING ANSIBLE	Ξ
PLAYBOOKS	186
18.8. ENSURING THE ABSENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	188
18.9. ENSURING THE ABSENCE OF MEMBER MANAGERS FROM IDM HOST GROUPS USING ANSIBLE	
PLAYBOOKS	190
CHAPTER 19. DEFINING IDM PASSWORD POLICIES	192
19.1. WHAT IS A PASSWORD POLICY	192
19.2. PASSWORD POLICIES IN IDM	192
19.3. PASSWORD POLICY PRIORITIES IN IDM	194
19.4. ENSURING THE PRESENCE OF A PASSWORD POLICY IN IDM USING AN ANSIBLE PLAYBOOK	194
19.5. ADDING A NEW PASSWORD POLICY IN IDM USING THE WEBUI OR THE CLI	196
19.5.1. Adding a new password policy in the IdM WebUI	196
19.5.2. Adding a new password policy in the IdM CLI	197
19.6. ADDITIONAL PASSWORD POLICY OPTIONS IN IDM	197
19.7. APPLYING ADDITIONAL PASSWORD POLICY OPTIONS TO AN IDM GROUP	198
19.8. USING AN ANSIBLE PLAYBOOK TO APPLY ADDITIONAL PASSWORD POLICY OPTIONS TO AN IDN	
GROUP	200
CHAPTER 20. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT	204
20.1. SUDO ACCESS ON AN IDM CLIENT	204
20.2. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE CLI	204
20.2. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE CLI	204
20.4. GRANTING SUDO ACCESS TO AN AD USER ON AN IDM CLIENT USING THE CLI	210
20.4. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE IDM WEB UI 20.5. CREATING A SUDO RULE ON THE CLI THAT RUNS A COMMAND AS A SERVICE ACCOUNT ON AN	
CLIENT	212
20.6. CREATING A SUDO RULE IN THE IDM WEBUI THAT RUNS A COMMAND AS A SERVICE ACCOUNT	ON
AN IDM CLIENT	215
20.7. ENABLING GSSAPI AUTHENTICATION FOR SUDO ON AN IDM CLIENT	217
20.8. ENABLING GSSAPI AUTHENTICATION AND ENFORCING KERBEROS AUTHENTICATION INDICATOR SUDO ON AN IDM CLIENT	DRS 219
20.9. SSSD OPTIONS CONTROLLING GSSAPI AUTHENTICATION FOR PAM SERVICES	222
20.10. TROUBLESHOOTING GSSAPI AUTHENTICATION FOR SUDO	223
20.11. USING AN ANSIBLE PLAYBOOK TO ENSURE SUDO ACCESS FOR AN IDM USER ON AN IDM CLIEN	Т
	225
20.12. MANAGING MULTIPLE IDM SUDO RULES IN A SINGLE ANSIBLE TASK	227
CHAPTER 21. ENSURING THE PRESENCE OF HOST-BASED ACCESS CONTROL RULES IN IDM USING	
ANSIBLE PLAYBOOKS	230
21.1. HOST-BASED ACCESS CONTROL RULES IN IDM	230
21.2. ENSURING THE PRESENCE OF AN HBAC RULE IN IDM USING AN ANSIBLE PLAYBOOK	230
CHARTER 22 MANACING IDM CERTIFICATES LISING ANGIRI E	222
CHAPTER 22. MANAGING IDM CERTIFICATES USING ANSIBLE	233

22.1. USING ANSIBLE TO REQUEST SSL CERTIFICATES FOR IDM HOSTS, SERVICES AND USERS 22.2. USING ANSIBLE TO REVOKE SSL CERTIFICATES FOR IDM HOSTS, SERVICES AND USERS 22.3. USING ANSIBLE TO RESTORE SSL CERTIFICATES FOR IDM USERS, HOSTS, AND SERVICES 22.4. USING ANSIBLE TO RETRIEVE SSL CERTIFICATES FOR IDM USERS, HOSTS, AND SERVICES	233 234 235 236
CHAPTER 23. VAULTS IN IDM 23.1. VAULTS AND THEIR BENEFITS 23.2. VAULT OWNERS, MEMBERS, AND ADMINISTRATORS	238 238 238
23.3. STANDARD, SYMMETRIC, AND ASYMMETRIC VAULTS 23.4. USER, SERVICE, AND SHARED VAULTS 23.5. VAULT CONTAINERS 23.6. BASIC IDM VAULT COMMANDS 23.7. INSTALLING THE KEY RECOVERY AUTHORITY IN IDM	239 240 240 240 241
CHAPTER 24. USING ANSIBLE TO MANAGE IDM USER VAULTS: STORING AND RETRIEVING SECF 24.1. ENSURING THE PRESENCE OF A STANDARD USER VAULT IN IDM USING ANSIBLE 24.2. ARCHIVING A SECRET IN A STANDARD USER VAULT IN IDM USING ANSIBLE 24.3. RETRIEVING A SECRET FROM A STANDARD USER VAULT IN IDM USING ANSIBLE	RETS 243 243 244 246
CHAPTER 25. USING ANSIBLE TO MANAGE IDM SERVICE VAULTS: STORING AND RETRIEVING SI	ECRETS . 249
25.1. ENSURING THE PRESENCE OF AN ASYMMETRIC SERVICE VAULT IN IDM USING ANSIBLE 25.2. ADDING MEMBER SERVICES TO AN ASYMMETRIC VAULT USING ANSIBLE 25.3. STORING AN IDM SERVICE SECRET IN AN ASYMMETRIC VAULT USING ANSIBLE 25.4. RETRIEVING A SERVICE SECRET FOR AN IDM SERVICE USING ANSIBLE 25.5. CHANGING AN IDM SERVICE VAULT SECRET WHEN COMPROMISED USING ANSIBLE 25.6. ADDITIONAL RESOURCES	249 251 253 254 257 260
CHAPTER 26. ENSURING THE PRESENCE AND ABSENCE OF SERVICES IN IDM USING ANSIBLE 26.1. ENSURING THE PRESENCE OF AN HTTP SERVICE IN IDM USING AN ANSIBLE PLAYBOOK 26.2. ENSURING THE PRESENCE OF MULTIPLE SERVICES IN IDM ON AN IDM CLIENT USING A SIN ANSIBLE TASK	261
26.3. ENSURING THE PRESENCE OF AN HTTP SERVICE IN IDM ON A NON-IDM CLIENT USING AN PLAYBOOK	ANSIBLE 264
26.4. ENSURING THE PRESENCE OF AN HTTP SERVICE ON AN IDM CLIENT WITHOUT DNS USING ANSIBLE PLAYBOOK	AN 265
26.5. ENSURING THE PRESENCE OF AN EXTERNALLY SIGNED CERTIFICATE IN AN IDM SERVICE EUSING AN ANSIBLE PLAYBOOK	ENTRY 267
26.6. USING AN ANSIBLE PLAYBOOK TO ALLOW IDM USERS, GROUPS, HOSTS, OR HOST GROUP CREATE A KEYTAB OF A SERVICE	269
26.7. USING AN ANSIBLE PLAYBOOK TO ALLOW IDM USERS, GROUPS, HOSTS, OR HOST GROUP RETRIEVE A KEYTAB OF A SERVICE	271
26.8. ENSURING THE PRESENCE OF A KERBEROS PRINCIPAL ALIAS OF A SERVICE USING AN ANS PLAYBOOK	SIBLE 273
26.9. ENSURING THE ABSENCE OF AN HTTP SERVICE IN IDM USING AN ANSIBLE PLAYBOOK 26.10. ADDITIONAL RESOURCES	275 277
CHAPTER 27. MANAGING GLOBAL DNS CONFIGURATION IN IDM USING ANSIBLE PLAYBOOKS 27.1. HOW IDM ENSURES THAT GLOBAL FORWARDERS FROM /ETC/RESOLV.CONF ARE NOT REN NETWORKMANAGER	
27.2. ENSURING THE PRESENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE	279
27.3. ENSURING THE ABSENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE	281
27.4. THE ACTION: MEMBER OPTION IN IPADNSCONFIG ANSIBLE-FREEIPA MODULES 27.5. DNS FORWARD POLICIES IN IDM	283 284
27.6. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT THE FORWARD FIRST POLICY IS SET IN IT	OM DNS

27.7. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT GLOBAL FORWARDERS ARE DISABLED IN IDM	
27.0 LICING AN ANCIDLE DI AVDOOKTO ENGLIDE THAT CVNICHDONIZATION OF FORWARD AND DEVE	287
27.8. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT SYNCHRONIZATION OF FORWARD AND REVER LOOKUP ZONES IS DISABLED IN IDM DNS	288
CHAPTER 28. USING ANSIBLE PLAYBOOKS TO MANAGE IDM DNS ZONES	290
28.1. SUPPORTED DNS ZONE TYPES	290
28.2. CONFIGURATION ATTRIBUTES OF PRIMARY IDM DNS ZONES	291
28.3. USING ANSIBLE TO CREATE A PRIMARY ZONE IN IDM DNS	293
28.4. USING AN ANSIBLE PLAYBOOK TO ENSURE THE PRESENCE OF A PRIMARY DNS ZONE IN IDM WITMULTIPLE VARIABLES	TH 295
28.5. USING AN ANSIBLE PLAYBOOK TO ENSURE THE PRESENCE OF A ZONE FOR REVERSE DNS LOOF WHEN AN IP ADDRESS IS GIVEN	KUP 297
CHAPTER 29. USING ANSIBLE TO MANAGE DNS LOCATIONS IN IDM	300
29.1. DNS-BASED SERVICE DISCOVERY	300
29.2. DEPLOYMENT CONSIDERATIONS FOR DNS LOCATIONS	301
29.3. DNS TIME TO LIVE (TTL)	301
29.4. USING ANSIBLE TO ENSURE AN IDM LOCATION IS PRESENT	301
29.5. USING ANSIBLE TO ENSURE AN IDM LOCATION IS ABSENT	303
29.6. ADDITIONAL RESOURCES	304
CHAPTER 30. MANAGING DNS FORWARDING IN IDM	305
30.1. THE TWO ROLES OF AN IDM DNS SERVER	305
30.2. DNS FORWARD POLICIES IN IDM	306
30.3. ADDING A GLOBAL FORWARDER IN THE IDM WEB UI	306
30.4. ADDING A GLOBAL FORWARDER IN THE CLI	309
30.5. ADDING A DNS FORWARD ZONE IN THE IDM WEB UI	310
30.6. ADDING A DNS FORWARD ZONE IN THE CLI	313
30.7. ESTABLISHING A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE	314
30.8. ENSURING THE PRESENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE	316
30.9. ENSURING THE ABSENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE	317
30.10. ENSURING DNS GLOBAL FORWARDERS ARE DISABLED IN IDM USING ANSIBLE	319
30.11. ENSURING THE PRESENCE OF A DNS FORWARD ZONE IN IDM USING ANSIBLE	320
30.12. ENSURING A DNS FORWARD ZONE HAS MULTIPLE FORWARDERS IN IDM USING ANSIBLE	322
30.13. ENSURING A DNS FORWARD ZONE IS DISABLED IN IDM USING ANSIBLE	324
30.14. ENSURING THE ABSENCE OF A DNS FORWARD ZONE IN IDM USING ANSIBLE	326
CHAPTER 31. USING ANSIBLE TO MANAGE DNS RECORDS IN IDM	328
31.1. DNS RECORDS IN IDM	328
31.2. COMMON IPA DNSRECORD-* OPTIONS	329
31.3. ENSURING THE PRESENCE OF A AND AAAA DNS RECORDS IN IDM USING ANSIBLE	331
31.4. ENSURING THE PRESENCE OF A AND PTR DNS RECORDS IN IDM USING ANSIBLE	333
31.5. ENSURING THE PRESENCE OF MULTIPLE DNS RECORDS IN IDM USING ANSIBLE	335
31.6. ENSURING THE PRESENCE OF MULTIPLE CNAME RECORDS IN IDM USING ANSIBLE	337
31.7. ENSURING THE PRESENCE OF AN SRV RECORD IN IDM USING ANSIBLE	339
CHAPTER 32. USING ANSIBLE TO AUTOMOUNT NFS SHARES FOR IDM USERS	341
32.1. AUTOFS AND AUTOMOUNT IN IDM	341
32.2. SETTING UP AN NFS SERVER WITH KERBEROS IN A RED HAT ENTERPRISE LINUX IDENTITY MANAGEMENT DOMAIN	342
32.3. CONFIGURING AUTOMOUNT LOCATIONS, MAPS, AND KEYS IN IDM BY USING ANSIBLE	343
32.4. USING ANSIBLE TO ADD IDM USERS TO A GROUP THAT OWNS NFS SHARES	345
32.5. CONFIGURING AUTOMOUNT ON AN IDM CLIENT	347
32.6. VERIFYING THAT AN IDM USER CAN ACCESS NFS SHARES ON AN IDM CLIENT	347

CHAPTER 33. USING ANSIBLE TO INTEGRATE IDM WITH NIS DOMAINS AND NETGROUPS	349
33.1. NIS AND ITS BENEFITS	349
33.2. NIS IN IDM	349
33.3. NIS NETGROUPS IN IDM	350
33.4. USING ANSIBLE TO ENSURE THAT A NETGROUP IS PRESENT	350
33.5. USING ANSIBLE TO ENSURE THAT MEMBERS ARE PRESENT IN A NETGROUP	351
33.6. USING ANSIBLE TO ENSURE THAT A MEMBER IS ABSENT FROM A NETGROUP	352
33.7. USING ANSIBLE TO ENSURE THAT A NETGROUP IS ABSENT	353
CHAPTER 34. USING ANSIBLE TO CONFIGURE HBAC AND SUDO RULES IN IDM	355
CHAPTER 35. USING ANSIBLE TO DELEGATE AUTHENTICATION FOR IDM USERS TO EXTERNAL IDENT	TITY
PROVIDERS	360
35.1. THE BENEFITS OF CONNECTING IDM TO AN EXTERNAL IDP	360
35.2. HOW IDM INCORPORATES LOGINS VIA EXTERNAL IDPS	360
35.3. USING ANSIBLE TO CREATE A REFERENCE TO AN EXTERNAL IDENTITY PROVIDER	361
35.4. USING ANSIBLE TO ENABLE AN IDM USER TO AUTHENTICATE VIA AN EXTERNAL IDP	362
35.5. RETRIEVING AN IDM TICKET-GRANTING TICKET AS AN EXTERNAL IDP USER	364
35.6. LOGGING IN TO AN IDM CLIENT VIA SSH AS AN EXTERNAL IDP USER	366
35.7. THE PROVIDER OPTION IN THE IPAIDP ANSIBLE MODULE	366
CHAPTER 36. USING CONSTRAINED DELEGATION IN IDM	371
36.1. CONSTRAINED DELEGATION IN IDENTITY MANAGEMENT	371
36.2. CONFIGURING THE WEB CONSOLE TO ALLOW A USER AUTHENTICATED WITH A SMART CARD TO SSH TO A REMOTE HOST WITHOUT BEING ASKED TO AUTHENTICATE AGAIN	O 372
36.3. USING ANSIBLE TO CONFIGURE THE WEB CONSOLE TO ALLOW A USER AUTHENTICATED WITH	
SMART CARD TO SSH TO A REMOTE HOST WITHOUT BEING ASKED TO AUTHENTICATE AGAIN	373
36.4. CONFIGURING A WEB CONSOLE TO ALLOW A USER AUTHENTICATED WITH A SMART CARD TO F	RUN
SUDO WITHOUT BEING ASKED TO AUTHENTICATE AGAIN	376
36.5. USING ANSIBLE TO CONFIGURE A WEB CONSOLE TO ALLOW A USER AUTHENTICATED WITH A	
SMART CARD TO RUN SUDO WITHOUT BEING ASKED TO AUTHENTICATE AGAIN	377
36.6. ADDITIONAL RESOURCES	380
CHAPTER 37. JOINING RHEL SYSTEMS TO AN ACTIVE DIRECTORY BY USING RHEL SYSTEM ROLES	381
37.1. JOINING RHEL TO AN ACTIVE DIRECTORY DOMAIN BY USING THE AD_INTEGRATION RHEL SYSTE	281

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your feedback on our documentation. Let us know how we can improve it.

Submitting feedback through Jira (account required)

- 1. Log in to the Jira website.
- 2. Click **Create** in the top navigation bar
- 3. Enter a descriptive title in the **Summary** field.
- 4. Enter your suggestion for improvement in the **Description** field. Include links to the relevant parts of the documentation.
- 5. Click **Create** at the bottom of the dialogue.

CHAPTER 1. ANSIBLE TERMINOLOGY

The chapters in this title use the official Ansible terminology. If you are not familiar with the terminology, read the official Ansible upstream documentation before proceeding, especially the following sections:

- The Basic concepts in Ansible section provides an overview of the most commonly used concepts in Ansible.
- The User guide outlines the most common situations and questions when starting to use Ansible, such as using the command line; working with an inventory; interacting with data; writing tasks, plays, and playbooks; and executing playbooks.
- How to build your inventory offers tips on how to design your inventory. An inventory is a list or a group of lists that Ansible uses to work against multiple managed nodes or hosts in your infrastructure.
- Intro to playbooks introduces the concept of an Ansible playbook as a repeatable and re-usable system for managing configurations, deploying machines, and deploying complex applications.
- The Ansible roles section explains how to automate loading variables, tasks, and handlers based on a known file structure.
- The Glossary explains terms that are used elsewhere in the Ansible documentation.

CHAPTER 2. INSTALLING AN IDENTITY MANAGEMENT SERVER USING AN ANSIBLE PLAYBOOK

The following sections describe how to configure a system as an IdM server by using Ansible. Configuring a system as an IdM server establishes an IdM domain and enables the system to offer IdM services to IdM clients. The deployment is managed by the **ipaserver** Ansible role.

Prerequisites

- You understand Ansible and IdM concepts:
 - Ansible roles
 - Ansible nodes
 - Ansible inventory
 - Ansible tasks
 - Ansible modules
 - Ansible plays and playbooks

2.1. ANSIBLE AND ITS ADVANTAGES FOR INSTALLING IDM

Ansible is an automation tool used to configure systems, deploy software, and perform rolling updates. Ansible includes support for Identity Management (IdM), and you can use Ansible modules to automate installation tasks such as the setup of an IdM server, replica, client, or an entire IdM topology.

Advantages of using Ansible to install IdM

The following list presents advantages of installing Identity Management using Ansible in contrast to manual installation.

- You do not need to log into the managed node.
- You do not need to configure settings on each host to be deployed individually. Instead, you can have one inventory file to deploy a complete cluster.
- You can reuse an inventory file later for management tasks, for example to add users and hosts. You can reuse an inventory file even for such tasks as are not related to IdM.

Additional resources

- Automating Red Hat Enterprise Linux Identity Management installation
- Planning Identity Management
- Preparing the system for IdM server installation

2.2. INSTALLING THE ANSIBLE-FREEIPA PACKAGE

The following procedure describes how to install the the **ansible-freeipa** roles.

Prerequisites

- Ensure that the controller is a Red Hat Enterprise Linux system with a valid subscription. If this is not the case, see the official Ansible documentation Installation guide for alternative installation instructions.
- Ensure that you can reach the managed node over the **SSH** protocol from the controller. Check that the managed node is listed in the /**root**/.**ssh/known_hosts** file of the controller.

Procedure

Run the following procedure on the Ansible controller.

- 1. Enable the required repository:
 - # subscription-manager repos --enable rhel-9-for-x86_64-appstream-rpms
- 2. Install the IdM Ansible roles:
 - # dnf install ansible-freeipa

The roles are installed to the /usr/share/ansible/roles/ directory.

2.3. ANSIBLE ROLES LOCATION IN THE FILE SYSTEM

By default, the **ansible-freeipa** roles are installed to the /usr/share/ansible/roles/ directory. The structure of the **ansible-freeipa** package is as follows:

• The /usr/share/ansible/roles/ directory stores the ipaserver, ipareplica, and ipaclient roles on the Ansible controller. Each role directory stores examples, a basic overview, the license and documentation about the role in a **README.md** Markdown file.

```
[root@server]# Is -1 /usr/share/ansible/roles/ ipaclient ipareplica ipaserver
```

• The /usr/share/doc/ansible-freeipa/ directory stores the documentation about individual roles and the topology in **README.md** Markdown files. It also stores the **playbooks**/ subdirectory.

```
[root@server]# Is -1 /usr/share/doc/ansible-freeipa/playbooks
README-client.md
README.md
README-replica.md
README-server.md
README-topology.md
```

The /usr/share/doc/ansible-freeipa/playbooks/ directory stores the example playbooks:

```
[root@server]# Is -1 /usr/share/doc/ansible-freeipa/playbooks/install-client.yml install-cluster.yml install-replica.yml install-server.yml uninstall-client.yml
```

uninstall-cluster.yml uninstall-replica.yml uninstall-server.yml

2.4. SETTING THE PARAMETERS FOR A DEPLOYMENT WITH AN INTEGRATED DNS AND AN INTEGRATED CA AS THE ROOT CA

Complete this procedure to configure the inventory file for installing an IdM server with an integrated CA as the root CA in an environment that uses the IdM integrated DNS solution.



NOTE

The inventory in this procedure uses the **INI** format. You can, alternatively, use the **YAML** or **JSON** formats.

Procedure

- 1. Create a ~/**MyPlaybooks**/ directory:
 - \$ mkdir MyPlaybooks
- 2. Create a ~/MyPlaybooks/inventory file.
- 3. Open the inventory file for editing. Specify the fully-qualified domain names (**FQDN**) of the host you want to use as an IdM server. Ensure that the **FQDN** meets the following criteria:
 - Only alphanumeric characters and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.
- 4. Specify the IdM domain and realm information.
- 5. Specify that you want to use integrated DNS by adding the following option:
 - ipaserver_setup_dns=true
- 6. Specify the DNS forwarding settings. Choose one of the following options:
 - Use the ipaserver_auto_forwarders=true option if you want the installer to use forwarders from the /etc/resolv.conf file. Do not use this option if the nameserver specified in the /etc/resolv.conf file is the localhost 127.0.0.1 address or if you are on a virtual private network and the DNS servers you are using are normally unreachable from the public internet.
 - Use the ipaserver_forwarders option to specify your forwarders manually. The installation process adds the forwarder IP addresses to the /etc/named.conf file on the installed IdM server.
 - Use the **ipaserver_no_forwarders=true** option to configure root DNS servers to be used instead.



NOTE

With no DNS forwarders, your environment is isolated, and names from other DNS domains in your infrastructure are not resolved.

- 7. Specify the DNS reverse record and zone settings. Choose from the following options:
 - Use the **ipaserver_allow_zone_overlap=true** option to allow the creation of a (reverse) zone even if the zone is already resolvable.
 - Use the **ipaserver reverse zones** option to specify your reverse zones manually.
 - Use the **ipaserver_no_reverse=true** option if you do not want the installer to create a reverse DNS zone.



NOTE

Using IdM to manage reverse zones is optional. You can use an external DNS service for this purpose instead.

- 8. Specify the passwords for **admin** and for the **Directory Manager**. Use the Ansible Vault to store the password, and reference the Vault file from the playbook file. Alternatively and less securely, specify the passwords directly in the inventory file.
- 9. Optional: Specify a custom **firewalld** zone to be used by the IdM server. If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of an inventory file with the required server information (excluding the passwords)

[ipaserver] server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=true
ipaserver_auto_forwarders=true
[...]

Example of an inventory file with the required server information (including the passwords)

[ipaserver] server.idm.example.com

[ipaserver:vars] ipaserver_domain=idm.example.com ipaserver_realm=IDM.EXAMPLE.COM

```
ipaserver_setup_dns=true
ipaserver_auto_forwarders=true
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
[...]
```

Example of an inventory file with a custom firewalld zone

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=true
ipaserver_auto_forwarders=true
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
ipaserver_firewalld_zone=custom zone
```

Example playbook to set up an IdM server using admin and Directory Manager passwords stored in an Ansible Vault file

--- name: Playbook to configure IPA server hosts: ipaserver become: true vars_files:
- playbook_sensitive_data.yml

roles:
- role: ipaserver state: present

Example playbook to set up an IdM server using admin and Directory Manager passwords from an inventory file

--- name: Playbook to configure IPA server hosts: ipaserver become: true

roles:
- role: ipaserver

Additional resources

• man ipa-server-install(1)

state: present

/usr/share/doc/ansible-freeipa/README-server.md

2.5. SETTING THE PARAMETERS FOR A DEPLOYMENT WITH EXTERNAL DNS AND AN INTEGRATED CA AS THE ROOT CA

Complete this procedure to configure the inventory file for installing an IdM server with an integrated CA as the root CA in an environment that uses an external DNS solution.



NOTE

The inventory file in this procedure uses the **INI** format. You can, alternatively, use the **YAML** or **JSON** formats.

Procedure

- 1. Create a ~/MyPlaybooks/ directory:
 - \$ mkdir MyPlaybooks
- 2. Create a ~/MyPlaybooks/inventory file.
- 3. Open the inventory file for editing. Specify the fully-qualified domain names (**FQDN**) of the host you want to use as an IdM server. Ensure that the **FQDN** meets the following criteria:
 - Only alphanumeric characters and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.
- 4. Specify the IdM domain and realm information.
- 5. Make sure that the **ipaserver_setup_dns** option is set to **no** or that it is absent.
- 6. Specify the passwords for **admin** and for the **Directory Manager**. Use the Ansible Vault to store the password, and reference the Vault file from the playbook file. Alternatively and less securely, specify the passwords directly in the inventory file.
- 7. Optional: Specify a custom **firewalld** zone to be used by the IdM server. If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of an inventory file with the required server information (excluding the passwords)

[ipaserver] server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
[...]

Example of an inventory file with the required server information (including the passwords)

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234

[...]
```

Example of an inventory file with a custom firewalld zone

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
ipaserver_firewalld_zone=custom zone
```

Example playbook to set up an IdM server using admin and Directory Manager passwords stored in an Ansible Vault file

--- name: Playbook to configure IPA server hosts: ipaserver become: true vars_files:
- playbook_sensitive_data.yml

roles:
- role: ipaserver state: present

Example playbook to set up an IdM server using admin and Directory Manager passwords from an inventory file

--- name: Playbook to configure IPA server hosts: ipaserver become: true

roles:
- role: ipaserver

state: present

Additional resources

- man ipa-server-install(1)
- /usr/share/doc/ansible-freeipa/README-server.md

2.6. DEPLOYING AN IDM SERVER WITH AN INTEGRATED CA AS THE ROOT CA USING AN ANSIBLE PLAYBOOK

Complete this procedure to deploy an IdM server with an integrated certificate authority (CA) as the root CA using an Ansible playbook.

Prerequisites

- The managed node is a Red Hat Enterprise Linux 9 system with a static IP address and a working package manager.
- You have set the parameters that correspond to your scenario by choosing one of the following procedures:
 - Procedure with integrated DNS
 - Procedure with external DNS

Procedure

1. Run the Ansible playbook:

 $\$\ ansible-playbook \ \hbox{-i \sim/MyPlaybooks/inventory \sim/MyPlaybooks/install-server.yml}$

- 2. Choose one of the following options:
 - If your IdM deployment uses external DNS: add the DNS resource records contained in the /tmp/ipa.system.records.UFRPto.db file to the existing external DNS servers. The process of updating the DNS records varies depending on the particular DNS solution.

...
Restarting the KDC
Please add records in this file to your DNS system:
/tmp/ipa.system.records.UFRBto.db
Restarting the web server

...



IMPORTANT

The server installation is not complete until you add the DNS records to the existing DNS servers.

- If your IdM deployment uses integrated DNS:
 - Add DNS delegation from the parent domain to the IdM DNS domain. For example, if the IdM DNS domain is *idm.example.com*, add a name server (NS) record to the example.com parent domain.



IMPORTANT

Repeat this step each time after an IdM DNS server is installed.

Add an _ntp._udp service (SRV) record for your time server to your IdM DNS. The
presence of the SRV record for the time server of the newly-installed IdM server in IdM
DNS ensures that future replica and client installations are automatically configured to
synchronize with the time server used by this primary IdM server.

2.7. SETTING THE PARAMETERS FOR A DEPLOYMENT WITH AN INTEGRATED DNS AND AN EXTERNAL CA AS THE ROOT CA

Complete this procedure to configure the inventory file for installing an IdM server with an external CA as the root CA in an environment that uses the IdM integrated DNS solution.



NOTE

The inventory file in this procedure uses the **INI** format. You can, alternatively, use the **YAML** or **JSON** formats.

Procedure

- 1. Create a ~/MyPlaybooks/ directory:
 - \$ mkdir MyPlaybooks
- 2. Create a ~/MyPlaybooks/inventory file.
- 3. Open the inventory file for editing. Specify the fully-qualified domain names (**FQDN**) of the host you want to use as an IdM server. Ensure that the **FQDN** meets the following criteria:
 - Only alphanumeric characters and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.
- 4. Specify the IdM domain and realm information.
- 5. Specify that you want to use integrated DNS by adding the following option:
 - ipaserver_setup_dns=true
- 6. Specify the DNS forwarding settings. Choose one of the following options:
 - Use the **ipaserver_auto_forwarders=true** option if you want the installation process to use forwarders from the /**etc/resolv.conf** file. This option is not recommended if the nameserver specified in the /**etc/resolv.conf** file is the localhost 127.0.0.1 address or if you are on a virtual private network and the DNS servers you are using are normally unreachable from the public internet.
 - Use the ipaserver_forwarders option to specify your forwarders manually. The installation process adds the forwarder IP addresses to the /etc/named.conf file on the installed IdM server.

 Use the ipaserver_no_forwarders=true option to configure root DNS servers to be used instead.



NOTE

With no DNS forwarders, your environment is isolated, and names from other DNS domains in your infrastructure are not resolved.

- 7. Specify the DNS reverse record and zone settings. Choose from the following options:
 - Use the **ipaserver_allow_zone_overlap=true** option to allow the creation of a (reverse) zone even if the zone is already resolvable.
 - Use the **ipaserver_reverse_zones** option to specify your reverse zones manually.
 - Use the **ipaserver_no_reverse=true** option if you do not want the installation process to create a reverse DNS zone.



NOTE

Using IdM to manage reverse zones is optional. You can use an external DNS service for this purpose instead.

- 8. Specify the passwords for **admin** and for the **Directory Manager**. Use the Ansible Vault to store the password, and reference the Vault file from the playbook file. Alternatively and less securely, specify the passwords directly in the inventory file.
- 9. Optional: Specify a custom **firewalld** zone to be used by the IdM server. If you do not set a custom zone, IdM adds its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of an inventory file with the required server information (excluding the passwords)

[ipaserver] server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=true
ipaserver_auto_forwarders=true
[...]

Example of an inventory file with the required server information (including the passwords)

[ipaserver] server.idm.example.com

```
[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=true
ipaserver_auto_forwarders=true
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
[...]
```

Example of an inventory file with a custom firewalld zone

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=true
ipaserver_auto_forwarders=true
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
ipaserver_firewalld_zone=custom zone

[...]
```

10. Create a playbook for the first step of the installation. Enter instructions for generating the certificate signing request (CSR) and copying it from the controller to the managed node.

```
-name: Playbook to configure IPA server Step 1
hosts: ipaserver
become: true
vars_files:
- playbook_sensitive_data.yml
vars:
    ipaserver_external_ca: true

roles:
- role: ipaserver
    state: present

post_tasks:
- name: Copy CSR /root/ipa.csr from node to "{{ groups.ipaserver[0] + '-ipa.csr' }}"
fetch:
    src: /root/ipa.csr
    dest: "{{ groups.ipaserver[0] + '-ipa.csr' }}"
flat: true
```

11. Create another playbook for the final step of the installation.

 name: Playbook to configure IPA server Step 2 hosts: ipaserver become: true vars_files:

- playbook_sensitive_data.yml

vars:

ipaserver_external_cert_files:

- "/root/servercert20240601.pem"
- "/root/cacert.pem"

pre_tasks:

- name: Copy "{{ groups.ipaserver[0] }}-{{ item }}" to "/root/{{ item }}" on node ansible.builtin.copy:

src: "{{ groups.ipaserver[0] }}-{{ item }}"

dest: "/root/{{ item }}"

force: true with_items:

- servercert20240601.pem
- cacert.pem

roles:

 role: ipaserver state: present

Additional resources

- man ipa-server-install(1)
- /usr/share/doc/ansible-freeipa/README-server.md

2.8. SETTING THE PARAMETERS FOR A DEPLOYMENT WITH EXTERNAL DNS AND AN EXTERNAL CA AS THE ROOT CA

Complete this procedure to configure the inventory file for installing an IdM server with an external CA as the root CA in an environment that uses an external DNS solution.



NOTE

The inventory file in this procedure uses the **INI** format. You can, alternatively, use the **YAML** or **JSON** formats.

Procedure

1. Create a ~/MyPlaybooks/ directory:

\$ mkdir MyPlaybooks

- 2. Create a ~/MyPlaybooks/inventory file.
- 3. Open the inventory file for editing. Specify the fully-qualified domain names (**FQDN**) of the host you want to use as an IdM server. Ensure that the **FQDN** meets the following criteria:
 - Only alphanumeric characters and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.

- 4. Specify the IdM domain and realm information.
- 5. Make sure that the **ipaserver_setup_dns** option is set to **no** or that it is absent.
- 6. Specify the passwords for **admin** and for the **Directory Manager**. Use the Ansible Vault to store the password, and reference the Vault file from the playbook file. Alternatively and less securely, specify the passwords directly in the inventory file.
- 7. Optional: Specify a custom **firewalld** zone to be used by the IdM server. If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of an inventory file with the required server information (excluding the passwords)

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
[...]
```

Example of an inventory file with the required server information (including the passwords)

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234

[...]
```

Example of an inventory file with a custom firewalld zone

```
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
```

[ipaserver]

ipaserver_firewalld_zone=custom zone

[...]

8. Create a playbook for the first step of the installation. Enter instructions for generating the certificate signing request (CSR) and copying it from the controller to the managed node.

```
-name: Playbook to configure IPA server Step 1
hosts: ipaserver
become: true
vars_files:
- playbook_sensitive_data.yml
vars:
    ipaserver_external_ca: true

roles:
- role: ipaserver
    state: present

post_tasks:
- name: Copy CSR /root/ipa.csr from node to "{{ groups.ipaserver[0] + '-ipa.csr' }}"
fetch:
    src: /root/ipa.csr
    dest: "{{ groups.ipaserver[0] + '-ipa.csr' }}"
flat: true
```

9. Create another playbook for the final step of the installation.

```
- name: Playbook to configure IPA server Step 2
hosts: ipaserver
 become: true
 vars files:
 - playbook_sensitive_data.yml
  ipaserver_external_cert_files:
   - "/root/servercert20240601.pem"
   - "/root/cacert.pem"
 pre_tasks:
 - name: Copy "{{ groups.ipaserver[0] }}-{{ item }}" to "/root/{{ item }}" on node
  ansible.builtin.copy:
   src: "{{ groups.ipaserver[0] }}-{{ item }}"
   dest: "/root/{{ item }}"
   force: true
  with items:
  - servercert20240601.pem
  - cacert.pem
 roles:
 - role: ipaserver
  state: present
```

Additional resources

- Installing an IdM server: Without integrated DNS, with an external CA as the root CA
- man ipa-server-install(1)
- /usr/share/doc/ansible-freeipa/README-server.md

2.9. DEPLOYING AN IDM SERVER WITH AN EXTERNAL CA AS THE ROOT CA USING AN ANSIBLE PLAYBOOK

Complete this procedure to deploy an IdM server with an external certificate authority (CA) as the root CA using an Ansible playbook.

Prerequisites

- The managed node is a Red Hat Enterprise Linux 9 system with a static IP address and a working package manager.
- You have set the parameters that correspond to your scenario by choosing one of the following procedures:
 - Procedure with integrated DNS
 - Procedure with external DNS

Procedure

1. Run the Ansible playbook with the instructions for the first step of the installation, for example **install-server-step1.yml**:

\$ ansible-playbook --vault-password-file=password_file -v -i ~/MyPlaybooks/inventory ~/MyPlaybooks/install-server-step1.yml

- 2. Locate the **ipa.csr** certificate signing request file on the controller and submit it to the external CA.
- 3. Place the IdM CA certificate signed by the external CA in the controller file system so that the playbook in the next step can find it.
- 4. Run the Ansible playbook with the instructions for the final step of the installation, for example **install-server-step2.yml**:

\$ ansible-playbook -v -i ~/MyPlaybooks/inventory ~/MyPlaybooks/install-server-step2.yml

- 5. Choose one of the following options:
 - If your IdM deployment uses external DNS: add the DNS resource records contained in the /tmp/ipa.system.records.UFRPto.db file to the existing external DNS servers. The process of updating the DNS records varies depending on the particular DNS solution.

Restarting the KDC

Please add records in this file to your DNS system:

/tmp/ipa.system.records.UFRBto.db Restarting the web server

. . .



IMPORTANT

The server installation is not complete until you add the DNS records to the existing DNS servers.

- If your IdM deployment uses integrated DNS:
 - Add DNS delegation from the parent domain to the IdM DNS domain. For example, if the IdM DNS domain is *idm.example.com*, add a name server (NS) record to the *example.com* parent domain.



IMPORTANT

Repeat this step each time after an IdM DNS server is installed.

Add an _ntp._udp service (SRV) record for your time server to your IdM DNS. The
presence of the SRV record for the time server of the newly-installed IdM server in IdM
DNS ensures that future replica and client installations are automatically configured to
synchronize with the time server used by this primary IdM server.

2.10. UNINSTALLING AN IDM SERVER USING AN ANSIBLE PLAYBOOK



NOTE

In an existing Identity Management (IdM) deployment, **replica** and **server** are interchangeable terms.

Complete this procedure to uninstall an IdM replica using an Ansible playbook. In this example:

- IdM configuration is uninstalled from **server123.idm.example.com**.
- server123.idm.example.com and the associated host entry are removed from the IdM topology.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
 - You have stored your **ipaadmin_password** in the **secret.yml** Ansible vault.
 - For the **ipaserver_remove_from_topology** option to work, the system must be running on RHEL 9.3 or later.

- On the managed node:
 - The system is running on RHEL 9.

Procedure

1. Create your Ansible playbook file **uninstall-server.yml** with the following content:

- name: Playbook to uninstall an IdM replica

hosts: ipaserver become: true

roles:

- role: ipaserver

ipaserver_remove_from_domain: true

state: absent

The **ipaserver_remove_from_domain** option unenrolls the host from the IdM topology.



NOTE

If the removal of server123.idm.example.com should lead to a disconnected topology, the removal will be aborted. For more information, see Using an Ansible playbook to uninstall an IdM server even if this leads to a disconnected topology.

2. Uninstall the replica:

\$ ansible-playbook --vault-password-file=password_file -v -i <path_to_inventory_directory>/inventory <path_to_playbooks_directory>/uninstall-server.yml

3. Ensure that all name server (NS) DNS records pointing to **server123.idm.example.com** are deleted from your DNS zones. This applies regardless of whether you use integrated DNS managed by IdM or external DNS. For more information on how to delete DNS records from IdM, see Deleting DNS records in the IdM CLI.

2.11. USING AN ANSIBLE PLAYBOOK TO UNINSTALL AN IDM SERVER EVEN IF THIS LEADS TO A DISCONNECTED TOPOLOGY



NOTE

In an existing Identity Management (IdM) deployment, **replica** and **server** are interchangeable terms.

Complete this procedure to uninstall an IdM replica using an Ansible playbook even if this results in a disconnected IdM topology. In the example, **server456.idm.example.com** is used to remove the replica and the associated host entry with the FQDN of **server123.idm.example.com** from the topology, leaving certain replicas disconnected from **server456.idm.example.com** and the rest of the topology.



NOTE

If removing a replica from the topology using only the **remove_server_from_domain** does not result in a disconnected topology, no other options are required. If the result is a disconnected topology, you must specify which part of the domain you want to preserve. In that case, you must do the following:

- Specify the **ipaserver_remove_on_server** value.
- Set ipaserver ignore topology disconnect to True.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - The system is running on RHEL 9.3 or later.
 - You have installed the **ansible-freeipa** package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
 - You have stored your **ipaadmin_password** in the **secret.yml** Ansible vault.
- On the managed node:
 - The system is running on 9 or later.

Procedure

1. Create your Ansible playbook file **uninstall-server.yml** with the following content:

- name: Playbook to uninstall an IdM replica

hosts: ipaserver become: true

roles:

- role: ipaserver

ipaserver_remove_from_domain: true

ipaserver_remove_on_server: server456.idm.example.com

ipaserver_ignore_topology_disconnect: true

state: absent



NOTE

Under normal circumstances, if the removal of server123 does not result in a disconnected topology: if the value for **ipaserver_remove_on_server** is not set, the replica on which server123 is removed is automatically determined using the replication agreements of server123.

2. Uninstall the replica:

\$ ansible-playbook --vault-password_file=password_file -v -i <path_to_inventory_directory>/hosts <path_to_playbooks_directory>/uninstall-server.yml

3. Ensure that all name server (NS) DNS records pointing to **server123.idm.example.com** are deleted from your DNS zones. This applies regardless of whether you use integrated DNS managed by IdM or external DNS. For more information on how to delete DNS records from IdM, see Deleting DNS records in the IdM CLI.

Additional resources

- Inventory basics: formats, hosts, and groups
- You can see sample Ansible playbooks for installing an IdM server and a list of possible variables in the **ansible-freeipa** upstream documentation.

CHAPTER 3. INSTALLING AN IDENTITY MANAGEMENT REPLICA USING AN ANSIBLE PLAYBOOK

Configuring a system as an IdM replica by using Ansible enrolls it into an IdM domain and enables the system to use IdM services on IdM servers in the domain.

The deployment is managed by the **ipareplica** Ansible role. The role can use the autodiscovery mode for identifying the IdM servers, domain and other settings. However, if you deploy multiple replicas in a tierlike model, with different groups of replicas being deployed at different times, you must define specific servers or replicas for each group.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible control node.
- You understand the general Ansible and IdM concepts.
- You have planned the replica topology in your deployment .

3.1. SPECIFYING THE BASE, SERVER AND CLIENT VARIABLES FOR INSTALLING THE IDM REPLICA

Complete this procedure to configure the inventory file for installing an IdM replica.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package on the Ansible controller.

Procedure

- 1. Open the inventory file for editing. Specify the fully-qualified domain names (FQDN) of the hosts to become IdM replicas. The FQDNs must be valid DNS names:
 - Only numbers, alphabetic characters, and hyphens (•) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.

Example of a simple inventory hosts file with only the replicas' FQDN defined

[ipareplicas] replica1.idm.example.com replica2.idm.example.com replica3.idm.example.com [...]

If the IdM server is already deployed and the SRV records are set properly in the IdM DNS zone, the script automatically discovers all the other required values.

2. Optional: Provide additional information in the inventory file based on how you have designed your topology:

Scenario 1

If you want to avoid autodiscovery and have all replicas listed in the **[ipareplicas]** section use a specific IdM server, set the server in the **[ipaservers]** section of the inventory file.

Example inventory hosts file with the FQDN of the IdM server and replicas defined

[ipaservers] server.idm.example.com

[ipareplicas] replica1.idm.example.com replica2.idm.example.com replica3.idm.example.com [...]

Scenario 2

Alternatively, if you want to avoid autodiscovery but want to deploy specific replicas with specific servers, set the servers for specific replicas individually in the **[ipareplicas]** section in the inventory file.

Example inventory file with a specific IdM server defined for a specific replica

[ipaservers] server.idm.example.com replica1.idm.example.com

[ipareplicas]
replica2.idm.example.com
replica3.idm.example.com ipareplica servers=replica1.idm.example.com

In the example above, **replica3.idm.example.com** uses the already deployed **replica1.idm.example.com** as its replication source.

Scenario 3

If you are deploying several replicas in one batch and time is a concern to you, multitier replica deployment can be useful for you. Define specific groups of replicas in the inventory file, for example [ipareplicas_tier1] and [ipareplicas_tier2], and design separate plays for each group in the install-replica.yml playbook.

Example inventory file with replica tiers defined

[ipaservers] server.idm.example.com

[ipareplicas_tier1] replica1.idm.example.com

[ipareplicas_tier2]
replica2.idm.example.com \
ipareplica_servers=replica1.idm.example.com,server.idm.example.com

The first entry in **ipareplica_servers** will be used. The second entry will be used as a fallback option. When using multiple tiers for deploying IdM replicas, you must have separate tasks in the playbook to first deploy replicas from tier1 and then replicas from tier2:

Example of a playbook file with different plays for different replica groups

- name: Playbook to configure IPA replicas (tier1)

hosts: ipareplicas tier1

become: true

roles:

 role: ipareplica state: present

- name: Playbook to configure IPA replicas (tier2)

hosts: ipareplicas tier2

become: true

roles:

 role: ipareplica state: present

3. Optional: Provide additional information regarding **firewalld** and DNS:

Scenario 1

If you want the replica to use a specified **firewalld** zone, for example an internal one, you can specify it in the inventory file. If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of a simple inventory hosts file with a custom firewalld zone

[ipaservers] server.idm.example.com

[ipareplicas] replica1.idm.example.com replica2.idm.example.com replica3.idm.example.com [...]

[ipareplicas:vars] ipareplica_firewalld_zone=custom zone

Scenario 2

If you want the replica to host the IdM DNS service, add the **ipareplica_setup_dns=true** line to the **[ipareplicas:vars]** section. Additionally, specify if you want to use per-server DNS forwarders:

- To configure per-server forwarders, add the ipareplica_forwarders variable and a list of strings to the [ipareplicas:vars] section, for example: ipareplica_forwarders=192.0.2.1,192.0.2.2
- To configure no per-server forwarders, add the following line to the **[ipareplicas:vars]** section: **ipareplica_no_forwarders=true**.
- To configure per-server forwarders based on the forwarders listed in the /etc/resolv.conf file of the replica, add the ipareplica_auto_forwarders variable to the [ipareplicas:vars] section.

Example inventory file with instructions to set up DNS and per-server forwarders on the replicas

```
[ipaservers] server.idm.example.com
```

[ipareplicas] replica1.idm.example.com replica2.idm.example.com replica3.idm.example.com [...]

[ipareplicas:vars] ipareplica_setup_dns=true ipareplica_forwarders=192.0.2.1,192.0.2.2

Scenario 3

Specify the DNS resolver using the **ipaclient_configure_dns_resolve** and **ipaclient_dns_servers** options (if available) to simplify cluster deployments. This is especially useful if your IdM deployment is using integrated DNS:

An inventory file snippet specifying a DNS resolver:

```
[...]
[ipaclient:vars]
ipaclient_configure_dns_resolver=true
ipaclient_dns_servers=192.168.100.1
```



NOTE

The **ipaclient_dns_servers** list must contain only IP addresses. Host names are not allowed.

Additional resources

/usr/share/ansible/roles/ipareplica/README.md

3.2. SPECIFYING THE CREDENTIALS FOR INSTALLING THE IDM REPLICA USING AN ANSIBLE PLAYBOOK

Complete this procedure to configure the authorization for installing the IdM replica.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package on the Ansible controller.

Procedure

- 1. Specify the password of a user authorized to deploy replicas for example the IdM admin.
 - Use the Ansible Vault to store the password, and reference the Vault file from the playbook file, for example **install-replica.yml**:

Example playbook file using principal from inventory file and password from an Ansible Vault file

- name: Playbook to configure IPA replicas

hosts: ipareplicas become: true vars files:

- playbook sensitive data.yml

roles:

 role: ipareplica state: present

For details how to use Ansible Vault, see the official Ansible Vault documentation.

Less securely, provide the credentials of admin directly in the inventory file. Use the
ipaadmin_password option in the [ipareplicas:vars] section of the inventory file. The
inventory file and the install-replica.yml playbook file can then look as follows:

Example inventory hosts.replica file

[...]
[ipareplicas:vars]
ipaadmin_password=Secret123

Example playbook using principal and password from inventory file

- name: Playbook to configure IPA replicas

hosts: ipareplicas become: true

roles:

 role: ipareplica state: present • Alternatively but also less securely, provide the credentials of another user authorized to deploy a replica directly in the inventory file. To specify a different authorized user, use the ipaadmin_principal option for the user name, and the ipaadmin_password option for the password. The inventory file and the install-replica.yml playbook file can then look as follows:

Example inventory hosts.replica file

[...]
[ipareplicas:vars]
ipaadmin_principal=my_admin
ipaadmin_password=my_admin_secret123

Example playbook using principal and password from inventory file

- name: Playbook to configure IPA replicas

hosts: ipareplicas become: true

roles:

 role: ipareplica state: present



NOTE

As of RHEL 9.5, during the installation of an IdM replica, checking if the provided Kerberos principal has the required privilege also extends to checking user ID overrides. As a result, you can deploy a replica using the credentials of an AD administrator that is configured to act as an IdM administrator.

Additional resources

/usr/share/ansible/roles/ipareplica/README.md

3.3. DEPLOYING AN IDM REPLICA USING AN ANSIBLE PLAYBOOK

Complete this procedure to use an Ansible playbook to deploy an IdM replica.

Prerequisites

- The managed node is a Red Hat Enterprise Linux 9 system with a static IP address and a working package manager.
- You have configured the inventory file for installing an IdM replica .
- You have configured the authorization for installing the IdM replica .

Procedure

Run the Ansible playbook:

\$ ansible-playbook -i ~/MyPlaybooks/inventory ~/MyPlaybooks/install-replica.yml

Next steps

• In large deployments, you might want to tune specific parameters of IdM replicas for better performance. Consult the Tuning Performance in Identity Management title to find tuning instructions to best suit your scenario.

3.4. UNINSTALLING AN IDM REPLICA USING AN ANSIBLE PLAYBOOK



NOTE

In an existing Identity Management (IdM) deployment, **replica** and **server** are interchangeable terms. For information on how to uninstall an IdM server, see Uninstalling an IdM server using an Ansible playbook or Using an Ansible playbook to uninstall an IdM server even if this leads to a disconnected topology.

Additional resources

• Introduction to IdM servers and clients

CHAPTER 4. INSTALLING AN IDENTITY MANAGEMENT CLIENT USING AN ANSIBLE PLAYBOOK

Learn more about how to configure a system as an Identity Management (IdM) client by using Ansible. Configuring a system as an IdM client enrolls it into an IdM domain and enables the system to use IdM services on IdM servers in the domain.

The deployment is managed by the **ipaclient** Ansible role. By default, the role uses the autodiscovery mode for identifying the IdM servers, domain and other settings. The role can be modified to have the Ansible playbook use the settings specified, for example in the inventory file.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible control node.
- You are using Ansible version 2.15 or later.
- You understand the general Ansible and IdM concepts.

4.1. SETTING THE PARAMETERS OF THE INVENTORY FILE FOR THE AUTODISCOVERY CLIENT INSTALLATION MODE

To install an Identity Management (IdM) client using an Ansible playbook, configure the target host parameters in an inventory file, for example **inventory**:

- The information about the host
- The authorization for the task

The inventory file can be in one of many formats, depending on the inventory plugins you have. The **INI-like** format is one of Ansible's defaults and is used in the examples below.



NOTE

To use smart cards with the graphical user interface in RHEL, ensure that you include the **ipaclient_mkhomedir** variable in your Ansible playbook.

Procedure

- 1. Open your **inventory** file for editing.
- 2. Specify the fully-qualified hostname (FQDN) of the host to become an IdM client. The fully qualified domain name must be a valid DNS name:
 - Only numbers, alphabetic characters, and hyphens (•) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case. No capital letters are allowed.

If the SRV records are set properly in the IdM DNS zone, the script automatically discovers all the other required values.

Example of a simple inventory hosts file with only the client FQDN defined

[ipaclients] client.idm.example.com [...]

- 3. Specify the credentials for enrolling the client. The following authentication methods are available:
 - The password of a user authorized to enroll clients This is the default option.
 - Use the Ansible Vault to store the password, and reference the Vault file from the playbook file, for example **install-client.yml**, directly:

Example playbook file using principal from inventory file and password from an Ansible Vault file

- name: Playbook to configure IPA clients with username/password

hosts: ipaclients become: true vars_files:

- playbook_sensitive_data.yml

roles:

role: ipaclient state: present

• Less securely, provide the credentials of admin using the ipaadmin_password option in the [ipaclients:vars] section of the inventory/hosts file. Alternatively, to specify a different authorized user, use the ipaadmin_principal option for the user name, and the ipaadmin_password option for the password. The inventory/hosts inventory file and the install-client.yml playbook file can then look as follows:

Example inventory hosts file

[...]
[ipaclients:vars]
ipaadmin_principal=my_admin
ipaadmin_password=Secret123

Example Playbook using principal and password from inventory file

- name: Playbook to unconfigure IPA clients

hosts: ipaclients become: true

roles:

 role: ipaclient state: true

The client keytab from the previous enrollment if it is still available.
 This option is available if the system was previously enrolled as an Identity Management client. To use this authentication method, uncomment the #ipaclient_keytab option, specifying the path to the file storing the keytab, for example in the [ipaclient:vars] section of inventory/hosts.

- A random, one-time password (OTP) to be generated during the enrollment. To use this
 authentication method, use the ipaclient_use_otp=true option in your inventory file. For
 example, you can uncomment the ipaclient_use_otp=true option in the [ipaclients:vars]
 section of the inventory/hosts file. Note that with OTP you must also specify one of the
 following options:
 - The password of a user authorized to enroll clients for example by providing a value for ipadmin_password in the [ipaclients:vars] section of the inventory/hosts file.
 - The admin keytab, for example by providing a value for **ipadmin_keytab** in the **[ipaclients:vars]** section of **inventory/hosts**.
- 4. Optional: Specify the DNS resolver using the **ipaclient_configure_dns_resolve** and **ipaclient_dns_servers** options (if available) to simplify cluster deployments. This is especially useful if your IdM deployment is using integrated DNS:

An inventory file snippet specifying a DNS resolver:

```
[...]
[ipaclients:vars]
ipaadmin_password: "{{ ipaadmin_password }}"
ipaclient_domain=idm.example.com
ipaclient_configure_dns_resolver=true
ipaclient_dns_servers=192.168.100.1
```



NOTE

The **ipaclient_dns_servers** list must contain only IP addresses. Host names are not allowed.

5. Starting with RHEL 9.3, you can also specify the **ipaclient_subid: true** option to have subid ranges configured for IdM users on the IdM level.

Additional resources

- /usr/share/ansible/roles/ipaclient/README.md
- Managing subID ranges manually

4.2. SETTING THE PARAMETERS OF THE INVENTORY FILE WHEN AUTODISCOVERY IS NOT POSSIBLE DURING CLIENT INSTALLATION

To install an Identity Management client using an Ansible playbook, configure the target host parameters in an inventory file, for example **inventory/hosts**:

- The information about the host, the IdM server and the IdM domain or the IdM realm
- The authorization for the task

The inventory file can be in one of many formats, depending on the inventory plugins you have. The **INI-like** format is one of Ansible's defaults and is used in the examples below.



NOTE

To use smart cards with the graphical user interface in RHEL, ensure that you include the **ipaclient mkhomedir** variable in your Ansible playbook.

Procedure

- 1. Specify the fully-qualified hostname (FQDN) of the host to become an IdM client. The fully qualified domain name must be a valid DNS name:
 - Only numbers, alphabetic characters, and hyphens (•) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case. No capital letters are allowed.
- 2. Specify other options in the relevant sections of the **inventory/hosts** file:
 - The FQDN of the servers in the **[ipaservers]** section to indicate which IdM server the client will be enrolled with
 - One of the two following options:
 - The **ipaclient_domain** option in the **[ipaclients:vars]** section to indicate the DNS domain name of the IdM server the client will be enrolled with
 - The **ipaclient_realm** option in the **[ipaclients:vars]** section to indicate the name of the Kerberos realm controlled by the IdM server

Example of an inventory hosts file with the client FQDN, the server FQDN and the domain defined

```
[ipaclients]
client.idm.example.com

[ipaservers]
server.idm.example.com

[ipaclients:vars]
ipaclient_domain=idm.example.com
[...]
```

- 3. Specify the credentials for enrolling the client. The following authentication methods are available:
 - The password of a user authorized to enroll clients This is the default option.
 - Use the Ansible Vault to store the password, and reference the Vault file from the playbook file, for example **install-client.yml**, directly:

Example playbook file using principal from inventory file and password from an Ansible Vault file

 name: Playbook to configure IPA clients with username/password hosts: ipaclients become: true vars_files: playbook_sensitive_data.yml

roles:

role: ipaclient state: present

Less securely, the credentials of admin to be provided using the ipaadmin_password option in the [ipaclients:vars] section of the inventory/hosts file. Alternatively, to specify a different authorized user, use the ipaadmin_principal option for the user name, and the ipaadmin_password option for the password. The install-client.yml playbook file can then look as follows:

Example inventory hosts file

[...]
[ipaclients:vars]
ipaadmin_principal=my_admin
ipaadmin_password=Secret123

Example Playbook using principal and password from inventory file

- name: Playbook to unconfigure IPA clients

hosts: ipaclients become: true

roles:

role: ipaclient state: true

- The client keytab from the previous enrollment if it is still available:
 This option is available if the system was previously enrolled as an Identity Management client. To use this authentication method, uncomment the ipaclient_keytab option, specifying the path to the file storing the keytab, for example in the [ipaclient:vars] section of inventory/hosts.
- A random, one-time password (OTP) to be generated during the enrollment. To use this
 authentication method, use the ipaclient_use_otp=true option in your inventory file. For
 example, you can uncomment the #ipaclient_use_otp=true option in the [ipaclients:vars]
 section of the inventory/hosts file. Note that with OTP you must also specify one of the
 following options:
 - The password of a user authorized to enroll clients for example by providing a value for ipadmin_password in the [ipaclients:vars] section of the inventory/hosts file.
 - The admin keytab, for example by providing a value for ipaadmin_keytab in the [ipaclients:vars] section of inventory/hosts.
- 4. Starting with RHEL 9.3, you can also specify the **ipaclient_subid: true** option to have subid ranges configured for IdM users on the IdM level.

Additional resources

- /usr/share/ansible/roles/ipaclient/README.md
- Managing subID ranges manually

4.3. AUTHORIZATION OPTIONS FOR IDM CLIENT ENROLLMENT USING AN ANSIBLE PLAYBOOK

You can authorize IdM client enrollment by using any of the following methods:

- A random, one-time password (OTP) + administrator password
- A random, one-time password (OTP) + an admin keytab
- The client keytab from the previous enrollment
- The password of a user authorized to enroll a client (admin) stored in an inventory file
- The password of a user authorized to enroll a client (admin) stored in an Ansible vault

It is possible to have the OTP generated by an IdM administrator before the IdM client installation. In that case, you do not need any credentials for the installation other than the OTP itself.

The following are sample inventory files for these methods:

Table 4.1. Sample inventory files

Authorization option	Inventory file
A random, one-time password (OTP) + administrator password	[ipaclients:vars] ipaadmin_password=Secret123 ipaclient_use_otp=true
A random, one-time password (OTP)	[ipaclients:vars] ipaclient_otp= <w5ypari=7m.> This scenario assumes that the OTP was already generated by an IdM admin before the installation.</w5ypari=7m.>
A random, one-time password (OTP) + an admin keytab	[ipaclients:vars] ipaadmin_keytab=/root/admin.keytab ipaclient_use_otp=true
The client keytab from the previous enrollment	[ipaclients:vars] ipaclient_keytab=/root/krb5.keytab
Password of an admin user stored in an inventory file	[ipaclients:vars] ipaadmin_password=Secret123

Authorization option	Inventory file
Password of an admin user stored in an Ansible vault file	[ipaclients:vars] []

If you are using the password of an **admin** user stored in an Ansible vault file, the corresponding playbook file must have an additional **vars_files** directive:

Table 4.2. User password stored in an Ansible vault

Inventory file	Playbook file
[ipaclients:vars] []	 name: Playbook to configure IPA clients hosts: ipaclients become: true vars_files: - ansible_vault_file.yml roles: - role: ipaclient state: present

In all the other authorization scenarios described above, a basic playbook file could look as follows:

- name: Playbook to configure IPA clients

hosts: ipaclients become: true

roles:

role: ipaclient state: true



NOTE

As of RHEL 9.2, in the two OTP authorization scenarios described above, the requesting of the administrator's TGT by using the **kinit** command occurs on the first specified or discovered IdM server. Therefore, no additional modification of the Ansible control node is required. Before RHEL 9.2, the **krb5-workstation** package was required on the control node.

4.4. DEPLOYING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK

Complete this procedure to use an Ansible playbook to deploy an IdM client in your IdM environment.

Prerequisites

- The managed node is a Red Hat Enterprise Linux 9 system with a static IP address and a working package manager.
- You have set the parameters of the IdM client deployment to correspond to your deployment scenario:
 - Setting the parameters of the inventory file for the autodiscovery client installation mode
 - Setting the parameters of the inventory file when autodiscovery is not possible during client installation

Procedure

• Run the Ansible playbook:

\$ ansible-playbook -v -i ~/MyPlaybooks/inventory ~/MyPlaybooks/install-client.yml

4.5. USING THE ONE-TIME PASSWORD METHOD IN ANSIBLE TO INSTALL AN IDM CLIENT

You can generate a one-time password (OTP) for a new host in Identity Management (IdM) and use it to enroll a system into the IdM domain. This procedure describes how to use Ansible to install an IdM client after generating an OTP for it on another IdM host.

This method of installing an IdM client is convenient if two system administrators with different privileges exist in your organisation:

- One that has the credentials of an IdM administrator.
- Another that has the required Ansible credentials, including root access to the host to become an IdM client.

The IdM administrator performs the first part of the procedure in which the OTP password is generated. The Ansible administrator performs the remaining part of the procedure in which the OTP is used to install an IdM client.

Prerequisites

- You have the IdM **admin** credentials or at least the **Host Enrollment** privilege and a permission to add DNS records in IdM.
- You have configured a user escalation method on the Ansible managed node to allow you to install an IdM client.
- If your Ansible control node is running on RHEL 8.7 or earlier, you must be able to install packages on your Ansible control node.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package on the Ansible controller.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.

• The managed node is a Red Hat Enterprise Linux 9 system with a static IP address and a working package manager.

Procedure

1. **SSH** to an IdM host as an IdM user with a role that has the **Host Enrollment** privilege and a permission to add DNS records:

\$ ssh admin@server.idm.example.com

2. Generate an OTP for the new client:

The **--ip-address=** *your_host_ip_address>* option adds the host to IdM DNS with the specified IP address.

3. Exit the IdM host:

\$ exit

logout

Connection to server.idm.example.com closed.

4. On the ansible controller, update the inventory file to include the random password:

```
[...]
[ipaclients]
client.idm.example.com

[ipaclients:vars]
ipaclient_domain=idm.example.com
ipaclient_otp=W5YpARI=7M.n
[...]
```

5. If your ansible controller is running RHEL ← 9.1, install the **kinit** utility provided by the **krb5-workstation** package:

\$ sudo dnf install krb5-workstation

6. Run the playbook to install the client:

\$ ansible-playbook -i inventory install-client.yml

4.6. TESTING AN IDENTITY MANAGEMENT CLIENT AFTER ANSIBLE INSTALLATION

The command line (CLI) informs you that the **ansible-playbook** command was successful, but you can also do your own test.

To test that the Identity Management client can obtain information about users defined on the server, check that you are able to resolve a user defined on the server. For example, to check the default **admin** user:

[user@client1 ~]\$ **id admin** uid=1254400000(admin) gid=1254400000(admins) groups=1254400000(admins)

To test that authentication works correctly, **su** - as another already existing IdM user:

[user@client1 ~]\$ **su - idm_user**Last login: Thu Oct 18 18:39:11 CEST 2018 from 192.168.122.1 on pts/0
[idm_user@client1 ~]\$

4.7. UNINSTALLING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK

Complete this procedure to use an Ansible playbook to uninstall your host as an IdM client.

Prerequisites

- IdM administrator credentials.
- The managed node is a Red Hat Enterprise Linux 9 system with a static IP address.

Procedure

 Run the Ansible playbook with the instructions to uninstall the client, for example uninstallclient.yml:

\$ ansible-playbook -v -i ~/MyPlaybooks/inventory ~/MyPlaybooks/uninstall-client.yml



IMPORTANT

The uninstallation of the client only removes the basic IdM configuration from the host but leaves the configuration files on the host in case you decide to re-install the client. In addition, the uninstallation has the following limitations:

- It does not remove the client host entry from the IdM LDAP server. The uninstallation only unenrolls the host.
- It does not remove any services residing on the client from IdM.
- It does not remove the DNS entries for the client from the IdM server.
- It does not remove the old principals for keytabs other than /etc/krb5.keytab.

Note that the uninstallation does remove all certificates that were issued for the host by the IdM CA.

Additional resources

• Uninstalling an IdM client

CHAPTER 5. PREPARING YOUR ENVIRONMENT FOR MANAGING IDM USING ANSIBLE PLAYBOOKS

As a system administrator managing Identity Management (IdM), when working with Red Hat Ansible Engine, it is good practice to do the following:

- Keep a subdirectory dedicated to Ansible playbooks in your home directory, for example ~/MyPlaybooks.
- Copy and adapt sample Ansible playbooks from the /usr/share/doc/ansible-freeipa/* and /usr/share/doc/rhel-system-roles/* directories and subdirectories into your ~/MyPlaybooks directory.
- Include your inventory file in your ~/MyPlaybooks directory.

Using this practice, you can find all your playbooks in one place.



NOTE

You can run your **ansible-freeipa** playbooks without invoking **root** privileges on the managed nodes. Exceptions include playbooks that use the **ipaserver**, **ipareplica**, **ipaclient**, **ipasmartcard_server**, **ipasmartcard_client** and **ipabackup ansible-freeipa** roles. These roles require privileged access to directories and the **dnf** software package manager.

The playbooks in the Red Hat Enterprise Linux IdM documentation assume the following security configuration:

- The IdM **admin** is your remote Ansible user on the managed nodes.
- You store the IdM **admin** password encrypted in an Ansible vault.
- You have placed the password that protects the Ansible vault in a password file.
- You block access to the vault password file to everyone except your local ansible user.
- You regularly remove and re-create the vault password file.

Consider also alternative security configurations.

5.1. PREPARING A CONTROL NODE AND MANAGED NODES FOR MANAGING IDM USING ANSIBLE PLAYBOOKS

Follow this procedure to create the **~/MyPlaybooks** directory and configure it so that you can use it to store and run Ansible playbooks.

Prerequisites

- You have installed an IdM server on your managed nodes, **server.idm.example.com** and **replica.idm.example.com**.
- You have configured DNS and networking so you can log in to the managed nodes, server.idm.example.com and replica.idm.example.com, directly from the control node.

You know the IdM admin password.

Procedure

1. Change into the ~/MyPlaybooks/ directory:

```
$ cd ~/MyPlaybooks
```

2. Create the ~/MyPlaybooks/ansible.cfg file with the following content:

```
[defaults] inventory = /home/your_username/MyPlaybooks/inventory remote_user = admin
```

3. Create the ~/MyPlaybooks/inventory file with the following content:

```
[eu]
server.idm.example.com

[us]
replica.idm.example.com

[ipaserver:children]
eu
us
```

This configuration defines two host groups, **eu** and **us**, for hosts in these locations. Additionally, this configuration defines the **ipaserver** host group, which contains all hosts from the **eu** and **us** groups.

4. Optional: Create an SSH public and private key. To simplify access in your test environment, do not set a password on the private key:

\$ ssh-keygen

5. Copy the SSH public key to the IdM **admin** account on each managed node:

```
$ ssh-copy-id admin@server.idm.example.com
$ ssh-copy-id admin@replica.idm.example.com
```

These commands require that you enter the IdM **admin** password.

6. Create a password_file file that contains the vault password:

redhat

7. Change the permissions to modify the file:

\$ chmod 0600 password_file

- 8. Create a **secret.yml** Ansible vault to store the IdM **admin** password:
 - a. Configure password_file to store the vault password:

\$ ansible-vault create --vault-password-file=password_file secret.yml

b. When prompted, enter the content of the **secret.yml** file:

ipaadmin_password: Secret123

NOTE

To use the encrypted **ipaadmin_password** in a playbook, you must use the **vars_file** directive. For example, a simple playbook to delete an IdM user can look as follows:

- name: Playbook to handle users

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Delete user robot

ipauser:

ipaadmin_password: "{{ ipaadmin_password }}"

name: robot state: absent

When executing a playbook, instruct Ansible use the vault password to decrypt **ipaadmin_password** by adding the **--vault-password-file=**password_file option. For example:

ansible-playbook -i inventory --vault-password-file=password_file del-user.yml



WARNING

For security reasons, remove the vault password file at the end of each session, and repeat steps 6-8 at the start of each new session.

Additional resources

- Different methods to provide the credentials required for ansible-freeipa playbooks
- Installing an Identity Management server using an Ansible playbook
- How to build your inventory

5.2. DIFFERENT METHODS TO PROVIDE THE CREDENTIALS REQUIRED FOR ANSIBLE-FREEIPA PLAYBOOKS

There are advantages and disadvantages in the different methods for providing the credentials required for running playbooks that use **ansible-freeipa** roles and modules.

Storing passwords in plain text in a playbook

Benefits:

- Not being prompted all the time you run the playbook.
- Easy to implement.

Drawbacks:

- Everyone with access to the file can read the password. Setting wrong permissions and sharing the file, for example in an internal or external repository, can compromise security.
- High maintenance work: if the password is changed, it needs to be changed in all playbooks.

Entering passwords interactively when you execute a playbook

Benefits:

- No-one can steal the password as it is not stored anywhere.
- You can update the password easily.
- Easy to implement.

Drawbacks:

• If you are using Ansible playbooks in scripts, the requirement to enter the password interactively can be inconvenient.

Storing passwords in an Ansible vault and the vault password in a file:

Benefits:

- The user password is stored encrypted.
- You can update the user password easily, by creating a new Ansible vault.
- You can update the password file that protects the ansible vault easily, by using the ansible-vault rekey --new-vault-password-file=NEW_VAULT_PASSWORD_FILE secret.yml command.
- If you are using Ansible playbooks in scripts, it is convenient not to have to enter the password protecting the Ansible vault interactively.

Drawbacks:

• It is vital that the file that contains the sensitive plain text password be protected through file permissions and other security measures.

Storing passwords in an Ansible vault and entering the vault password interactively

Benefits:

• The user password is stored encrypted.

- No-one can steal the vault password as it is not stored anywhere.
- You can update the user password easily, by creating a new Ansible vault.
- You can update the vault password easily too, by using the ansible-vault rekey file_name command.

Drawbacks:

• If you are using Ansible playbooks in scripts, the need to enter the vault password interactively can be inconvenient.

Additional resources

- Preparing a control node and managed nodes for managing IdM using Ansible playbooks
- What is Zero trust?
- Protecting sensitive data with Ansible vault

5.3. THE INVENTORY PLUGIN IN ANSIBLE-FREEIPA

You can use the **ansible-freeipa freeipa** inventory plugin to create dynamic inventories of Identity Management (IdM) servers to be used in **ansible-freeipa** playbooks. The plugin gathers data about the IdM servers in the domain, and selects only those that have a specified IdM server role or roles assigned. To use the plugin with the **ansible-playbook** command, set the value of the **-i** option to the inventory file that uses the **freeipa** plugin. As a result, the plays in the playbook are executed only against those servers that have the roles specified in the inventory file.

The example below describes how to use the **freeipa** plugin to determine the versions of the **bind** package on the IdM servers in the topology that have the DNS role.

Procedure

1. Create a file, for example **inventory.yml**, to generate a dynamic inventory based on your selected IdM server role or roles. For example, to create an inventory of servers that have the IdM DNS server role:

plugin: freeipa

server: server.idm.example.com ipaadmin password: Secret123

verify: ca.crt role: DNS server

- **server** defines the fully-qualified domain name of the host to start the scan.
- **verify** defines the server TLS certificate file for verification.
- role defines all the server roles that a host must have for the host to be returned.
- 2. Create a playbook, for example **bind-playbook.yml**, that you want to execute against the IdM servers identified by the **freeipa** inventory plugin. For example, to determine the release version of the **bind** package installed on the IdM DNS servers:

```
---
- name: Check bind version
hosts: ipaservers

tasks:
- name: Query bind package version
package:
    name: bind
    state: present
register: bind_version

- name: Display bind release info
debug:
    msg: "Bind release: {{ bind_version.results[0].version }}"
```

3. Optional: Create a graph representation of the IdM servers identified by the plugin:

```
$ ansible-inventory -i inventory.yml --graph @all:
|--@ungrouped
|--@ipaservers:
| |--replica01.idm.example.com
```

4. Run the Ansible playbook. Specify the inventory.yml file as inventory:

```
$ ansible-playbook -i inventory.yml bind-playbook.yml
[...]
TASK [Display bind release info]
ok: [10.0.193.174] => {
   "msg": "Bind release: 9.20.3"
}
[...]
```

CHAPTER 6. CONFIGURING GLOBAL IDM SETTINGS USING ANSIBLE PLAYBOOKS

Using the Ansible **config** module, you can retrieve and set global configuration parameters for Identity Management (IdM).

- Retrieving IdM configuration using an Ansible playbook
- Configuring the IdM CA renewal server using an Ansible playbook
- Configuring the default shell for IdM users using an Ansible playbook
- Configuring a NETBIOS name for an IdM domain by using Ansible
- Ensuring that IdM users and groups have SIDs by using Ansible

6.1. RETRIEVING IDM CONFIGURATION USING AN ANSIBLE PLAYBOOK

The following procedure describes how you can use an Ansible playbook to retrieve information about the current global IdM configuration.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

 Open the /usr/share/doc/ansible-freeipa/playbooks/config/retrieve-config.yml Ansible playbook file for editing:

- name: Playbook to handle global IdM configuration

hosts: ipaserver become: no gather_facts: no

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks:
- name: Query IPA global configuration ipaconfig:

ipaadmin password: "{{ ipaadmin password }}"

```
register: serverconfig
- debug:
  msg: "{{ serverconfig }}"
```

- 2. Adapt the file by changing the following:
 - The password of IdM administrator.
 - Other values, if necessary.
- 3. Save the file.
- 4. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

```
$ ansible-playbook --vault-password-file=password_file -v -i
path_to_inventory_directory/inventory.file /usr/share/doc/ansible-
freeipa/playbooks/config/retrieve-config.yml
[...]
TASK [debug]
ok: [server.idm.example.com] => {
  "msg": {
     "ansible facts": {
       "discovered_interpreter_
     "changed": false,
     "config": {
       "ca renewal master server": "server.idm.example.com",
       "configstring": [
          "AllowNThash",
          "KDC:Disable Last Success"
       ],
       "defaultgroup": "ipausers",
       "defaultshell": "/bin/bash",
       "emaildomain": "idm.example.com",
       "enable migration": false,
       "groupsearch": [
          "cn",
          "description"
       "homedirectory": "/home",
       "maxhostname": "64",
       "maxusername": "64",
       "pac_type": [
          "MS-PAC",
          "nfs:NONE"
       ],
       "pwdexpnotify": "4",
       "searchrecordslimit": "100",
       "searchtimelimit": "2",
       "selinuxusermapdefault": "unconfined u:s0-s0:c0.c1023",
       "selinuxusermaporder": [
          "guest_u:s0$xguest_u:s0$user_
       "usersearch": [
```

6.2. CONFIGURING THE IDM CA RENEWAL SERVER USING AN ANSIBLE PLAYBOOK

In an Identity Management (IdM) deployment that uses an embedded certificate authority (CA), the CA renewal server maintains and renews IdM system certificates. It ensures robust IdM deployments.

For more details on the role of the IdM CA renewal server, see Using IdM CA renewal server.

The following procedure describes how you can use an Ansible playbook to configure the IdM CA renewal server.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the secret.yml Ansible vault stores your ipaadmin_password.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Optional: Identify the current IdM CA renewal server:

```
$ ipa config-show | grep 'CA renewal'
IPA CA renewal master: server.idm.example.com
```

2. Create an inventory file, for example inventory.file, and define ipaserver in it:

```
[ipaserver] server.idm.example.com
```

3. Open the /usr/share/doc/ansible-freeipa/playbooks/config/set-ca-renewal-master-server.yml Ansible playbook file for editing:

- name: Playbook to handle global DNS configuration

hosts: ipaserver become: no gather_facts: no vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

name: set ca_renewal_master_server ipaconfig:

ipaadmin_password: "{{ ipaadmin_password }}"

ca renewal master server: carenewal.idm.example.com

- 4. Adapt the file by changing:
 - The password of IdM administrator set by the **ipaadmin_password** variable.
 - The name of the CA renewal server set by the **ca_renewal_master_server** variable.
- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/config/set-ca-renewal-master-server.yml

Verification

You can verify that the CA renewal server has been changed:

1. Log into **ipaserver** as IdM administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Request the identity of the IdM CA renewal server:

\$ ipa config-show | grep 'CA renewal'
IPA CA renewal master: carenewal.idm.example.com

The output shows the **carenewal.idm.example.com** server is the new CA renewal server.

6.3. CONFIGURING THE DEFAULT SHELL FOR IDM USERS USING AN ANSIBLE PLAYBOOK

The shell is a program that accepts and interprets commands. Several shells are available in Red Hat Enterprise Linux (RHEL), such as **bash**, **sh**, **ksh**, **zsh**, **fish**, and others. **Bash**, or /**bin/bash**, is a popular shell on most Linux systems, and it is normally the default shell for user accounts on RHEL.

The following procedure describes how you can use an Ansible playbook to configure **sh**, an alternative shell, as the default shell for IdM users.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

- 1. Optional: Use the **retrieve-config.yml** Ansible playbook to identify the current shell for IdM users. See Retrieving IdM configuration using an Ansible playbook for details.
- 2. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

3. Open the /usr/share/doc/ansible-freeipa/playbooks/config/ensure-config-options-areset.yml Ansible playbook file for editing:

- name: Playbook to ensure some config options are set

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

Set defaultlogin and maxusername

- ipaconfig:

ipaadmin_password: "{{ ipaadmin_password }}"

defaultshell: /bin/bash maxusername: 64

- 4. Adapt the file by changing the following:
 - The password of IdM administrator set by the **ipaadmin password** variable.
 - The default shell of the IdM users set by the **defaultshell** variable into /bin/sh.
- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/config/ensure-config-options-are-set.yml

Verification

You can verify that the default user shell has been changed by starting a new session in IdM:

1. Log into **ipaserver** as IdM administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server /]\$

2. Display the current shell:

[admin@server /]\$ echo "\$SHELL" /bin/sh

The logged-in user is using the **sh** shell.

6.4. CONFIGURING A NETBIOS NAME FOR AN IDM DOMAIN BY USING ANSIBLE

The NetBIOS name is used for Microsoft Windows' (SMB) type of sharing and messaging. You can use NetBIOS names to map a drive or connect to a printer.

Follow this procedure to use an Ansible playbook to configure a NetBIOS name for your Identity Management (IdM) domain.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - The ansible-freeipa package is installed.

Assumptions

- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password** and that you know the vault file password.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Create a netbios-domain-name-present.yml Ansible playbook file.

3. Add the following content to the file:

- name: Playbook to change IdM domain netbios name

hosts: ipaserver become: no gather_facts: no

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Set IdM domain netbios name

ipaconfig:

ipaadmin_password: "{{ ipaadmin_password }}"

netbios_name: IPADOM

- 4. Save the file.
- 5. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory *netbios-domain-name-present.yml*

When prompted, provide the vault file password.

Additional resources

Guidelines for configuring NetBIOS names

6.5. ENSURING THAT IDM USERS AND GROUPS HAVE SIDS BY USING ANSIBLE

The Identity Management (IdM) server can assign unique security identifiers (SIDs) to IdM users and groups internally, based on the data from the ID ranges of the local domain. The SIDs are stored in the user and group objects.

The goal of ensuring that IdM users and groups have SIDs is to allow the generation of the Privileged Attribute Certificate (PAC), which is the first step towards IdM-IdM trusts. If IdM users and groups have SIDs, IdM is able to issue Kerberos tickets with PAC data.

Follow this procedure to achieve the following goals:

- Generate SIDs for already existing IdM users and user groups.
- Enable the generation of SIDs for IdM new users and groups.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.

• The ansible-freeipa package is installed.

Assumptions

- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password** and that you know the vault file password.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

- 2. Create a sids-for-users-and-groups-present.yml Ansible playbook file.
- 3. Add the following content to the file:

- name: Playbook to ensure SIDs are enabled and users and groups have SIDs

hosts: ipaserver become: no gather_facts: no

vars files:

- /home/user name/MyPlaybooks/secret.yml

tasks:

- name: Enable SID and generate users and groups SIDS

ipaconfig:

ipaadmin_password: "{{ ipaadmin_password }}"

enable_sid: true add_sids: true

The **enable_sid** variable enables SID generation for future IdM users and groups. The **add_sids** variable generates SIDs for existing IdM users and groups.



NOTE

When using add_sids: true, you must also set the enable_sid variable to true.

- 4. Save the file.
- 5. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory sids-for-users-and-groups-present.yml

When prompted, provide the vault file password.

Additional resources

• The role of security and relative identifiers in IdM ID ranges .

6.6. ADDITIONAL RESOURCES

- See **README-config.md** in the /usr/share/doc/ansible-freeipa/ directory.
- See sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/config directory.


CHAPTER 7. MANAGING USER ACCOUNTS USING ANSIBLE PLAYBOOKS

You can manage users in IdM using Ansible playbooks. After presenting the user life cycle, learn how to use Ansible playbooks to ensure the presence or absence of users listed directly directly in the **YML** file.

7.1. USER LIFE CYCLE

Identity Management (IdM) supports three user account states:

- **Stage** users are not allowed to authenticate. This is an initial state. Some of the user account properties required for active users cannot be set, for example, group membership.
- Active users are allowed to authenticate. All required user account properties must be set in this state.
- **Preserved** users are former active users that are considered inactive and cannot authenticate to IdM. Preserved users retain most of the account properties they had as active users, but they are not part of any user groups.



You can delete user entries permanently from the IdM database.



IMPORTANT

Deleted user accounts cannot be restored. When you delete a user account, all the information associated with the account is permanently lost.

A new administrator can only be created by a user with administrator rights, such as the default admin user. If you accidentally delete all administrator accounts, the Directory Manager must create a new administrator manually in the Directory Server.



WARNING

Do not delete the **admin** user. As **admin** is a pre-defined user required by IdM, this operation causes problems with certain commands. If you want to define and use an alternative admin user, disable the pre-defined **admin** user with **ipa user-disable admin** after you granted admin permissions to at least one different user.



WARNING

Do not add local users to IdM. The Name Service Switch (NSS) always resolves IdM users and groups before resolving local users and groups. This means that, for example, IdM group membership does not work for local users.

7.2. ENSURING THE PRESENCE OF AN IDM USER USING AN ANSIBLE PLAYBOOK

The following procedure describes ensuring the presence of a user in IdM using an Ansible playbook.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the data of the user whose presence in IdM you want to ensure. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/user/add-user.yml file. For example, to create user named idm_user and add Password123 as the user password:

- name: Playbook to handle users

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Create user idm_user

ipauser:

ipaadmin_password: "{{ ipaadmin_password }}"

name: idm_user first: Alice last: Acme uid: 1000111 gid: 10011

phone: "+555123457"

email: idm_user@acme.com

passwordexpiration: "2023-01-19 23:59:59"

password: "Password123" update_password: on_create

You must use the following options to add a user:

• name: the login name

• first: the first name string

• last: the last name string

For the full list of available user options, see the /usr/share/doc/ansible-freeipa/README-user.md Markdown file.



NOTE

If you use the **update_password: on_create** option, Ansible only creates the user password when it creates the user. If the user is already created with a password, Ansible does not generate a new password.

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/add-ldM-user.yml

Verification

- You can verify if the new user account exists in IdM by using the **ipa user-show** command:
 - 1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Request information about idm_user.

\$ ipa user-show idm_user

User login: idm_user First name: Alice Last name: Acme

• • • •

The user named *idm_user* is present in IdM.

7.3. ENSURING THE PRESENCE OF MULTIPLE IDM USERS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of multiple users in IdM using an Ansible playbook.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the data of the users whose presence you want to ensure in IdM. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/user/ensure-users-present.yml file. For example, to create users idm_user_1, idm_user_2, and idm_user_3, and add Password123 as the password of idm_user_1:

- name: Playbook to handle users

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks: name: Create user idm_users ipauser: ipaadmin_password: "{{ ipaadmin_password }}" - name: idm user 1 first: Alice last: Acme uid: 10001 gid: 10011 phone: "+555123457" email: idm_user@acme.com passwordexpiration: "2023-01-19 23:59:59" password: "Password123" - name: idm_user_2 first: Bob last: Acme uid: 100011 gid: 10011 - name: idm_user_3 first: Eve last: Acme uid: 1000111 gid: 10011



NOTE

If you do not specify the **update_password**: **on_create** option, Ansible resets the user password every time the playbook is run: if the user has changed the password since the last time the playbook was run, Ansible resets password.

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/addusers.yml

Verification

- You can verify if the user account exists in IdM by using the **ipa user-show** command:
 - 1. Log into **ipaserver** as administrator:

\$ ssh administrator@server.idm.example.com Password: [admin@server /]\$

2. Display information about idm_user_1:

\$ ipa user-show idm_user_1
User login: idm_user_1
First name: Alice
Last name: Acme
Password: True
....

The user named idm_user_1 is present in IdM.

7.4. ENSURING THE PRESENCE OF MULTIPLE IDM USERS FROM A JSON FILE USING ANSIBLE PLAYBOOKS

The following procedure describes how you can ensure the presence of multiple users in IdM using an Ansible playbook. The users are stored in a **JSON** file.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary tasks. Reference the **JSON** file with the data of the users whose presence you want to ensure. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/README-user.md file:

- name: Ensure users' presence

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Include users_present.json

include_vars:

file: users_present.json

- name: Users present

ipauser:

ipaadmin_password: "{{ ipaadmin_password }}"

users: "{{ users }}"

 Create the users.json file, and add the IdM users into it. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/README-user.md file. For example, to create users idm_user_1, idm_user_2, and idm_user_3, and add Password123 as the password of idm_user_1:

```
{
  "users": [
     {
      "name": "idm_user_1",
      "first": "First 1",
      "password": "Password123"
     },
     {
      "name": "idm_user_2",
      "first": "First 2",
      "last": "Last 2"
     },
     {
      "name": "idm_user_3",
      "first": "First 3",
      "last": "Last 3"
     }
     ]
}
```

2. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-userspresent-jsonfile.yml

Verification

- You can verify if the user accounts are present in IdM using the **ipa user-show** command:
 - 1. Log into **ipaserver** as administrator:

```
$ ssh administrator@server.idm.example.com
Password:
[admin@server /]$
```

2. Display information about idm_user_1:

```
$ ipa user-show idm_user_1
User login: idm_user_1
First name: Alice
Last name: Acme
Password: True
....
```

The user named *idm_user_1* is present in IdM.

7.5. ENSURING THE ABSENCE OF USERS USING ANSIBLE PLAYBOOKS

The following procedure describes how you can use an Ansible playbook to ensure that specific users are absent from IdM.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

 Create an Ansible playbook file with the users whose absence from IdM you want to ensure. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansiblefreeipa/playbooks/user/ensure-users-present.yml file. For example, to delete users idm_user_1, idm_user_2, and idm_user_3:

```
---
- name: Playbook to handle users
hosts: ipaserver

vars_files:
- /home/user_name/MyPlaybooks/secret.yml
tasks:
- name: Delete users idm_user_1, idm_user_2, idm_user_3
ipauser:
    ipaadmin_password: "{{ ipaadmin_password }}"
    users:
    - name: idm_user_1
    - name: idm_user_2
    - name: idm_user_3
    state: absent
```

3. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/deleteusers.yml

Verification

You can verify that the user accounts do not exist in IdM by using the **ipa user-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh administrator@server.idm.example.com Password: [admin@server/]\$

2. Request information about idm_user_1:

\$ ipa user-show idm_user_1 ipa: ERROR: idm_user_1: user not found

The user named *idm_user_1* does not exist in IdM.

7.6. ADDITIONAL RESOURCES

- See the **README-user.md** Markdown file in the /usr/share/doc/ansible-freeipa/ directory.
- See sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/user directory.

CHAPTER 8. MANAGING USER GROUPS USING ANSIBLE PLAYBOOKS

This section introduces user group management using Ansible playbooks.

A user group is a set of users with common privileges, password policies, and other characteristics.

A user group in Identity Management (IdM) can include:

- IdM users
- other IdM user groups
- external users, which are users that exist outside of IdM

8.1. THE DIFFERENT GROUP TYPES IN IDM

IdM supports the following types of groups:

POSIX groups (the default)

POSIX groups support Linux POSIX attributes for their members. Note that groups that interact with Active Directory cannot use POSIX attributes.

POSIX attributes identify users as separate entities. Examples of POSIX attributes relevant to users include **uidNumber**, a user number (UID), and **gidNumber**, a group number (GID).

Non-POSIX groups

Non-POSIX groups do not support POSIX attributes. For example, these groups do not have a GID defined

All members of this type of group must belong to the IdM domain.

External groups

Use external groups to add group members that exist in an identity store outside of the IdM domain, such as:

- A local system
- An Active Directory domain
- A directory service

External groups do not support POSIX attributes. For example, these groups do not have a GID defined.

Table 8.1. User groups created by default

Group name	Default group members
ipausers	All IdM users
admins	Users with administrative privileges, including the default admin user

Group name	Default group members
editors	This is a legacy group that no longer has any special privileges
trust admins	Users with privileges to manage the Active Directory trusts

When you add a user to a user group, the user gains the privileges and policies associated with the group. For example, to grant administrative privileges to a user, add the user to the **admins** group.



WARNING

Do not delete the **admins** group. As **admins** is a pre-defined group required by IdM, this operation causes problems with certain commands.

In addition, IdM creates *user private groups* by default whenever a new user is created in IdM. For more information about private groups, see Adding users without a private group.


8.2. DIRECT AND INDIRECT GROUP MEMBERS

User group attributes in IdM apply to both direct and indirect members: when group B is a member of group A, all users in group B are considered indirect members of group A.

For example, in the following diagram:

- User 1 and User 2 are direct members of group A.
- User 3, User 4, and User 5 are indirect members of group A.

Figure 8.1. Direct and Indirect Group Membership



640 RHEL 0424

If you set a password policy for user group A, the policy also applies to all users in user group B.

8.3. ENSURING THE PRESENCE OF IDM GROUPS AND GROUP MEMBERS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of IdM groups and group members - both users and user groups - using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The users you want to reference in your Ansible playbook exist in IdM. For details on ensuring the presence of users using Ansible, see Managing user accounts using Ansible playbooks.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver] server.idm.example.com
```

2. Create an Ansible playbook file with the necessary user and group information:

```
- name: Playbook to handle groups
hosts: ipaserver
vars_files:
- /home/user_name/MyPlaybooks/secret.yml
- name: Create group ops with gid 1234
   ipaadmin_password: "{{ ipaadmin_password }}"
   name: ops
   gidnumber: 1234
- name: Create group sysops
  ipagroup:
   ipaadmin password: "{{ ipaadmin password }}"
   name: sysops
   user:
   - idm_user
 - name: Create group appops
  ipagroup:
   ipaadmin_password: "{{ ipaadmin_password }}"
```

name: appops

- name: Add group members sysops and appops to group ops

ipagroup:

ipaadmin_password: "{{ ipaadmin_password }}"

name: ops group: - sysops - appops

3. Run the playbook:

\$ ansible-playbook --vault-password_file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/add-groupmembers.yml

Verification

You can verify if the **ops** group contains **sysops** and **appops** as direct members and **idm_user** as an indirect member by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Display information about ops:

ipaserver]\$ ipa group-show ops

Group name: ops

GID: 1234

Member groups: sysops, appops Indirect Member users: idm_user

The appops and sysops groups - the latter including the idm_user user - exist in IdM.

Additional resources

• See the /usr/share/doc/ansible-freeipa/README-group.md Markdown file.

8.4. USING ANSIBLE TO ADD MULTIPLE IDM GROUPS IN A SINGLE TASK

You can use the **ansible-freeipa ipagroup** module to add, modify, and delete multiple Identity Management (IdM) user groups with a single Ansible task. For that, use the **groups** option of the **ipagroup** module.

Using the **groups** option, you can also specify multiple group variables that only apply to a particular group. Define this group by the **name** variable, which is the only mandatory variable for the **groups** option.

Complete this procedure to ensure the presence of the **sysops** and the **appops** groups in IdM in a single task. Define the sysops group as a nonposix group and the appops group as an external group.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
 - You are using RHEL 9.3 and later.
 - You have stored your **ipaadmin password** in the **secret.yml** Ansible vault.

Procedure

1. Create your Ansible playbook file **add-nonposix-and-external-groups.yml** with the following content:

- name: Playbook to add nonposix and external groups

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Add nonposix group sysops and external group appops

ipagroup:

ipaadmin_password: "{{ ipaadmin_password }}"

groups:

name: sysops nonposix: truename: appops

external: true

2. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i <path_to_inventory_directory>/hosts <path_to_playbooks_directory>/add-nonposix-and-external-groups.yml

Additional resources

• The group module in **ansible-freeipa** upstream docs

8.5. USING ANSIBLE TO ENABLE AD USERS TO ADMINISTER IDM

Follow this procedure to use an Ansible playbook to ensure that a user ID override is present in an Identity Management (IdM) group. The user ID override is the override of an Active Directory (AD) user that you created in the Default Trust View after you established a trust with AD. As a result of running the playbook, an AD user, for example an AD administrator, is able to fully administer IdM without having two different accounts and passwords.

Prerequisites

- You know the IdM **admin** password.
- You have installed a trust with AD.
- The user ID override of the AD user already exists in IdM. If it does not, create it with the **ipa idoverrideuser-add 'default trust view' ad_user@ad.example.com** command.
- The group to which you are adding the user ID override already exists in IdM.
- You are using the 4.8.7 version of IdM or later. To view the version of IdM you have installed on your server, enter **ipa --version**.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Create an **add-useridoverride-to-group.yml** playbook with the following content:

- name: Playbook to ensure presence of users in a group

hosts: ipaserver

- name: Ensure the ad_user@ad.example.com user ID override is a member of the admins group:

ipagroup:

ipaadmin_password: "{{ ipaadmin_password }}"

name: admins idoverrideuser:

- ad user@ad.example.com

In the example:

- Secret123 is the IdM **admin** password.
- admins is the name of the IdM POSIX group to which you are adding the ad_user@ad.example.com ID override. Members of this group have full administrator privileges.

- ad_user@ad.example.com is the user ID override of an AD administrator. The user is stored in the AD domain with which a trust has been established.
- 3. Save the file.
- 4. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory add-useridoverride-to-group.yml

Additional resources

- ID overrides for AD users
- /usr/share/doc/ansible-freeipa/README-group.md
- /usr/share/doc/ansible-freeipa/playbooks/user
- Using ID views in Active Directory environments
- Enabling AD users to administer IdM

8.6. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of IdM member managers - both users and user groups - using an Ansible playbook.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You must have the name of the user or group you are adding as member managers and the name of the group you want them to manage.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com 2. Create an Ansible playbook file with the necessary user and group member management information:

- name: Playbook to handle membership management

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

name: Ensure user test is present for group_a ipagroup:

ipaadmin_password: "{{ ipaadmin_password }}"

name: group_a

membermanager user: test

name: Ensure group_admins is present for group_a ipagroup:

ipaadmin_password: "{{ ipaadmin_password }}"

name: group_a

membermanager_group: group_admins

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/add-member-managers-user-groups.yml

Verification

You can verify if the **group_a** group contains **test** as a member manager and **group_admins** is a member manager of **group_a** by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Display information about managergroup1:

ipaserver]\$ ipa group-show group_a
Group name: group_a
GID: 1133400009

Membership managed by groups: group admins

Membership managed by users: test

Additional resources

- See ipa host-add-member-manager --help.
- See the **ipa** man page on your system.

8.7. ENSURING THE ABSENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the absence of IdM member managers - both users and user groups - using an Ansible playbook.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You must have the name of the existing member manager user or group you are removing and the name of the group they are managing.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary user and group member management information:

- name: Playbook to handle membership management

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

 name: Ensure member manager user and group members are absent for group_a ipagroup:

```
ipaadmin_password: "{{ ipaadmin_password }}"
```

name: group a

membermanager_user: test

membermanager_group: group_admins

action: member state: absent

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensuremember-managers-are-absent.yml

Verification

You can verify if the **group_a** group does not contain **test** as a member manager and **group_admins** as a member manager of **group_a** by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Display information about group_a:

ipaserver]\$ ipa group-show group_a Group name: group_a GID: 1133400009

Additional resources

- See ipa host-remove-member-manager --help.
- See the **ipa** man page on your system.

CHAPTER 9. USING ANSIBLE TO AUTOMATE GROUP MEMBERSHIP IN IDM

Using automatic group membership, you can assign users and hosts user groups and host groups automatically, based on their attributes. For example, you can:

- Divide employees' user entries into groups based on the employees' manager, location, position or any other attribute. You can list all attributes by entering **ipa user-add --help** on the command-line.
- Divide hosts into groups based on their class, location, or any other attribute. You can list all attributes by entering **ipa host-add --help** on the command-line.
- Add all users or all hosts to a single global group.

You can use Red Hat Ansible Engine to automate the management of automatic group membership in Identity Management (IdM).

9.1. USING ANSIBLE TO ENSURE THAT AN AUTOMEMBER RULE FOR AN IDM USER GROUP IS PRESENT

The following procedure describes how to use an Ansible playbook to ensure an **automember** rule for an Identity Management (IdM) group exists. In the example, the presence of an **automember** rule is ensured for the **testing_group** user group.

Prerequisites

- You know the IdM **admin** password.
- The **testing_group** user group exists in IdM.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

- 1. Navigate to your ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Copy the **automember-group-present.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/automember/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/automember/automember-group-present.yml automember-group-present-copy.yml

- 3. Open the automember-group-present-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipaautomember** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **testing_group**.
 - Set the **automember_type** variable to **group**.
 - Ensure that the **state** variable is set to **present**.

This is the modified Ansible playbook file for the current example:

- name: Automember group present example

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure group automember rule admins is present

ipaautomember:

ipaadmin_password: "{{ ipaadmin_password }}"

name: testing_group

automember_type: group

state: present

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory automember-group-present-copy.yml

9.2. USING ANSIBLE TO ENSURE THAT A SPECIFIED CONDITION IS PRESENT IN AN IDM USER GROUP AUTOMEMBER RULE

Additional resources

The following procedure describes how to use an Ansible playbook to ensure that a specified condition exists in an **automember** rule for an Identity Management (IdM) group. In the example, the presence of a UID-related condition in the **automember** rule is ensured for the **testing_group** group. By specifying the .* condition, you ensure that all future IdM users automatically become members of the **testing_group**.

Prerequisites

- You know the IdM **admin** password.
- The **testing group** user group and automember user group rule exist in IdM.

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **automember-hostgroup-rule-present.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/automember/ directory and name it, for example, automember-usergroup-rule-present.yml:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/automember/automember-hostgroup-rule-present.yml automember-usergroup-rule-present.yml

- 3. Open the **automember-usergroup-rule-present.yml** file for editing.
- 4. Adapt the file by modifying the following parameters:
 - Rename the playbook to correspond to your use case, for example: Automember user group rule member present.
 - Rename the task to correspond to your use case, for example: Ensure an automember condition for a user group is present.
 - Set the following variables in the **ipaautomember** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **testing_group**.
 - Set the **automember_type** variable to **group**.
 - Ensure that the **state** variable is set to **present**.
 - Ensure that the **action** variable is set to **member**.
 - Set the inclusive key variable to UID.
 - Set the **inclusive expression** variable to .*

This is the modified Ansible playbook file for the current example:

- name: Automember user group rule member present

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure an automember condition for a user group is present

ipaautomember:

ipaadmin_password: "{{ ipaadmin_password }}"

name: testing_group automember_type: group

state: present
action: member
inclusive:
- key: UID
expression: .*

5. Save the file.

6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory automember-usergroup-rule-present.yml

Verification

1. Log in as an IdM administrator.

\$ kinit admin

2. Add a user, for example:

\$ ipa user-add user101 --first user --last 101

Added user "user101"

User login: user101 First name: user Last name: 101

Member of groups: ipausers, testing_group

...

9.3. USING ANSIBLE TO ENSURE THAT A CONDITION IS ABSENT FROM AN IDM USER GROUP AUTOMEMBER RULE

Additional resources

The following procedure describes how to use an Ansible playbook to ensure a condition is absent from an **automember** rule for an Identity Management (IdM) group. In the example, the absence of a condition in the **automember** rule is ensured that specifies that users whose **initials** are **dp** should be included. The automember rule is applied to the **testing_group** group. By applying the condition, you ensure that no future IdM user whose initials are **dp** becomes a member of the **testing_group**.

Prerequisites

- You know the IdM **admin** password.
- The **testing_group** user group and automember user group rule exist in IdM.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

- 1. Navigate to your ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- Copy the automember-hostgroup-rule-absent.yml Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/automember/ directory and name it, for example, automember-usergroup-rule-absent.yml:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/automember/automember-hostgroup-rule-absent.yml automember-usergroup-rule-absent.yml
- 3. Open the **automember-usergroup-rule-absent.yml** file for editing.
- 4. Adapt the file by modifying the following parameters:
 - Rename the playbook to correspond to your use case, for example: **Automember user** group rule member absent.
 - Rename the task to correspond to your use case, for example: **Ensure an automember condition for a user group is absent**.
 - Set the following variables in the ipaautomember task section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **testing_group**.
 - Set the automember type variable to group.
 - Ensure that the state variable is set to absent.
 - Ensure that the **action** variable is set to **member**.
 - Set the **inclusive key** variable to **initials**.

• Set the **inclusive expression** variable to **dp**.

This is the modified Ansible playbook file for the current example:

- name: Automember user group rule member absent

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure an automember condition for a user group is absent ipaautomember:

ipaadmin_password: "{{ ipaadmin_password }}"

name: testing_group automember_type: group

state: absent action: member inclusive: - key: initials

expression: dp

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory automember-usergroup-rule-absent.yml

Verification

1. Log in as an IdM administrator.

\$ kinit admin

2. View the automember group:

\$ ipa automember-show --type=group testing_group
Automember Rule: testing_group

The absence of an **Inclusive Regex: initials=dp** entry in the output confirms that the **testing_group** automember rule does not contain the condition specified.

9.4. USING ANSIBLE TO ENSURE THAT AN AUTOMEMBER RULE FOR AN IDM USER GROUP IS ABSENT

Additional resources

The following procedure describes how to use an Ansible playbook to ensure an **automember** rule is absent for an Identity Management (IdM) group. In the example, the absence of an **automember** rule is ensured for the **testing_group** group.

Deleting an automember rule also deletes all conditions associated with the rule. To remove only specific conditions from a rule, see Using Ansible to ensure that a condition is absent in an IdM user group automember rule.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **automember-group-absent.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/automember/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/automember/automember-group-absent.yml automember-group-absent-copy.yml

- 3. Open the automember-group-absent-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipaautomember** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **testing_group**.
 - Set the **automember_type** variable to **group**.
 - Ensure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Automember group absent example

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure group automember rule admins is absent ipaautomember:

ipaadmin_password: "{{ ipaadmin_password }}"

name: testing_group automember_type: group

state: absent

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory automember-group-absent.yml

Additional resources

- See the **README-automember.md** file in the /usr/share/doc/ansible-freeipa/ directory.
- See the /usr/share/doc/ansible-freeipa/playbooks/automember directory.

9.5. USING ANSIBLE TO ENSURE THAT A CONDITION IS PRESENT IN AN IDM HOST GROUP AUTOMEMBER RULE

Follow this procedure to use Ansible to ensure that a condition is present in an IdM host group automember rule. The example describes how to ensure that hosts with the **FQDN** of .*.idm.example.com are members of the primary_dns_domain_hosts host group and hosts whose **FQDN** is .*.example.org are not members of the primary_dns_domain_hosts host group.

Prerequisites

- You know the IdM **admin** password.
- The **primary_dns_domain_hosts** host group and automember host group rule exist in IdM.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **automember-hostgroup-rule-present.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/automember/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/automember/automember-hostgroup-rule-present.yml automember-hostgroup-rule-present-copy.yml

- 3. Open the automember-hostgroup-rule-present-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipaautomember** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **primary_dns_domain_hosts**.
 - Set the automember_type variable to hostgroup.
 - Ensure that the **state** variable is set to **present**.
 - Ensure that the **action** variable is set to **member**.
 - Ensure that the **inclusive key** variable is set to **fqdn**.
 - Set the corresponding **inclusive expression** variable to .*.idm.example.com.
 - Set the **exclusive key** variable to **fqdn**.
 - Set the corresponding exclusive expression variable to .*.example.org.

This is the modified Ansible playbook file for the current example:

- name: Automember user group rule member present

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure an automember condition for a user group is present

ipaautomember:

ipaadmin_password: "{{ ipaadmin_password }}"

name: primary_dns_domain_hosts automember_type: hostgroup

state: present action: member inclusive:

- key: fqdn

expression: .*.idm.example.com

exclusive: - key: fqdn

Koyi iqaii

expression: .*.example.org

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory automember-hostgroup-rule-present-copy.yml

Additional Legonices

- See the **README-automember.md** file in the /usr/share/doc/ansible-freeipa/ directory.
- See the /usr/share/doc/ansible-freeipa/playbooks/automember directory.

CHAPTER 10. USING ANSIBLE PLAYBOOKS TO MANAGE SELF-SERVICE RULES IN IDM

Learn about self-service rules in Identity Management (IdM) and how to create and edit self-service access rules using Ansible playbooks. With self-service access control rules, an IdM entity can perform specified operations on its IdM Directory Server entry.

10.1. SELF-SERVICE ACCESS CONTROL IN IDM

Self-service access control rules define which operations an Identity Management (IdM) entity can perform on its IdM Directory Server entry: for example, IdM users have the ability to update their own passwords.

This method of control allows an authenticated IdM entity to edit specific attributes within its LDAP entry, but does not allow **add** or **delete** operations on the entire entry.



WARNING

Be careful when working with self-service access control rules: configuring access control rules improperly can inadvertently elevate an entity's privileges.

10.2. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS PRESENT

The following procedure describes how to use an Ansible playbook to define self-service rules and ensure their presence on an Identity Management (IdM) server. In this example, the new **Users can manage their own name details** rule grants users the ability to change their own **givenname**, **displayname**, **title** and **initials** attributes. This allows them to, for example, change their display name or initials if they want to.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

Make a copy of the selfservice-present.yml file located in the /usr/share/doc/ansible-freeipa/playbooks/selfservice/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-present.yml selfservice-present-copy.yml

- 3. Open the **selfservice-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaselfservice** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the new self-service rule.
 - Set the permission variable to a comma-separated list of permissions to grant: read and write.
 - Set the **attribute** variable to a list of attributes that users can manage themselves: **givenname**, **displayname**, **title**, and **initials**.

This is the modified Ansible playbook file for the current example:

- name: Self-service present

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure self-service rule "Users can manage their own name details" is present ipaselfservice:

ipaadmin_password: "{{ ipaadmin_password }}"
name: "Users can manage their own name details"

permission: read, write

attribute:

- givenname
- displayname
- title
- initials
- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory selfservice-present-copy.yml

Additional resources

- Self-service access control in IdM
- The README-selfservice.md file in the /usr/share/doc/ansible-freeipa/ directory

• The /usr/share/doc/ansible-freeipa/playbooks/selfservice directory

10.3. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS ABSENT

The following procedure describes how to use an Ansible playbook to ensure a specified self-service rule is absent from your IdM configuration. The example below describes how to make sure the **Users can manage their own name details** self-service rule does not exist in IdM. This will ensure that users cannot, for example, change their own display name or initials.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **selfservice-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/selfservice/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-absent.yml selfservice-absent-copy.yml

- 3. Open the **selfservice-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaselfservice** task section:
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the self-service rule.
 - Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Self-service absent

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure self-service rule "Users can manage their own name details" is absent ipaselfservice:

ipaadmin_password: "{{ ipaadmin_password }}"
name: "Users can manage their own name details"
state: absent

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory selfservice-absent-copy.yml

Additional resources

- Self-service access control in IdM
- The README-selfservice.md file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/selfservice directory

10.4. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE HAS SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that an already existing self-service rule has specific settings. In the example, you ensure the **Users can manage their own name details** self-service rule also has the **surname** member attribute.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The Users can manage their own name details elf-service rule exists in IdM.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **selfservice-member-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/selfservice/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-member-present.yml selfservice-member-present-copy.yml

- 3. Open the **selfservice-member-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaselfservice** task section:
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the self-service rule to modify.
 - Set the **attribute** variable to **surname**.
 - Set the action variable to member.

This is the modified Ansible playbook file for the current example:

- name: Self-service member present

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure selfservice "Users can manage their own name details" member attribute surname is present

ipaselfservice:

ipaadmin_password: "{{ ipaadmin_password }}"
name: "Users can manage their own name details"

attribute:
- surname

action: member

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory selfservice-member-present-copy.yml

Additional resources

- Self-service access control in IdM
- The **README-selfservice.md** file available in the /usr/share/doc/ansible-freeipa/ directory
- The sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/selfservice directory

10.5. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE DOES NOT HAVE SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that a self-service rule does not have specific settings. You can use this playbook to make sure a self-service rule does not grant undesired access. In the example, you ensure the **Users can manage their own name details**self-service rule does not have the **givenname** and **surname** member attributes.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The Users can manage their own name details elf-service rule exists in IdM.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **selfservice-member-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/selfservice/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-member-absent.yml selfservice-member-absent-copy.yml

- 3. Open the **selfservice-member-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaselfservice** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the self-service rule you want to modify.
 - Set the **attribute** variable to **givenname** and **surname**.
 - Set the **action** variable to **member**.
 - Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Self-service member absent

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks:

- name: Ensure selfservice "Users can manage their own name details" member attributes givenname and surname are absent

ipaselfservice:

ipaadmin_password: "{{ ipaadmin_password }}"
name: "Users can manage their own name details"

attribute:
- givenname

- surname

action: member state: absent

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory selfservice-member-absent-copy.yml

Additional resources

- Self-service access control in IdM
- The README-selfservice.md file in the /usr/share/doc/ansible-freeipa/ directory
- The sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/selfservice directory

CHAPTER 11. DELEGATING PERMISSIONS TO USER GROUPS TO MANAGE USERS USING ANSIBLE PLAYBOOKS

Delegation is one of the access control methods in IdM, along with self-service rules and role-based access control (RBAC). You can use delegation to assign permissions to one group of users to manage entries for another group of users.

11.1. DELEGATION RULES

You can delegate permissions to user groups to manage users by creating delegation rules.

Delegation rules allow a specific user group to perform write (edit) operations on specific attributes for users in another user group. This form of access control rule is limited to editing the values of a subset of attributes you specify in a delegation rule; it does not grant the ability to add or remove whole entries or control over unspecified attributes.

Delegation rules grant permissions to existing user groups in IdM. You can use delegation to, for example, allow the **managers** user group to manage selected attributes of users in the **employees** user group.

11.2. CREATING AN ANSIBLE INVENTORY FILE FOR IDM

When working with Ansible, it is good practice to create, in your home directory, a subdirectory dedicated to Ansible playbooks that you copy and adapt from the /usr/share/doc/ansible-freeipa/* and /usr/share/doc/rhel-system-roles/* subdirectories. This practice has the following advantages:

- You can find all your playbooks in one place.
- You can run your playbooks without invoking root privileges.

Procedure

1. Create a directory for your Ansible configuration and playbooks in your home directory:

\$ mkdir ~/MyPlaybooks/

2. Change into the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks

3. Create the ~/MyPlaybooks/ansible.cfg file with the following content:

[defaults]
inventory = /home/<username>/MyPlaybooks/inventory

[privilege_escalation]
become=True

4. Create the ~/MyPlaybooks/inventory file with the following content:

[eu] server.idm.example.com [us]
replica.idm.example.com
[ipaserver:children]
eu
us

This configuration defines two host groups, **eu** and **us**, for hosts in these locations. Additionally, this configuration defines the **ipaserver** host group, which contains all hosts from the **eu** and **us** groups.

11.3. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS PRESENT

The following procedure describes how to use an Ansible playbook to define privileges for a new IdM delegation rule and ensure its presence. In the example, the new **basic manager attributes** delegation rule grants the **managers** group the ability to read and write the following attributes for members of the **employees** group:

- businesscategory
- departmentnumber
- employeenumber
- employeetype

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **delegation-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/delegation/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-present.yml delegation-present-copy.yml

- 3. Open the **delegation-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipadelegation** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the new delegation rule.
 - Set the permission variable to a comma-separated list of permissions to grant: read and write.
 - Set the **attribute** variable to a list of attributes the delegated user group can manage: **businesscategory**, **departmentnumber**, **employeenumber**, and **employeetype**.
 - Set the **group** variable to the name of the group that is being given access to view or modify attributes.
 - Set the **membergroup** variable to the name of the group whose attributes can be viewed or modified.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage a delegation rule

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure delegation "basic manager attributes" is present ipadelegation:

ipaadmin_password: "{{ ipaadmin_password }}"

name: "basic manager attributes"

permission: read, write

attribute:

- businesscategory
- departmentnumber
- employeenumber
- employeetype

group: managers

membergroup: employees

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i ~/MyPlaybooks/inventory delegation-present-copy.yml

Additional resources

- Delegation rules
- The README-delegation.md file in the /usr/share/doc/ansible-freeipa/ directory

• Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/ipadelegation directory

11.4. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS ABSENT

The following procedure describes how to use an Ansible playbook to ensure a specified delegation rule is absent from your IdM configuration. The example below describes how to make sure the custom **basic** manager attributes delegation rule does not exist in IdM.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks>/

2. Make a copy of the **delegation-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/delegation/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-present.yml delegation-absent-copy.yml

- 3. Open the **delegation-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipadelegation** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the delegation rule.
 - Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Delegation absent

hosts: ipaserver

vars files:

- /home/user name/MyPlaybooks/secret.yml

tasks:

 name: Ensure delegation "basic manager attributes" is absent ipadelegation:

ipaadmin_password: "{{ ipaadmin_password }}"

name: "basic manager attributes"

state: absent

5. Save the file.

6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i ~/MyPlaybooks/inventory delegation-absent-copy.yml

Additional resources

- Delegation rules
- The **README-delegation.md** file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/ipadelegation directory

11.5. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE HAS SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that a delegation rule has specific settings. You can use this playbook to modify a delegation role you have previously created. In the example, you ensure the **basic manager attributes** delegation rule only has the **departmentnumber** member attribute.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The basic manager attributes delegation rule exists in IdM.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **delegation-member-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/delegation/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-member-present.yml delegation-member-present-copy.yml

- 3. Open the **delegation-member-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipadelegation** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the delegation rule to modify.
 - Set the attribute variable to departmentnumber.
 - Set the **action** variable to **member**.

This is the modified Ansible playbook file for the current example:

- name: Delegation member present

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure delegation "basic manager attributes" member attribute departmentnumber is present

ipadelegation:

ipaadmin_password: "{{ ipaadmin_password }}"

name: "basic manager attributes"

attribute:

- departmentnumber

action: member

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i ~/MyPlaybooks/inventory delegation-member-present-copy.yml

Additional resources

- Delegation rules
- The **README-delegation.md** file in the /usr/share/doc/ansible-freeipa/ directory
- The sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/ipadelegation directory

11.6. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE DOES NOT HAVE SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that a delegation rule does not have specific settings. You can use this playbook to make sure a delegation role does not grant undesired access. In the example, you ensure the **basic manager attributes** delegation rule does not have the **employeenumber** and **employeetype** member attributes.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The basic manager attributes delegation rule exists in IdM.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **delegation-member-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/delegation/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-member-absent.yml delegation-member-absent-copy.yml

- 3. Open the **delegation-member-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipadelegation** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the delegation rule to modify.
 - Set the attribute variable to employeenumber and employeetype.
 - Set the **action** variable to **member**.
 - Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Delegation member absent

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure delegation "basic manager attributes" member attributes employeenumber and employeetype are absent

ipadelegation:

ipaadmin_password: "{{ ipaadmin_password }}"
name: "basic manager attributes"

attribute:

- employeenumber

- employeetype action: member state: absent

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password_file=password_file -v -i ~/MyPlaybooks/inventory delegation-member-absent-copy.yml

Additional resources

- Delegation rules
- The **README-delegation.md** file in the /usr/share/doc/ansible-freeipa/ directory.
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/ipadelegation directory

CHAPTER 12. USING ANSIBLE PLAYBOOKS TO MANAGE ROLE-BASED ACCESS CONTROL IN IDM

Role-based access control (RBAC) is a policy-neutral access-control mechanism defined around roles and privileges. The components of RBAC in Identity Management (IdM) are roles, privileges and permissions:

- **Permissions** grant the right to perform a specific task such as adding or deleting users, modifying a group, and enabling read-access.
- Privileges combine permissions, for example all the permissions needed to add a new user.
- Roles grant a set of privileges to users, user groups, hosts or host groups.

Especially in large companies, using RBAC can help create a hierarchical system of administrators with their individual areas of responsibility.

Learn about operations you can perform when managing RBAC using Ansible playbooks.

12.1. PERMISSIONS IN IDM

Permissions are the lowest level unit of role-based access control, they define operations together with the LDAP entries to which those operations apply. Comparable to building blocks, permissions can be assigned to as many privileges as needed.

One or more **rights** define what operations are allowed:

- write
- read
- search
- compare
- add
- delete
- all

These operations apply to three basic targets:

- **subtree**: a domain name (DN); the subtree under this DN
- target filter: an LDAP filter
- target: DN with possible wildcards to specify entries

Additionally, the following convenience options set the corresponding attribute(s):

- type: a type of object (user, group, etc); sets subtree and target filter
- memberof: members of a group; sets a target filter



NOTE

Setting the **memberof** attribute permission is not applied if the target LDAP entry does not contain any reference to group membership.

• **targetgroup**: grants access to modify a specific group (such as granting the rights to manage group membership); sets a **target**

With IdM permissions, you can control which users have access to which objects and even which attributes of these objects. IdM enables you to allow or block individual attributes or change the entire visibility of a specific IdM function, such as users, groups, or sudo, to all anonymous users, all authenticated users, or just a certain group of privileged users.

For example, the flexibility of this approach to permissions is useful for an administrator who wants to limit access of users or groups only to the specific sections these users or groups need to access and to make the other sections completely hidden to them.



NOTE

A permission cannot contain other permissions.

12.2. DEFAULT MANAGED PERMISSIONS

Managed permissions are permissions that come by default with IdM. They behave like other permissions created by the user, with the following differences:

- You cannot delete them or modify their name, location, and target attributes.
- They have three sets of attributes:
 - Default attributes, the user cannot modify them, as they are managed by IdM
 - o Included attributes, which are additional attributes added by the user
 - Excluded attributes, which are attributes removed by the user

A managed permission applies to all attributes that appear in the default and included attribute sets but not in the excluded set.



NOTE

While you cannot delete a managed permission, setting its bind type to permission and removing the managed permission from all privileges effectively disables it.

Names of all managed permissions start with **System:**, for example **System: Add Sudo rule** or **System: Modify Services**. Earlier versions of IdM used a different scheme for default permissions. For example, the user could not delete them and was only able to assign them to privileges. Most of these default permissions have been turned into managed permissions, however, the following permissions still use the previous scheme:

- Add Automember Rebuild Membership Task
- Add Configuration Sub-Entries
- Add Replication Agreements

- Certificate Remove Hold
- Get Certificates status from the CA
- Read DNA Range
- Modify DNA Range
- Read PassSync Managers Configuration
- Modify PassSync Managers Configuration
- Read Replication Agreements
- Modify Replication Agreements
- Remove Replication Agreements
- Read LDBM Database Configuration
- Request Certificate
- Request Certificate ignoring CA ACLs
- Request Certificates from a different host
- Retrieve Certificates from the CA
- Revoke Certificate
- Write IPA Configuration



NOTE

If you attempt to modify a managed permission from the command line, the system does not allow you to change the attributes that you cannot modify, the command fails. If you attempt to modify a managed permission from the Web UI, the attributes that you cannot modify are disabled.

12.3. PRIVILEGES IN IDM

A privilege is a group of permissions applicable to a role. While a permission provides the rights to do a single operation, there are certain IdM tasks that require multiple permissions to succeed. Therefore, a privilege combines the different permissions required to perform a specific task.

For example, setting up an account for a new IdM user requires the following permissions:

- Creating a new user entry
- Resetting a user password
- Adding the new user to the default IPA users group

Combining these three low-level tasks into a higher level task in the form of a custom privilege named, for example, **Add User** makes it easier for a system administrator to manage roles. IdM already contains several default privileges. Apart from users and user groups, privileges are also assigned to hosts and

host groups, as well as network services. This practice permits a fine-grained control of operations by a set of users on a set of hosts using specific network services.



NOTE

A privilege may not contain other privileges.

12.4. ROLES IN IDM

A role is a list of privileges that users specified for the role possess.

In effect, permissions grant the ability to perform given low-level tasks (such as creating a user entry and adding an entry to a group), privileges combine one or more of these permissions needed for a higher-level task (such as creating a new user in a given group). Roles gather privileges together as needed: for example, a User Administrator role would be able to add, modify, and delete users.



IMPORTANT

Roles are used to classify permitted actions. They are not used as a tool to implement privilege separation or to protect from privilege escalation.



NOTE

Roles can not contain other roles.

12.5. PREDEFINED ROLES IN IDENTITY MANAGEMENT

Red Hat Enterprise Linux Identity Management provides the following range of pre-defined roles:

Table 12.1. Predefined Roles in Identity Management

Role	Privilege	Description
Enrollment Administrator	Host Enrollment	Responsible for client, or host, enrollment
helpdesk	Modify Users and Reset passwords, Modify Group membership	Responsible for performing simple user administration tasks
IT Security Specialist	Netgroups Administrators, HBAC Administrator, Sudo Administrator	Responsible for managing security policy such as host-based access controls, sudo rules
IT Specialist	Host Administrators, Host Group Administrators, Service Administrators, Automount Administrators	Responsible for managing hosts

Role	Privilege	Description
Security Architect	Delegation Administrator, Replication Administrators, Write IPA Configuration, Password Policy Administrator	Responsible for managing the Identity Management environment, creating trusts, creating replication agreements
User Administrator	User Administrators, Group Administrators, Stage User Administrators	Responsible for creating users and groups

12.6. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE WITH PRIVILEGES IS PRESENT

To exercise more granular control over role-based access (RBAC) to resources in Identity Management (IdM) than the default roles provide, create a custom role.

The following procedure describes how to use an Ansible playbook to define privileges for a new IdM custom role and ensure its presence. In the example, the new **user_and_host_administrator** role contains a unique combination of the following privileges that are present in IdM by default:

- Group Administrators
- User Administrators
- Stage User Administrators
- Group Administrators

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

- 1. Navigate to the ~/<MyPlaybooks>/ directory:
 - \$ cd ~/<MyPlaybooks>/
- 2. Make a copy of the **role-member-user-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-user-present.yml rolemember-user-present-copy.yml

- 3. Open the role-member-user-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the new role.
 - Set the **privilege** list to the names of the IdM privileges that you want to include in the new
 - Optionally, set the user variable to the name of the user to whom you want to grant the new role.
 - Optionally, set the group variable to the name of the group to which you want to grant the new role.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: true

gather_facts: no

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- iparole:

ipaadmin_password: "{{ ipaadmin_password }}"

name: user and host administrator

user: idm user01 group: idm group01

privilege:

- Group Administrators

- User Administrators
- Stage User Administrators
- Group Administrators
- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the secret.yml file, and the inventory file:

\$ ansible-playbook --vault-password-file=password file -v -i ~/<MyPlaybooks>/inventory role-member-user-present-copy.yml

Additional resources

- Encrypting content with Ansible Vault
- Roles in IdM

- The **README-role** file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/iparole directory

12.7. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE IS ABSENT

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to ensure the absence of an obsolete role so that no administrator assigns it to any user accidentally.

The following procedure describes how to use an Ansible playbook to ensure a role is absent. The example below describes how to make sure the custom **user_and_host_administrator** role does not exist in IdM.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/<MyPlaybooks>/ directory:

\$ cd ~/<MyPlaybooks>/

2. Make a copy of the **role-is-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-is-absent.yml role-is-absent-copy.yml

- 3. Open the **role-is-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role.
 - Ensure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: true gather_facts: no

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- iparole:

ipaadmin_password: "{{ ipaadmin_password }}"

name: user_and_host_administrator

state: absent

5. Save the file.

6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i ~/<MyPlaybooks>/inventory role-is-absent-copy.yml

Additional resources

- Encrypting content with Ansible Vault
- Roles in IdM
- The **README-role** Markdown file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/iparole directory

12.8. USING ANSIBLE TO ENSURE THAT A GROUP OF USERS IS ASSIGNED TO AN IDM RBAC ROLE

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to assign a role to a specific group of users, for example junior administrators.

The following example describes how to use an Ansible playbook to ensure the built-in IdM RBAC **helpdesk** role is assigned to **junior_sysadmins**.

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/<MyPlaybooks>/ directory:

\$ cd ~/<MyPlaybooks>/

2. Make a copy of the **role-member-group-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-group-present.yml role-member-group-present-copy.yml

- 3. Open the role-member-group-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **group** variable to the name of the group.
 - Set the action variable to member.

This is the modified Ansible playbook file for the current example:

--

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: true gather_facts: no

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- iparole:

ipaadmin_password: "{{ ipaadmin_password }}"

name: helpdesk

group: junior_sysadmins

action: member

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i ~/<MyPlaybooks>/inventory role-member-group-present-copy.yml

Additional resources

- Encrypting content with Ansible Vault
- Roles in IdM

- The **README-role** Markdown file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/iparole directory

12.9. USING ANSIBLE TO ENSURE THAT SPECIFIC USERS ARE NOT ASSIGNED TO AN IDM RBAC ROLE

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to ensure that an RBAC role is not assigned to specific users after they have, for example, moved to different positions within the company.

The following procedure describes how to use an Ansible playbook to ensure that the users named user_01 and user_02 are not assigned to the helpdesk role.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

- 1. Navigate to the ~/<MyPlaybooks>/ directory:
 - \$ cd ~/<MyPlaybooks>/
- 2. Make a copy of the **role-member-user-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-user-absent.yml role-member-user-absent-copy.yml
- 3. Open the role-member-user-absent-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **user** list to the names of the users.
 - Set the action variable to member.
 - Set the state variable to absent.

This is the modified Ansible playbook file for the current example:

```
-name: Playbook to manage IPA role with members.
hosts: ipaserver
become: true
gather_facts: no

vars_files:
-/home/user_name/MyPlaybooks/secret.yml
tasks:
- iparole:
    ipaadmin_password: "{{ ipaadmin_password }}"
    name: helpdesk
    user
- user_01
- user_02
    action: member
    state: absent
```

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

```
$ ansible-playbook --vault-password-file=password_file -v -i ~/<MyPlaybooks>/inventory role-member-user-absent-copy.yml
```

Additional resources

- Encrypting content with Ansible Vault
- Roles in IdM
- The **README-role** Markdown file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/iparole directory

12.10. USING ANSIBLE TO ENSURE A SERVICE IS A MEMBER OF AN IDM RBAC ROLE

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to ensure that a specific service that is enrolled into IdM is a member of a particular role. The following example describes how to ensure that the custom **web_administrator** role can manage the **HTTP** service that is running on the **clientO1.idm.example.com** server.

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.

- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The web_administrator role exists in IdM.
- The HTTP/client01.idm.example.com@IDM.EXAMPLE.COM service exists in IdM.

Procedure

1. Navigate to the ~/<MyPlaybooks>/ directory:

\$ cd ~/<MyPlaybooks>/

2. Make a copy of the **role-member-service-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-service-present-absent.yml role-member-service-present-copy.yml

- 3. Open the role-member-service-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **service** list to the name of the service.
 - Set the action variable to member.

This is the modified Ansible playbook file for the current example:

 name: Playbook to manage IPA role with members. hosts: ipaserver become: true

become: true gather_facts: no

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks:

- iparole:

ipaadmin_password: "{{ ipaadmin_password }}"
name: web administrator

name. web_administr

service:

- HTTP/client01.idm.example.com

action: member

5. Save the file.

6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i ~/<MyPlaybooks>/inventory role-member-service-present-copy.yml

Additional resources

- Encrypting content with Ansible Vault
- Roles in IdM
- The **README-role** Markdown file in the /usr/share/doc/ansible-freeipa/ directory
- The sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/iparole directory

12.11. USING ANSIBLE TO ENSURE A HOST IS A MEMBER OF AN IDM RBAC ROLE

As a system administrator managing role-based access control in Identity Management (IdM), you may want to ensure that a specific host or host group is associated with a specific role. The following example describes how to ensure that the custom **web_administrator** role can manage the **clientO1.idm.example.com** IdM host on which the **HTTP** service is running.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The web_administrator role exists in IdM.
- The client01.idm.example.com host exists in IdM.

Procedure

- 1. Navigate to the ~/<MyPlaybooks>/ directory:
 - \$ cd ~/<MyPlaybooks>/
- 2. Make a copy of the **role-member-host-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-host-present.yml role-member-host-present-copy.yml

- 3. Open the role-member-host-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **host** list to the name of the host.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: true gather_facts: no

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- iparole:

ipaadmin_password: "{{ ipaadmin_password }}"
name: web administrator

host:

- client01.idm.example.com

action: member

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i ~/<MyPlaybooks>/inventory role-member-host-present-copy.yml

Additional resources

- Encrypting content with Ansible Vault
- Roles in IdM
- The **README-role** Markdown file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/iparole directory

12.12. USING ANSIBLE TO ENSURE A HOST GROUP IS A MEMBER OF AN IDM RBAC ROLE

As a system administrator managing role-based access control in Identity Management (IdM), you may want to ensure that a specific host or host group is associated with a specific role. The following

example describes how to ensure that the custom **web_administrator** role can manage the **web_servers** group of IdM hosts on which the **HTTP** service is running.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The web_administrator role exists in IdM.
- The web_servers host group exists in IdM.

Procedure

1. Navigate to the ~/<MyPlaybooks>/ directory:

\$ cd ~/<MyPlaybooks>/

2. Make a copy of the **role-member-hostgroup-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-hostgroup-present.yml role-member-hostgroup-present-copy.yml

- 3. Open the role-member-hostgroup-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **hostgroup** list to the name of the hostgroup.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: true gather_facts: no

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks: - iparole:

ipaadmin_password: "{{ ipaadmin_password }}"
name: web_administrator
hostgroup:

web_serversaction: member

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i ~/<MyPlaybooks>/inventory role-member-hostgroup-present-copy.yml

Additional resources

- Encrypting content with Ansible Vault
- Roles in IdM
- The **README-role** Markdown file in the /usr/share/doc/ansible-freeipa/ directory
- The sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/iparole directory

CHAPTER 13. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PRIVILEGES

Role-based access control (RBAC) is a policy-neutral access-control mechanism defined around roles, privileges, and permissions. Especially in large companies, using RBAC can help create a hierarchical system of administrators with their individual areas of responsibility.

Learn how to use Ansible playbooks to manage RBAC privileges in Identity Management (IdM).

Prerequisites

You understand the concepts and principles of RBAC.

13.1. USING ANSIBLE TO ENSURE A CUSTOM IDM RBAC PRIVILEGE IS PRESENT

To have a fully-functioning custom privilege in Identity Management (IdM) role-based access control (RBAC), you need to proceed in stages:

- 1. Create a privilege with no permissions attached.
- 2. Add permissions of your choice to the privilege.

The following procedure describes how to create an empty privilege using an Ansible playbook so that you can later add permissions to it. The example describes how to create a privilege named **full_host_administration** that is meant to combine all IdM permissions related to host administration.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **privilege-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/privilege/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-present.yml privilege-present-copy.yml

- 3. Open the **privilege-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the new privilege, **full_host_administration**.
 - Optionally, describe the privilege using the **description** variable.

This is the modified Ansible playbook file for the current example:

- name: Privilege present example

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks

 name: Ensure privilege full_host_administration is present ipaprivilege:

ipaadmin_password: "{{ ipaadmin_password }}"

name: full_host_administration

description: This privilege combines all IdM permissions related to host

administration

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory privilege-present-copy.yml

13.2. USING ANSIBLE TO ENSURE MEMBER PERMISSIONS ARE PRESENT IN A CUSTOM IDM RBAC PRIVILEGE

To have a fully-functioning custom privilege in Identity Management (IdM) role-based access control (RBAC), you need to proceed in stages:

- 1. Create a privilege with no permissions attached.
- 2. Add permissions of your choice to the privilege.

The following procedure describes how to use an Ansible playbook to add permissions to a privilege created in the previous step. The example describes how to add all IdM permissions related to host administration to a privilege named **full_host_administration**. By default, the permissions are distributed between the **Host Enrollment**, **Host Administrators** and **Host Group Administrator** privileges.

- On the control node:
 - You are using Ansible version 2.14 or later.

- You have installed the **ansible-freeipa** package.
- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The *full_host_administration* privilege exists. For information about how to create a privilege using Ansible, see Using Ansible to ensure a custom IdM RBAC privilege is present.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **privilege-member-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/privilege/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-member-present.yml privilege-member-present-copy.yml

- 3. Open the **privilege-member-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the privilege.
 - Set the **permission** list to the names of the permissions that you want to include in the privilege.
 - Make sure that the **action** variable is set to **member**.

This is the modified Ansible playbook file for the current example:

- name: Privilege member present example

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure that permissions are present for the "full_host_administration" privilege ipaprivilege:

ipaadmin_password: "{{ ipaadmin_password }}"
name: full_host_administration
permission:

- "System: Add krbPrincipalName to a Host"
- "System: Enroll a Host"

- "System: Manage Host Certificates"
- "System: Manage Host Enrollment Password"
- "System: Manage Host Keytab"
- "System: Manage Host Principals"
- "Retrieve Certificates from the CA"
- "Revoke Certificate"
- "System: Add Hosts"
- "System: Add krbPrincipalName to a Host"
- "System: Enroll a Host"
- "System: Manage Host Certificates"
- "System: Manage Host Enrollment Password"
- "System: Manage Host Keytab"
- "System: Manage Host Keytab Permissions"
- "System: Manage Host Principals"
- "System: Manage Host SSH Public Keys"
- "System: Manage Service Keytab"
- "System: Manage Service Keytab Permissions"
- "System: Modify Hosts"
- "System: Remove Hosts"
- "System: Add Hostgroups"
- "System: Modify Hostgroup Membership"
- "System: Modify Hostgroups"
- "System: Remove Hostgroups"
- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory privilegemember-present-copy.yml

13.3. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE DOES NOT INCLUDE A PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control.

The following procedure describes how to use an Ansible playbook to remove a permission from a privilege. The example describes how to remove the **Request Certificates ignoring CA ACLs** permission from the default **Certificate Administrators** privilege because, for example, the administrator considers it a security risk.

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.

• The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **privilege-member-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/privilege/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-member-absent.yml privilege-member-absent-copy.yml

- 3. Open the **privilege-member-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the privilege.
 - Set the **permission** list to the names of the permissions that you want to remove from the privilege.
 - Make sure that the **action** variable is set to **member**.
 - Make sure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Privilege absent example

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure that the "Request Certificate ignoring CA ACLs" permission is absent from the "Certificate Administrators" privilege

ipaprivilege:

ipaadmin_password: "{{ ipaadmin_password }}"
name: Certificate Administrators

permission:

- "Request Certificate ignoring CA ACLs"

action: member state: absent

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory privilege-member-absent-copy.yml

13.4. USING ANSIBLE TO RENAME A CUSTOM IDM RBAC PRIVILEGE

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control.

The following procedure describes how to rename a privilege because, for example, you have removed a few permissions from it. As a result, the name of the privilege is no longer accurate. In the example, the administrator renames a **full_host_administration** privilege to **limited_host_administration**.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The *full_host_administration* privilege exists. For more information about how to add a privilege, see Using Ansible to ensure a custom IdM RBAC privilege is present.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **privilege-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/privilege/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-present.yml rename-privilege.yml

- 3. Open the **rename-privilege.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the current name of the privilege.
 - Add the **rename** variable and set it to the new name of the privilege.
 - Add the **state** variable and set it to **renamed**.

5. Rename the playbook itself, for example:

- name: Rename a privilege

hosts: ipaserver

6. Rename the task in the playbook, for example:

[...] tasks:

- name: Ensure the full_host_administration privilege is renamed to limited host administration

ipaprivilege:

[...]

This is the modified Ansible playbook file for the current example:

- name: Rename a privilege

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks

- name: Ensure the full_host_administration privilege is renamed to limited_host_administration

ipaprivilege:

ipaadmin_password: "{{ ipaadmin_password }}"

name: full_host_administration rename: limited_host_administration

state: renamed

- 7. Save the file.
- 8. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory rename-privilege.yml

13.5. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE IS ABSENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control. The following procedure describes how to use an Ansible playbook to ensure that an RBAC privilege is absent. The example describes how to ensure that the **CA administrator** privilege is absent. As a result of the procedure, the **admin** administrator becomes the only user capable of managing certificate authorities in IdM.

- On the control node:
 - You are using Ansible version 2.14 or later.

- You have installed the **ansible-freeipa** package.
- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **privilege-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/privilege/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-absent.yml privilege-absent-copy.yml

- 3. Open the **privilege-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the privilege you want to remove.
 - Make sure that the **state** variable is set it to **absent**.
- 5. Rename the task in the playbook, for example:

[...]

tasks:

- name: Ensure privilege "CA administrator" is absent ipaprivilege:

[...]

This is the modified Ansible playbook file for the current example:

- name: Privilege absent example

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure privilege "CA administrator" is absent ipaprivilege:

ipaadmin_password: "{{ ipaadmin_password }}"

name: CA administrator

state: absent

- 6. Save the file.
- 7. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory privilege-absent-copy.yml

13.6. ADDITIONAL RESOURCES

- See Privileges in IdM.
- See Permissions in IdM.
- See the **README-privilege** file available in the /usr/share/doc/ansible-freeipa/ directory.
- See the sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/ipaprivilege directory.

CHAPTER 14. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PERMISSIONS IN IDM

Role-based access control (RBAC) is a policy-neutral access control mechanism defined around roles, privileges, and permissions. Especially in large companies, using RBAC can help create a hierarchical system of administrators with their individual areas of responsibility.

Learn about operations you can perform when managing RBAC permissions in Identity Management (IdM) using Ansible playbooks:

Prerequisites

• You understand the concepts and principles of RBAC.

14.1. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS PRESENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure a permission is present in IdM so that it can be added to a privilege. The example describes how to ensure the following target state:

- The **MyPermission** permission exists.
- The **MyPermission** permission can only be applied to hosts.
- A user granted a privilege that contains the permission can do all of the following possible operations on an entry:
 - Write
 - Read
 - Search
 - Compare
 - Add
 - Delete

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.

• The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **permission-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-present.yml permission-present-copy.yml

- 3. Open the **permission-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.
 - Set the **object_type** variable to **host**.
 - Set the **right** variable to **all**.

This is the modified Ansible playbook file for the current example:

--- name: Permission present example
hosts: ipaserver

vars_files:
- /home/user_name/MyPlaybooks/secret.yml
tasks:
- name: Ensure that the "MyPermission" permission is present
ipapermission:
 ipaadmin_password: "{{ ipaadmin_password }}"
 name: MyPermission
 object_type: host
 right: all

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory permission-present-copy.yml

14.2. USING ANSIBLE TO ENSURE AN RBAC PERMISSION WITH AN ATTRIBUTE IS PRESENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure a permission is present in IdM so that it can be added to a privilege. The example describes how to ensure the following target state:

- The MyPermission permission exists.
- The MyPermission permission can only be used to add hosts.
- A user granted a privilege that contains the permission can do all of the following possible operations on a host entry:
 - Write
 - Read
 - Search
 - Compare
 - Add
 - Delete
- The host entries created by a user that is granted a privilege that contains the **MyPermission** permission can have a **description** value.



NOTE

The type of attribute that you can specify when creating or modifying a permission is not constrained by the IdM LDAP schema. However, specifying, for example, attrs: car_licence if the object_type is host later results in the ipa: ERROR: attribute "car-license" not allowed error message when you try to exercise the permission and add a specific car licence value to a host.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **permission-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-present.yml permission-present-with-attribute.yml

- 3. Open the **permission-present-with-attribute.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.
 - Set the **object_type** variable to **host**.
 - Set the **right** variable to **all**.
 - Set the attrs variable to description.

This is the modified Ansible playbook file for the current example:

- name: Permission present example

hosts: ipaserver

vars files:

- /home/user name/MyPlaybooks/secret.yml

tasks:

- name: Ensure that the "MyPermission" permission is present with an attribute ipapermission:

ipaadmin_password: "{{ ipaadmin_password }}"

name: MyPermission

object_type: host

right: all

attrs: description

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory permission-present-with-attribute.yml

Additional resources

See User and group schema in Linux Domain Identity, Authentication and Policy Guide in RHEL
 7.

14.3. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS ABSENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure a permission is absent in IdM so that it cannot be added to a privilege.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **permission-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-absent.yml permission-absent-copy.yml

- 3. Open the **permission-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.

This is the modified Ansible playbook file for the current example:

- name: Permission absent example

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure that the "MyPermission" permission is absent ipapermission:

ipaadmin_password: "{{ ipaadmin_password }}"

name: MyPermission

state: absent

5. Save the file.

6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory permission-absent-copy.yml

14.4. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS A MEMBER OF AN IDM RBAC PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure that an attribute is a member of an RBAC permission in IdM. As a result, a user with the permission can create entries that have the attribute.

The example describes how to ensure that the host entries created by a user with a privilege that contains the **MyPermission** permission can have **gecos** and **description** values.



NOTE

The type of attribute that you can specify when creating or modifying a permission is not constrained by the IdM LDAP schema. However, specifying, for example, attrs: car_licence if the object_type is host later results in the ipa: ERROR: attribute "car-license" not allowed error message when you try to exercise the permission and add a specific car licence value to a host.

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The MyPermission permission exists.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **permission-member-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-member-present.yml permission-member-present-copy.yml

- 3. Open the **permission-member-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.
 - Set the **attrs** list to the **description** and **gecos** variables.
 - Make sure the **action** variable is set to **member**.

This is the modified Ansible playbook file for the current example:

- name: Permission member present example

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure that the "gecos" and "description" attributes are present in "MyPermission"

ipapermission:

ipaadmin_password: "{{ ipaadmin_password }}"

name: MyPermission

attrs:

- description
- gecos

action: member

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory permission-member-present-copy.yml

14.5. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS NOT A MEMBER OF AN IDM RBAC PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure that an attribute is not a member of an RBAC permission in IdM. As a result, when a user with the permission creates an entry in IdM LDAP, that entry cannot have a value associated with the attribute.

The example describes how to ensure the following target state:

- The **MyPermission** permission exists.
- The host entries created by a user with a privilege that contains the **MyPermission** permission cannot have the **description** attribute.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The MyPermission permission exists.

Procedure

- 1. Navigate to the ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Make a copy of the **permission-member-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-member-absent.yml permission-member-absent-copy.yml
- 3. Open the **permission-member-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.

- Set the attrs variable to description.
- Set the action variable to member.
- Make sure the state variable is set to absent

This is the modified Ansible playbook file for the current example:

- name: Permission absent example

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

 name: Ensure that an attribute is not a member of "MyPermission" ipapermission:

ipaadmin_password: "{{ ipaadmin_password }}"

name: MyPermission attrs: description action: member state: absent

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory permission-member-absent-copy.yml

14.6. USING ANSIBLE TO RENAME AN IDM RBAC PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control.

The following procedure describes how to use an Ansible playbook to rename a permission. The example describes how to rename **MyPermission** to **MyNewPermission**.

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

- The **MyPermission** exists in IdM.
- The MyNewPermission does not exist in IdM.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **permission-renamed.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-renamed.yml permission-renamed-copy.yml

- 3. Open the **permission-renamed-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.

This is the modified Ansible playbook file for the current example:

- name: Permission present example

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Rename the "MyPermission" permission ipapermission:

ipaadmin_password: "{{ ipaadmin_password }}"

name: MyPermission

rename: MyNewPermission

state: renamed

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory permission-renamed-copy.yml

14.7. ADDITIONAL RESOURCES

• See Permissions in IdM.

- See Privileges in IdM.
- See the **README-permission** file available in the /usr/share/doc/ansible-freeipa/ directory.
- See the sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/ipapermission directory.

CHAPTER 15. USING ANSIBLE TO MANAGE THE REPLICATION TOPOLOGY IN IDM

You can maintain multiple Identity Management (IdM) servers and let them replicate each other for redundancy purposes to mitigate or prevent server loss. For example, if one server fails, the other servers keep providing services to the domain. You can also recover the lost server by creating a new replica based on one of the remaining servers.

Data stored on an IdM server is replicated based on replication agreements: when two servers have a replication agreement configured, they share their data. The data that is replicated is stored in the topology **suffixes**. When two replicas have a replication agreement between their suffixes, the suffixes form a topology **segment**.

This chapter describes how to use Ansible to manage IdM replication agreements, topology segments, and topology suffixes.

15.1. USING ANSIBLE TO ENSURE A REPLICATION AGREEMENT EXISTS IN IDM

Data stored on an Identity Management (IdM) server is replicated based on replication agreements: when two servers have a replication agreement configured, they share their data. Replication agreements are always bilateral: the data is replicated from the first replica to the other one as well as from the other replica to the first one.

Follow this procedure to use an Ansible playbook to ensure that a replication agreement of the **domain** type exists between **server.idm.example.com** and **replica.idm.example.com**.

Prerequisites

- Ensure that you understand the recommendations for designing your IdM topology listed in Guidelines for connecting IdM replicas in a topology .
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password** and that you have access to a file that stores the password protecting the **secret.yml** file.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **add-topologysegment.yml** Ansible playbook file provided by the **ansible-freeipa** package:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/add-topologysegment.yml add-topologysegment-copy.yml

- 3. Open the add-topologysegment-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipatopologysegment** task section:
 - Indicate that the value of the ipaadmin_password variable is defined in the secret.yml
 Ansible vault file.
 - Set the **suffix** variable to either **domain** or **ca**, depending on what type of segment you want to add.
 - Set the **left** variable to the name of the IdM server that you want to be the left node of the replication agreement.
 - Set the **right** variable to the name of the IdM server that you want to be the right node of the replication agreement.
 - Ensure that the **state** variable is set to **present**.

This is the modified Ansible playbook file for the current example:

- name: Playbook to handle topologysegment

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Add topology segment

ipatopologysegment:

ipaadmin_password: "{{ ipaadmin_password }}"

suffix: domain

left: server.idm.example.com right: replica.idm.example.com

state: present

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory add-topologysegment-copy.yml

Additional resources

- Explaining Replication Agreements, Topology Suffixes, and Topology Segments
- /usr/share/doc/ansible-freeipa/README-topology.md

Sample playbooks in /usr/share/doc/ansible-freeipa/playbooks/topology

15.2. USING ANSIBLE TO ENSURE REPLICATION AGREEMENTS EXIST BETWEEN MULTIPLE IDM REPLICAS

Data stored on an Identity Management (IdM) server is replicated based on replication agreements: when two servers have a replication agreement configured, they share their data. Replication agreements are always bilateral: the data is replicated from the first replica to the other one as well as from the other replica to the first one.

Follow this procedure to ensure replication agreements exist between multiple pairs of replicas in IdM.

Prerequisites

- Ensure that you understand the recommendations for designing your IdM topology listed in Connecting the replicas in a topology .
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password** and that you have access to a file that stores the password protecting the **secret.yml** file.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **add-topologysegments.yml** Ansible playbook file provided by the **ansible-freeipa** package:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/add-topologysegments.yml add-topologysegments-copy.yml

- 3. Open the add-topologysegments-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **vars** section:
 - Indicate that the value of the **ipaadmin_password** variable is defined in the **secret.yml** Ansible vault file.
 - For every topology segment, add a line in the **ipatopology_segments** section and set the following variables:

- Set the **suffix** variable to either **domain** or **ca**, depending on what type of segment you want to add
- Set the **left** variable to the name of the IdM server that you want to be the left node of the replication agreement.
- Set the **right** variable to the name of the IdM server that you want to be the right node of the replication agreement.
- 5. In the **tasks** section of the **add-topologysegments-copy.yml** file, ensure that the **state** variable is set to **present**.

This is the modified Ansible playbook file for the current example:

```
- name: Add topology segments
hosts: ipaserver
 gather_facts: false
  ipaadmin_password: "{{ ipaadmin_password }}"
  ipatopology segments:
  - {suffix: domain, left: replica1.idm.example.com , right: replica2.idm.example.com }
  - {suffix: domain, left: replica2.idm.example.com , right: replica3.idm.example.com }
  - {suffix: domain, left: replica3.idm.example.com , right: replica4.idm.example.com }
  - {suffix: domain+ca, left: replica4.idm.example.com , right: replica1.idm.example.com }
vars files:
 - /home/user_name/MyPlaybooks/secret.yml
- name: Add topology segment
  ipatopologysegment:
   ipaadmin_password: "{{ ipaadmin_password }}"
   suffix: "{{ item.suffix }}"
   name: "{{ item.name | default(omit) }}"
   left: "{{ item.left }}"
   right: "{{ item.right }}"
   state: present
  loop: "{{ ipatopology_segments | default([]) }}"
```

- 6. Save the file.
- 7. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory add-topologysegments-copy.yml

Additional resources

- Explaining Replication Agreements, Topology Suffixes, and Topology Segments
- /usr/share/doc/ansible-freeipa/README-topology.md
- Sample playbooks in /usr/share/doc/ansible-freeipa/playbooks/topology

15.3. USING ANSIBLE TO CHECK IF A REPLICATION AGREEMENT EXISTS BETWEEN TWO REPLICAS

Data stored on an Identity Management (IdM) server is replicated based on replication agreements: when two servers have a replication agreement configured, they share their data. Replication agreements are always bilateral: the data is replicated from the first replica to the other one as well as from the other replica to the first one.

Follow this procedure to verify that replication agreements exist between multiple pairs of replicas in IdM. In contrast to Using Ansible to ensure a replication agreement exists in IdM , this procedure does not modify the existing configuration.

Prerequisites

- Ensure that you understand the recommendations for designing your Identity Management (IdM) topology listed in Connecting the replicas in a topology.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password** and that you have access to a file that stores the password protecting the **secret.yml** file.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

- 1. Navigate to your ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Copy the **check-topologysegments.yml** Ansible playbook file provided by the **ansible-freeipa** package:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/check-topologysegments.yml check-topologysegments-copy.yml
- 3. Open the **check-topologysegments-copy.yml** file for editing.
- 4. Adapt the file by setting the following variables in the **vars** section:
 - Indicate that the value of the ipaadmin_password variable is defined in the secret.yml
 Ansible vault file.
 - For every topology segment, add a line in the ipatopology_segments section and set the following variables:
 - Set the **suffix** variable to either **domain** or **ca**, depending on the type of segment you are adding.

- Set the **left** variable to the name of the IdM server that you want to be the left node of the replication agreement.
- Set the **right** variable to the name of the IdM server that you want to be the right node of the replication agreement.
- 5. In the **tasks** section of the **check-topologysegments-copy.yml** file, ensure that the **state** variable is set to **present**.

This is the modified Ansible playbook file for the current example:

```
- name: Add topology segments
 hosts: ipaserver
 gather_facts: false
 vars:
  ipaadmin_password: "{{ ipaadmin_password }}"
  ipatopology_segments:
  - {suffix: domain, left: replica1.idm.example.com, right: replica2.idm.example.com }
  - {suffix: domain, left: replica2.idm.example.com, right: replica3.idm.example.com}
  - {suffix: domain, left: replica3.idm.example.com, right: replica4.idm.example.com}
  - {suffix: domain+ca, left: replica4.idm.example.com, right:
replica1.idm.example.com }
 vars_files:
 - /home/user_name/MyPlaybooks/secret.yml
 tasks:
 - name: Check topology segment
  ipatopologysegment:
   ipaadmin_password: "{{ ipaadmin_password }}"
   suffix: "{{ item.suffix }}"
   name: "{{ item.name | default(omit) }}"
   left: "{{ item.left }}"
   right: "{{ item.right }}"
   state: checked
  loop: "{{ ipatopology_segments | default([]) }}"
```

- 6. Save the file.
- 7. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory check-topologysegments-copy.yml

Additional resources

- Explaining Replication Agreements, Topology Suffixes, and Topology Segments
- /usr/share/doc/ansible-freeipa/README-topology.md
- Sample playbooks in /usr/share/doc/ansible-freeipa/playbooks/topology

15.4. USING ANSIBLE TO VERIFY THAT A TOPOLOGY SUFFIX EXISTS IN IDM

In the context of replication agreements in Identity Management (IdM), topology suffixes store the data that is replicated. IdM supports two types of topology suffixes: **domain** and **ca**. Each suffix represents a separate back end, a separate replication topology. When a replication agreement is configured, it joins two topology suffixes of the same type on two different servers.

The **domain** suffix contains all domain-related data, such as data about users, groups, and policies. The **ca** suffix contains data for the Certificate System component. It is only present on servers with a certificate authority (CA) installed.

Follow this procedure to use an Ansible playbook to ensure that a topology suffix exists in IdM. The example describes how to ensure that the **domain** suffix exists in IdM.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password** and that you have access to a file that stores the password protecting the **secret.yml** file.
- The target node, that is the node on which the ansible-freeipa module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

- Navigate to your ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Copy the **verify-topologysuffix.yml** Ansible playbook file provided by the **ansible-freeipa** package:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/ verify-topologysuffix.yml verify-topologysuffix-copy.yml
- 3. Open the **verify-topologysuffix-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipatopologysuffix** section:
 - Indicate that the value of the **ipaadmin_password** variable is defined in the **secret.yml** Ansible vault file.
 - Set the **suffix** variable to **domain**. If you are verifying the presence of the **ca** suffix, set the variable to **ca**.
 - Ensure that the **state** variable is set to **verified**. No other option is possible.

This is the modified Ansible playbook file for the current example:

- name: Playbook to handle topologysuffix

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks

- name: Verify topology suffix

ipatopologysuffix:

ipaadmin_password: "{{ ipaadmin_password }}"

suffix: domain state: verified

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory verify-topologysuffix-copy.yml

Additional resources

- Explaining Replication Agreements, Topology Suffixes, and Topology Segments
- /usr/share/doc/ansible-freeipa/README-topology.md
- Sample playbooks in /usr/share/doc/ansible-freeipa/playbooks/topology

15.5. USING ANSIBLE TO REINITIALIZE AN IDM REPLICA

If a replica has been offline for a long period of time or its database has been corrupted, you can reinitialize it. Reinitialization refreshes the replica with an updated set of data. Reinitialization can, for example, be used if an authoritative restore from backup is required.



NOTE

In contrast to replication updates, during which replicas only send changed entries to each other, reinitialization refreshes the whole database.

The local host on which you run the command is the reinitialized replica. To specify the replica from which the data is obtained, use the **direction** option.

Follow this procedure to use an Ansible playbook to reinitialize the **domain** data on **replica.idm.example.com** from **server.idm.example.com**.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.

- You have installed the **ansible-freeipa** package.
- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password** and that you have access to a file that stores the password protecting the **secret.yml** file.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **reinitialize-topologysegment.yml** Ansible playbook file provided by the **ansible-freeipa** package:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/reinitialize-topologysegment.yml reinitialize-topologysegment-copy.yml

- 3. Open the reinitialize-topologysegment-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipatopologysegment** section:
 - Indicate that the value of the ipaadmin_password variable is defined in the secret.yml
 Ansible vault file.
 - Set the **suffix** variable to **domain**. If you are reinitializing the **ca** data, set the variable to **ca**.
 - Set the **left** variable to the left node of the replication agreement.
 - Set the **right** variable to the right node of the replication agreement.
 - Set the **direction** variable to the direction of the reinitializing data. The **left-to-right** direction means that data flows from the left node to the right node.
 - Ensure that the **state** variable is set to **reinitialized**.
 This is the modified Ansible playbook file for the current example:

 name: Playbook to handle topologysegment hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks:

 name: Reinitialize topology segment ipatopologysegment:

ipaadmin_password: "{{ ipaadmin_password }}"

suffix: domain

left: server.idm.example.com

right: replica.idm.example.com

direction: left-to-right state: reinitialized

5. Save the file.

6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory reinitialize-topologysegment-copy.yml

Additional resources

- Explaining Replication Agreements, Topology Suffixes, and Topology Segments
- /usr/share/doc/ansible-freeipa/README-topology.md
- Sample playbooks in /usr/share/doc/ansible-freeipa/playbooks/topology

15.6. USING ANSIBLE TO ENSURE A REPLICATION AGREEMENT IS ABSENT IN IDM

Data stored on an Identity Management (IdM) server is replicated based on replication agreements: when two servers have a replication agreement configured, they share their data. Replication agreements are always bilateral: the data is replicated from the first replica to the other one as well as from the other replica to the first one.

Follow this procedure to ensure a replication agreement between two replicas does not exist in IdM. The example describes how to ensure a replication agreement of the **domain** type does not exist between the **replica01.idm.example.com** and **replica02.idm.example.com** IdM servers.

Prerequisites

- You understand the recommendations for designing your IdM topology listed in Connecting the replicas in a topology.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password** and that you have access to a file that stores the password protecting the **secret.yml** file.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **delete-topologysegment.yml** Ansible playbook file provided by the **ansible-freeipa** package:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/delete-topologysegment.yml delete-topologysegment-copy.yml

- 3. Open the **delete-topologysegment-copy.yml** file for editing.
- 4. Adapt the file by setting the following variables in the **ipatopologysegment** task section:
 - Indicate that the value of the **ipaadmin_password** variable is defined in the **secret.yml** Ansible vault file.
 - Set the **suffix** variable to **domain**. Alternatively, if you are ensuring that the **ca** data are not replicated between the left and right nodes, set the variable to **ca**.
 - Set the **left** variable to the name of the IdM server that is the left node of the replication agreement.
 - Set the **right** variable to the name of the IdM server that is the right node of the replication agreement.
 - Ensure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Playbook to handle topologysegment

hosts: ipaserver

vars_files:

- /home/user name/MyPlaybooks/secret.yml

tasks:

- name: Delete topology segment

ipatopologysegment:

ipaadmin_password: "{{ ipaadmin_password }}"

suffix: domain

left: replica01.idm.example.com right: replica02.idm.example.com:

state: absent

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory delete-topologysegment-copy.yml

Additional resources

• Explaining Replication Agreements, Topology Suffixes, and Topology Segments

- /usr/share/doc/ansible-freeipa/README-topology.md
- Sample playbooks in /usr/share/doc/ansible-freeipa/playbooks/topology

15.7. ADDITIONAL RESOURCES

- Planning the replica topology.
- Installing an IdM replica .

CHAPTER 16. MANAGING IDM SERVERS BY USING ANSIBLE

You can use **Red Hat Ansible Engine** to manage the servers in your Identity Management (IdM) topology. You can use the **server** module in the **ansible-freeipa** package to check the presence or absence of a server in the IdM topology. You can also hide any replica or make a replica visible.

The section contains the following topics:

- Checking that an IdM server is present by using Ansible
- Ensuring that an IdM server is absent from an IdM topology by using Ansible
- Ensuring the absence of an IdM server despite hosting a last IdM server role
- Ensuring that an IdM server is absent but not necessarily disconnected from other IdM servers
- Ensuring that an existing IdM server is hidden using an Ansible playbook
- Ensuring that an existing IdM server is visible using an Ansible playbook
- Ensuring that an existing IdM server has an IdM DNS location assigned
- Ensuring that an existing IdM server has no IdM DNS location assigned

16.1. CHECKING THAT AN IDM SERVER IS PRESENT BY USING ANSIBLE

You can use the **ipaserver ansible-freeipa** module in an Ansible playbook to verify that an Identity Management (IdM) server exists.



NOTE

The **ipaserver** Ansible module does not install the IdM server.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the secret.yml Ansible vault stores your ipaadmin password.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
 - The **SSH** connection from the control node to the IdM server defined in the inventory file is working correctly.

Procedure

Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **server-present.yml** Ansible playbook file located in the /**usr/share/doc/ansible-freeipa/playbooks/server/** directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/server/server-present.yml server-present-copy.yml

- 3. Open the **server-present-copy.yml** file for editing.
- 4. Adapt the file by setting the following variables in the **ipaserver** task section and save the file:
 - Set the **ipaadmin password** variable to the password of the IdM **admin**.
 - Set the **name** variable to the **FQDN** of the server. The **FQDN** of the example server is **server123.idm.example.com**.

- name: Server present example

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure server server123.idm.example.com is present ipaserver:

ipaadmin_password: "{{ ipaadmin_password }}"
name: server123.idm.example.com

5. Run the Ansible playbook and specify the playbook file and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory server-present-copy.yml

Additional resources

- Installing an Identity Management server using an Ansible playbook
- The README-server.md file in the /usr/share/doc/ansible-freeipa/ directory
- The sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/server directory

16.2. ENSURING THAT AN IDM SERVER IS ABSENT FROM AN IDM TOPOLOGY BY USING ANSIBLE

Use an Ansible playbook to ensure an Identity Management (IdM) server does not exist in an IdM topology, even as a host.

In contrast to the **ansible-freeipa ipaserver** role, the **ipaserver** module used in this playbook does not uninstall IdM services from the server.

Prerequisites

• On the control node:

- You are using Ansible version 2.14 or later.
- You have installed the **ansible-freeipa** package.
- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
 - The **SSH** connection from the control node to the IdM server defined in the inventory file is working correctly.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **server-absent.yml** Ansible playbook file located in the **/usr/share/doc/ansible-freeipa/playbooks/server/** directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/server/server-absent.yml server-absent-copy.yml

- 3. Open the **server-absent-copy.yml** file for editing.
- 4. Adapt the file by setting the following variables in the **ipaserver** task section and save the file:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to the **FQDN** of the server. The **FQDN** of the example server is **server123.idm.example.com**.
 - Ensure that the **state** variable is set to **absent**.

- name: Server absent example

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure server server123.idm.example.com is absent

ipaserver:

ipaadmin_password: "{{ ipaadmin_password }}"

name: server123.idm.example.com

state: absent

5. Run the Ansible playbook and specify the playbook file and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory server-absent-copy.yml

6. Make sure all name server (NS) DNS records pointing to **server123.idm.example.com** are deleted from your DNS zones. This applies regardless of whether you use integrated DNS managed by IdM or external DNS.

Additional resources

- Uninstalling an IdM server
- The README-server.md file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/server directory

16.3. ENSURING THE ABSENCE OF AN IDM SERVER DESPITE HOSTING A LAST IDM SERVER ROLE

You can use Ansible to ensure that an Identity Management (IdM) server is absent even if the last IdM service instance is running on the server. A certificate authority (CA), key recovery authority (KRA), or DNS server are all examples of IdM services.



WARNING

If you remove the last server that serves as a CA, KRA, or DNS server, you disrupt IdM functionality seriously. You can manually check which services are running on which IdM servers with the **ipa service-find** command. The principal name of a CA server is **dogtag**/**server_name**/**REALM_NAME**.

In contrast to the **ansible-freeipa ipaserver** role, the **ipaserver** module used in this playbook does not uninstall IdM services from the server.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
 - The **SSH** connection from the control node to the IdM server defined in the inventory file is working correctly.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **server-absent-ignore-last-of-role.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/server/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/server/server-absent-ignore-last-of-role.yml server-absent-ignore-last-of-role-copy.yml

- 3. Open the server-absent-ignore-last-of-role-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipaserver** task section and save the file:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to the **FQDN** of the server. The **FQDN** of the example server is **server123.idm.example.com**.
 - Ensure that the **ignore_last_of_role** variable is set to **true**.
 - Set the **state** variable to **absent**.

- name: Server absent with last of role skip example

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure server "server123.idm.example.com" is absent with last of role skip ipaserver:

ipaadmin_password: "{{ ipaadmin_password }}"

name: server123.idm.example.com

ignore last of role: true

state: absent

5. Run the Ansible playbook and specify the playbook file and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory server-absent-ignore-last-of-role-copy.yml

6. Make sure all name server (NS) DNS records that point to **server123.idm.example.com** are deleted from your DNS zones. This applies regardless of whether you use integrated DNS managed by IdM or external DNS.

Additional resources

- Uninstalling an IdM server
- The README-server.md file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/server directory

16.4. ENSURING THAT AN IDM SERVER IS ABSENT BUT NOT NECESSARILY DISCONNECTED FROM OTHER IDM SERVERS

If you are removing an Identity Management (IdM) server from the topology, you can keep its replication agreements intact with an Ansible playbook. The playbook also ensures that the IdM server does not exist in IdM, even as a host.



IMPORTANT

Ignoring a server's replication agreements when removing it is only recommended when the other servers are dysfunctional servers that you are planning to remove anyway. Removing a server that serves as a central point in the topology can split your topology into two disconnected clusters.

You can remove a dysfunctional server from the topology with the **ipa server-del** command.



NOTE

If you remove the last server that serves as a certificate authority (CA), key recovery authority (KRA), or DNS server, you seriously disrupt the Identity Management (IdM) functionality. To prevent this problem, the playbook makes sure these services are running on another server in the domain before it uninstalls a server that serves as a CA, KRA, or DNS server.

In contrast to the **ansible-freeipa ipaserver** role, the **ipaserver** module used in this playbook does not uninstall IdM services from the server.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
 - The **SSH** connection from the control node to the IdM server defined in the inventory file is working correctly.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **server-absent-ignore_topology_disconnect.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/server/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/server/server-absent-ignore_topology_disconnect.yml server-absent-ignore_topology_disconnect-copy.yml

- 3. Open the server-absent-ignore_topology_disconnect-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipaserver** task section and save the file:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the name variable to the FQDN of the server. The FQDN of the example server is server123.idm.example.com.
 - Ensure that the **ignore_topology_disconnect** variable is set to **true**.
 - Ensure that the **state** variable is set to **absent**.

- name: Server absent with ignoring topology disconnects example

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks

- name: Ensure server "server123.idm.example.com" with ignoring topology disconnects ipaserver:

ipaadmin_password: "{{ ipaadmin_password }}"

name: server123.idm.example.com ignore topology disconnect: true

state: absent

5. Run the Ansible playbook and specify the playbook file and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory server-absent-ignore_topology_disconnect-copy.yml

6. Optional: Make sure all name server (NS) DNS records pointing to **server123.idm.example.com** are deleted from your DNS zones. This applies regardless of whether you use integrated DNS managed by IdM or external DNS.

Additional resources

- Uninstalling an IdM server
- The README-server.md file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/server directory.

16.5. ENSURING THAT AN EXISTING IDM SERVER IS HIDDEN USING AN ANSIBLE PLAYBOOK

Use the **ipaserver ansible-freeipa** module in an Ansible playbook to ensure that an existing Identity Management (IdM) server is hidden. Note that this playbook does not install the IdM server.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
 - The **SSH** connection from the control node to the IdM server defined in the inventory file is working correctly.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **server-hidden.yml** Ansible playbook file located in the /**usr/share/doc/ansible-freeipa/playbooks/server/** directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/server/server-hidden.yml server-hiddencopy.yml

- 3. Open the **server-hidden-copy.yml** file for editing.
- 4. Adapt the file by setting the following variables in the **ipaserver** task section and save the file:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the name variable to the FQDN of the server. The FQDN of the example server is server123.idm.example.com.
 - Ensure that the **hidden** variable is set to **True**.

- name: Server hidden example

hosts: ipaserver vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure server server123.idm.example.com is hidden ipaserver:

ipaadmin_password: "{{ ipaadmin_password }}"

name: server123.idm.example.com

hidden: True

5. Run the Ansible playbook and specify the playbook file and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory server-hidden-copy.yml

Additional resources

- Installing an Identity Management server using an Ansible playbook
- The hidden replica mode
- The **README-server.md** file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/server directory

16.6. ENSURING THAT AN EXISTING IDM SERVER IS VISIBLE BY USING AN ANSIBLE PLAYBOOK

Use the **ipaserver ansible-freeipa** module in an Ansible playbook to ensure that an existing Identity Management (IdM) server is visible. Note that this playbook does not install the IdM server.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
 - The **SSH** connection from the control node to the IdM server defined in the inventory file is working correctly.

Procedure

- 1. Navigate to your ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Copy the **server-not-hidden.yml** Ansible playbook file located in the **/usr/share/doc/ansible-freeipa/playbooks/server/** directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/server/server-not-hidden.yml server-not-hidden.yml
- 3. Open the **server-not-hidden-copy.yml** file for editing.
- 4. Adapt the file by setting the following variables in the **ipaserver** task section and save the file:

- Set the **ipaadmin_password** variable to the password of the IdM **admin**.
- Set the **name** variable to the **FQDN** of the server. The **FQDN** of the example server is **server123.idm.example.com**.
- Ensure that the **hidden** variable is set to **no**.

- name: Server not hidden example

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure server server123.idm.example.com is not hidden

ipaserver:

ipaadmin_password: "{{ ipaadmin_password }}"

name: server123.idm.example.com

hidden: no

5. Run the Ansible playbook and specify the playbook file and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory server-not-hidden-copy.yml

Additional resources

- Installing an Identity Management server using an Ansible playbook
- The hidden replica mode
- The README-server.md file in the /usr/share/doc/ansible-freeipa/ directory
- The sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/server directory

16.7. ENSURING THAT AN EXISTING IDM SERVER HAS AN IDM DNS LOCATION ASSIGNED

Use the **ipaserver ansible-freeipa** module in an Ansible playbook to ensure that an existing Identity Management (IdM) server is assigned a specific IdM DNS location.

Note that the **ipaserver** Ansible module does not install the IdM server.

Prerequisites

- You know the IdM **admin** password.
- The IdM DNS location exists. The example location is **germany**.
- You have **root** access to the server. The example server is **server123.idm.example.com**.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.

- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the secret.yml Ansible vault stores your ipaadmin_password.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
 - The **SSH** connection from the control node to the IdM server defined in the inventory file is working correctly.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **server-location.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/server/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/server/server-location.yml server-location-copy.yml

- 3. Open the **server-location-copy.yml** file for editing.
- 4. Adapt the file by setting the following variables in the **ipaserver** task section and save the file:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **server123.idm.example.com**.
 - Set the **location** variable to **germany**.

This is the modified Ansible playbook file for the current example:

- name: Server enabled example

hosts: ipaserver vars files:

- /home/user name/MyPlaybooks/secret.yml

tasks:

- name: Ensure server server123.idm.example.com with location "germany" is present ipaserver:

ipaadmin_password: "{{ ipaadmin_password }}"

name: server123.idm.example.com

location: germany

5. Run the Ansible playbook and specify the playbook file and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory server-location-copy.yml

6. Connect to **server123.idm.example.com** as **root** using **SSH**:

ssh root@server123.idm.example.com

7. Restart the **named-pkcs11** service on the server for the updates to take effect immediately:

[root@server123.idm.example.com ~]# systemctl restart named-pkcs11

Additional resources

- Installing an Identity Management server using an Ansible playbook
- Using Ansible to ensure an IdM location is present
- The **README-server.md** file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/server directory

16.8. ENSURING THAT AN EXISTING IDM SERVER HAS NO IDM DNS LOCATION ASSIGNED

Use the **ipaserver ansible-freeipa** module in an Ansible playbook to ensure that an existing Identity Management (IdM) server has no IdM DNS location assigned to it. Do not assign a DNS location to servers that change geographical location frequently. Note that the playbook does not install the IdM server.

Prerequisites

- You know the IdM **admin** password.
- You have **root** access to the server. The example server is **server123.idm.example.com**.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
 - The **SSH** connection from the control node to the IdM server defined in the inventory file is working correctly.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **server-no-location.yml** Ansible playbook file located in the **/usr/share/doc/ansible-freeipa/playbooks/server/** directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/server/server-no-location.yml server-no-location-copy.yml

- 3. Open the **server-no-location-copy.yml** file for editing.
- 4. Adapt the file by setting the following variables in the **ipaserver** task section and save the file:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **server123.idm.example.com**.
 - Ensure that the **location** variable is set to "".

- name: Server no location example

hosts: ipaserver

vars files:

 $\hbox{- /home/user_name/MyPlaybooks/secret.yml}$

tasks

- name: Ensure server server123.idm.example.com is present with no location ipaserver:

ipaadmin_password: "{{ ipaadmin_password }}"

name: server123.idm.example.com

location: ""

5. Run the Ansible playbook and specify the playbook file and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory server-no-location-copy.yml

6. Connect to **server123.idm.example.com** as **root** using **SSH**:

ssh root@server123.idm.example.com

7. Restart the **named-pkcs11** service on the server for the updates to take effect immediately:

[root@server123.idm.example.com ~]# systemctl restart named-pkcs11

Additional resources

- Installing an Identity Management server using an Ansible playbook
- Using Ansible to manage DNS locations in IdM
- The README-server.md file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/server directory

CHAPTER 17. MANAGING HOSTS USING ANSIBLE PLAYBOOKS

Ansible is an automation tool used to configure systems, deploy software, and perform rolling updates. Ansible includes support for Identity Management (IdM), and you can use Ansible modules to automate host management.

17.1. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH FQDN USING ANSIBLE PLAYBOOKS

Follow this procedure to ensure the presence of host entries in Identity Management (IdM) using Ansible playbooks. The host entries are only defined by their **fully-qualified domain names** (FQDNs).

Specifying the **FQDN** name of the host is enough if at least one of the following conditions applies:

- The IdM server is not configured to manage DNS.
- The host does not have a static IP address or the IP address is not known at the time the host is
 configured. Adding a host defined only by an FQDN essentially creates a placeholder entry in the
 IdM DNS service. For example, laptops may be preconfigured as IdM clients, but they do not
 have IP addresses at the time they are configured. When the DNS service dynamically updates
 its records, the host's current IP address is detected and its DNS record is updated.



NOTE

Without Ansible, host entries are created in IdM using the **ipa host-add** command. The result of adding a host to IdM is the state of the host being present in IdM. Because of the Ansible reliance on idempotence, to add a host to IdM using Ansible, you must create a playbook in which you define the state of the host as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com 2. Create an Ansible playbook file with the **FQDN** of the host whose presence in IdM you want to ensure. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/host/add-host.yml file:

 name: Host present hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

name: Host host01.idm.example.com present ipahost:

ipaadmin_password: "{{ ipaadmin_password }}"

name: host01.idm.example.com

state: present force: true

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-host-is-present.yml



NOTE

The procedure results in a host entry in the IdM LDAP server being created but not in enrolling the host into the IdM Kerberos realm. For that, you must deploy the host as an IdM client. For details, see Installing an Identity Management client using an Ansible playbook.

Verification

1. Log in to your IdM server as admin:

\$ ssh admin@server.idm.example.com Password:

2. Enter the **ipa host-show** command and specify the name of the host:

\$ ipa host-show host01.idm.example.com

Host name: host01.idm.example.com

Principal name: host/host01.idm.example.com@IDM.EXAMPLE.COM Principal alias: host/host01.idm.example.com@IDM.EXAMPLE.COM

Password: False Keytab: False

Managed by: host01.idm.example.com

The output confirms that **hostO1.idm.example.com** exists in IdM.

17.2. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH DNS INFORMATION USING ANSIBLE PLAYBOOKS

Follow this procedure to ensure the presence of host entries in Identity Management (IdM) using Ansible playbooks. The host entries are defined by their **fully-qualified domain names** (FQDNs) and their IP addresses.



NOTE

Without Ansible, host entries are created in IdM using the **ipa host-add** command. The result of adding a host to IdM is the state of the host being present in IdM. Because of the Ansible reliance on idempotence, to add a host to IdM using Ansible, you must create a playbook in which you define the state of the host as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the **fully-qualified domain name** (FQDN) of the host whose presence in IdM you want to ensure. In addition, if the IdM server is configured to manage DNS and you know the IP address of the host, specify a value for the **ip_address** parameter. The IP address is necessary for the host to exist in the DNS resource records. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/host/host-present.yml file. You can also include other, additional information:

 name: Host present hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks:
- name: Ensure host01.idm.example.com is present ipahost:

ipaadmin_password: "{{ ipaadmin_password }}"

name: host01.idm.example.com

description: Example host ip_address: 192.168.0.123

locality: Lab

ns_host_location: Lab ns_os_version: RHEL 7

ns_hardware_platform: Lenovo T61

mac address:

- "08:00:27:E3:B1:2D" - "52:54:00:BD:97:1E"

state: present

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-host-is-present.yml



NOTE

The procedure results in a host entry in the IdM LDAP server being created but not in enrolling the host into the IdM Kerberos realm. For that, you must deploy the host as an IdM client. For details, see Installing an Identity Management client using an Ansible playbook.

Verification

1. Log in to your IdM server as admin:

\$ ssh admin@server.idm.example.com Password:

2. Enter the **ipa host-show** command and specify the name of the host:

\$ ipa host-show host01.idm.example.com

Host name: host01.idm.example.com

Description: Example host

Locality: Lab Location: Lab

Platform: Lenovo T61 Operating system: RHEL 7

Principal name: host/host01.idm.example.com@IDM.EXAMPLE.COM Principal alias: host/host01.idm.example.com@IDM.EXAMPLE.COM

MAC address: 08:00:27:E3:B1:2D, 52:54:00:BD:97:1E

Password: False Keytab: False

Managed by: host01.idm.example.com

The output confirms **hostO1.idm.example.com** exists in IdM.

17.3. ENSURING THE PRESENCE OF MULTIPLE IDM HOST ENTRIES WITH RANDOM PASSWORDS USING ANSIBLE PLAYBOOKS

The **ipahost** module allows the system administrator to ensure the presence or absence of multiple host

entries in IdM using just one Ansible task. Follow this procedure to ensure the presence of multiple host entries that are only defined by their **fully-qualified domain names** (FQDNs). Running the Ansible playbook generates random passwords for the hosts.



NOTE

Without Ansible, host entries are created in IdM using the **ipa host-add** command. The result of adding a host to IdM is the state of the host being present in IdM. Because of the Ansible reliance on idempotence, to add a host to IdM using Ansible, you must create a playbook in which you define the state of the host as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the fully-qualified domain name (FQDN) of the hosts whose presence in IdM you want to ensure. To make the Ansible playbook generate a random password for each host even when the host already exists in IdM and update_password is limited to on_create, add the random: true and force: true options. To simplify this step, you can copy and modify the example from the /usr/share/doc/ansible-freeipa/README-host.md Markdown file:

- name: Ensure hosts with random password

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks:

- name: Hosts host01.idm.example.com and host02.idm.example.com present with random passwords

ipahost:

ipaadmin_password: "{{ ipaadmin_password }}"

hosts:

- name: host01.idm.example.com

random: true force: true

- name: host02.idm.example.com

random: true force: true register: ipahost

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hostsare-present.yml

[...]

TASK [Hosts host01.idm.example.com and host02.idm.example.com present with random passwords]

changed: [r8server.idm.example.com] => {"changed": true, "host":

 $\\ \{ "host 01. idm. example.com" : \\ \{ "random password" : "0HoIRvjUdH0Ycbf6uYdWTxH" \}, \\ \{ (random password) : \\ \{ (random$

"host02.idm.example.com": {"randompassword": "5VdLgrf3wvojmACdHC3uA3s"}}}



NOTE

To deploy the hosts as IdM clients using random, one-time passwords (OTPs), see Authorization options for IdM client enrollment using an Ansible playbook or Installing a client by using a one-time password: Interactive installation.

Verification

1. Log in to your IdM server as admin:

\$ ssh admin@server.idm.example.com Password:

2. Enter the **ipa host-show** command and specify the name of one of the hosts:

\$ ipa host-show host01.idm.example.com

Host name: host01.idm.example.com

Password: True Keytab: False

Managed by: host01.idm.example.com

The output confirms **hostO1.idm.example.com** exists in IdM with a random password.

17.4. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH MULTIPLE IP ADDRESSES USING ANSIBLE PLAYBOOKS

Follow this procedure to ensure the presence of a host entry in Identity Management (IdM) using Ansible playbooks. The host entry is defined by its **fully-qualified domain name** (FQDN) and its multiple IP addresses.



NOTE

In contrast to the **ipa host** utility, the Ansible **ipahost** module can ensure the presence or absence of several IPv4 and IPv6 addresses for a host. The ipa host-mod command cannot handle IP addresses.

Prerequisites

- You know the IdM administrator password.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the ansible-freeipa module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file. Specify, as the name of the ipahost variable, the fully-qualified domain name (FQDN) of the host whose presence in IdM you want to ensure. Specify each of the multiple IPv4 and IPv6 ip address values on a separate line by using the ip_address syntax. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansiblefreeipa/playbooks/host/host-member-ipaddresses-present.yml file. You can also include additional information:

- name: Host member IP addresses present

hosts: ipaserver

vars_files:

- /home/user name/MyPlaybooks/secret.yml

- name: Ensure host101.example.com IP addresses present

ipaadmin_password: "{{ ipaadmin_password }}"

name: host01.idm.example.com

ip address:

- 192.168.0.123
- fe80::20c:29ff:fe02:a1b3
- 192.168.0.124
- fe80::20c:29ff:fe02:a1b4

force: true

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-host-with-multiple-IP-addreses-is-present.yml



NOTE

The procedure creates a host entry in the IdM LDAP server but does not enroll the host into the IdM Kerberos realm. For that, you must deploy the host as an IdM client. For details, see Installing an Identity Management client using an Ansible playbook.

Verification

1. Log in to your IdM server as admin:

\$ ssh admin@server.idm.example.com Password:

2. Enter the **ipa host-show** command and specify the name of the host:

\$ ipa host-show host01.idm.example.com

Principal name: host/host01.idm.example.com@IDM.EXAMPLE.COM Principal alias: host/host01.idm.example.com@IDM.EXAMPLE.COM

Password: False Keytab: False

Managed by: host01.idm.example.com

The output confirms that **hostO1.idm.example.com** exists in IdM.

- 3. To verify that the multiple IP addresses of the host exist in the IdM DNS records, enter the **ipa dnsrecord-show** command and specify the following information:
 - The name of the IdM domain
 - The name of the host

\$ ipa dnsrecord-show idm.example.com host01

[...]

Record name: host01

A record: 192.168.0.123, 192.168.0.124

AAAA record: fe80::20c:29ff:fe02:a1b3, fe80::20c:29ff:fe02:a1b4

The output confirms that all the IPv4 and IPv6 addresses specified in the playbook are correctly associated with the **host01.idm.example.com** host entry.

17.5. ENSURING THE ABSENCE OF AN IDM HOST ENTRY USING ANSIBLE PLAYBOOKS

Follow this procedure to ensure the absence of host entries in Identity Management (IdM) using Ansible playbooks.

Prerequisites

IdM administrator credentials

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

 Create an Ansible playbook file with the fully-qualified domain name (FQDN) of the host whose absence from IdM you want to ensure. If your IdM domain has integrated DNS, use the updatedns: true option to remove the associated records of any kind for the host from the DNS.

To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/host/delete-host.yml file:

 name: Host absent hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

name: Host host01.idm.example.com absent ipahost:

ipaadmin_password: "{{ ipaadmin_password }}"

name: host01.idm.example.com

updatedns: true state: absent

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-host-absent.yml



NOTE

The procedure results in:

- The host not being present in the IdM Kerberos realm.
- The host entry not being present in the IdM LDAP server.

To remove the specific IdM configuration of system services, such as System Security Services Daemon (SSSD), from the client host itself, you must run the **ipa-client-install -- uninstall** command on the client. For details, see Uninstalling an IdM client.

Verification

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com
Password:
[admin@server/]\$

2. Display information about *hostO1.idm.example.com*:

\$ ipa host-show host01.idm.example.com ipa: ERROR: host01.idm.example.com: host not found

The output confirms that the host does not exist in IdM.

17.6. ADDITIONAL RESOURCES

- See the /usr/share/doc/ansible-freeipa/README-host.md Markdown file.
- See the additional playbooks in the /usr/share/doc/ansible-freeipa/playbooks/host directory.

CHAPTER 18. MANAGING HOST GROUPS USING ANSIBLE PLAYBOOKS

Learn more about host groups in Identity Management (IdM) and using Ansible to perform operations involving host groups in Identity Management (IdM).

18.1. HOST GROUPS IN IDM

IdM host groups can be used to centralize control over important management tasks, particularly access control.

Definition of host groups

A host group is an entity that contains a set of IdM hosts with common access control rules and other characteristics. For example, you can define host groups based on company departments, physical locations, or access control requirements.

A host group in IdM can include:

- IdM servers and clients
- Other IdM host groups

Host groups created by default

By default, the IdM server creates the host group **ipaservers** for all IdM server hosts.

Direct and indirect group members

Group attributes in IdM apply to both direct and indirect members: when host group B is a member of host group A, all members of host group B are considered indirect members of host group A.

18.2. ENSURING THE PRESENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

Follow this procedure to ensure the presence of host groups in Identity Management (IdM) using Ansible playbooks.



NOTE

Without Ansible, host group entries are created in IdM using the **ipa hostgroup-add** command. The result of adding a host group to IdM is the state of the host group being present in IdM. Because of the Ansible reliance on idempotence, to add a host group to IdM using Ansible, you must create a playbook in which you define the state of the host group as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.

- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

```
[ipaserver] server.idm.example.com
```

Create an Ansible playbook file with the necessary host group information. For example, to
ensure the presence of a host group named databases, specify name: databases in the
ipahostgroup task. To simplify this step, you can copy and modify the example in the
/usr/share/doc/ansible-freeipa/playbooks/user/ensure-hostgroup-is-present.yml file.

```
    name: Playbook to handle hostgroups
hosts: ipaserver
    vars files:
```

- /home/user_name/MyPlaybooks/secret.yml

Ensure host-group databases is present

- ipahostgroup:

ipaadmin_password: "{{ ipaadmin_password }}"

name: databases state: present

In the playbook, **state: present** signifies a request to add the host group to IdM unless it already exists there.

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hostgroup-is-present.yml

Verification

1. Log into **ipaserver** as admin:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about the host group whose presence in IdM you wanted to ensure:

\$ ipa hostgroup-show databases

Host-group: databases

The databases host group exists in IdM.

18.3. ENSURING THE PRESENCE OF HOSTS IN IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

Follow this procedure to ensure the presence of hosts in host groups in Identity Management (IdM) using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The hosts you want to reference in your Ansible playbook exist in IdM. For details, see Ensuring the presence of an IdM host entry using Ansible playbooks.
- The host groups you reference from the Ansible playbook file have been added to IdM. For details, see Ensuring the presence of IdM host groups using Ansible playbooks.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com

Create an Ansible playbook file with the necessary host information. Specify the name of the
host group using the **name** parameter of the **ipahostgroup** variable. Specify the name of the
host with the **host** parameter of the **ipahostgroup** variable. To simplify this step, you can copy
and modify the examples in the /usr/share/doc/ansible-

freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-present-in-hostgroup.yml file:

- name: Playbook to handle hostgroups

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

Ensure host-group databases is present

- ipahostgroup:

ipaadmin_password: "{{ ipaadmin_password }}"

name: databases

host:

- db.idm.example.com

action: member

This playbook adds the **db.idm.example.com** host to the **databases** host group. The **action: member** line indicates that when the playbook is run, no attempt is made to add the **databases** group itself. Instead, only an attempt is made to add **db.idm.example.com** to **databases**.

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hostsor-hostgroups-are-present-in-hostgroup.yml

Verification

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com

Password:

[admin@server/]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about a host group to see which hosts are present in it:

\$ ipa hostgroup-show databases

Host-group: databases

Member hosts: db.idm.example.com

The **db.idm.example.com** host is present as a member of the **databases** host group.

18.4. NESTING IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

Follow this procedure to ensure the presence of nested host groups in Identity Management (IdM) host groups using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The host groups you reference from the Ansible playbook file exist in IdM. For details, see Ensuring the presence of IdM host groups using Ansible playbooks.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary host group information. To ensure that a nested host group A exists in a host group B: in the Ansible playbook, specify, among the ipahostgroup variables, the name of the host group B using the name variable. Specify the name of the nested hostgroup A with the hostgroup variable. To simplify this step, you can copy and modify the examples in the /usr/share/doc/ansible-

freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-present-in-hostgroup.yml file:

- name: Playbook to handle hostgroups

hosts: ipaserver

vars_files:

 $\hbox{- /home/user_name/MyPlaybooks/secret.yml}$

tasks:

Ensure hosts and hostgroups are present in existing databases hostgroup

- ipahostgroup:

ipaadmin password: "{{ ipaadmin password }}"

name: databases

hostgroup:

- mysql-server
- oracle-server

action: member

This Ansible playbook ensures the presence of the **myqsl-server** and **oracle-server** host groups in the **databases** host group. The **action: member** line indicates that when the playbook is run, no attempt is made to add the **databases** group itself to IdM.

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hostsor-hostgroups-are-present-in-hostgroup.yml

Verification

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password: [admin@server /]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about the host group in which nested host groups are present:

\$ ipa hostgroup-show databases

Host-group: databases

Member hosts: db.idm.example.com

Member host-groups: mysql-server, oracle-server

The mysql-server and oracle-server host groups exist in the databases host group.

18.5. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of member managers in IdM hosts and host groups using an Ansible playbook.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You must have the name of the host or host group you are adding as member managers and the name of the host group you want them to manage.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary host and host group member management information:

- name: Playbook to handle host group membership management hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml tasks:

 name: Ensure member manager user example_member is present for group_name ipahostgroup:

ipaadmin_password: "{{ ipaadmin_password }}"
name: group_name
membermanager_user: example_member

 name: Ensure member manager group project_admins is present for group_name ipahostgroup:

ipaadmin_password: "{{ ipaadmin_password }}"
name: group_name
membermanager_group: project_admins

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/add-member-managers-host-groups.yml

Verification

You can verify if the **group_name** group contains **example_member** and **project_admins** as member managers by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server /]\$

2. Display information about testhostgroup:

ipaserver]\$ ipa hostgroup-show group_name

Host-group: group_name

Member hosts: server.idm.example.com Member host-groups: testhostgroup2

Membership managed by groups: project_admins Membership managed by users: example_member

Additional resources

- See ipa hostgroup-add-member-manager --help.
- See the **ipa** man page on your system.

18.6. ENSURING THE ABSENCE OF HOSTS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

Follow this procedure to ensure the absence of hosts from host groups in Identity Management (IdM) using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The hosts you want to reference in your Ansible playbook exist in IdM. For details, see Ensuring the presence of an IdM host entry using Ansible playbooks.
- The host groups you reference from the Ansible playbook file exist in IdM. For details, see Ensuring the presence of IdM host groups using Ansible playbooks.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary host and host group information. Specify the name of the host group using the **name** parameter of the **ipahostgroup** variable. Specify the name of the host whose absence from the host group you want to ensure using the **host** parameter of the **ipahostgroup** variable. To simplify this step, you can copy and modify the examples in the /usr/share/doc/ansible-freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-absent-in-hostgroup.yml file:

- name: Playbook to handle hostgroups

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks

Ensure host-group databases is absent

- ipahostgroup:

ipaadmin_password: "{{ ipaadmin_password }}"

name: databases

host:

- db.idm.example.com

action: member state: absent

This playbook ensures the absence of the **db.idm.example.com** host from the **databases** host group. The **action:** member line indicates that when the playbook is run, no attempt is made to remove the **databases** group itself.

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hostsor-hostgroups-are-absent-in-hostgroup.yml

Verification

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com

Password:

[admin@server/]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about the host group and the hosts it contains:

\$ ipa hostgroup-show databases

Host-group: databases

Member host-groups: mysql-server, oracle-server

The db.idm.example.com host does not exist in the databases host group.

18.7. ENSURING THE ABSENCE OF NESTED HOST GROUPS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

Follow this procedure to ensure the absence of nested host groups from outer host groups in Identity Management (IdM) using Ansible playbooks.

Prerequisites

• You know the IdM administrator password.

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The host groups you reference from the Ansible playbook file exist in IdM. For details, see Ensuring the presence of IdM host groups using Ansible playbooks.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com

Create an Ansible playbook file with the necessary host group information. Specify, among the ipahostgroup variables, the name of the outer host group using the name variable. Specify the name of the nested hostgroup with the hostgroup variable. To simplify this step, you can copy and modify the examples in the /usr/share/doc/ansible-

freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-absent-in-hostgroup.yml file:

- name: Playbook to handle hostgroups

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

Ensure hosts and hostgroups are absent in existing databases hostgroup

- ipahostgroup:

ipaadmin_password: "{{ ipaadmin_password }}"

name: databases

hostgroup:

- mysql-server

- oracle-server

action: member state: absent

This playbook makes sure that the **mysql-server** and **oracle-server** host groups are absent from the **databases** host group. The **action: member** line indicates that when the playbook is run, no attempt is made to ensure the **databases** group itself is deleted from IdM.

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hostsor-hostgroups-are-absent-in-hostgroup.yml

Verification

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password: [admin@server /]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about the host group from which nested host groups should be absent:

\$ ipa hostgroup-show databases

Host-group: databases

The output confirms that the **mysql-server** and **oracle-server** nested host groups are absent from the outer **databases** host group.

18.8. ENSURING THE ABSENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

Follow this procedure to ensure the absence of host groups in Identity Management (IdM) using Ansible playbooks.



NOTE

Without Ansible, host group entries are removed from IdM using the **ipa hostgroup-del** command. The result of removing a host group from IdM is the state of the host group being absent from IdM. Because of the Ansible reliance on idempotence, to remove a host group from IdM using Ansible, you must create a playbook in which you define the state of the host group as absent: **state: absent**

Prerequisites

- You know the IdM administrator password.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.

• The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary host group information. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/user/ensure-hostgroup-is-absent.yml file.

- name: Playbook to handle hostgroups

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks

- Ensure host-group databases is absent

ipahostgroup:

ipaadmin_password: "{{ ipaadmin_password }}"

name: databases state: absent

This playbook ensures the absence of the **databases** host group from IdM. The **state: absent** means a request to delete the host group from IdM unless it is already deleted.

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hostgroup-is-absent.yml

Verification

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password: [admin@server /]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about the host group whose absence you ensured:

\$ ipa hostgroup-show databases

ipa: ERROR: databases: host group not found

The databases host group does not exist in IdM.

18.9. ENSURING THE ABSENCE OF MEMBER MANAGERS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the absence of member managers in IdM hosts and host groups using an Ansible playbook.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You must have the name of the user or user group you are removing as member managers and the name of the host group they are managing.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver] server.idm.example.com
```

state: absent

2. Create an Ansible playbook file with the necessary host and host group member management information:

```
name: Playbook to handle host group membership management hosts: ipaserver
vars_files:
    -/home/user_name/MyPlaybooks/secret.yml tasks:
    - name: Ensure member manager host and host group members are absent for group_name
    ipahostgroup:
    ipaadmin_password: "{{ ipaadmin_password }}"
    name: group_name
    membermanager_user: example_member
    membermanager_group: project_admins
    action: member
```

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensuremember-managers-host-groups-are-absent.yml

Verification

You can verify if the **group_name** group does not contain **example_member** or **project_admins** as member managers by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Display information about testhostgroup:

ipaserver]\$ ipa hostgroup-show group_name
Host-group: group_name
Member hosts: server.idm.example.com
Member host-groups: testhostgroup2

Additional resources

- See ipa hostgroup-add-member-manager --help.
- See the **ipa** man page on your system.

CHAPTER 19. DEFINING IDM PASSWORD POLICIES

Password policies help to reduce the risk of someone discovering and misusing a user's password. You can add Identity Management (IdM) password policies in the IdM WebUI or the CLI. Additionally, you can add a new password policy in IdM using an Ansible playbook.

19.1. WHAT IS A PASSWORD POLICY

A password policy is a set of rules that passwords must meet. For example, a password policy can define the minimum password length and the maximum password lifetime. All users affected by this policy are required to set a sufficiently long password and change it frequently enough to meet the specified conditions. In this way, password policies help reduce the risk of someone discovering and misusing a user's password.

19.2. PASSWORD POLICIES IN IDM

Passwords are the most common way for Identity Management (IdM) users to authenticate to the IdM Kerberos domain. Password policies define the requirements that these IdM user passwords must meet. The IdM password policy is set in the underlying LDAP directory, but the Kerberos Key Distribution Center (KDC) enforces the password policy.

Password policy attributes lists the attributes you can use to define a password policy in IdM.

Table 19.1. Password Policy Attributes

Attribute	Explanation	Example
Max lifetime	The maximum amount of time in days that a password is valid before a user must reset it. The default value is 90 days. Note that if the attribute is set to 0, the password never expires.	Max lifetime = 180 User passwords are valid only for 180 days. After that, IdM prompts users to change them.
Min lifetime	The minimum amount of time in hours that must pass between two password change operations.	Min lifetime = 1 After users change their passwords, they must wait at least 1 hour before changing them again.
History size	The number of previous passwords that are stored. A user cannot reuse a password from their password history but can reuse old passwords that are not stored.	History size = 0 In this case, the password history is empty and users can reuse any of their previous passwords.

Attribute	Explanation	Example
Character classes	The number of different character classes the user must use in the password. The character classes are: * Uppercase characters * Lowercase characters * Digits * Special characters, such as comma (,), period (.), asterisk (*) * Other UTF-8 characters Using a character three or more times in a row decreases the character class by one. For example: * Secret1 has 3 character classes: uppercase, lowercase, digits * Secret111 has 2 character classes: uppercase, lowercase, digits, and a -1 penalty for using 1 repeatedly	Character classes = 0 The default number of classes required is 0. To configure the number, run the ipa pwpolicy-mod command with the-minclasses option. See also the Important note below this table.
Min length	The minimum number of characters in a password. If any of the additional password policy options are set, then the minimum length of passwords is 6 characters.	Min length = 8 Users cannot use passwords shorter than 8 characters.
Max failures	The maximum number of failed login attempts before IdM locks the user account.	Max failures = 6 IdM locks the user account when the user enters a wrong password 7 times in a row.
Failure reset interval	The amount of time in seconds after which IdM resets the current number of failed login attempts.	Failure reset interval = 60 If the user waits for more than 1 minute after the number of failed login attempts defined in Max failures , the user can attempt to log in again without risking a user account lock.
Lockout duration	The amount of time in seconds that the user account is locked after the number of failed login attempts defined in Max failures .	Lockout duration = 600 Users with locked accounts are unable to log in for 10 minutes.



IMPORTANT

Use the English alphabet and common symbols for the character classes requirement if you have a diverse set of hardware that may not have access to international characters and symbols. For more information about character class policies in passwords, see the Red Hat Knowledgebase solution What characters are valid in a password? .

19.3. PASSWORD POLICY PRIORITIES IN IDM

Password policies help reduce the risk of someone discovering and misusing a user's password. The default password policy is the *global password policy*. You can also create additional group password policies. The global policy rules apply to all users without a group password policy. Group password policies apply to all members of the corresponding user group.

Note that only one password policy can be in effect at a time for any user. If a user has multiple password policies assigned, one of them takes precedence based on priority according to the following rules:

- Every group password policy has a priority set. The lower the value, the higher the policy's priority. The lowest supported value is **0**.
- If multiple password policies are applicable to a user, the policy with the lowest priority value takes precedence. All rules defined in other policies are ignored.
- The password policy with the lowest priority value applies to all password policy attributes, even the attributes that are not defined in the policy.

The global password policy does not have a priority value set. It serves as a fallback policy when no group policy is set for a user. The global policy can never take precedence over a group policy.

You can use the **ipa pwpolicy-show --user=user_name** command to check which policy is currently in effect for a particular user.

19.4. ENSURING THE PRESENCE OF A PASSWORD POLICY IN IDM USING AN ANSIBLE PLAYBOOK

Follow this procedure to ensure the presence of a password policy in Identity Management (IdM) using an Ansible playbook.

In the default **global_policy** password policy in IdM, the number of different character classes in the password is set to 0. The history size is also set to 0.

Complete this procedure to enforce a stronger password policy for an IdM group using an Ansible playbook.



NOTE

You cannot define a password policy for an individual user.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.

- You have installed the **ansible-freeipa** package.
- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.
- The group for which you are ensuring the presence of a password policy exists in IdM.

Procedure

1. Create an inventory file, for example **inventory.file**, and define the **FQDN** of your IdM server in the **[ipaserver]** section:

```
[ipaserver] server.idm.example.com
```

2. Create your Ansible playbook file that defines the password policy whose presence you want to ensure. To simplify this step, copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/pwpolicy/pwpolicy_present.yml file:

```
- name: Tests
hosts: ipaserver
vars files:
- /home/user_name/MyPlaybooks/secret.yml
- name: Ensure presence of pwpolicy for group ops
  ipapwpolicy:
   ipaadmin_password: "{{ ipaadmin_password }}"
   name: ops
   minlife: 7
   maxlife: 49
   history: 5
   priority: 1
   lockouttime: 300
   minlength: 8
   minclasses: 4
   maxfail: 3
   failinterval: 5
```

For details on what the individual variables mean, see Password policy attributes.

3. Run the playbook:

```
$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory_/new_pwpolicy_present.yml
```

You have successfully used an Ansible playbook to ensure that a password policy for the **ops** group is present in IdM.



IMPORTANT

The priority of the **ops** password policy is set to 1, whereas the **global_policy** password policy has no priority set. For this reason, the **ops** policy automatically supersedes **global_policy** for the **ops** group and is enforced immediately.

global_policy serves as a fallback policy when no group policy is set for a user, and it can never take precedence over a group policy.

Additional resources

- See the **README-pwpolicy.md** file in the /usr/share/doc/ansible-freeipa/ directory.
- See Password policy priorities in IdM.

19.5. ADDING A NEW PASSWORD POLICY IN IDM USING THE WEBUI OR THE CLI

Password policies help reduce the risk of someone discovering and misusing a user's password. The default password policy is the *global password policy*. You can also create additional group password policies.

19.5.1. Adding a new password policy in the IdM WebUI

Password policies help reduce the risk of someone discovering and misusing a user's password. The default password policy is the *global password policy*. You can also create additional group password policies.

Prerequisites

- A user group to which the policy applies.
- A priority assigned to the policy

Procedure

- Log in to the IdM Web UI.
 For details, see Accessing the IdM Web UI in a web browser .
- 2. Select Policy>Password Policies.
- 3. Click Add.
- 4. Define the user group and priority.
- 5. Click Add to confirm.

To configure the attributes of the new password policy, see Password policies in IdM.

Additional resources

• See Password policy priorities in IdM .

19.5.2. Adding a new password policy in the IdM CLI

Password policies help reduce the risk of someone discovering and misusing a user's password. The default password policy is the *global password policy*. You can also create additional group password policies.

Prerequisites

- A user group to which the policy applies.
- A priority assigned to the policy

Procedure

- 1. Open terminal and connect to the IdM server.
- 2. Use the ipa pwpolicy-add command. Specify the user group and priority:

\$ ipa pwpolicy-add Group: group_name Priority: priority_level

3. Optional: Use the **ipa pwpolicy-find** command to verify that the policy has been successfully added:

\$ ipa pwpolicy-find

To configure the attributes of the new password policy, see Password policies in IdM.

Additional resources

• See Password policy priorities in IdM .

19.6. ADDITIONAL PASSWORD POLICY OPTIONS IN IDM

As an Identity Management (IdM) administrator, you can strengthen the default password requirements by enabling additional password policy options based on the **libpwquality** feature set. The additional password policy options include the following:

--maxrepeat

Specifies the maximum acceptable number of same consecutive characters in the new password.

--maxsequence

Specifies the maximum length of monotonic character sequences in the new password. Examples of such a sequence are **12345** or **fedcb**. Most such passwords will not pass the simplicity check.

--dictcheck

If nonzero, checks whether the password, with possible modifications, matches a word in a dictionary. Currently **libpwquality** performs the dictionary check using the **cracklib** library.

--usercheck

If nonzero, checks whether the password, with possible modifications, contains the user name in some form. It is not performed for user names shorter than 3 characters.

You cannot apply the additional password policy options to existing passwords. If you apply any of the additional options, IdM automatically sets the **--minlength** option, the minimum number of characters in a password, to **6** characters.



NOTE

In a mixed environment with RHEL 7, RHEL 8, and RHEL 9 servers, you can enforce the additional password policy settings only on servers running on RHEL 8.4 and later. If a user is logged in to an IdM client and the IdM client is communicating with an IdM server running on RHEL 8.3 or earlier, then the new password policy requirements set by the system administrator are not applied. To ensure consistent behavior, upgrade or update all servers to RHEL 8.4 and later.

Additional resources:

- Applying additional password policies to an IdM group
- pwquality(3) man page on your system

19.7. APPLYING ADDITIONAL PASSWORD POLICY OPTIONS TO AN IDM GROUP

Follow this procedure to apply additional password policy options in Identity Management (IdM). The example describes how to strengthen the password policy for the **managers** group by making sure that the new passwords do not contain the users' respective user names and that the passwords contain no more than two identical characters in succession.

Prerequisites

- You are logged in as an IdM administrator.
- The **managers** group exists in IdM.
- The **managers** password policy exists in IdM.

Procedure

1. Apply the user name check to all new passwords suggested by the users in the managers group:





If you do not specify the name of the password policy, the default **global_policy** is modified.

2. Set the maximum number of identical consecutive characters to 2 in the **managers** password policy:

\$ ipa pwpolicy-mod --maxrepeat=2 managers

A password now will not be accepted if it contains more than 2 identical consecutive characters. For example, the **eR873mUi111YJQ** combination is unacceptable because it contains three 1s in succession.

Verification

1. Add a test user named **test_user**:

\$ ipa user-add test_user
First name: test
Last name: user
-----Added user "test_user"

- 2. Add the test user to the **managers** group:
 - a. In the IdM Web UI, click Identity>Groups>User Groups.
 - b. Click the managers group name.
 - c. Click Add.
 - d. On the Add users into user group 'managers' page, check test_user.
 - e. Click the > arrow to move the user to the **Prospective** column.
 - f. Click Add.
- 3. Reset the password for the test user:
 - a. Go to Identity>Users.
 - b. Click test_user.
 - c. From the Actions menu, click Reset Password.
 - d. Enter a temporary password for the user.
- 4. Try to obtain a Kerberos ticket-granting ticket (TGT) for the test_user:
 - a. On the command line, run the following command:

\$ kinit test_user

- b. Enter the temporary password.
- c. The system informs you that you must change your password. Enter a password that contains the user name of **test_user**:

Password expired. You must change it now.

Enter new password:

Enter it again:

Password change rejected: Password not changed.

Unspecified password quality failure while trying to change password.

Please try again.

d. The system informs you that the entered password was rejected. Enter a password that contains three or more identical characters in succession:

Password change rejected: Password not changed. Unspecified password quality failure while trying to change password. Please try again.

Enter new password: Enter it again:

e. The system informs you that the entered password was rejected. Enter a password that meets the criteria of the **managers** password policy:

Password change rejected: Password not changed. Unspecified password quality failure while trying to change password. Please try again.

Enter new password: Enter it again:

5. View the obtained TGT:

\$ klist

Ticket cache: KCM:0:33945

Default principal: test_user@IDM.EXAMPLE.COM

Valid starting Expires Service principal 07/07/2021 12:44:44 07/08/2021 12:44:44

krbtgt@IDM.EXAMPLE.COM@IDM.EXAMPLE.COM

The managers password policy now works correctly for users in the managers group.

Additional resources

Additional password policies in IdM

19.8. USING AN ANSIBLE PLAYBOOK TO APPLY ADDITIONAL PASSWORD POLICY OPTIONS TO AN IDM GROUP

You can use an Ansible playbook to apply additional password policy options to strengthen the password policy requirements for a specific IdM group. You can use the **maxrepeat**, **maxsequence**, **dictcheck** and **usercheck** password policy options for this purpose. The example describes how to set the following requirements for the **managers** group:

- A users new password does not contain the users respective user name.
- The password contains no more than two identical characters in succession.
- Any monotonic character sequences in the passwords are not longer than 3 characters. This means that the system does not accept a password with a sequence such as 1234 or abcd.

Prerequisites

• You have configured your Ansible control node to meet the following requirements:

- You are using Ansible version 2.14 or later.
- You have installed the **ansible-freeipa** package on the Ansible controller.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
- You have stored your **ipaadmin password** in the **secret.yml** Ansible vault.
- The group for which you are ensuring the presence of a password policy exists in IdM.

Procedure

1. Create your Ansible playbook file **manager_pwpolicy_present.yml** that defines the password policy whose presence you want to ensure. To simplify this step, copy and modify the following example:

```
-name: Tests
hosts: ipaserver

vars_files:
- /home/user_name/MyPlaybooks/secret.yml
tasks:
- name: Ensure presence of usercheck and maxrepeat pwpolicy for group managers
ipapwpolicy:
    ipaadmin_password: "{{ ipaadmin_password }}"
    name: managers
    usercheck: True
    maxrepeat: 2
    maxsequence: 3
```

2. Run the playbook:

```
$ ansible-playbook --vault-password-file=password_file -v -i
path_to_inventory_directory/inventory.file
path_to_playbooks_directory_/manager_pwpolicy_present.yml
```

Verification

1. Add a test user named **test_user**:

```
$ ipa user-add test_user
First name: test
Last name: user
------
Added user "test_user"
```

- 2. Add the test user to the **managers** group:
 - a. In the IdM Web UI, click Identity>Groups>User Groups.
 - b. Click managers.

- c. Click Add.
- d. On the Add users into user group 'managers' page, check test_user.
- e. Click the > arrow to move the user to the **Prospective** column.
- f. Click Add.
- 3. Reset the password for the test user:
 - a. Go to Identity>Users.
 - b. Click **test_user**.
 - c. From the Actions menu, click Reset Password.
 - d. Enter a temporary password for the user.
- 4. Try to obtain a Kerberos ticket-granting ticket (TGT) for the test_user:
 - a. On the command line, enter the following command:

\$ kinit test_user

- b. Enter the temporary password.
- c. The system informs you that you must change your password. Enter a password that contains the user name of **test_user**:

Password expired. You must change it now.

Enter new password:

Enter it again:

Password change rejected: Password not changed.

Unspecified password quality failure while trying to change password.

Please try again.

d. The system informs you that the entered password was rejected. Enter a password that contains three or more identical characters in succession:

Password change rejected: Password not changed.

Unspecified password quality failure while trying to change password.

Please try again.

Enter new password:

Enter it again:

e. The system informs you that the entered password was rejected. Enter a password that contains a monotonic character sequence longer than 3 characters. Examples of such sequences include 1234 and fedc:

Password change rejected: Password not changed.

Unspecified password quality failure while trying to change password.

Please try again.

Enter new password:

Enter it again:

_

f. The system informs you that the entered password was rejected. Enter a password that meets the criteria of the **managers** password policy:

Password change rejected: Password not changed. Unspecified password quality failure while trying to change password. Please try again.

Enter new password:

Enter it again:

5. Verify that you have obtained a TGT, which is only possible after having entered a valid password:

\$ klist

Ticket cache: KCM:0:33945

Default principal: test_user@IDM.EXAMPLE.COM

Valid starting Expires Service principal 07/07/2021 12:44:44 07/08/2021 12:44:44 krbtgt@IDM.EXAMPLE.COM@IDM.EXAMPLE.COM

Additional resources

- Additional password policies in IdM
- /usr/share/doc/ansible-freeipa/README-pwpolicy.md
- /usr/share/doc/ansible-freeipa/playbooks/pwpolicy

CHAPTER 20. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT

Learn more about granting **sudo** access to users in Identity Management.

20.1. SUDO ACCESS ON AN IDM CLIENT

System administrators can grant **sudo** access to allow non-root users to execute administrative commands that are normally reserved for the **root** user. Consequently, when users need to perform an administrative command normally reserved for the **root** user, they precede that command with **sudo**. After entering their password, the command is executed as if they were the **root** user. To execute a **sudo** command as another user or group, such as a database service account, you can configure a *RunAs alias* for a **sudo** rule.

If a Red Hat Enterprise Linux (RHEL) 8 host is enrolled as an Identity Management (IdM) client, you can specify **sudo** rules defining which IdM users can perform which commands on the host in the following ways:

- Locally in the /etc/sudoers file
- Centrally in IdM

You can create a central sudo rule for an IdM client using the command line (CLI) and the IdM Web UI.

You can also configure password-less authentication for **sudo** using the Generic Security Service Application Programming Interface (GSSAPI), the native way for UNIX-based operating systems to access and authenticate Kerberos services. You can use the **pam_sss_gss.so** Pluggable Authentication Module (PAM) to invoke GSSAPI authentication via the SSSD service, allowing users to authenticate to the **sudo** command with a valid Kerberos ticket.

Additional resources

Managing sudo access

20.2. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE CLI

In Identity Management (IdM), you can grant **sudo** access for a specific command to an IdM user account on a specific IdM host. First, add a **sudo** command and then create a **sudo** rule for one or more commands.

For example, complete this procedure to create the **idm_user_reboot sudo** rule to grant the **idm_user** account the permission to run the /**usr/sbin/reboot** command on the **idmclient** machine.

Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for **idm_user** in IdM and unlocked the account by creating a password for the user. For details on adding a new IdM user using the CLI, see Adding users using the command line.
- No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local /**etc/passwd** file.

Procedure

1. Retrieve a Kerberos ticket as the IdM admin.

[root@idmclient ~]# kinit admin

2. Add the /usr/sbin/reboot command to the IdM database of sudo commands:

```
[root@idmclient ~]# ipa sudocmd-add /usr/sbin/reboot
------
Added Sudo Command "/usr/sbin/reboot"
------
Sudo Command: /usr/sbin/reboot
```

3. Create a **sudo** rule named **idm_user_reboot**:

```
[root@idmclient ~]# ipa sudorule-add idm_user_reboot
-----
Added Sudo Rule "idm_user_reboot"
------
Rule name: idm_user_reboot
Enabled: TRUE
```

4. Add the /usr/sbin/reboot command to the idm_user_reboot rule:

```
[root@idmclient ~]# ipa sudorule-add-allow-command idm_user_reboot --sudocmds
'/usr/sbin/reboot'
Rule name: idm_user_reboot
Enabled: TRUE
Sudo Allow Commands: /usr/sbin/reboot
-------
Number of members added 1
```

5. Apply the idm_user_reboot rule to the IdM idmclient host:

6. Add the idm_user account to the idm_user_reboot rule:

```
[root@idmclient ~]# ipa sudorule-add-user idm_user_reboot --users idm_user
Rule name: idm_user_reboot
Enabled: TRUE
Users: idm_user
Hosts: idmclient.idm.example.com
Sudo Allow Commands: /usr/sbin/reboot
```

Number of members added 1

- 7. Optional: Define the validity of the **idm_user_reboot** rule:
 - a. To define the time at which a **sudo** rule starts to be valid, use the **ipa sudorule-mod sudo_rule_name** command with the **--setattr sudonotbefore=DATE** option. The DATE value must follow the **yyyymmddHHMMSSZ** format, with seconds specified explicitly. For example, to set the start of the validity of the **idm_user_reboot** rule to 31 December 2025 12:34:00, enter:

[root@idmclient ~]# ipa sudorule-mod idm_user_reboot --setattr sudonotbefore=20251231123400Z

b. To define the time at which a sudo rule stops being valid, use the --setattr sudonotafter=DATE option. For example, to set the end of the idm_user_reboot rule validity to 31 December 2026 12:34:00, enter:

[root@idmclient ~]# ipa sudorule-mod idm_user_reboot --setattr sudonotafter=20261231123400Z



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification

- 1. Log in to the **idmclient** host as the **idm user** account.
- 2. Display which **sudo** rules the **idm_user** account is allowed to perform.

[idm_user@idmclient ~]\$ sudo -I

Matching Defaults entries for idm_user on idmclient:

!visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR
LS COLORS",

env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT
LC MESSAGES",

env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER LC_TELEPHONE", env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS _XKB_CHARSET XAUTHORITY KRB5CCNAME",

secure_path=/sbin\:/bin\:/usr/sbin\:/usr/bin

User idm_user may run the following commands on idmclient: (root) /usr/sbin/reboot

3. Reboot the machine using **sudo**. Enter the password for **idm user** when prompted:

[idm_user@idmclient ~]\$ sudo /usr/sbin/reboot [sudo] password for idm_user:

20.3. GRANTING SUDO ACCESS TO AN AD USER ON AN IDM CLIENT USING THE CLI

Identity Management (IdM) system administrators can use IdM user groups to set access permissions, host-based access control, **sudo** rules, and other controls on IdM users. IdM user groups grant and restrict access to IdM domain resources.

You can add both Active Directory (AD) users and AD groups to IdM user groups. To do that:

- 1. Add the AD users or groups to a *non-POSIX* external IdM group.
- 2. Add the non-POSIX external IdM group to an IdM POSIX group.

You can then manage the privileges of the AD users by managing the privileges of the POSIX group. For example, you can grant **sudo** access for a specific command to an IdM POSIX user group on a specific IdM host.

It is also possible to add AD user groups as members to IdM external groups. This might make it easier to define policies for Windows users, by keeping the user and group management within the single AD realm.



IMPORTANT

Do **not** use ID overrides of AD users for SUDO rules in IdM. ID overrides of AD users represent only POSIX attributes of AD users, not AD users themselves.

You can add ID overrides as group members. However, you can only use this functionality to manage IdM resources in the IdM API. The possibility to add ID overrides as group members is not extended to POSIX environments and you therefore cannot use it for membership in **sudo** or host-based access control (HBAC) rules.

Follow this procedure to create the ad_users_reboot sudo rule to grant the administrator@addomain.com AD user the permission to run the /usr/sbin/reboot command on the idmclient IdM host, which is normally reserved for the root user. administrator@ad-domain.com is a member of the ad_users_external non-POSIX group, which is, in turn, a member of the ad_users POSIX group.

Prerequisites

- You have obtained the IdM **admin** Kerberos ticket-granting ticket (TGT).
- A cross-forest trust exists between the IdM domain and the ad-domain.com AD domain.
- No local **administrator** account is present on the **idmclient** host: the **administrator** user is not listed in the local /**etc/passwd** file.

Procedure

- Create the ad_users group that contains the ad_users_external group with the administrator@ad-domain member:
 - a. Optional: Create or select a corresponding group in the AD domain to use to manage AD users in the IdM realm. You can use multiple AD groups and add them to different groups on the IdM side.

b. Create the *ad_users_external* group and indicate that it contains members from outside the IdM domain by adding the **--external** option:

[root@ipaserver ~]# ipa group-add --desc='AD users external map' ad_users_external --external

Added group "ad users external"

Group name: ad_users_external Description: AD users external map



NOTE

Ensure that the external group that you specify here is an AD security group with a **global** or **universal** group scope as defined in the Active Directory security groups document. For example, the **Domain users** or **Domain admins** AD security groups cannot be used because their group scope is **domain local**.

c. Create the ad_users group:

[root@ipaserver ~]# ipa group-add --desc='AD users' ad users

Added group "ad_users"

Group name: ad_users Description: AD users GID: 129600004

d. Add the administrator@ad-domain.com AD user to ad_users_external as an external member:

[root@ipaserver ~]# ipa group-add-member ad_users_external --external "administrator@ad-domain.com"

[member user]:

[member group]:

Group name: ad_users_external Description: AD users external map

External member: S-1-5-21-3655990580-1375374850-1633065477-513

Number of members added 1

The AD user must be identified by a fully-qualified name, such as **DOMAIN\user_name** or **user_name@DOMAIN**. The AD identity is then mapped to the AD SID for the user. The same applies to adding AD groups.

e. Add ad_users_external to ad_users as a member:

[root@ipaserver ~]# ipa group-add-member ad_users --groups ad_users_external

Group name: ad_users Description: AD users GID: 129600004

Member groups: ad_users_external

Number of members added 1

2. Grant the members of ad users the permission to run /usr/sbin/reboot on the idmclient host:

a. Add the /usr/sbin/reboot command to the IdM database of sudo commands:

[root@idmclient ~]# ipa sudocmd-add /usr/sbin/reboot Added Sudo Command "/usr/sbin/reboot" Sudo Command: /usr/sbin/reboot

b. Create a **sudo** rule named **ad_users_reboot**:

[root@idmclient ~]# ipa sudorule-add ad_users_reboot Added Sudo Rule "ad users reboot" -----Rule name: ad users reboot Enabled: True

c. Add the /usr/sbin/reboot command to the ad_users_reboot rule:

[root@idmclient ~]# ipa sudorule-add-allow-command ad_users_reboot --sudocmds '/usr/sbin/reboot' Rule name: ad_users_reboot Enabled: True Sudo Allow Commands: /usr/sbin/reboot Number of members added 1 -----

d. Apply the ad users reboot rule to the IdM idmclient host:

[root@idmclient ~]# ipa sudorule-add-host ad_users_reboot --hosts idmclient.idm.example.com Rule name: ad users reboot Enabled: True

Hosts: idmclient.idm.example.com Sudo Allow Commands: /usr/sbin/reboot

Number of members added 1

e. Add the **ad_users** group to the **ad_users_reboot** rule:

[root@idmclient ~]# ipa sudorule-add-user ad_users_reboot --groups ad_users

Rule name: ad_users_reboot

Enabled: TRUE

User Groups: ad_users

Hosts: idmclient.idm.example.com Sudo Allow Commands: /usr/sbin/reboot Number of members added 1



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification

 Log in to the idmclient host as administrator@ad-domain.com, an indirect member of the ad_users group:

\$ ssh administrator@ad-domain.com@ipaclient Password:

2. Optional: Display the **sudo** commands that **administrator@ad-domain.com** is allowed to execute:

[administrator@ad-domain.com@idmclient ~]\$ sudo -I

Matching Defaults entries for administrator@ad-domain.com on idmclient:

!visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
 env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR

LS_COLORS",
 env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
 env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT

LC_MESSAGES",
 env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER LC_TELEPHONE",
 env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS_XKB_CHARSET XAUTHORITY

KRB5CCNAME".

User administrator@ad-domain.com may run the following commands on idmclient: (root) /usr/sbin/reboot

3. Reboot the machine using **sudo**. Enter the password for **administrator@ad-domain.com** when prompted:

[administrator@ad-domain.com@idmclient ~]\$ **sudo** /**usr/sbin/reboot** [sudo] password for administrator@ad-domain.com:

Additional resources

Active Directory users and Identity Management groups

secure path=/sbin\:/bin\:/usr/sbin\:/usr/bin

Include users and groups from a trusted Active Directory domain into SUDO rules

20.4. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE IDM WEB UI

In Identity Management (IdM), you can grant **sudo** access for a specific command to an IdM user account on a specific IdM host. First, add a **sudo** command and then create a **sudo** rule for one or more commands.

Complete this procedure to create the **idm_user_reboot** sudo rule to grant the **idm_user** account the permission to run the /usr/sbin/reboot command on the **idmclient** machine.

Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for idm_user in IdM and unlocked the account by creating a
 password for the user. For details on adding a new IdM user using the command line, see Adding
 users using the command line.
- No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local /etc/passwd file.

Procedure

- 1. Add the /usr/sbin/reboot command to the IdM database of sudo commands:
 - a. Navigate to Policy>Sudo>Sudo Commands.
 - b. Click Add in the upper right corner to open the Add sudo command dialog box.
 - c. Enter the command you want the user to be able to perform using **sudo**: /usr/sbin/reboot.
 - d. Click Add.
- 2. Use the new **sudo** command entry to create a sudo rule to allow **idm_user** to reboot the **idmclient** machine:
 - a. Navigate to Policy>Sudo>Sudo rules.
 - b. Click **Add** in the upper right corner to open the **Add sudo rule** dialog box.
 - c. Enter the name of the **sudo** rule: **idm_user_reboot**.
 - d. Click Add and Edit
 - e. Specify the user:
 - i. In the **Who** section, check the **Specified Users and Groups** radio button.
 - ii. In the **Users** section, click **Add** to open the **Add users into sudo rule** "idm_user_reboot" dialog box.
 - iii. In the **Available** column, check the **idm_user** checkbox, and click the arrow to move it to the **Prospective** column.
 - iv. Click Add.
 - f. Specify the host:
 - i. In the Access this host section, check the Specified Hosts and Groups radio button.
 - ii. In the **Hosts** section, click **Add** to open the **Add hosts into sudo rule** "idm_user_reboot" dialog box.
 - iii. In **Available** column, check the **idmclient.idm.example.com** checkbox, and click the arrow to move it to the **Prospective** column.

- iv. Click Add.
- g. Specify the commands:
 - In the Run Commands section, check the Specified Commands and Groups radio button.
 - ii. In the **Sudo Allow Commands** section, click **Add** to open the **Add allow sudo commands into sudo rule "idm_user_reboot"** dialog box.
 - iii. In the **Available** column, check the /**usr/sbin/reboot** checkbox, and click the arrow to move it to the **Prospective** column.
 - iv. Click Add to return to the idm_sudo_reboot page.
- h. Click **Save** in the top left corner.

The new rule is enabled by default.



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification

- 1. Log in to idmclient as idm_user.
- 2. Reboot the machine using **sudo**. Enter the password for **idm_user** when prompted:

\$ sudo /usr/sbin/reboot [sudo] password for idm_user:

If the **sudo** rule is configured correctly, the machine reboots.

20.5. CREATING A SUDO RULE ON THE CLI THAT RUNS A COMMAND AS A SERVICE ACCOUNT ON AN IDM CLIENT

In IdM, you can configure a **sudo** rule with a *RunAs alias* to run a **sudo** command as another user or group. For example, you might have an IdM client that hosts a database application, and you need to run commands as the local service account that corresponds to that application.

Use this example to create a **sudo** rule on the command line called **run_third-party-app_report** to allow the **idm_user** account to run the **/opt/third-party-app/bin/report** command as the **thirdpartyapp** service account on the **idmclient** host.

Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for idm_user in IdM and unlocked the account by creating a
 password for the user. For details on adding a new IdM user using the CLI, see Adding users
 using the command line.
- No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local /etc/passwd file.

- You have a custom application named third-party-app installed on the idmclient host.
- The **report** command for the **third-party-app** application is installed in the **/opt/third-party-app/bin/report** directory.
- You have created a local service account named thirdpartyapp to execute commands for the third-party-app application.

Procedure

1. Retrieve a Kerberos ticket as the IdM **admin**.

[root@idmclient ~]# kinit admin

2. Add the /opt/third-party-app/bin/report command to the IdM database of sudo commands:

```
[root@idmclient ~]# ipa sudocmd-add /opt/third-party-app/bin/report
------
Added Sudo Command "/opt/third-party-app/bin/report"
------
Sudo Command: /opt/third-party-app/bin/report
```

3. Create a **sudo** rule named **run_third-party-app_report**:

4. Use the **--users=**<**user**> option to specify the RunAs user for the **sudorule-add-runasuser** command:

```
[root@idmclient ~]# ipa sudorule-add-runasuser run_third-party-app_report --
users=thirdpartyapp
Rule name: run_third-party-app_report
Enabled: TRUE
RunAs External User: thirdpartyapp
-------
Number of members added 1
```

The user (or group specified with the **--groups=*** option) can be external to IdM, such as a local service account or an Active Directory user. Do not add a **%** prefix for group names.

5. Add the /opt/third-party-app/bin/report command to the run_third-party-app_report rule:

Rule name: run_third-party-app_report

Enabled: TRUE

Sudo Allow Commands: /opt/third-party-app/bin/report

RunAs External User: thirdpartyapp

Number of members added 1

6. Apply the **run_third-party-app_report** rule to the IdM **idmclient** host:

[root@idmclient ~]# ipa sudorule-add-host run_third-party-app_report --hosts idmclient.idm.example.com

Rule name: run third-party-app report

Enabled: TRUE

Hosts: idmclient.idm.example.com

Sudo Allow Commands: /opt/third-party-app/bin/report

RunAs External User: thirdpartyapp

Number of members added 1

7. Add the idm_user account to the run_third-party-app_report rule:

[root@idmclient ~]# ipa sudorule-add-user run third-party-app report --users idm user

Rule name: run_third-party-app_report

Enabled: TRUE Users: idm_user

Hosts: idmclient.idm.example.com

Sudo Allow Commands: /opt/third-party-app/bin/report

RunAs External User: thirdpartyapp

Number of members added 1



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification

- 1. Log in to the **idmclient** host as the **idm_user** account.
- 2. Test the new sudo rule:
 - a. Display which **sudo** rules the **idm_user** account is allowed to perform.

[idm_user@idmclient ~]\$ sudo -I

Matching Defaults entries for idm_user@idm.example.com on idmclient:

!visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,

env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR

LS_COLORS",

env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",

env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT

LC_MESSAGES",

env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER LC_TELEPHONE",

LO_ILLLITIONE,

env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS _XKB_CHARSET XAUTHORITY KRB5CCNAME",

secure_path=/sbin\:/usr/sbin\:/usr/bin

User idm_user@idm.example.com may run the following commands on idmclient: (thirdpartyapp) /opt/third-party-app/bin/report

b. Run the **report** command as the **thirdpartyapp** service account.

[idm_user@idmclient ~]\$ **sudo -u** *thirdpartyapp* /opt/third-party-app/bin/report [sudo] password for idm_user@idm.example.com:
Executing report...
Report successful.

20.6. CREATING A SUDO RULE IN THE IDM WEBUI THAT RUNS A COMMAND AS A SERVICE ACCOUNT ON AN IDM CLIENT

In IdM, you can configure a **sudo** rule with a *RunAs alias* to run a **sudo** command as another user or group. For example, you might have an IdM client that hosts a database application, and you need to run commands as the local service account that corresponds to that application.

Use this example to create a **sudo** rule in the IdM WebUI called **run_third-party-app_report** to allow the **idm_user** account to run the **/opt/third-party-app/bin/report** command as the **thirdpartyapp** service account on the **idmclient** host.

Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for idm_user in IdM and unlocked the account by creating a
 password for the user. For details on adding a new IdM user using the CLI, see Adding users
 using the command line.
- No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local /etc/passwd file.
- You have a custom application named **third-party-app** installed on the **idmclient** host.
- The **report** command for the **third-party-app** application is installed in the **/opt/third-party-app/bin/report** directory.
- You have created a local service account named **thirdpartyapp** to execute commands for the **third-party-app** application.

Procedure

- 1. Add the /opt/third-party-app/bin/report command to the IdM database of sudo commands:
 - a. Navigate to Policy>Sudo>Sudo Commands.
 - b. Click Add in the upper right corner to open the Add sudo command dialog box.
 - c. Enter the command: /opt/third-party-app/bin/report.
 - d. Click Add.
- 2. Use the new **sudo** command entry to create the new **sudo** rule:

- a. Navigate to Policy → Sudo → Sudo rules.
- b. Click **Add** in the upper right corner to open the **Add sudo rule** dialog box.
- c. Enter the name of the **sudo** rule: run_third-party-app_report.
- d. Click Add and Edit
- e. Specify the user:
 - i. In the Who section, check the Specified Users and Groups radio button.
 - ii. In the **User** section, click **Add** to open the **Add users into sudo rule "run_third-party-app_report"** dialog box.
 - In the Available column, check the idm_user checkbox, and move it to the Prospective column.
 - iv. Click Add.
- f. Specify the host:
 - i. In the Access this host section, check the Specified Hosts and Groups radio button.
 - ii. In the **Hosts** section, click **Add** to open the **Add hosts into sudo rule "run_third-party-app_report"** dialog box.
 - iii. In the **Available** column, check the **idmclient.idm.example.com** checkbox, and move it to the **Prospective** column.
 - iv. Click Add.
- g. Specify the commands:
 - In the Run Commands section, check the Specified Commands and Groups radio button.
 - ii. In the **Sudo Allow Commands** section, click **Add** to open the **Add allow sudo commands into sudo rule "run_third-party-app_report"** dialog box.
 - iii. In the **Available** column, check the **/opt/third-party-app/bin/report** checkbox, and move it to the **Prospective** column.
 - iv. Click Add to return to the run_third-party-app_report page.
- h. Specify the RunAs user:
 - i. In the As Whom section, check the Specified Users and Groups radio button.
 - ii. In the RunAs Users section, click Add to open the Add RunAs users into sudo rule "run_third-party-app_report" dialog box.
 - iii. Enter the **thirdpartyapp** service account in the **External** box and move it to the **Prospective** column.
 - iv. Click Add to return to the run_third-party-app_report page.
- i. Click **Save** in the top left corner.

The new rule is enabled by default.



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification

- 1. Log in to the **idmclient** host as the **idm_user** account.
- 2. Test the new sudo rule:
 - a. Display which **sudo** rules the **idm_user** account is allowed to perform.

```
[idm_user@idmclient ~]$ sudo -I

Matching Defaults entries for idm_user@idm.example.com on idmclient:
    !visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
    env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR

LS_COLORS",
    env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
    env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT

LC_MESSAGES",
    env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER

LC_TELEPHONE",
    env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS_XKB_CHARSET

XAUTHORITY KRB5CCNAME",
    secure_path=/sbin\:/bin\:/usr/sbin\:/usr/bin
```

User idm_user@idm.example.com may run the following commands on idmclient: (thirdpartyapp) /opt/third-party-app/bin/report

b. Run the **report** command as the **thirdpartyapp** service account.

[idm_user@idmclient ~]\$ **sudo -u** *thirdpartyapp* /opt/third-party-app/bin/report [sudo] password for idm_user@idm.example.com:
Executing report...
Report successful.

20.7. ENABLING GSSAPI AUTHENTICATION FOR SUDO ON AN IDM CLIENT

Enable Generic Security Service Application Program Interface (GSSAPI) authentication on an IdM client for the **sudo** and **sudo -i** commands via the **pam_sss_gss.so** PAM module. With this configuration, IdM users can authenticate to the **sudo** command with their Kerberos ticket.

- You have created a **sudo** rule for an IdM user that applies to an IdM host. For this example, you
 have created the **idm_user_reboot sudo** rule to grant the **idm_user** account the permission to
 run the /usr/sbin/reboot command on the **idmclient** host.
- You need root privileges to modify the /etc/sssd/sssd.conf file and PAM files in the /etc/pam.d/ directory.

Procedure

- 1. Open the /etc/sssd/sssd.conf configuration file.

```
[domain/<domain_name>]
pam_gssapi_services = sudo, sudo-i
```

- 3. Save and close the /etc/sssd/sssd.conf file.
- 4. Restart the SSSD service to load the configuration changes.

[root@idmclient ~]# systemctl restart sssd

- 5. On RHEL 9.2 or later:
 - a. Optional: Determine if you have selected the **sssd authselect** profile:

```
# authselect current
Profile ID: sssd
```

b. If the **sssd authselect** profile is selected, enable GSSAPI authentication:

authselect enable-feature with-gssapi

- c. If the **sssd authselect** profile is not selected, select it and enable GSSAPI authentication:
 - # authselect select sssd with-gssapi
- 6. On RHEL 9.1 or earlier:
 - a. Open the /etc/pam.d/sudo PAM configuration file.
 - b. Add the following entry as the first line of the **auth** section in the /etc/pam.d/sudo file.

```
#%PAM-1.0

auth sufficient pam_sss_gss.so
auth include system-auth
account include system-auth
password include system-auth
session include system-auth
```

c. Save and close the /etc/pam.d/sudo file.

Verification

1. Log into the host as the **idm user** account.

[root@idm-client ~]# **ssh -l** *idm_user@idm.example.com* **localhost** idm_user@idm.example.com's password:

2. Verify that you have a ticket-granting ticket as the idm_user account.

[idmuser@idmclient ~]\$ klist Ticket cache: KCM:1366201107

Default principal: idm_user@IDM.EXAMPLE.COM

Valid starting Expires Service principal

01/08/2021 09:11:48 01/08/2021 19:11:48

krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM

renew until 01/15/2021 09:11:44

3. Optional: If you do not have Kerberos credentials for the **idm_user** account, delete your current Kerberos credentials and request the correct ones.

[idm_user@idmclient ~]\$ kdestroy -A

[idm_user@idmclient ~]\$ kinit idm_user@IDM.EXAMPLE.COM Password for idm_user@idm.example.com:

4. Reboot the machine using **sudo**, without specifying a password.

[idm_user@idmclient ~]\$ sudo /usr/sbin/reboot

Additional resources

- The GSSAPI entry in the IdM terminology listing
- Granting sudo access to an IdM user on an IdM client using IdM Web UI
- Granting sudo access to an IdM user on an IdM client using the CLI
- pam_sss_gss (8) and sssd.conf (5) man pages on your system

20.8. ENABLING GSSAPI AUTHENTICATION AND ENFORCING KERBEROS AUTHENTICATION INDICATORS FOR SUDO ON AN IDM CLIENT

Enable Generic Security Service Application Program Interface (GSSAPI) authentication on an IdM client for the **sudo** and **sudo -i** commands via the **pam_sss_gss.so** PAM module. Additionally, only users who have logged in with a smart card will authenticate to those commands with their Kerberos ticket.



NOTE

You can use this procedure as a template to configure GSSAPI authentication with SSSD for other PAM-aware services, and further restrict access to only those users that have a specific authentication indicator attached to their Kerberos ticket.

- You have created a **sudo** rule for an IdM user that applies to an IdM host. For this example, you have created the **idm_user_reboot sudo** rule to grant the **idm_user** account the permission to run the /usr/sbin/reboot command on the **idmclient** host.
- You have configured smart card authentication for the **idmclient** host.

You need root privileges to modify the /etc/sssd/sssd.conf file and PAM files in the /etc/pam.d/ directory.

Procedure

- 1. Open the /etc/sssd/sssd.conf configuration file.
- 2. Add the following entries to the [domain/<idm_domain_name>] section.

```
[domain/<idm_domain_name>]
pam_gssapi_services = sudo, sudo-i
pam_gssapi_indicators_map = sudo:pkinit, sudo-i:pkinit
```

- 3. Save and close the /etc/sssd/sssd.conf file.
- 4. Restart the SSSD service to load the configuration changes.
 - [root@idmclient ~]# systemctl restart sssd
- 5. On RHEL 9.2 or later:
 - a. Determine if you have selected the **sssd authselect** profile:

```
# authselect current
Profile ID: sssd
```

b. Optional: Select the **sssd authselect** profile:

authselect select sssd

c. Enable GSSAPI authentication:

authselect enable-feature with-gssapi

d. Configure the system to authenticate only users with smart cards:

authselect with-smartcard-required

- 6. On RHEL 9.1 or earlier:
 - a. Open the /etc/pam.d/sudo PAM configuration file.
 - b. Add the following entry as the first line of the auth section in the /etc/pam.d/sudo file.

```
#%PAM-1.0

auth sufficient pam_sss_gss.so
auth include system-auth
account include system-auth
password include system-auth
session include system-auth
```

- c. Save and close the /etc/pam.d/sudo file.
- d. Open the /etc/pam.d/sudo-i PAM configuration file.

e. Add the following entry as the first line of the auth section in the /etc/pam.d/sudo-i file.

```
#%PAM-1.0

auth sufficient pam_sss_gss.so

auth include sudo
account include sudo
password include sudo
session optional pam_keyinit.so force revoke
session include sudo
```

f. Save and close the /etc/pam.d/sudo-i file.

Verification

1. Log into the host as the **idm_user** account and authenticate with a smart card.

```
[root@idmclient ~]# ssh -l idm_user@idm.example.com localhost PIN for smart_card
```

2. Verify that you have a ticket-granting ticket as the smart card user.

```
[idm_user@idmclient ~]$ klist
Ticket cache: KEYRING:persistent:1358900015:krb_cache_TObtNMd
Default principal: idm_user@IDM.EXAMPLE.COM

Valid starting Expires Service principal
02/15/2021 16:29:48 02/16/2021 02:29:48
krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM
renew until 02/22/2021 16:29:44
```

3. Display which **sudo** rules the **idm user** account is allowed to perform.

```
[idm_user@idmclient ~]$ sudo -I

Matching Defaults entries for idmuser on idmclient:

!visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
    env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR

LS_COLORS",
    env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
    env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT

LC_MESSAGES",
    env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER LC_TELEPHONE",
    env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS_XKB_CHARSET XAUTHORITY

KRB5CCNAME",
    secure_path=/sbin\:/bin\:/bin\:/usr/sbin\:/usr/bin

User idm_user_may run the following commands on idmclient:
```

4. Reboot the machine using **sudo**, without specifying a password.

[idm_user@idmclient ~]\$ sudo /usr/sbin/reboot

(root) /usr/sbin/reboot

Additional resources

- SSSD options controlling GSSAPI authentication for PAM services
- The GSSAPI entry in the IdM terminology listing
- Configuring Identity Management for smart card authentication
- Kerberos authentication indicators
- Granting sudo access to an IdM user on an IdM client using IdM Web UI
- Granting sudo access to an IdM user on an IdM client using the CLI.
- pam_sss_gss (8) and sssd.conf (5) man pages on your system

20.9. SSSD OPTIONS CONTROLLING GSSAPI AUTHENTICATION FOR PAM SERVICES

You can use the following options for the /etc/sssd/sssd.conf configuration file to adjust the GSSAPI configuration within the SSSD service.

pam_gssapi_services

GSSAPI authentication with SSSD is disabled by default. You can use this option to specify a comma-separated list of PAM services that are allowed to try GSSAPI authentication using the **pam_sss_gss.so** PAM module. To explicitly disable GSSAPI authentication, set this option to -.

pam_gssapi_indicators_map

This option only applies to Identity Management (IdM) domains. Use this option to list Kerberos authentication indicators that are required to grant PAM access to a service. Pairs must be in the format *PAM_service*:_<required_authentication_indicator>_.

Valid authentication indicators are:

- **otp** for two-factor authentication
- radius for RADIUS authentication
- **pkinit** for PKINIT, smart card, or certificate authentication
- hardened for hardened passwords

pam_gssapi_check_upn

This option is enabled and set to **true** by default. If this option is enabled, the SSSD service requires that the user name matches the Kerberos credentials. If **false**, the **pam_sss_gss.so** PAM module authenticates every user that is able to obtain the required service ticket.

Examples

The following options enable Kerberos authentication for the **sudo** and **sudo-i** services, requires that **sudo** users authenticated with a one-time password, and user names must match the Kerberos principal. Because these settings are in the **[pam]** section, they apply to all domains:

```
[pam]
pam_gssapi_services = sudo, sudo-i
pam_gssapi_indicators_map = sudo:otp
pam_gssapi_check_upn = true
```

You can also set these options in individual **[domain]** sections to overwrite any global values in the **[pam]** section. The following options apply different GSSAPI settings to each domain:

For the idm.example.com domain

- Enable GSSAPI authentication for the **sudo** and **sudo -i** services.
- Require certificate or smart card authentication authenticators for the **sudo** command.
- Require one-time password authentication authenticators for the **sudo -i** command.
- Enforce matching user names and Kerberos principals.

For the ad.example.com domain

- Enable GSSAPI authentication only for the sudo service.
- Do not enforce matching user names and principals.

```
[domain/idm.example.com]

pam_gssapi_services = sudo, sudo-i

pam_gssapi_indicators_map = sudo:pkinit, sudo-i:otp

pam_gssapi_check_upn = true
...

[domain/ad.example.com]

pam_gssapi_services = sudo

pam_gssapi_check_upn = false
...
```

Additional resources

• Kerberos authentication indicators

20.10. TROUBLESHOOTING GSSAPI AUTHENTICATION FOR SUDO

If you are unable to authenticate to the **sudo** service with a Kerberos ticket from IdM, use the following scenarios to troubleshoot your configuration.

Prerequisites

- You have enabled GSSAPI authentication for the sudo service. See Enabling GSSAPI authentication for sudo on an IdM client.
- You need root privileges to modify the /etc/sssd/sssd.conf file and PAM files in the /etc/pam.d/ directory.

Procedure

• If you see the following error, the Kerberos service might not able to resolve the correct realm for the service ticket based on the host name:

Server not found in Kerberos database

In this situation, add the hostname directly to **[domain_realm]** section in the /etc/krb5.conf Kerberos configuration file:

```
[idm-user@idm-client ~]$ cat /etc/krb5.conf
...

[domain_realm]
    .example.com = EXAMPLE.COM
    example.com = EXAMPLE.COM
    server.example.com = EXAMPLE.COM
```

• If you see the following error, you do not have any Kerberos credentials:

No Kerberos credentials available

In this situation, retrieve Kerberos credentials with the **kinit** utility or authenticate with SSSD:

[idm-user@idm-client ~]\$ kinit idm-user@IDM.EXAMPLE.COM Password for idm-user@idm.example.com:

• If you see either of the following errors in the /var/log/sssd/sssd_pam.log log file, the Kerberos credentials do not match the username of the user currently logged in:

User with UPN [<UPN>] was not found.

UPN [<UPN>] does not match target user [<username>].

In this situation, verify that you authenticated with SSSD, or consider disabling the **pam gssapi check upn** option in the /**etc/sssd/sssd.conf** file:

```
[idm-user@idm-client ~]$ cat /etc/sssd/sssd.conf
...
pam_gssapi_check_upn = false
```

- For additional troubleshooting, you can enable debugging output for the **pam_sss_gss.so** PAM module.
 - Add the **debug** option at the end of all **pam_sss_gss.so** entries in PAM files, such as /etc/pam.d/sudo and /etc/pam.d/sudo-i:

```
[root@idm-client ~]# cat /etc/pam.d/sudo
#%PAM-1.0
auth sufficient pam_sss_gss.so debug
auth include system-auth
account include system-auth
password include system-auth
session include system-auth
```

```
[root@idm-client ~]# cat /etc/pam.d/sudo-i
#%PAM-1.0
auth sufficient pam_sss_gss.so debug
auth include sudo
```

```
account include sudo
password include sudo
session optional pam_keyinit.so force revoke
session include sudo
```

• Try to authenticate with the **pam_sss_gss.so** module and review the console output. In this example, the user did not have any Kerberos credentials.

```
[idm-user@idm-client ~]$ sudo Is -I /etc/sssd/sssd.conf
pam sss gss: Initializing GSSAPI authentication with SSSD
pam_sss_gss: Switching euid from 0 to 1366201107
pam_sss_gss: Trying to establish security context
pam sss gss: SSSD User name: idm-user@idm.example.com
pam sss gss: User domain: idm.example.com
pam sss gss: User principal:
pam_sss_gss: Target name: host@idm.example.com
pam_sss_gss: Using ccache: KCM:
pam sss gss: Acquiring credentials, principal name will be derived
pam sss gss: Unable to read credentials from [KCM:] [maj:0xd0000, min:0x96c73ac3]
pam_sss_gss: GSSAPI: Unspecified GSS failure. Minor code may provide more
information
pam_sss_gss: GSSAPI: No credentials cache found
pam_sss_gss: Switching euid from 1366200907 to 0
pam_sss_gss: System error [5]: Input/output error
```

20.11. USING AN ANSIBLE PLAYBOOK TO ENSURE SUDO ACCESS FOR AN IDM USER ON AN IDM CLIENT

In Identity Management (IdM), you can ensure **sudo** access to a specific command is granted to an IdM user account on a specific IdM host.

Complete this procedure to ensure a **sudo** rule named **idm_user_reboot** exists. The rule grants **idm_user** the permission to run the /**usr/sbin/reboot** command on the **idmclient** machine.

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You have ensured the presence of a user account for idm_user in IdM and unlocked the account by creating a password for the user. For details on adding a new IdM user using the command line, see link: Adding users using the command line.

 No local idm_user account exists on idmclient. The idm_user user is not listed in the /etc/passwd file on idmclient.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaservers** in it:

[ipaservers] server.idm.example.com

- 2. Add one or more **sudo** commands:
 - a. Create an ensure-reboot-sudocmd-is-present.yml Ansible playbook that ensures the presence of the /usr/sbin/reboot command in the IdM database of sudo commands. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/sudocmd/ensure-sudocmd-is-present.yml file:

--- name: Playbook to manage sudo command hosts: ipaserver

vars_files:
- /home/user_name/MyPlaybooks/secret.yml tasks:
Ensure sudo command is present
- ipasudocmd:
 ipaadmin_password: "{{ ipaadmin_password }}"
 name: /usr/sbin/reboot
 state: present

b. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensurereboot-sudocmd-is-present.yml

- 3. Create a **sudo** rule that references the commands:
 - a. Create an ensure-sudorule-for-idmuser-on-idmclient-is-present.yml Ansible playbook that uses the sudo command entry to ensure the presence of a sudo rule. The sudo rule allows idm_user to reboot the idmclient machine. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/sudorule/ensuresudorule-is-present.yml file:

```
---
- name: Tests
hosts: ipaserver

vars_files:
- /home/user_name/MyPlaybooks/secret.yml
tasks:
# Ensure a sudorule is present granting idm_user the permission to run /usr/sbin/reboot
on idmclient
- ipasudorule:
    ipaadmin_password: "{{ ipaadmin_password }}"
```

name: idm_user_reboot description: A test sudo rule. allow_sudocmd: /usr/sbin/reboot host: idmclient.idm.example.com

user: idm_user state: present

b. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-sudorule-for-idmuser-on-idmclient-is-present.yml

Verification

Test that the **sudo** rule whose presence you have ensured on the IdM server works on **idmclient** by verifying that **idm_user** can reboot **idmclient** using **sudo**. Note that it can take a few minutes for the changes made on the server to take effect on the client.

- 1. Log in to idmclient as idm_user.
- 2. Reboot the machine using **sudo**. Enter the password for **idm_user** when prompted:

\$ sudo /usr/sbin/reboot [sudo] password for idm_user:

If **sudo** is configured correctly, the machine reboots.

Additional resources

• See the **README-sudocmd.md**, **README-sudocmdgroup.md**, and **README-sudorule.md** files in the /usr/share/doc/ansible-freeipa/ directory.

20.12. MANAGING MULTIPLE IDM SUDO RULES IN A SINGLE ANSIBLE TASK

Using the **sudorules** option available in the **ansible-freeipa** module, you can ensure the presence or absence of multiple Identity Management (IdM) **sudo** rules in a single Ansible task. Using the option, you can thus define your **sudo** rules more easily, and execute them more efficiently.

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You are using RHEL 9.6 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password** and that you have access to a file that stores the password protecting the **secret.yml** file.

• The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

The example further assumes the following:

- The user01 and user02 users exist in IdM.
- The usergroup01 user group exists in IdM.
- The hostgroup01 and hostgroup02 host groups exist in IdM.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

```
$ cd ~/MyPlaybooks/
```

2. Create an **ensure-presence-of-multiple-sudorules-in-a-task.yml** file with the following content:

```
- name: Playbook to handle sudorules
hosts: ipaserver
become: true
tasks:
# Ensure sudo command name: /usr/sbin/dmidecode is present
- ipasudocmd:
   ipaadmin_password: "{{ ipaadmin_password }}"
   name: /usr/sbin/dmidecode
# Ensure sudo command /usr/sbin/reboot is present
- ipasudocmd:
   ipaadmin_password: "{{ ipaadmin_password }}"
   name: /usr/sbin/reboot
# Ensure sudo command /usr/bin/yum is present
- ipasudocmd:
   ipaadmin password: "{{ ipaadmin password }}"
   name: /usr/bin/yum
# Ensure a sudo command group is present
- ipasudocmdgroup:
   ipaadmin_password: "{{ ipaadmin_password }}"
   name: sudogroup01
   sudocmd:
   - /usr/sbin/dmidecode
   - /usr/sbin/reboot
 - name: Ensure multiple sudo rules are present using batch mode
  ipasudorule:
   ipaadmin password: "{{ ipaadmin password }}"
   sudorules:
    - name: testrule01
     user:
      - user01
```

- user02

group:

- usergroup01

allow_sudocmd:

- /usr/bin/yum

allow_sudocmdgroup:

- sudogroup01
- name: testrule02

hostgroup:

- hostgroup01
- hostgroup02

NOTE

Using the **sudorules** option, you can specify multiple **sudo** rule variables that only apply to a particular **sudo** rule. This **sudo** rule is defined by the **name** variable, which is the only mandatory variable for the **sudorules** option. In the example, the **user**, **group**, **allow_sudocmd**, and **allow_sudocmdgroup** variables are applied to the **testruleO1 sudo** rule.

- 3. Save the file.
- 4. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory ensure-presence-of-multiple-sudorules-in-a-task.yml

CHAPTER 21. ENSURING THE PRESENCE OF HOST-BASED ACCESS CONTROL RULES IN IDM USING ANSIBLE PLAYBOOKS

Ansible is an automation tool used to configure systems, deploy software, and perform rolling updates. It includes support for Identity Management (IdM).

Learn more about Identity Management (IdM) host-based access policies and how to define them using Ansible.

21.1. HOST-BASED ACCESS CONTROL RULES IN IDM

Host-based access control (HBAC) rules define which users or user groups can access which hosts or host groups by using which services or services in a service group. As a system administrator, you can use HBAC rules to achieve the following goals:

- Limit access to a specified system in your domain to members of a specific user group.
- Allow only a specific service to be used to access systems in your domain.

By default, IdM is configured with a default HBAC rule named **allow_all**, which means universal access to every host for every user via every relevant service in the entire IdM domain.

You can fine-tune access to different hosts by replacing the default **allow_all** rule with your own set of HBAC rules. For centralized and simplified access control management, you can apply HBAC rules to user groups, host groups, or service groups instead of individual users, hosts, or services.

21.2. ENSURING THE PRESENCE OF AN HBAC RULE IN IDM USING AN ANSIBLE PLAYBOOK

Follow this procedure to ensure the presence of a host-based access control (HBAC) rule in Identity Management (IdM) using an Ansible playbook.

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The users and user groups you want to use for your HBAC rule exist in IdM. See Managing user accounts using Ansible playbooks and Ensuring the presence of IdM groups and group members using Ansible playbooks for details.

The hosts and host groups to which you want to apply your HBAC rule exist in IdM. See
 Managing hosts using Ansible playbooks and Managing host groups using Ansible playbooks for
 details.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

 Create your Ansible playbook file that defines the HBAC policy whose presence you want to ensure. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/hbacrule/ensure-hbacrule-allhostspresent.yml file:

- name: Playbook to handle hbacrules

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks

Ensure idm_user can access client.idm.example.com via the sshd service

- ipahbacrule:

ipaadmin_password: "{{ ipaadmin_password }}"

name: login user: idm_user

host: client.idm.example.com

hbacsvc: - sshd

state: present

3. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-new-hbacrule-present.yml

Verification

- 1. Log in to the IdM Web UI as administrator.
- 2. Navigate to Policy → Host-Based-Access-Control → HBAC Test
- 3. In the **Who** tab, select idm_user.
- 4. In the Accessing tab, select client.idm.example.com.
- 5. In the Via service tab, select sshd.
- 6. In the **Rules** tab, select **login**.
- 7. In the **Run test** tab, click the **Run test** button. If you see ACCESS GRANTED, the HBAC rule is implemented successfully.

Additional resources

- See the **README-hbacsvc.md**, **README-hbacsvcgroup.md**, and **README-hbacrule.md** files in the /usr/share/doc/ansible-freeipa directory.
- See the playbooks in the subdirectories of the /usr/share/doc/ansible-freeipa/playbooks directory.

CHAPTER 22. MANAGING IDM CERTIFICATES USING ANSIBLE

You can use the **ansible-freeipa ipacert** module to request, revoke, and retrieve SSL certificates for Identity Management (IdM) users, hosts and services. You can also restore a certificate that has been put on hold.

22.1. USING ANSIBLE TO REQUEST SSL CERTIFICATES FOR IDM HOSTS, SERVICES AND USERS

You can use the **ansible-freeipa ipacert** module to request SSL certificates for Identity Management (IdM) users, hosts and services. They can then use these certificates to authenticate to IdM.

Complete this procedure to request a certificate for an HTTP server from an IdM certificate authority (CA) using an Ansible playbook.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
 - You have stored your **ipaadmin_password** in the **secret.yml** Ansible vault.
- Your IdM deployment has an integrated CA.

Procedure

 Generate a certificate-signing request (CSR) for your user, host or service. For example, to use the **openssI** utility to generate a CSR for the **HTTP** service running on client.idm.example.com, enter:

openssl req -new -newkey rsa:2048 -days 365 -nodes -keyout new.key -out new.csr - subj '/CN=client.idm.example.com,O=IDM.EXAMPLE.COM'

As a result, the CSR is stored in new.csr.

2. Create your Ansible playbook file request-certificate.yml with the following content:

 name: Playbook to request a certificate hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

 name: Request a certificate for a web server ipacert:

ipaadmin_password: "{{ ipaadmin_password }}"

state: requested

```
csr: |
----BEGIN CERTIFICATE REQUEST-----
```

MIGYMEwCAQAwGTEXMBUGA1UEAwwOZnJIZWIwYSBydWxlcyEwKjAFBgMrZXADIQBs HlqIr4b/XNK+K8QLJKIzfvuNK0buBhLz3LAzY7QDEqAAMAUGAytlcANBAF4oSCbA 5alPukCidnZJdr491G4LBE+URecYXsPknwYb+V+ONnf5ycZHyaFv+jkUBFGFeDgU SYaXm/gF8cDYjQI= -----END CERTIFICATE REQUEST-----

-----END CERTIFICATE REQUEST----principal: HTTP/client.idm.example.com
register: cert

Replace the certificate request with the CSR from new.csr.

3. Request the certificate:

\$ ansible-playbook --vault-password-file=password_file -v -i <path_to_inventory_directory>/hosts <path_to_playbooks_directory>/request-certificate.yml

Additional resources

• The cert module in **ansible-freeipa** upstream docs

22.2. USING ANSIBLE TO REVOKE SSL CERTIFICATES FOR IDM HOSTS, SERVICES AND USERS

You can use the **ansible-freeipa ipacert** module to revoke SSL certificates used by Identity Management (IdM) users, hosts and services to authenticate to IdM.

Complete this procedure to revoke a certificate for an HTTP server using an Ansible playbook. The reason for revoking the certificate is "keyCompromise".

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
 - You have stored your **ipaadmin_password** in the **secret.yml** Ansible vault.
 - You have obtained the serial number of the certificate, for example by entering the openssl x509 -noout -text -in path_to_certificate> command. In this example, the serial number of the certificate is 123456789.
- Your IdM deployment has an integrated CA.

Procedure

1. Create your Ansible playbook file revoke-certificate.yml with the following content:

- name: Playbook to revoke a certificate

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Revoke a certificate for a web server

ipacert:

ipaadmin_password: "{{ ipaadmin_password }}"

serial number: 123456789

revocation_reason: "keyCompromise"

state: revoked

2. Revoke the certificate:

\$ ansible-playbook --vault-password-file=password_file -v -i <path_to_inventory_directory>/hosts <path_to_playbooks_directory>/revoke-certificate.yml

Additional resources

- The cert module in **ansible-freeipa** upstream docs
- Reason Code in RFC 5280

22.3. USING ANSIBLE TO RESTORE SSL CERTIFICATES FOR IDM USERS, HOSTS, AND SERVICES

You can use the **ansible-freeipa ipacert** module to restore a revoked SSL certificate previously used by an Identity Management (IdM) user, host or a service to authenticate to IdM.



NOTE

You can only restore a certificate that was put on hold. You may have put it on hold because, for example, you were not sure if the private key had been lost. However, now you have recovered the key and as you are certain that no-one has accessed it in the meantime, you want to reinstate the certificate.

Complete this procedure to use an Ansible playbook to release a certificate for a service enrolled into IdM from hold. This example describes how to release a certificate for an HTTP service from hold.

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.

- You have stored your **ipaadmin_password** in the **secret.yml** Ansible vault.
- Your IdM deployment has an integrated CA.
- You have obtained the serial number of the certificate, for example by entering the openssl x509 -noout -text -in path/to/certificate command. In this example, the certificate serial number is 123456789.

Procedure

1. Create your Ansible playbook file **restore-certificate.yml** with the following content:

- name: Playbook to restore a certificate

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Restore a certificate for a web service

ipacert:

ipaadmin_password: "{{ ipaadmin_password }}"

serial number: 123456789

state: released

2. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i <path_to_inventory_directory>/hosts <path_to_playbooks_directory>/restore-certificate.yml

Additional resources

• The cert module in **ansible-freeipa** upstream docs

22.4. USING ANSIBLE TO RETRIEVE SSL CERTIFICATES FOR IDM USERS, HOSTS, AND SERVICES

You can use the **ansible-freeipa ipacert** module to retrieve an SSL certificate issued for an Identity Management (IdM) user, host or a service, and store it in a file on the managed node.

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
 - You have stored your **ipaadmin_password** in the **secret.yml** Ansible vault.

• You have obtained the serial number of the certificate, for example by entering the **openssl x509 -noout -text -in <path_to_certificate>** command. In this example, the serial number of the certificate is 123456789, and the file in which you store the retrieved certificate is **cert.pem**.

Procedure

1. Create your Ansible playbook file **retrieve-certificate.yml** with the following content:

- name: Playbook to retrieve a certificate and store it locally on the managed node hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Retrieve a certificate and save it to file 'cert.pem'

ipacert:

ipaadmin_password: "{{ ipaadmin_password }}"

serial_number: 123456789 certificate out: cert.pem

state: retrieved

2. Retrieve the certificate:

\$ ansible-playbook --vault-password-file=password_file -v -i <path_to_inventory_directory>/hosts <path_to_playbooks_directory>/retrieve-certificate.yml

Additional resources

• The cert module in **ansible-freeipa** upstream docs

CHAPTER 23. VAULTS IN IDM

Learn more about vaults in Identity Management (IdM).

23.1. VAULTS AND THEIR BENEFITS

You can use an Identity Management (IdM) vault to keep all your sensitive data stored securely but conveniently in one place.

A vault is a secure location in IdM for storing, retrieving, sharing, and recovering a secret. A secret is security-sensitive data, usually authentication credentials, that only a limited group of people or entities can access. For example, secrets include:

- Passwords
- PINs
- Private SSH keys

A vault is comparable to a password manager. Just like a password manager, a vault typically requires a user to generate and remember one primary password to unlock and access any information stored in the vault. However, a user can also decide to have a standard vault. A standard vault does not require the user to enter any password to access the secrets stored in the vault.



NOTE

The purpose of vaults in IdM is to store authentication credentials that allow you to authenticate to external, non-IdM-related services.

IdM vaults are characterized by the following:

- Vaults are only accessible to the vault owner and those IdM users that the vault owner selects to be the vault members. In addition, the IdM administrator has access to all vaults.
- If a user does not have sufficient privileges to create a vault, an IdM administrator can create the vault and set the user as its owner.
- Users and services can access the secrets stored in a vault from any machine enrolled in the IdM domain.
- One vault can only contain one secret, for example, one file. However, the file itself can contain multiple secrets such as passwords, keytabs or certificates.



NOTE

Vault is only available from the IdM command line (CLI), not from the IdM Web UI.

23.2. VAULT OWNERS, MEMBERS, AND ADMINISTRATORS

Identity Management (IdM) distinguishes the following vault user types:

Vault owner

A vault owner is a user or service with basic management privileges on the vault. For example, a vault owner can modify the properties of the vault or add new vault members.

Each vault must have at least one owner. A vault can also have multiple owners.

Vault member

A vault member is a user or service that can access a vault created by another user or service.

Vault administrator

Vault administrators have unrestricted access to all vaults and are allowed to perform all vault operations. In the context of IdM role-based access control (RBAC), a vault administrator is any IdM user with the **Vault Administrators** privilege.



NOTE

Symmetric and asymmetric vaults are protected with a password or key. Special access control rules apply for an administrator to:

- Access secrets in symmetric and asymmetric vaults.
- Change or reset the vault password or key.

Vault User

The vault user represents the user in whose container the vault is located. The **Vault user** information is displayed in the output of specific commands, such as **ipa vault-show**:

\$ ipa vault-show my_vault Vault name: my_vault Type: standard Owner users: user Vault user: user

For details on vault containers and user vaults, see Vault containers.

Additional resources

- Standard, symmetric and asymmetric vaults
- Using Ansible playbooks to manage role-based access control in IdM

23.3. STANDARD, SYMMETRIC, AND ASYMMETRIC VAULTS

Based on the level of security and access control, IdM classifies vaults into the following types:

Standard vaults

Vault owners and vault members can archive and retrieve the secret inside a vault without having to use a password or key.

Symmetric vaults

Secrets in the vault are protected with a symmetric key. Vault owners and members can archive and retrieve the secrets, but they must provide the vault password.

Asymmetric vaults

Secrets in the vault are protected with asymmetric keys. Users archive the secret by using a public key and retrieve it by using a private key. Vault owners can both archive and retrieve secrets. Vault members can only archive secrets.

23.4. USER, SERVICE, AND SHARED VAULTS

Based on ownership, IdM classifies vaults into several types. The table below contains information about each type, its owner and use.

Table 23.1. IdM vaults based on ownership

Туре	Description	Owner	Note
User vault	A private vault for a user	A single user	Any user can own one or more user vaults if allowed by IdM administrator
Service vault	A private vault for a service	A single service	Any service can own one or more user vaults if allowed by IdM administrator
Shared vault	A vault shared by multiple users and services	The vault administrator who created the vault	Users and services can own one or more user vaults if allowed by IdM administrator. The vault administrators other than the one that created the vault also have full access to the vault.

23.5. VAULT CONTAINERS

A vault container is a collection of vaults. The table below lists the default vault containers that Identity Management (IdM) provides.

Table 23.2. Default vault containers in IdM

Туре	Description	Purpose
User container	A private container for a user	Stores user vaults for a particular user
Service container	A private container for a service	Stores service vaults for a particular service
Shared container	A container for multiple users and services	Stores vaults that can be shared by multiple users or services

IdM creates user and service containers for each user or service automatically when the first private vault for the user or service is created. After the user or service is deleted, IdM removes the container and its contents.

23.6. BASIC IDM VAULT COMMANDS

You can use the basic commands outlined below to manage Identity Management (IdM) vaults. The table below contains a list of **ipa vault-*** commands with the explanation of their purpose.



NOTE

Before running any **ipa vault-*** command, install the Key Recovery Authority (KRA) certificate system component on one or more of the servers in your IdM domain. For details, see Installing the Key Recovery Authority in IdM .

Table 23.3. Basic IdM vault commands with explanations

Command	Purpose
ipa help vault	Displays conceptual information about IdM vaults and sample vault commands.
ipa vault-addhelp, ipa vault-findhelp	Adding the help option to a specific ipa vault-* command displays the options and detailed help available for that command.
ipa vault-show user_vaultuser idm_user	When accessing a user vault as a vault member, you must specify the vault owner. If you do not specify the vault owner, IdM informs you that it did not find the vault: [admin@server ~]\$ ipa vault-show user_vault ipa: ERROR: user_vault: vault not found
ipa vault-show shared_vault shared	When accessing a shared vault, you must specify that the vault you want to access is a shared vault. Otherwise, IdM informs you it did not find the vault: [admin@server ~]\$ ipa vault-show shared_vault ipa: ERROR: shared_vault: vault not found

23.7. INSTALLING THE KEY RECOVERY AUTHORITY IN IDM

Follow this procedure to enable vaults in Identity Management (IdM) by installing the Key Recovery Authority (KRA) Certificate System (CS) component on a specific IdM server.

Prerequisites

- You are logged in as **root** on the ldM server.
- An IdM certificate authority is installed on the IdM server.
- You have the **Directory Manager** credentials.

Procedure

Install the KRA:





NOTE

To make the vault service highly available and resilient, install the KRA on two IdM servers or more. Maintaining multiple KRA servers prevents data loss.



IMPORTANT

You can install the first KRA of an IdM cluster on a hidden replica. However, installing additional KRAs requires temporarily activating the hidden replica before you install the KRA clone on a non-hidden replica. Then you can hide the originally hidden replica again.

Additional resources

- Demoting or promoting hidden replicas
- The hidden replica mode

CHAPTER 24. USING ANSIBLE TO MANAGE IDM USER VAULTS: STORING AND RETRIEVING SECRETS

This chapter describes how to manage user vaults in Identity Management using the Ansible **vault** module. Specifically, it describes how a user can use Ansible playbooks to perform the following three consecutive actions:

- Create a user vault in IdM .
- Store a secret in the vault .
- Retrieve a secret from the vault .

The user can do the storing and the retrieving from two different IdM clients.

Prerequisites

 The Key Recovery Authority (KRA) Certificate System component has been installed on one or more of the servers in your IdM domain. For details, see Installing the Key Recovery Authority in IdM.

24.1. ENSURING THE PRESENCE OF A STANDARD USER VAULT IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to create a vault container with one or more private vaults to securely store sensitive information. In the example used in the procedure below, the <code>idm_user</code> user creates a vault of the standard type named <code>my_vault</code>. The standard vault type ensures that <code>idm_user</code> will not be required to authenticate when accessing the file. <code>idm_user</code> will be able to retrieve the file from any IdM client to which the user is logged in.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the password of idm_user.

Procedure

1. Navigate to the MyPlaybooks directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/vault/ensure-standard-vault-is-present.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/vault/ensure-standard-vault-is-present.yml ensure-standard-vault-is-present-copy.yml

- 3. Open the ensure-standard-vault-is-present-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_principal** variable to **idm_user**.
 - Set the **ipaadmin password** variable to the password of **idm_user**.
 - Set the **user** variable to **idm_user**.
 - Set the **name** variable to **my_vault**.
 - Set the vault_type variable to standard.
 This the modified Ansible playbook file for the current example:

--- name: Tests
hosts: ipaserver
gather_facts: false

tasks:
- ipavault:
 ipaadmin_principal: idm_user
 ipaadmin_password: idm_user_password
 user: idm_user
 name: my_vault
 vault_type: standard

- 5. Save the file.
- 6. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-standard-vault-is-present-copy.yml

24.2. ARCHIVING A SECRET IN A STANDARD USER VAULT IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to store sensitive information in a personal vault. In the example used, the **idm_user** user archives a file with sensitive information named **password.txt** in a vault named **my_vault**.

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.

- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the password of idm_user.
- idm_user is the owner, or at least a member user of my_vault.
- You have access to password.txt, the secret that you want to archive in my vault.

Procedure

1. Navigate to the MyPlaybooks directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/vault/data-archive-in-symmetric-vault.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/vault/data-archive-in-symmetric-vault.yml data-archive-in-symmetric-vault-copy.yml

- 3. Open the data-archive-in-standard-vault-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_principal** variable to **idm_user**.
 - Set the **ipaadmin_password** variable to the password of **idm_user**.
 - Set the **user** variable to **idm_user**.
 - Set the **name** variable to **my_vault**.
 - Set the **in** variable to the full path to the file with sensitive information.
 - Set the action variable to member.
 This the modified Ansible playbook file for the current example:

- name: Tests hosts: ipaserver gather_facts: false

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:
- ipavault:

ipaadmin principal: idm user

ipaadmin_password: idm_user_password

user: idm_user name: my_vault

in: /usr/share/doc/ansible-freeipa/playbooks/vault/password.txt

action: member

5. Save the file.

6. Run the playbook:

\$ ansible-playbook -v -i inventory.file data-archive-in-standard-vault-copy.yml

24.3. RETRIEVING A SECRET FROM A STANDARD USER VAULT IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to retrieve a secret from the user personal vault. In the example used in the procedure below, the <code>idm_user</code> user retrieves a file with sensitive data from a vault of the standard type named <code>my_vault</code> onto an IdM client named <code>hostO1</code>. <code>idm_user</code> does not have to authenticate when accessing the file. <code>idm_user</code> can use Ansible to retrieve the file from any IdM client on which Ansible is installed.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the password of idm_user.
- idm_user is the owner of my_vault.
- idm user has stored a secret in my vault.
- Ansible can write into the directory on the IdM host into which you want to retrieve the secret.
- idm_user can read from the directory on the IdM host into which you want to retrieve the secret.

Procedure

1. Navigate to the MyPlaybooks directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/vault/data-archive-in-symmetric-vault.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/vault/retrive-data-symmetric-vault.yml retrieve-data-symmetric-vault-copy.yml

3. Open your inventory file and mention, in a clearly defined section, the IdM client onto which you want to retrieve the secret. For example, to instruct Ansible to retrieve the secret onto host01.idm.example.com, enter:

[ipahost] host01.idm.example.com

- 4. Open the retrieve-data-standard-vault.yml-copy.yml file for editing.
- 5. Adapt the file by setting the **hosts** variable to **ipahost**.
- 6. Adapt the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin principal** variable to **idm_user**.
 - Set the **ipaadmin_password** variable to the password of **idm_user**.
 - Set the **user** variable to **idm_user**.
 - Set the **name** variable to **my_vault**.
 - Set the **out** variable to the full path of the file into which you want to export the secret.
 - Set the **state** variable to **retrieved**.
 This the modified Ansible playbook file for the current example:

 name: Tests hosts: ipahost gather_facts: false

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

- ipavault:

ipaadmin_principal: idm_user

ipaadmin_password: idm_user_password

user: idm_user name: my_vault

out: /tmp/password_exported.txt

state: retrieved

- 7. Save the file.
- 8. Run the playbook:

\$ ansible-playbook -v -i inventory.file retrieve-data-standard-vault.yml-copy.yml

Verification

1. **SSH** to host01 as user01:

\$ ssh user01@host01.idm.example.com

2. View the file specified by the **out** variable in the Ansible playbook file:

\$ vim /tmp/password_exported.txt

You can now see the exported secret.

Additional resources

• For more information about using Ansible to manage IdM vaults and user secrets and about playbook variables, see the README-vault.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory and the sample playbooks available in the /usr/share/doc/ansible-freeipa/playbooks/vault/ directory.

CHAPTER 25. USING ANSIBLE TO MANAGE IDM SERVICE VAULTS: STORING AND RETRIEVING SECRETS

This section describes how an administrator can use the **ansible-freeipa vault** module to securely store a service secret in a centralized location. The vault used in the example is asymmetric, which means that to use it, the administrator needs to perform the following steps:

- 1. Generate a private key using, for example, the **openssI** utility.
- 2. Generate a public key based on the private key.

The service secret is encrypted with the public key when an administrator archives it into the vault. Afterwards, a service instance hosted on a specific machine in the domain retrieves the secret using the private key. Only the service and the administrator are allowed to access the secret.

If the secret is compromised, the administrator can replace it in the service vault and then redistribute it to those individual service instances that have not been compromised.

Prerequisites

 All the IdM servers in the ipaserver host category defined in the playbooks below have the Key Recovery Authority (KRA) Certificate System component installed on them. For details, see Installing the Key Recovery Authority in IdM.

In the procedures:

- The IdM admin user is the administrator who manages the service password.
- private-key-to-an-externally-signed-certificate.pem is the file containing the service secret, in this case a private key to an externally signed certificate. Do not confuse this private key with the private key used to retrieve the secret from the vault.
- secret_vault is the vault created to store the service secret.
- HTTP/webserver1.idm.example.com is the service that is the owner of the vault.
- HTTP/webserver2.idm.example.com and HTTP/webserver3.idm.example.com are the vault member services.
- **service-public.pem** is the service public key used to encrypt the password stored in **password_vault**.
- **service-private.pem** is the service private key used to decrypt the password stored in **secret_vault**.

25.1. ENSURING THE PRESENCE OF AN ASYMMETRIC SERVICE VAULT IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to create a service vault container with one or more private vaults to securely store sensitive information. In the example used in the procedure below, the administrator creates an asymmetric vault named **secret_vault**. This ensures that the vault members have to authenticate using a private key to retrieve the secret in the vault. The vault members will be able to retrieve the file from any IdM client.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to the MyPlaybooks directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/vault/ensure-asymmetric-vault-is-present.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/vault/ensure-asymmetric-vault-is-present.yml ensure-asymmetric-vault-is-present-copy.yml

- 3. Obtain the public key of the service instance. For example, using the **openssI** utility:
 - a. Generate the **service-private.pem** private key.

```
$ openssl genrsa -out service-private.pem 2048
Generating RSA private key, 2048 bit long modulus
.+++
e is 65537 (0x10001)
```

b. Generate the **service-public.pem** public key based on the private key.

\$ openssI rsa -in service-private.pem -out service-public.pem -pubout writing RSA key

- 4. Open the ensure-asymmetric-vault-is-present-copy.yml file for editing.
- 5. Add a task that copies the **service-public.pem** public key from the Ansible controller to the **server.idm.example.com** server.
- 6. Modify the rest of the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_password** variable to the IdM administrator password.
 - Define the name of the vault using the **name** variable, for example **secret_vault**.
 - Set the vault_type variable to asymmetric.

- Set the **service** variable to the principal of the service that owns the vault, for example **HTTP/webserver1.idm.example.com**.
- Set the **public_key_file** to the location of your public key.

 This is the modified Ansible playbook file for the current example:

- name: Tests hosts: ipaserver gather facts: false

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Copy public key to ipaserver.

copy:

src: /path/to/service-public.pem

dest: /usr/share/doc/ansible-freeipa/playbooks/vault/service-public.pem

mode: 0600

- name: Add data to vault, from a LOCAL file.

ipavault:

ipaadmin_password: "{{ ipaadmin_password }}"

name: secret_vault
vault_type: asymmetric

service: HTTP/webserver1.idm.example.com

public key file: /usr/share/doc/ansible-freeipa/playbooks/vault/service-public.pem

- 7. Save the file.
- 8. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-asymmetric-service-vault-is-present-copy.yml

25.2. ADDING MEMBER SERVICES TO AN ASYMMETRIC VAULT USING ANSIBLE

Follow this procedure to use an Ansible playbook to add member services to a service vault so that they can all retrieve the secret stored in the vault. In the example used in the procedure below, the IdM administrator adds the HTTP/webserver2.idm.example.com and

HTTP/webserver3.idm.example.com service principals to the secret_vault vault that is owned by HTTP/webserver1.idm.example.com.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.

- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You have created an asymmetric vault to store the service secret.

Procedure

1. Navigate to the MyPlaybooks directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/vault/data-archive-inasymmetric-vault.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/vault/data-archive-in-asymmetricvault.yml data-archive-in-asymmetric-vault-copy.yml

- 3. Open the data-archive-in-asymmetric-vault-copy.yml file for editing.
- 4. Modify the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_password** variable to the IdM administrator password.
 - Set the name variable to the name of the vault, for example secret_vault.
 - Set the **service** variable to the service owner of the vault, for example HTTP/webserver1.idm.example.com.
 - Define the services that you want to have access to the vault secret using the services variable.
 - Set the **action** variable to **member**. This the modified Ansible playbook file for the current example:

- name: Tests

hosts: ipaserver gather_facts: false

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- ipavault:

ipaadmin_password: "{{ ipaadmin_password }}"

name: secret_vault

service: HTTP/webserver1.idm.example.com

services:

- HTTP/webserver2.idm.example.com
- HTTP/webserver3.idm.example.com

action: member

- 5. Save the file.
- 6. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file addservices-to-an-asymmetric-vault.yml

25.3. STORING AN IDM SERVICE SECRET IN AN ASYMMETRIC VAULT USING ANSIBLE

Follow this procedure to use an Ansible playbook to store a secret in a service vault so that it can be later retrieved by the service. In the example used in the procedure below, the administrator stores a **PEM** file with the secret in an asymmetric vault named **secret_vault**. This ensures that the service will have to authenticate using a private key to retrieve the secret from the vault. The service will be able to retrieve the file from any IdM client.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You have created an asymmetric vault to store the service secret.
- The secret is stored locally on the Ansible controller, for example in the /usr/share/doc/ansible-freeipa/playbooks/vault/private-key-to-an-externally-signed-certificate.pem file.

Procedure

- 1. Navigate to the **MyPlaybooks** directory:
 - \$ cd ~/MyPlaybooks/
- 2. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/vault/data-archive-in-asymmetric-vault.yml Ansible playbook file. For example:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/vault/data-archive-in-asymmetric-vault.yml data-archive-in-asymmetric-vault-copy.yml
- 3. Open the data-archive-in-asymmetric-vault-copy.yml file for editing.
- 4. Modify the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_password** variable to the IdM administrator password.
 - Set the **name** variable to the name of the vault, for example **secret_vault**.

- Set the **service** variable to the service owner of the vault, for example **HTTP/webserver1.idm.example.com**.
- Set the in variable to "{{ lookup('file', 'private-key-to-an-externally-signed-certificate.pem') | b64encode }}". This ensures that Ansible retrieves the file with the private key from the working directory on the Ansible controller rather than from the IdM server.
- Set the action variable to member.
 This the modified Ansible playbook file for the current example:

 name: Tests hosts: ipaserver gather_facts: false

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- ipavault:

ipaadmin_password: "{{ ipaadmin_password }}"

name: secret vault

service: HTTP/webserver1.idm.example.com

in: "{{ lookup('file', 'private-key-to-an-externally-signed-certificate.pem') | b64encode }}"

action: member

- 5. Save the file.
- 6. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file data-archive-in-asymmetric-vault-copy.yml

25.4. RETRIEVING A SERVICE SECRET FOR AN IDM SERVICE USING ANSIBLE

Follow this procedure to use an Ansible playbook to retrieve a secret from a service vault on behalf of the service. In the example used in the procedure below, running the playbook retrieves a **PEM** file with the secret from an asymmetric vault named **secret_vault**, and stores it in the specified location on all the hosts listed in the Ansible inventory file as **ipaservers**.

The services authenticate to IdM using keytabs, and they authenticate to the vault using a private key. You can retrieve the file on behalf of the service from any IdM client on which **ansible-freeipa** is installed.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.

- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You have created an asymmetric vault to store the service secret.
- You have archived the secret in the vault.
- You have stored the private key used to retrieve the service vault secret in the location specified by the private_key_file variable on the Ansible controller.

Procedure

1. Navigate to the MyPlaybooks directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/vault/retrieve-data-asymmetric-vault.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/vault/retrieve-data-asymmetric-vault.yml retrieve-data-asymmetric-vault-copy.yml

- 3. Open your inventory file and define the following hosts:
 - Define your IdM server in the [ipaserver] section.
 - Define the hosts onto which you want to retrieve the secret in the [webservers] section.
 For example, to instruct Ansible to retrieve the secret to webserver1.idm.example.com,
 webserver2.idm.example.com, and webserver3.idm.example.com,

[ipaserver] server.idm.example.com

[webservers] webserver1.idm.example.com webserver2.idm.example.com webserver3.idm.example.com

- 4. Open the retrieve-data-asymmetric-vault-copy.yml file for editing.
- 5. Modify the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name** variable to the name of the vault, for example **secret_vault**.
 - Set the **service** variable to the service owner of the vault, for example **HTTP/webserver1.idm.example.com**.
 - Set the private_key_file variable to the location of the private key used to retrieve the service vault secret.

- Set the **out** variable to the location on the IdM server where you want to retrieve the **private-key-to-an-externally-signed-certificate.pem** secret, for example the current working directory.
- Set the action variable to member.
 This the modified Ansible playbook file for the current example:

```
-name: Retrieve data from vault
hosts: ipaserver
become: no
gather_facts: false

vars_files:
- /home/user_name/MyPlaybooks/secret.yml
tasks:
- name: Retrieve data from the service vault
ipavault:
    ipaadmin_password: "{{ ipaadmin_password }}"
    name: secret_vault
    service: HTTP/webserver1.idm.example.com
    vault_type: asymmetric
    private_key: "{{ lookup('file', 'service-private.pem') | b64encode }}"
    out: private-key-to-an-externally-signed-certificate.pem
    state: retrieved
```

6. Add a section to the playbook that retrieves the data file from the IdM server to the Ansible controller:

```
---
- name: Retrieve data from vault
hosts: ipaserver
become: no
gather_facts: false
tasks:
[...]
- name: Retrieve data file
fetch:
    src: private-key-to-an-externally-signed-certificate.pem
    dest: ./
    flat: true
    mode: 0600
```

7. Add a section to the playbook that transfers the retrieved **private-key-to-an-externally-signed-certificate.pem** file from the Ansible controller on to the webservers listed in the **webservers** section of the inventory file:

```
---
- name: Send data file to webservers become: no gather_facts: no hosts: webservers tasks:
- name: Send data to webservers copy:
```

src: private-key-to-an-externally-signed-certificate.pem

dest: /etc/pki/tls/private/httpd.key

mode: 0444

- 8. Save the file.
- 9. Run the playbook:

\$ ansible-playbook --vault-password_file=password_file -v -i inventory.file retrieve-data-asymmetric-vault-copy.yml

25.5. CHANGING AN IDM SERVICE VAULT SECRET WHEN COMPROMISED USING ANSIBLE

Follow this procedure to reuse an Ansible playbook to change the secret stored in a service vault when a service instance has been compromised. The scenario in the following example assumes that on webserver3.idm.example.com, the retrieved secret has been compromised, but not the key to the asymmetric vault storing the secret. In the example, the administrator reuses the Ansible playbooks used when storing a secret in an asymmetric vault and retrieving a secret from the asymmetric vault onto IdM hosts. At the start of the procedure, the IdM administrator stores a new PEM file with a new secret in the asymmetric vault, adapts the inventory file so as not to retrieve the new secret on to the compromised web server, webserver3.idm.example.com, and then re-runs the two procedures.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the **IdM administrator** password.
- You have created an asymmetric vault to store the service secret.
- You have generated a new **httpd** key for the web services running on IdM hosts to replace the compromised old key.
- The new httpd key is stored locally on the Ansible controller, for example in the /usr/share/doc/ansible-freeipa/playbooks/vault/private-key-to-an-externally-signed-certificate.pem file.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/vault directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/vault

2. Open your inventory file and make sure that the following hosts are defined correctly:

- The IdM server in the [ipaserver] section.
- The hosts onto which you want to retrieve the secret in the [webservers] section. For example, to instruct Ansible to retrieve the secret to webserver1.idm.example.com and webserver2.idm.example.com, enter:

[ipaserver] server.idm.example.com

[webservers] webserver1.idm.example.com webserver2.idm.example.com



IMPORTANT

Make sure that the list does not contain the compromised webserver, in the current example **webserver3.idm.example.com**.

3. Make a copy of the data-archive-in-asymmetric-vault.yml Ansible playbook file, for example:

 $\$\ cp\ data-archive-in-asymmetric-vault.yml\ data-archive-in-asymmetric-vault-copy.yml$

- 4. Open the data-archive-in-asymmetric-vault-copy.yml file for editing.
- 5. Modify the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_password** variable to the IdM administrator password.
 - Set the **name** variable to the name of the vault, for example **secret_vault**.
 - Set the **service** variable to the service owner of the vault, for example HTTP/webserver.idm.example.com.
 - Set the in variable to "{{ lookup('file', 'new-private-key-to-an-externally-signed-certificate.pem') | b64encode }}". This ensures that Ansible retrieves the file with the private key from the working directory on the Ansible controller rather than from the IdM server.
 - Set the action variable to member.
 This the modified Ansible playbook file for the current example:

 name: Tests hosts: ipaserver gather_facts: false

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks:
- ipavault:

ipaadmin_password : "{{ ipaadmin_password }}"

name: secret_vault

```
service: HTTP/webserver.idm.example.com
in: "{{ lookup('file', 'new-private-key-to-an-externally-signed-certificate.pem') | b64encode
}}"
action: member
```

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file data-archive-in-asymmetric-vault-copy.yml

- 8. Open the retrieve-data-asymmetric-vault-copy.yml file for editing.
- 9. Modify the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name** variable to the name of the vault, for example **secret_vault**.
 - Set the **service** variable to the service owner of the vault, for example **HTTP/webserver1.idm.example.com**.
 - Set the private_key_file variable to the location of the private key used to retrieve the service vault secret.
 - Set the out variable to the location on the IdM server where you want to retrieve the new-private-key-to-an-externally-signed-certificate.pem secret, for example the current working directory.
 - Set the action variable to member.
 This the modified Ansible playbook file for the current example:

```
- name: Retrieve data from vault
 hosts: ipaserver
 become: no
 gather_facts: false
 vars files:
 - /home/user name/MyPlaybooks/secret.yml
 tasks:
 - name: Retrieve data from the service vault
  ipavault:
   ipaadmin_password: "{{ ipaadmin_password }}"
   name: secret vault
   service: HTTP/webserver1.idm.example.com
   vault_type: asymmetric
   private_key: "{{ lookup('file', 'service-private.pem') | b64encode }}"
   out: new-private-key-to-an-externally-signed-certificate.pem
   state: retrieved
```

10. Add a section to the playbook that retrieves the data file from the IdM server to the Ansible controller:

- name: Retrieve data from vault

hosts: ipaserver become: true gather_facts: false

tasks:

- name: Retrieve data file

fetch:

src: new-private-key-to-an-externally-signed-certificate.pem

dest: ./ flat: true mode: 0600

11. Add a section to the playbook that transfers the retrieved **new-private-key-to-an-externally-signed-certificate.pem** file from the Ansible controller on to the webservers listed in the **webservers** section of the inventory file:

- name: Send data file to webservers

become: true gather_facts: no hosts: webservers

tasks:

- name: Send data to webservers

copy:

src: new-private-key-to-an-externally-signed-certificate.pem

dest: /etc/pki/tls/private/httpd.key

mode: 0444

- 12. Save the file.
- 13. Run the playbook:

\$ ansible-playbook --vault-password_file=password_file -v -i inventory.file retrieve-data-asymmetric-vault-copy.yml

25.6. ADDITIONAL RESOURCES

- See the README-vault.md Markdown file in the /usr/share/doc/ansible-freeipa/ directory.
- See the sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/vault/ directory.

CHAPTER 26. ENSURING THE PRESENCE AND ABSENCE OF SERVICES IN IDM USING ANSIBLE

With the Ansible **service** module, Identity Management (IdM) administrator can ensure that specific services that are not native to IdM are present or absent in IdM. For example, you can use the **service** module to:

- Check that a manually installed service is present on an IdM client and automatically install that service if it is absent. For details, see:
 - Ensuring the presence of an HTTP service in IdM on an IdM client.
 - Ensuring the presence of an HTTP service in IdM on a non-IdM client.
 - Ensuring the presence of an HTTP service on an IdM client without DNS.
- Check that a service enrolled in IdM has a certificate attached and automatically install that certificate if it is absent. For details, see:
- Ensuring the presence of an externally-signed certificate in an IdM service entry.
- Allow IdM users and hosts to retrieve and create the service keytab. For details, see:
 - Allowing IdM users, groups, hosts, or host groups to create a keytab of a service.
 - Allowing IdM users, groups, hosts, or host groups to retrieve a keytab of a service.
- Allow IdM users and hosts to add a Kerberos alias to a service. For details, see:
 - Ensuring the presence of a Kerberos principal alias for a service.
- Check that a service is not present on an IdM client and automatically remove that service if it is present. For details, see:
 - Ensuring the absence of an HTTP service in IdM on an IdM client.

26.1. ENSURING THE PRESENCE OF AN HTTP SERVICE IN IDM USING AN ANSIBLE PLAYBOOK

Follow this procedure to ensure the presence of an HTTP server in IdM using an Ansible playbook.

Prerequisites

- The system to host the HTTP service is an IdM client.
- You have the IdM administrator password.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-copy.yml

4. Open the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-copy.yml Ansible playbook file for editing:

- name: Playbook to manage IPA service.

hosts: ipaserver gather_facts: false

vars files:

- /home/user_name/MyPlaybooks/secret.yml tasks:

Ensure service is present

- ipaservice:

ipaadmin_password: "{{ ipaadmin_password }}"

name: HTTP/client.idm.example.com

- 5. Adapt the file:
 - Change the IdM administrator password defined by the **ipaadmin_password** variable.
 - Change the name of your IdM client on which the HTTP service is running, as defined by the name variable of the ipaservice task.
- 6. Save and exit the file.
- 7. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the secret.yml file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-copy.yml

Verification

- 1. Log into the IdM Web UI as IdM administrator.
- 2. Navigate to **Identity** → **Services**.

If HTTP/client.idm.example.com@IDM.EXAMPLE.COM is listed in the Services list, the Ansible playbook has been successfully added to IdM.

Additional resources

• To secure the communication between the HTTP server and browser clients, see adding TLS encryption to an Apache HTTP Server.

• To request a certificate for the HTTP service, see the procedure described in Obtaining an IdM certificate for a service using certmonger.

26.2. ENSURING THE PRESENCE OF MULTIPLE SERVICES IN IDM ON AN IDM CLIENT USING A SINGLE ANSIBLE TASK

You can use the **ansible-freeipa ipaservice** module to add, modify, and delete multiple Identity Management (IdM) services with a single Ansible task. For that, use the **services** option of the **ipaservice** module.

Using the **services** option, you can also specify multiple service variables that only apply to a particular service. Define this service by the **name** variable, which is the only mandatory variable for the **services** option.

Complete this procedure to ensure the presence of the HTTP/client01.idm.example.com@IDM.EXAMPLE.COM and the ftp/client02.idm.example.com@IDM.EXAMPLE.COM services in IdM with a single task.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
 - You are using RHEL 9.3 and later.
 - You have stored your **ipaadmin password** in the **secret.yml** Ansible vault.

Procedure

1. Create your Ansible playbook file **add-http-and-ftp-services.yml** with the following content:

- name: Playbook to add multiple services in a single task

hosts: ipaserver vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

 name: Add HTTP and ftp services ipaservice:

ipaadmin_password: "{{ ipaadmin_password }}"

services:

- name: HTTP/client01.idm.example.com@IDM.EXAMPLE.COM
- name: ftp/client02.idm.example.com@IDM.EXAMPLE.COM
- 2. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory add-http-and-ftp-services.yml

Additional resources

• The service module in **ansible-freeipa** upstream docs

26.3. ENSURING THE PRESENCE OF AN HTTP SERVICE IN IDM ON A NON-IDM CLIENT USING AN ANSIBLE PLAYBOOK

Follow this procedure to ensure the presence of an HTTP server in IdM on a host that is not an IdM client using an Ansible playbook. By adding the HTTP server to IdM you are also adding the host to IdM.

Prerequisites

- You have installed an HTTP service on your host.
- The host on which you have set up HTTP is not an IdM client. Otherwise, follow the steps in enrolled the HTTP service into IdM.
- You have the IdM administrator password.
- The DNS A record or the AAAA record if IPv6 is used for the host is available.
- If the server runs RHEL 9.2 or later and the FIPS mode is enabled, clients must either support the Extended Master Secret (EMS) extension or use TLS 1.3. TLS 1.2 connections without EMS fail. For more information, see the Red Hat Knowledgebase solution TLS extension "Extended Master Secret" enforced.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-without-host-check.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-without-host-check.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-without-host-check-copy.yml

4. Open the copied file, /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-without-host-check-copy.yml, for editing. Locate the ipaadmin_password and name variables in the ipaservice task:

- name: Playbook to manage IPA service.

hosts: ipaserver gather_facts: false

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks

Ensure service is present

- ipaservice:

ipaadmin_password: "{{ ipaadmin_password }}"
name: HTTP/www2.example.com

skip host check: true

- 5. Adapt the file:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name** variable to the name of the host on which the HTTP service is running.
- 6. Save and exit the file.
- 7. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-without-host-check-copy.yml

Verification

- 1. Log into the IdM Web UI as IdM administrator.
- 2. Navigate to **Identity** → **Services**.

You can now see HTTP/client.idm.example.com@IDM.EXAMPLE.COM listed in the Services list.

Additional resources

• To secure the communication, see adding TLS encryption to an Apache HTTP Server .

26.4. ENSURING THE PRESENCE OF AN HTTP SERVICE ON AN IDM CLIENT WITHOUT DNS USING AN ANSIBLE PLAYBOOK

Follow this procedure to ensure the presence of an HTTP server running on an IdM client that has no DNS entry using an Ansible playbook. The scenario implied is that the IdM host has no DNS A entry available - or no DNS AAAA entry if IPv6 is used instead of IPv4.

Prerequisites

- The system to host the HTTP service is enrolled in IdM.
- The DNS A or DNS AAAA record for the host may not exist. Otherwise, if the DNS record for the host does exist, follow the procedure in Ensuring the presence of an HTTP service in IdM using an Ansible playbook.
- You have the IdM administrator password.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-with-host-force.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-with-host-force.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-with-host-force-copy.yml

4. Open the copied file, /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-with-host-force-copy.yml, for editing. Locate the ipaadmin_password and name variables in the ipaservice task:

--- name: Playbook to manage IPA service.
hosts: ipaserver
gather_facts: false

vars_files:
- /home/user_name/MyPlaybooks/secret.yml
tasks:
Ensure service is present
- ipaservice:
 ipaadmin_password: "{{ ipaadmin_password }}"
 name: HTTP/ihavenodns.info

5. Adapt the file:

- Set the **ipaadmin_password** variable to your IdM administrator password.
- Set the **name** variable to the name of the host on which the HTTP service is running.
- 6. Save and exit the file.

force: true

7. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the secret.yml file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-with-host-force-copy.yml

Verification

1. Log into the IdM Web UI as IdM administrator.

2. Navigate to **Identity** → **Services**.

You can now see HTTP/client.idm.example.com@IDM.EXAMPLE.COM listed in the Services list.

Additional resources

• To secure the communication, see adding TLS encryption to an Apache HTTP Server .

26.5. ENSURING THE PRESENCE OF AN EXTERNALLY SIGNED CERTIFICATE IN AN IDM SERVICE ENTRY USING AN ANSIBLE PLAYBOOK

Follow this procedure to use the **ansible-freeipa service** module to ensure that a certificate issued by an external certificate authority (CA) is attached to the IdM entry of the HTTP service. Having the certificate of an HTTP service signed by an external CA rather than the IdM CA is particularly useful if your IdM CA uses a self-signed certificate.

Prerequisites

- You have installed an HTTP service on your host.
- You have enrolled the HTTP service into IdM.
- You have the IdM administrator password.
- You have an externally signed certificate whose Subject corresponds to the principal of the HTTP service.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-certificate-present.yml file, for example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-member-certificate-present.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-member-certificate-present-copy.yml

4. Optional: If the certificate is in the Privacy Enhanced Mail (PEM) format, convert the certificate to the Distinguished Encoding Rules (DER) format for easier handling through the command line (CLI):

\$ openssl x509 -outform der -in cert1.pem -out cert1.der

5. Decode the **DER** file to standard output using the **base64** command. Use the **-w0** option to disable wrapping:

\$ base64 cert1.der -w0
MIIC/zCCAeegAwIBAgIUV74O+4kXeg21o4vxfRRtyJm...

- 6. Copy the certificate from the standard output to the clipboard.
- 7. Open the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-certificate-present-copy.yml file for editing and view its contents:

--- name: Service certificate present.
hosts: ipaserver
gather_facts: false

vars_files:
- /home/user_name/MyPlaybooks/secret.yml
tasks:
Ensure service certificate is present
- ipaservice:
 ipaadmin_password: "{{ ipaadmin_password }}"
 name: HTTP/client.idm.example.com
 certificate: |
 - MIICBjCCAW8CFHnm32VcXaUDGfEGdDL/...
[...]
 action: member
 state: present

- 8. Adapt the file:
 - Replace the certificate, defined using the certificate variable, with the certificate you copied from the CLI. Note that if you use the certificate: variable with the "|" pipe character as indicated, you can enter the certificate THIS WAY rather than having it to enter it in a single line. This makes reading the certificate easier.
 - Change the IdM administrator password, defined by the **ipaadmin_password** variable.
 - Change the name of your IdM client on which the HTTP service is running, defined by the name variable.
 - Change any other relevant variables.
- 9. Save and exit the file.
- 10. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-member-certificate-present-copy.yml

Verification

1. Log into the IdM Web UI as IdM administrator.

- 2. Navigate to **Identity** → **Services**.
- 3. Click the name of the service with the newly added certificate, for example HTTP/client.idm.example.com.

In the **Service Certificate** section on the right, you can now see the newly added certificate.

26.6. USING AN ANSIBLE PLAYBOOK TO ALLOW IDM USERS, GROUPS, HOSTS, OR HOST GROUPS TO CREATE A KEYTAB OF A SERVICE

A keytab is a file containing pairs of Kerberos principals and encrypted keys. Keytab files are commonly used to allow scripts to automatically authenticate using Kerberos, without requiring human interaction or access to password stored in a plain-text file. The script is then able to use the acquired credentials to access files stored on a remote system.

As an Identity Management (IdM) administrator, you can allow other users to retrieve or even create a keytab for a service running in IdM. By allowing specific users and user groups to create keytabs, you can delegate the administration of the service to them without sharing the IdM administrator password. This delegation provides a more fine-grained system administration.

Follow this procedure to allow specific IdM users, user groups, hosts, and host groups to create a keytab for the HTTP service running on an IdM client. Specifically, it describes how you can allow the **user01** IdM user to create a keytab for the HTTP service running on an IdM client named **client.idm.example.com**.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You have enrolled the HTTP service into IdM.
- The system to host the HTTP service is an IdM client.
- The IdM users and user groups that you want to allow to create the keytab exist in IdM.
- The IdM hosts and host groups that you want to allow to create the keytab exist in IdM.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_create_keytab-present.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-memberallow_create_keytab-present.yml /usr/share/doc/ansiblefreeipa/playbooks/service/service-member-allow_create_keytab-present-copy.yml

- 4. Open the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_create_keytab-present-copy.yml Ansible playbook file for editing.
- 5. Adapt the file by changing the following:
 - The IdM administrator password specified by the **ipaadmin password** variable.
 - The name of your IdM client on which the HTTP service is running. In the current example, it is HTTP/client.idm.example.com
 - The names of IdM users that are listed in the **allow_create_keytab_user:** section. In the current example, it is **user01**.
 - The names of IdM user groups that are listed in the **allow_create_keytab_group:** section.
 - The names of IdM hosts that are listed in the allow create keytab host: section.
 - The names of IdM host groups that are listed in the **allow_create_keytab_hostgroup:** section.
 - The name of the task specified by the **name** variable in the **tasks** section. After being adapted for the current example, the copied file looks like this:

 name: Service member allow_create_keytab present hosts: ipaserver

vars files:

- /home/user name/MyPlaybooks/secret.yml

tasks

- name: Service HTTP/client.idm.example.com members allow_create_keytab present for user01

ipaservice:

ipaadmin_password: "{{ ipaadmin_password }}"
name: HTTP/client.idm.example.com
allow_create_keytab_user:

- user01

action: member

6. Save the file.

7. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_create_keytab-present-copy.yml

Verification

1. SSH to an IdM server as an IdM user that has the privilege to create a keytab for the particular HTTP service:

\$ ssh user01@server.idm.example.com Password:

2. Use the **ipa-getkeytab** command to generate the new keytab for the HTTP service:

\$ ipa-getkeytab -s server.idm.example.com -p HTTP/client.idm.example.com -k /etc/httpd/conf/krb5.keytab

The **-s** option specifies a Key Distribution Center (KDC) server to generate the keytab.

The **-p** option specifies the principal whose keytab you want to create.

The **-k** option specifies the keytab file to append the new key to. The file will be created if it does not exist.

If the command does not result in an error, you have successfully created a keytab of HTTP/client.idm.example.com as user01.

26.7. USING AN ANSIBLE PLAYBOOK TO ALLOW IDM USERS, GROUPS, HOSTS, OR HOST GROUPS TO RETRIEVE A KEYTAB OF A SERVICE

A keytab is a file containing pairs of Kerberos principals and encrypted keys. Keytab files are commonly used to allow scripts to automatically authenticate using Kerberos, without requiring human interaction or access to a password stored in a plain-text file. The script is then able to use the acquired credentials to access files stored on a remote system.

As IdM administrator, you can allow other users to retrieve or even create a keytab for a service running in IdM.

Follow this procedure to allow specific IdM users, user groups, hosts, and host groups to retrieve a keytab for the HTTP service running on an IdM client. Specifically, it describes how to allow the **user01** IdM user to retrieve the keytab of the HTTP service running on **client.idm.example.com**.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.

- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You have enrolled the HTTP service into IdM.
- The IdM users and user groups that you want to allow to retrieve the keytab exist in IdM.
- The IdM hosts and host groups that you want to allow to retrieve the keytab exist in IdM.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_retrieve_keytab-present.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-memberallow_retrieve_keytab-present.yml /usr/share/doc/ansiblefreeipa/playbooks/service/service-member-allow_retrieve_keytab-present-copy.yml

- 4. Open the copied file, /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_retrieve_keytab-present-copy.yml, for editing:
- 5. Adapt the file:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name** variable of the **ipaservice** task to the principal of the HTTP service. In the current example, it is **HTTP/client.idm.example.com**
 - Specify the names of IdM users in the allow_retrieve_keytab_group: section. In the current example, it is user01.
 - Specify the names of IdM user groups in the **allow_retrieve_keytab_group:** section.
 - Specify the names of IdM hosts in the **allow retrieve keytab group:** section.
 - Specify the names of IdM host groups in the **allow_retrieve_keytab_group:** section.
 - Specify the name of the task using the name variable in the tasks section.
 After being adapted for the current example, the copied file looks like this:

- name: Service member allow_retrieve_keytab present

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Service HTTP/client.idm.example.com members allow_retrieve_keytab present for user01

ipaservice:

ipaadmin_password: "{{ ipaadmin_password }}"

name: HTTP/client.idm.example.com

allow_retrieve_keytab_user:

- user01

action: member

- 6. Save the file.
- 7. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_retrieve_keytab-present-copy.yml

Verification

1. SSH to an IdM server as an IdM user with the privilege to retrieve a keytab for the HTTP service:

\$ ssh user01@server.idm.example.com Password:

2. Use the **ipa-getkeytab** command with the **-r** option to retrieve the keytab:

\$ ipa-getkeytab -r -s server.idm.example.com -p HTTP/client.idm.example.com -k /etc/httpd/conf/krb5.keytab

The **-s** option specifies a Key Distribution Center (KDC) server from which you want to retrieve the keytab.

The **-p** option specifies the principal whose keytab you want to retrieve.

The **-k** option specifies the keytab file to which you want to append the retrieved key. The file will be created if it does not exist.

If the command does not result in an error, you have successfully retrieved a keytab of HTTP/client.idm.example.com as user01.

26.8. ENSURING THE PRESENCE OF A KERBEROS PRINCIPAL ALIAS OF A SERVICE USING AN ANSIBLE PLAYBOOK

In some scenarios, it is beneficial for IdM administrator to enable IdM users, hosts, or services to authenticate against Kerberos applications using a Kerberos principal alias. These scenarios include:

- The user name changed, but the user should be able to log into the system using both the previous and new user names.
- The user needs to log in using the email address even if the IdM Kerberos realm differs from the email domain.

Follow this procedure to create the principal alias of **HTTP/mycompany.idm.example.com** for the HTTP service running on **client.idm.example.com**.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You have set up an HTTP service on your host.
- You have enrolled the HTTP service into IdM.
- The host on which you have set up HTTP is an IdM client.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-principal-present.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-member-principal-present.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-member-principal-present-copy.yml

- 4. Open the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-principal-present-copy.yml Ansible playbook file for editing.
- 5. Adapt the file by changing the following:
 - The IdM administrator password specified by the **ipaadmin password** variable.

- The name of the service specified by the **name** variable. This is the canonical principal name of the service. In the current example, it is **HTTP/client.idm.example.com**.
- The Kerberos principal alias specified by the **principal** variable. This is the alias you want to
 add to the service defined by the **name** variable. In the current example, it is
 host/mycompany.idm.example.com.
- The name of the task specified by the **name** variable in the **tasks** section.
 After being adapted for the current example, the copied file looks like this:

- name: Service member principal present

hosts: ipaserver

vars files:

 $\hbox{-/home/user_name/MyPlaybooks/secret.yml}$

tasks

- name: Service HTTP/client.idm.example.com member principals

host/mycompany.idm.exmaple.com present

ipaservice:

ipaadmin_password: "{{ ipaadmin_password }}"
name: HTTP/client.idm.example.com

principal:

- host/mycompany.idm.example.com

action: member

- 6. Save the file.
- 7. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-member-principal-present-copy.yml

If running the playbook results in 0 unreachable and 0 failed tasks, you have successfully created the **host/mycompany.idm.example.com** Kerberos principal for the **HTTP/client.idm.example.com** service.

Additional resources

Managing Kerberos principal aliases for users, hosts, and services

26.9. ENSURING THE ABSENCE OF AN HTTP SERVICE IN IDM USING AN ANSIBLE PLAYBOOK

Follow this procedure to unenroll a service from IdM. More specifically, it describes how to use an Ansible playbook to ensure the absence of an HTTP server named **HTTP/client.idm.example.com** in IdM.

Prerequisites

• You have the IdM administrator password.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-absent.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-is-absent.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-is-absent-copy.yml

- 4. Open the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-absent-copy.yml Ansible playbook file for editing.
- 5. Adapt the file by changing the following:
 - The IdM administrator password defined by the **ipaadmin_password** variable.
 - The Kerberos principal of the HTTP service, as defined by the **name** variable of the **ipaservice** task.

After being adapted for the current example, the copied file looks like this:

- name: Playbook to manage IPA service.

hosts: ipaserver gather_facts: false

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

Ensure service is absent

- ipaservice:

ipaadmin_password: "{{ ipaadmin_password }}"

name: HTTP/client.idm.example.com

state: absent

- 6. Save and exit the file.
- 7. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-is-absent-copy.yml

Verification

1. Log into the IdM Web UI as IdM administrator.

2. Navigate to **Identity** → **Services**.

If you cannot see the HTTP/client.idm.example.com@IDM.EXAMPLE.COM service in the Services list, you have successfully ensured its absence in IdM.

26.10. ADDITIONAL RESOURCES

- See the **README-service.md** Markdown file in the /usr/share/doc/ansible-freeipa/ directory.
- See sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/config directory.

CHAPTER 27. MANAGING GLOBAL DNS CONFIGURATION IN IDM USING ANSIBLE PLAYBOOKS

Using the Red Hat Ansible Engine **dnsconfig** module, you can configure global configuration for Identity Management (IdM) DNS. Settings defined in global DNS configuration are applied to all IdM DNS servers. However, the global configuration has lower priority than the configuration for a specific IdM DNS zone.

The **dnsconfig** module supports the following variables:

- The global forwarders, specifically their IP addresses and the port used for communication.
- The global forwarding policy: only, first, or none. For more details on these types of DNS forward policies, see DNS forward policies in IdM.
- The synchronization of forward lookup and reverse lookup zones.

Prerequisites

- DNS service is installed on the IdM server. For more information about how to install an IdM server with integrated DNS, see one of the following links:
 - Installing an IdM server: With integrated DNS, with an integrated CA as the root CA
 - Installing an IdM server: With integrated DNS, with an external CA as the root CA
 - Installing an IdM server: With integrated DNS, without a CA

This chapter includes the following sections:

- How IdM ensures that global forwarders from /etc/resolv.conf are not removed by NetworkManager
- Ensuring the presence of a DNS global forwarder in IdM using Ansible
- Ensuring the absence of a DNS global forwarder in IdM using Ansible
- The **action: member** option in ipadnsconfig ansible-freeipa modules
- An introduction to DNS forward policies in IdM
- Using an Ansible playbook to ensure that the forward first policy is set in IdM DNS global configuration
- Using an Ansible playbook to ensure that global forwarders are disabled in IdM DNS
- Using an Ansible playbook to ensure that synchronization of forward and reverse lookup zones is disabled in IdM DNS

27.1. HOW IDM ENSURES THAT GLOBAL FORWARDERS FROM /ETC/RESOLV.CONF ARE NOT REMOVED BY NETWORKMANAGER

Installing Identity Management (IdM) with integrated DNS configures the /etc/resolv.conf file to point to the 127.0.0.1 localhost address:

Generated by NetworkManager search idm.example.com nameserver 127.0.0.1

In certain environments, such as networks that use **Dynamic Host Configuration Protocol** (DHCP), the **NetworkManager** service may revert changes to the /etc/resolv.conf file. To make the DNS configuration persistent, the IdM DNS installation process also configures the **NetworkManager** service in the following way:

 The DNS installation script creates an /etc/NetworkManager/conf.d/zzz-ipa.conf NetworkManager configuration file to control the search order and DNS server list:

auto-generated by IPA installer [main] dns=default [global-dns] searches=\$DOMAIN [global-dns-domain-*] servers=127.0.0.1

2. The **NetworkManager** service is reloaded, which always creates the /etc/resolv.conf file with the settings from the last file in the /etc/NetworkManager/conf.d/ directory. This is in this case the zzz-ipa.conf file.



IMPORTANT

Do not modify the /etc/resolv.conf file manually.

27.2. ENSURING THE PRESENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure the presence of a DNS global forwarder in IdM. In the example procedure below, the IdM administrator ensures the presence of a DNS global forwarder to a DNS server with an Internet Protocol (IP) v4 address of **7.7.9.9** and IP v6 address of **2001:db8::1:0** on port **53**.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.

- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the **forwarders-absent.yml** Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-presence-of-a-global-forwarder.yml
- 4. Open the **ensure-presence-of-a-global-forwarder.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to ensure the presence of a global forwarder in IdM DNS**.
 - b. In the tasks section, change the name of the task to Ensure the presence of a DNS global forwarder to 7.7.9.9 and 2001:db8::1:0 on port 53.
 - c. In the **forwarders** section of the **ipadnsconfig** portion:
 - i. Change the first **ip_address** value to the IPv4 address of the global forwarder: **7.7.9.9**.
 - ii. Change the second **ip_address** value to the IPv6 address of the global forwarder: **2001:db8::1:0**.
 - iii. Verify the **port** value is set to **53**.
 - d. Change the **state** to **present**.This the modified Ansible playbook file for the current example:

 name: Playbook to ensure the presence of a global forwarder in IdM DNS hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks:

- name: Ensure the presence of a DNS global forwarder to 7.7.9.9 and 2001:db8::1:0 on port 53

ipadnsconfig: forwarders:

- ip_address: 7.7.9.9- ip_address: 2001:db8::1:0

port: 53 state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-presence-of-a-global-forwarder.yml

Additional resources

• The README-dnsconfig.md file in the /usr/share/doc/ansible-freeipa/ directory

27.3. ENSURING THE ABSENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure the absence of a DNS global forwarder in IdM. In the example procedure below, the IdM administrator ensures the absence of a DNS global forwarder with an Internet Protocol (IP) v4 address of **8.8.6.6** and IP v6 address of **2001:4860:4860:4860** on port **53**.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com 3. Make a copy of the forwarders-absent.yml Ansible playbook file. For example:

\$ cp forwarders-absent.yml ensure-absence-of-a-global-forwarder.yml

- 4. Open the ensure-absence-of-a-global-forwarder.yml file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to ensure the absence of a global forwarder in IdM DNS**.
 - b. In the tasks section, change the name of the task to Ensure the absence of a DNS global forwarder to 8.8.6.6 and 2001:4860:4860:8800 on port 53.
 - c. In the **forwarders** section of the **ipadnsconfig** portion:
 - i. Change the first **ip_address** value to the IPv4 address of the global forwarder: **8.8.6.6**.
 - ii. Change the second **ip_address** value to the IPv6 address of the global forwarder: **2001:4860:4860::8800**.
 - iii. Verify the **port** value is set to **53**.
 - d. Set the **action** variable to **member**.
 - e. Verify the state is set to absent.

This the modified Ansible playbook file for the current example:

 name: Playbook to ensure the absence of a global forwarder in IdM DNS hosts: ipaserver

vars files:

- /home/user name/MyPlaybooks/secret.yml

tasks:

- name: Ensure the absence of a DNS global forwarder to 8.8.6.6 and

2001:4860:4860::8800 on port 53

ipadnsconfig: forwarders:

- ip_address: 8.8.6.6

- ip_address: 2001:4860:4860::8800

port: 53 action: member state: absent



IMPORTANT

If you only use the **state: absent** option in your playbook without also using **action: member**, the playbook fails.

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-absence-of-a-global-forwarder.yml

Additional resources

- The README-dnsconfig.md file in the /usr/share/doc/ansible-freeipa/ directory
- The action: member option in ipadnsconfig ansible-freeipa modules

27.4. THE ACTION: MEMBER OPTION IN IPADNSCONFIG ANSIBLE-FREEIPA MODULES

Excluding global forwarders in Identity Management (IdM) by using the **ansible-freeipa ipadnsconfig** module requires using the **action: member** option in addition to the **state: absent** option. If you only use **state: absent** in your playbook without also using **action: member**, the playbook fails. Consequently, to remove all global forwarders, you must specify all of them individually in the playbook. In contrast, the **state: present** option does not require **action: member**.

The following table provides configuration examples for both adding and removing DNS global forwarders that demonstrate the correct use of the action: member option. The table shows, in each line:

- The global forwarders configured before executing a playbook
- An excerpt from the playbook
- The global forwarders configured after executing the playbook

Table 27.1. ipadnsconfig management of global forwarders

Forwarders before	Playbook excerpt	Forwarders after
8.8.6.6	[] tasks: - name: Ensure the presence of DNS global forwarder 8.8.6.7 ipadnsconfig: forwarders: - ip_address: 8.8.6.7 state: present	8.8.6.7
8.8.6.6	[] tasks: - name: Ensure the presence of DNS global forwarder 8.8.6.7 ipadnsconfig: forwarders: - ip_address: 8.8.6.7 action: member state: present	8.8.6.6, 8.8.6.7

Forwarders before	Playbook excerpt	Forwarders after
8.8.6.6, 8.8.6.7	[] tasks: - name: Ensure the absence of DNS global forwarder 8.8.6.7 ipadnsconfig: forwarders: - ip_address: 8.8.6.7 state: absent	Trying to execute the playbook results in an error. The original configuratio n - 8.8.6.6, 8.8.6.7 - is left unchanged.
8.8.6.6, 8.8.6.7	[] tasks: - name: Ensure the absence of DNS global forwarder 8.8.6.7 ipadnsconfig: forwarders: - ip_address: 8.8.6.7 action: member state: absent	8.8.6.6

27.5. DNS FORWARD POLICIES IN IDM

IdM supports the **first** and **only** standard BIND forward policies, as well as the **none** IdM-specific forward policy.

Forward first (default)

The IdM BIND service forwards DNS queries to the configured forwarder. If a query fails because of a server error or timeout, BIND falls back to the recursive resolution using servers on the Internet. The **forward first** policy is the default policy, and it is suitable for optimizing DNS traffic.

Forward only

The IdM BIND service forwards DNS queries to the configured forwarder. If a query fails because of a server error or timeout, BIND returns an error to the client. The **forward only** policy is recommended for environments with split DNS configuration.

None (forwarding disabled)

DNS queries are not forwarded with the **none** forwarding policy. Disabling forwarding is only useful as a zone-specific override for global forwarding configuration. This option is the IdM equivalent of specifying an empty list of forwarders in BIND configuration.



NOTE

You cannot use forwarding to combine data in IdM with data from other DNS servers. You can only forward queries for specific subzones of the primary zone in IdM DNS.

By default, the BIND service does not forward queries to another server if the queried DNS name belongs to a zone for which the IdM server is authoritative. In such a situation, if the queried DNS name cannot be found in the IdM database, the **NXDOMAIN** answer is returned. Forwarding is not used.

Example 27.1. Example Scenario

The IdM server is authoritative for the **test.example**. DNS zone. BIND is configured to forward queries to the DNS server with the **192.0.2.254** IP address.

When a client sends a query for the **nonexistent.test.example.** DNS name, BIND detects that the IdM server is authoritative for the **test.example.** zone and does not forward the query to the **192.0.2.254.** server. As a result, the DNS client receives the **NXDomain** error message, informing the user that the queried domain does not exist.

27.6. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT THE FORWARD FIRST POLICY IS SET IN IDM DNS GLOBAL CONFIGURATION

Follow this procedure to use an Ansible playbook to ensure that global forwarding policy in IdM DNS is set to **forward first**.

If you use the **forward first** DNS forwarding policy, DNS queries are forwarded to the configured forwarder. If a query fails because of a server error or timeout, BIND falls back to the recursive resolution using servers on the Internet. The forward first policy is the default policy. It is suitable for traffic optimization.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.
- Your IdM environment contains an integrated DNS server.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig

2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **set-configuration.yml** Ansible playbook file. For example:

\$ cp set-configuration.yml set-forward-policy-to-first.yml

- 4. Open the **set-forward-policy-to-first.yml** file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsconfig** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the forward_policy variable to first.
 Delete all the other lines of the original playbook that are irrelevant. This is the modified Ansible playbook file for the current example:

- name: Playbook to set global forwarding policy to first

hosts: ipaserver become: true

tasks:

- name: Set global forwarding policy to first.

ipadnsconfig:

ipaadmin_password: "{{ ipaadmin_password }}"

forward policy: first

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file set-forward-policy-to-first.yml

Additional resources

- DNS forward policies in IdM
- The README-dnsconfig.md file in the /usr/share/doc/ansible-freeipa/ directory
- For more sample playbooks, see the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory.

27.7. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT GLOBAL FORWARDERS ARE DISABLED IN IDM DNS

Follow this procedure to use an Ansible playbook to ensure that global forwarders are disabled in IdM DNS. The disabling is done by setting the **forward policy** variable to **none**.

Disabling global forwarders causes DNS queries not to be forwarded. Disabling forwarding is only useful as a zone-specific override for global forwarding configuration. This option is the IdM equivalent of specifying an empty list of forwarders in BIND configuration.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.
- Your IdM environment contains an integrated DNS server.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the disable-global-forwarders.yml Ansible playbook file. For example:
 - \$ cp disable-global-forwarders.yml disable-global-forwarders-copy.yml
- 4. Open the disable-global-forwarders-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsconfig** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **forward_policy** variable to **none**.
 This is the modified Ansible playbook file for the current example:

- name: Playbook to disable global DNS forwarders

hosts: ipaserver become: true

tasks:

- name: Disable global forwarders.

ipadnsconfig:

ipaadmin password: "{{ ipaadmin password }}"

forward policy: none

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file disable-global-forwarders-copy.yml

Additional resources

- DNS forward policies in IdM
- The README-dnsconfig.md file in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory

27.8. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT SYNCHRONIZATION OF FORWARD AND REVERSE LOOKUP ZONES IS DISABLED IN IDM DNS

Follow this procedure to use an Ansible playbook to ensure that forward and reverse lookup zones are not synchronized in IdM DNS.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.
- Your IdM environment contains an integrated DNS server.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig

2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the disallow-reverse-sync.yml Ansible playbook file. For example:

\$ cp disallow-reverse-sync.yml disallow-reverse-sync-copy.yml

- 4. Open the disallow-reverse-sync-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsconfig** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **allow_sync_ptr** variable to **no**.

 This is the modified Ansible playbook file for the current example:

- name: Playbook to disallow reverse record synchronization

hosts: ipaserver become: true

tasks:

- name: Disallow reverse record synchronization.

ipadnsconfig:

ipaadmin_password: "{{ ipaadmin_password }}"

allow_sync_ptr: no

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file disallow-reverse-sync-copy.yml

Additional resources

- The **README-dnsconfig.md** file in the /usr/share/doc/ansible-freeipa/ directory
- For more sample playbooks, see the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory.

CHAPTER 28. USING ANSIBLE PLAYBOOKS TO MANAGE IDM DNS ZONES

As Identity Management (IdM) administrator, you can manage how IdM DNS zones work using the **dnszone** module available in the **ansible-freeipa** package.

- What DNS zone types are supported in IdM
- What DNS attributes you can configure in IdM
- How to use an Ansible playbook to create a primary zone in IdM DNS
- How to use an Ansible playbook to ensure the presence of a primary IdM DNS zone with multiple variables
- How to use an Ansible playbook to ensure the presence of a zone for reverse DNS lookup when an IP address is given

Prerequisites

• DNS service is installed on the IdM server. For more information about how to use Ansible to install an IdM server with integrated DNS, see Installing an Identity Management server using an Ansible playbook.

28.1. SUPPORTED DNS ZONE TYPES

This section describes the two types of DNS zones that Identity Management (IdM) supports, *primary* and *forward* zones, and includes an example scenario for DNS forwarding.



NOTE

This section uses the BIND terminology for zone types, which is different from the terminology used for Microsoft Windows DNS. Primary zones in BIND serve the same purpose as *forward lookup zones* and *reverse lookup zones* in Microsoft Windows DNS. Forward zones in BIND serve the same purpose as *conditional forwarders* in Microsoft Windows DNS.

Primary DNS zones

Primary DNS zones contain authoritative DNS data and can accept dynamic DNS updates. This behavior is equivalent to the **type master** setting in standard BIND configuration. You can manage primary zones by using the **ipa dnszone-*** commands.

In compliance with standard DNS rules, every primary zone must contain **start of authority** (SOA) and **nameserver** (NS) records. IdM generates these records automatically when the DNS zone is created, but you must copy the NS records manually to the parent zone to create proper delegation.

In accordance with standard BIND behavior, queries for names for which the server is not authoritative are forwarded to other DNS servers. These DNS servers, also known as forwarders, may or may not be authoritative for the query.

Example 28.1. Example scenario for DNS forwarding

The IdM server contains the **test.example.** primary zone. This zone contains an NS delegation record for the **sub.test.example.** name. In addition, the **test.example.** zone is configured with the **192.0.2.254** forwarder IP address for the **sub.text.example** subzone.

A client querying the name **nonexistent.test.example.** receives the **NXDomain** answer, and no forwarding occurs because the IdM server is authoritative for this name.

On the other hand, querying for the **host1.sub.test.example.** name is forwarded to the configured forwarder **192.0.2.254** because the IdM server is not authoritative for this name.

Forward DNS zones

From the perspective of IdM, forward DNS zones do not contain any authoritative data. In fact, a forward "zone" usually only contains two pieces of information:

- A domain name
- The IP address of a DNS server associated with the domain

All queries for names belonging to the domain defined are forwarded to the specified IP address. This behavior is equivalent to the **type forward** setting in standard BIND configuration. You can manage forward zones by using the **ipa dnsforwardzone-*** commands.

Forward DNS zones are especially useful in the context of IdM-Active Directory (AD) trusts. If the IdM DNS server is authoritative for the **idm.example.com** zone and the AD DNS server is authoritative for the **ad.example.com** zone, then **ad.example.com** is a DNS forward zone for the **idm.example.com** primary zone. That means that when a query comes from an IdM client for the IP address of **somehost.ad.example.com**, the IdM DNS server forwards the query to an AD domain controller specified in the **ad.example.com** IdM DNS forward zone.

28.2. CONFIGURATION ATTRIBUTES OF PRIMARY IDM DNS ZONES

Identity Management (IdM) creates a new zone with certain default configuration, such as the refresh periods, transfer settings, or cache settings. In IdM DNS zone attributes, you can find the attributes of the default zone configuration that you can modify using one of the following options:

- The **dnszone-mod** command on the command line (CLI). For more information, see Editing the configuration of a primary DNS zone in IdM CLI.
- The IdM Web UI. For more information, see Editing the configuration of a primary DNS zone in IdM Web UI.
- An Ansible playbook that uses the **ipadnszone** module. For more information, see Using Ansible playbooks to manage IdM DNS zones.

Along with setting the actual information for the zone, the settings define how the DNS server handles the *start of authority* (SOA) record entries and how it updates its records from the DNS name server.

Table 28.1. IdM DNS zone attributes

Attribute	ansible-freeipa variable	Description
Authoritative name server	name_server	Sets the domain name of the primary DNS name server, also known as SOA MNAME.
		By default, each IdM server advertises itself in the SOA MNAME field. Consequently, the value stored in LDAP using name-server is ignored.
Administrator e- mail address	admin_email	Sets the email address to use for the zone administrator. This defaults to the root account on the host.
SOA serial	serial	Sets a serial number in the SOA record. Note that IdM sets the version number automatically and users are not expected to modify it.
SOA refresh	refresh	Sets the interval, in seconds, for a secondary DNS server to wait before requesting updates from the primary DNS server.
SOA retry	retry	Sets the time, in seconds, to wait before retrying a failed refresh operation.
SOA expire	expire	Sets the time, in seconds, that a secondary DNS server will try to perform a refresh update before ending the operation attempt.
SOA minimum	minimum	Sets the time to live (TTL) value in seconds for negative caching according to RFC 2308.
SOA time to live	ttl	Sets TTL in seconds for records at zone apex. In zone example.com , for example, all records (A, NS, or SOA) under name example.com are configured, but no other domain names, like test.example.com , are affected.
Default time to live	default_ttl	Sets the default time to live (TTL) value in seconds for negative caching for all values in a zone that never had an individual TTL value set before. Requires a restart of the named-pkcs11 service on all IdM DNS servers after changes to take effect.
BIND update policy	update_policy	Sets the permissions allowed to clients in the DNS zone.
Dynamic update	dynamic_updat e=TRUE FALSE	Enables dynamic updates to DNS records for clients. Note that if this is set to false, IdM client machines will not be able to add or update their IP address.

Attribute	ansible-freeipa variable	Description
Allow transfer	allow_transfer=s tring	Gives a list of IP addresses or network names which are allowed to transfer the given zone, separated by semicolons (;). Zone transfers are disabled by default. The default allow_transfer value is none.
Allow query	allow_query	Gives a list of IP addresses or network names which are allowed to issue DNS queries, separated by semicolons (;).
Allow PTR sync	allow_sync_ptr=	Sets whether A or AAAA records (forward records) for the zone will be automatically synchronized with the PTR (reverse) records.
Zone forwarders	forwarder=IP_add ress	Specifies a forwarder specifically configured for the DNS zone. This is separate from any global forwarders used in the IdM domain. To specify multiple forwarders, use the option multiple times.
Forward policy	forward_policy= none only first	Specifies the forward policy. For information about the supported policies, see DNS forward policies in IdM.

Additional resources

• See the **README-dnszone.md** file in the /usr/share/doc/ansible-freeipa/ directory.

28.3. USING ANSIBLE TO CREATE A PRIMARY ZONE IN IDM DNS

Follow this procedure to use an Ansible playbook to ensure that a primary DNS zone exists. In the example used in the procedure below, you ensure the presence of the **zone.idm.example.com** DNS zone.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnszone

2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **dnszone-present.yml** Ansible playbook file. For example:

\$ cp dnszone-present.yml dnszone-present-copy.yml

- 4. Open the dnszone-present-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnszone** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **zone_name** variable to **zone.idm.example.com**.

 This is the modified Ansible playbook file for the current example:

- name: Ensure dnszone present

hosts: ipaserver become: true

tasks:

- name: Ensure zone is present.

ipadnszone:

ipaadmin_password: "{{ ipaadmin_password }}"

zone name: zone.idm.example.com

state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file dnszone-present-copy.yml

Additional resources

- Supported DNS zone types
- The README-dnszone.md file in the /usr/share/doc/ansible-freeipa/ directory
- Sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory

28.4. USING AN ANSIBLE PLAYBOOK TO ENSURE THE PRESENCE OF A PRIMARY DNS ZONE IN IDM WITH MULTIPLE VARIABLES

Follow this procedure to use an Ansible playbook to ensure that a primary DNS zone exists. In the example used in the procedure below, an IdM administrator ensures the presence of the **zone.idm.example.com** DNS zone. The Ansible playbook configures multiple parameters of the zone.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

Procedure

- Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnszone
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:
 - [ipaserver] server.idm.example.com
- 3. Make a copy of the dnszone-all-params.yml Ansible playbook file. For example:
 - \$ cp dnszone-all-params.yml dnszone-all-params-copy.yml
- 4. Open the dnszone-all-params-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnszone** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **zone_name** variable to **zone.idm.example.com**.
 - Set the **allow_sync_ptr** variable to true if you want to allow the synchronization of forward and reverse records, that is the synchronization of A and AAAA records with PTR records.
 - Set the **dynamic_update** variable to true to enable IdM client machines to add or update their IP addresses.

• Set the **dnssec** variable to true to allow inline DNSSEC signing of records in the zone.



WARNING

DNSSEC is only available as Technology Preview in IdM.

- Set the **allow_transfer** variable to the IP addresses of secondary name servers in the zone.
- Set the **allow_query** variable to the IP addresses or networks that are allowed to issue queries.
- Set the **forwarders** variable to the IP addresses of global forwarders.
- Set the **serial** variable to the SOA record serial number.
- Define the refresh, retry, expire, minimum, ttl, and default_ttl values for DNS records in the zone.
- Define the NSEC3PARAM record for the zone using the **nsec3param_rec** variable.
- Set the **skip_overlap_check** variable to true to force DNS creation even if it overlaps with an existing zone.
- Set the skip_nameserver_check to true to force DNS zone creation even if the nameserver is not resolvable.

This is the modified Ansible playbook file for the current example:

```
- name: Ensure dnszone present
hosts: ipaserver
become: true
tasks:
- name: Ensure zone is present.
  ipadnszone:
   ipaadmin_password: "{{ ipaadmin_password }}"
   zone_name: zone.idm.example.com
   allow_sync_ptr: true
   dynamic_update: true
   dnssec: true
   allow transfer:
    - 1.1.1.1
    - 2.2.2.2
   allow_query:
    - 1.1.1.1
    -2.2.2.2
   forwarders:
    - ip_address: 8.8.8.8
    - ip_address: 8.8.4.4
     port: 52
```

serial: 1234

refresh: 3600 retry: 900

expire: 1209600 minimum: 3600

ttl: 60

default_ttl: 90

name server: server.idm.example.com.

admin_email: admin.admin@idm.example.com nsec3param_rec: "1 7 100 0123456789abcdef"

skip_overlap_check: true skip_nameserver_check: true

state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file dnszone-all-params-copy.yml

Additional resources

- See Supported DNS zone types.
- See Configuration attributes of primary IdM DNS zones .
- See the **README-dnszone.md** file in the /usr/share/doc/ansible-freeipa/ directory.
- See sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory.

28.5. USING AN ANSIBLE PLAYBOOK TO ENSURE THE PRESENCE OF A ZONE FOR REVERSE DNS LOOKUP WHEN AN IP ADDRESS IS GIVEN

Follow this procedure to use an Ansible playbook to ensure that a reverse DNS zone exists. In the example used in the procedure below, an IdM administrator ensures the presence of a reverse DNS lookup zone using the IP address and prefix length of an IdM host.

Providing the prefix length of the IP address of your DNS server using the **name_from_ip** variable allows you to control the zone name. If you do not state the prefix length, the system queries DNS servers for zones and, based on the **name_from_ip** value of **192.168.1.2**, the query can return any of the following DNS zones:

- 1.168.192.in-addr.arpa.
- 168.192.in-addr.arpa.
- 192.in-addr.arpa.

Because the zone returned by the query might not be what you expect, **name_from_ip** can only be used with the **state** option set to **present** to prevent accidental removals of zones.

Prerequisites

• You have configured your Ansible control node to meet the following requirements:

- You are using Ansible version 2.14 or later.
- You have installed the **ansible-freeipa** package.
- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnszone

2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the dnszone-reverse-from-ip.yml Ansible playbook file. For example:

- 4. Open the dnszone-reverse-from-ip-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnszone** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name_from_ip** variable to the IP of your IdM nameserver, and provide its prefix length.

This is the modified Ansible playbook file for the current example:

--- name: Ensure dnszone present hosts: ipaserver become: true

tasks:

- name: Ensure zone for reverse DNS lookup is present. ipadnszone: ipaadmin_password: "{{ ipaadmin_password }}" name_from_ip: 192.168.1.2/24 state: present register: result name: Display inferred zone name.
 debug:

msg: "Zone name: {{ result.dnszone.name }}"

The playbook creates a zone for reverse DNS lookup from the **192.168.1.2** IP address and its prefix length of 24. Next, the playbook displays the resulting zone name.

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file dnszone-reverse-from-ip-copy.yml

Additional resources

- Supported DNS zone types
- The **README-dnszone.md** file in the /usr/share/doc/ansible-freeipa/ directory.
- Sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory

CHAPTER 29. USING ANSIBLE TO MANAGE DNS LOCATIONS IN IDM

As Identity Management (IdM) administrator, you can manage IdM DNS locations using the **location** module available in the **ansible-freeipa** package.

- DNS-based service discovery
- Deployment considerations for DNS locations
- DNS time to live (TTL)
- Using Ansible to ensure an IdM location is present
- Using Ansible to ensure an IdM location is absent

29.1. DNS-BASED SERVICE DISCOVERY

DNS-based service discovery is a process in which a client uses the DNS protocol to locate servers in a network that offer a specific service, such as **LDAP** or **Kerberos**. One typical type of operation is to allow clients to locate authentication servers within the closest network infrastructure, because they provide a higher throughput and lower network latency, lowering overall costs.

The major advantages of service discovery are:

- No need for clients to be explicitly configured with names of nearby servers.
- DNS servers are used as central providers of policy. Clients using the same DNS server have access to the same policy about service providers and their preferred order.

In an Identity Management (IdM) domain, DNS service records (SRV records) exist for **LDAP**, **Kerberos**, and other services. For example, the following command queries the DNS server for hosts providing a TCP-based **Kerberos** service in an IdM DNS domain:

Example 29.1. DNS location independent results

\$ dig -t SRV +short _kerberos._tcp.idm.example.com 0 100 88 idmserver-01.idm.example.com. 0 100 88 idmserver-02.idm.example.com.

The output contains the following information:

- **0** (priority): Priority of the target host. A lower value is preferred.
- **100** (weight). Specifies a relative weight for entries with the same priority. For further information, see RFC 2782, section 3.
- 88 (port number): Port number of the service.
- Canonical name of the host providing the service.

In the example, the two host names returned have the same priority and weight. In this case, the client uses a random entry from the result list.

When the client is, instead, configured to query a DNS server that is configured in a DNS location, the output differs. For IdM servers that are assigned to a location, tailored values are returned. In the example below, the client is configured to query a DNS server in the location **germany**:

Example 29.2. DNS location-based results

\$ dig -t SRV +short _kerberos._tcp.idm.example.com _kerberos._tcp.germany._locations.idm.example.com.
0 100 88 idmserver-01.idm.example.com.
50 100 88 idmserver-02.idm.example.com.

The IdM DNS server automatically returns a DNS alias (CNAME) pointing to a DNS location specific SRV record which prefers local servers. This CNAME record is shown in the first line of the output. In the example, the host **idmserver-01.idm.example.com** has the lowest priority value and is therefore preferred. The **idmserver-02.idm.example.com** has a higher priority and thus is used only as backup for cases when the preferred host is unavailable.

29.2. DEPLOYMENT CONSIDERATIONS FOR DNS LOCATIONS

Identity Management (IdM) can generate location-specific service (SRV) records when using the integrated DNS. Because each IdM DNS server generates location-specific SRV records, you have to install at least one IdM DNS server in each DNS location.

The client's affinity to a DNS location is only defined by the DNS records received by the client. For this reason, you can combine IdM DNS servers with non-IdM DNS consumer servers and recursors if the clients doing DNS service discovery resolve location-specific records from IdM DNS servers.

In the majority of deployments with mixed IdM and non-IdM DNS services, DNS recursors select the closest IdM DNS server automatically by using round-trip time metrics. Typically, this ensures that clients using non-IdM DNS servers are getting records for the nearest DNS location and thus use the optimal set of IdM servers.

29.3. DNS TIME TO LIVE (TTL)

Clients can cache DNS resource records for an amount of time that is set in the zone's configuration. Because of this caching, a client might not be able to receive the changes until the time to live (TTL) value expires. The default TTL value in Identity Management (IdM) is **1 day**.

If your client computers roam between sites, you should adapt the TTL value for your IdM DNS zone. Set the value to a lower value than the time clients need to roam between sites. This ensures that cached DNS entries on the client expire before they reconnect to another site and thus query the DNS server to refresh location-specific SRV records.

Additional resources

• Configuration attributes of primary IdM DNS zones

29.4. USING ANSIBLE TO ENSURE AN IDM LOCATION IS PRESENT

As a system administrator of Identity Management (IdM), you can configure IdM DNS locations to allow clients to locate authentication servers within the closest network infrastructure.

The following procedure describes how to use an Ansible playbook to ensure a DNS location is present in IdM. The example describes how to ensure that the **germany** DNS location is present in IdM. As a result, you can assign particular IdM servers to this location so that local IdM clients can use them to reduce server response time.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You understand the deployment considerations for DNS locations.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **location-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/location/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/location/location-present.yml location-present-copy.yml

- 3. Open the **location-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipalocation** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the location.

This is the modified Ansible playbook file for the current example:

- name: location present example

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml tasks:

- name: Ensure that the "germany" location is present

ipalocation:

ipaadmin_password: "{{ ipaadmin_password }}"
name: germany

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory location-present-copy.yml

Additional resources

- Assigning an IdM server to a DNS location using the IdM Web UI
- Assigning an IdM server to a DNS location using the IdM CLI

29.5. USING ANSIBLE TO ENSURE AN IDM LOCATION IS ABSENT

As a system administrator of Identity Management (IdM), you can configure IdM DNS locations to allow clients to locate authentication servers within the closest network infrastructure.

The following procedure describes how to use an Ansible playbook to ensure that a DNS location is absent in IdM. The example describes how to ensure that the **germany** DNS location is absent in IdM. As a result, you cannot assign particular IdM servers to this location and local IdM clients cannot use them.

Prerequisites

- You know the IdM administrator password.
- No IdM server is assigned to the **germany** DNS location.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- The example assumes that you have created and configured the ~/MyPlaybooks/ directory as a central location to store copies of sample playbooks.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **location-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/location/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/location/location-absent.yml location-absent-copy.yml

- 3. Open the **location-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipalocation** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the DNS location.
 - Make sure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

- name: location absent example

hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure that the "germany" location is absent ipalocation:

ipaadmin_password: "{{ ipaadmin_password }}"

name: germany state: absent

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory location-absent-copy.yml

29.6. ADDITIONAL RESOURCES

- See the **README-location.md** file in the /usr/share/doc/ansible-freeipa/ directory.
- See sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/location directory.

CHAPTER 30. MANAGING DNS FORWARDING IN IDM

Follow these procedures to configure DNS global forwarders and DNS forward zones in the Identity Management (IdM) Web UI, the IdM CLI, and using Ansible:

- The two roles of an IdM DNS server
- DNS forward policies in IdM
- Adding a global forwarder in the IdM Web UI
- Adding a global forwarder in the CLI
- Adding a DNS Forward Zone in the IdM Web UI
- Adding a DNS Forward Zone in the CLI
- Establishing a DNS Global Forwarder in IdM using Ansible
- Ensuring the presence of a DNS global forwarder in IdM using Ansible
- Ensuring the absence of a DNS global forwarder in IdM using Ansible
- Ensuring DNS Global Forwarders are disabled in IdM using Ansible
- Ensuring the presence of a DNS Forward Zone in IdM using Ansible
- Ensuring a DNS Forward Zone has multiple forwarders in IdM using Ansible
- Ensuring a DNS Forward Zone is disabled in IdM using Ansible
- Ensuring the absence of a DNS Forward Zone in IdM using Ansible

30.1. THE TWO ROLES OF AN IDM DNS SERVER

DNS forwarding affects how a DNS service answers DNS queries. By default, the Berkeley Internet Name Domain (BIND) service integrated with IdM acts as both an *authoritative* and a *recursive* DNS server:

Authoritative DNS server

When a DNS client queries a name belonging to a DNS zone for which the IdM server is authoritative, BIND replies with data contained in the configured zone. Authoritative data always takes precedence over any other data.

Recursive DNS server

When a DNS client queries a name for which the IdM server is not authoritative, BIND attempts to resolve the query using other DNS servers. If forwarders are not defined, BIND asks the root servers on the Internet and uses a recursive resolution algorithm to answer the DNS query.

In some cases, it is not desirable to let BIND contact other DNS servers directly and perform the recursion based on data available on the Internet. You can configure BIND to use another DNS server, a *forwarder*, to resolve the query.

When you configure BIND to use a forwarder, queries and answers are forwarded back and forth between the IdM server and the forwarder, and the IdM server acts as the DNS cache for non-authoritative data.

30.2. DNS FORWARD POLICIES IN IDM

IdM supports the **first** and **only** standard BIND forward policies, as well as the **none** IdM-specific forward policy.

Forward first (default)

The IdM BIND service forwards DNS queries to the configured forwarder. If a query fails because of a server error or timeout, BIND falls back to the recursive resolution using servers on the Internet. The **forward first** policy is the default policy, and it is suitable for optimizing DNS traffic.

Forward only

The IdM BIND service forwards DNS queries to the configured forwarder. If a query fails because of a server error or timeout, BIND returns an error to the client. The **forward only** policy is recommended for environments with split DNS configuration.

None (forwarding disabled)

DNS queries are not forwarded with the **none** forwarding policy. Disabling forwarding is only useful as a zone-specific override for global forwarding configuration. This option is the IdM equivalent of specifying an empty list of forwarders in BIND configuration.



NOTE

You cannot use forwarding to combine data in IdM with data from other DNS servers. You can only forward queries for specific subzones of the primary zone in IdM DNS.

By default, the BIND service does not forward queries to another server if the queried DNS name belongs to a zone for which the IdM server is authoritative. In such a situation, if the queried DNS name cannot be found in the IdM database, the **NXDOMAIN** answer is returned. Forwarding is not used.

Example 30.1. Example Scenario

The IdM server is authoritative for the **test.example.** DNS zone. BIND is configured to forward queries to the DNS server with the **192.0.2.254** IP address.

When a client sends a query for the **nonexistent.test.example**. DNS name, BIND detects that the IdM server is authoritative for the **test.example**. zone and does not forward the query to the **192.0.2.254**. server. As a result, the DNS client receives the **NXDomain** error message, informing the user that the queried domain does not exist.

30.3. ADDING A GLOBAL FORWARDER IN THE IDM WEB UI


Follow this procedure to add a global DNS forwarder in the Identity Management (IdM) Web UI.

Prerequisites


- You are logged in to the IdM WebUI as IdM administrator.
- You know the Internet Protocol (IP) address of the DNS server to forward queries to.

Procedure


1. In the IdM Web UI, select **Network Services** → **DNS Global Configuration** → **DNS**.




2. In the DNS Global Configuration section, click Add.



3. Specify the IP address of the DNS server that will receive forwarded DNS queries.




4. Select the Forward policy.




5. Click **Save** at the top of the window.

Verification

1. Select Network Services → DNS Global Configuration → DNS.



2. Verify that the global forwarder, with the forward policy you specified, is present and enabled in the IdM Web UI.



30.4. ADDING A GLOBAL FORWARDER IN THE CLI

Follow this procedure to add a global DNS forwarder by using the command line (CLI).

Prerequisites

- You are logged in as IdM administrator.
- You know the Internet Protocol (IP) address of the DNS server to forward queries to.

Procedure

• Use the **ipa dnsconfig-mod** command to add a new global forwarder. Specify the IP address of the DNS forwarder with the **--forwarder** option.

[user@server ~]\$ **ipa dnsconfig-mod --forwarder=10.10.0.1** Server will check DNS forwarder(s).

This may take some time, please wait ...

Global forwarders: 10.10.0.1

IPA DNS servers: server.example.com

Verification

• Use the **dnsconfig-show** command to display global forwarders.

[user@server ~]\$ ipa dnsconfig-show

Global forwarders: 10.10.0.1

IPA DNS servers: server.example.com

30.5. ADDING A DNS FORWARD ZONE IN THE IDM WEB UI

Follow this procedure to add a DNS forward zone in the Identity Management (IdM) Web UI.



IMPORTANT

Do not use forward zones unless absolutely required. Forward zones are not a standard solution, and using them can lead to unexpected and problematic behavior. If you must use forward zones, limit their use to overriding a global forwarding configuration.


When creating a new DNS zone, Red Hat recommends to always use standard DNS delegation using nameserver (NS) records and to avoid forward zones. In most cases, using a global forwarder is sufficient, and forward zones are not necessary.

Prerequisites


- You are logged in to the IdM WebUI as IdM administrator.
- You know the Internet Protocol (IP) address of the DNS server to forward queries to.

Procedure


1. In the IdM Web UI, select **Network Services** → **DNS Forward Zones** → **DNS**.




2. In the DNS Forward Zones section, click Add.




3. In the **Add DNS forward zone** window, specify the forward zone name.



4. Click the **Add** button and specify the IP address of a DNS server to receive the forwarding request. You can specify multiple forwarders per forward zone.




5. Select the Forward policy.




6. Click **Add** at the bottom of the window to add the new forward zone.

Verification

1. In the IdM Web UI, select **Network Services** → **DNS Forward Zones** → **DNS**.



2. Verify that the forward zone you created, with the forwarders and forward policy you specified, is present and enabled in the IdM Web UI.



30.6. ADDING A DNS FORWARD ZONE IN THE CLI

Follow this procedure to add a DNS forward zone by using the command line (CLI).



IMPORTANT

Do not use forward zones unless absolutely required. Forward zones are not a standard solution, and using them can lead to unexpected and problematic behavior. If you must use forward zones, limit their use to overriding a global forwarding configuration.

When creating a new DNS zone, Red Hat recommends to always use standard DNS delegation using nameserver (NS) records and to avoid forward zones. In most cases, using a global forwarder is sufficient, and forward zones are not necessary.

Prerequisites

- You are logged in as IdM administrator.
- You know the Internet Protocol (IP) address of the DNS server to forward queries to.

Procedure

Use the **dnsforwardzone-add** command to add a new forward zone. Specify at least one
forwarder with the **--forwarder** option if the forward policy is not **none**, and specify the forward
policy with the **--forward-policy** option.

[user@server ~]\$ ipa dnsforwardzone-add forward.example.com. -- forwarder=10.10.0.14 --forwarder=10.10.1.15 --forward-policy=first

Zone name: forward.example.com. Zone forwarders: 10.10.0.14, 10.10.1.15

Forward policy: first

Verification

• Use the **dnsforwardzone-show** command to display the DNS forward zone you just created.

[user@server ~]\$ ipa dnsforwardzone-show forward.example.com.

Zone name: forward.example.com. Zone forwarders: 10.10.0.14, 10.10.1.15

Forward policy: first

30.7. ESTABLISHING A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to establish a DNS Global Forwarder in IdM.

In the example procedure below, the IdM administrator creates a DNS global forwarder to a DNS server with an Internet Protocol (IP) v4 address of **8.8.6.6** and IPv6 address of **2001:4860:4860::8800** on port **53**.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **set-configuration.yml** Ansible playbook file. For example:

\$ cp set-configuration.yml establish-global-forwarder.yml

- 4. Open the **establish-global-forwarder.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to establish a global forwarder** in IdM DNS.
 - b. In the tasks section, change the name of the task to Create a DNS global forwarder to 8.8.6.6 and 2001:4860:4860:8800.
 - c. In the **forwarders** section of the **ipadnsconfig** portion:
 - i. Change the first **ip_address** value to the IPv4 address of the global forwarder: **8.8.6.6**.
 - ii. Change the second **ip_address** value to the IPv6 address of the global forwarder: **2001:4860:4860::8800**.
 - iii. Verify the **port** value is set to **53**.
 - d. Change the **forward_policy** to **first**.

 This the modified Ansible playbook file for the current example:

 name: Playbook to establish a global forwarder in IdM DNS hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Create a DNS global forwarder to 8.8.6.6 and 2001:4860:4860::8800 ipadnsconfig:

forwarders:

- ip address: 8.8.6.6

- ip_address: 2001:4860:4860::8800

port: 53

forward_policy: first allow_sync_ptr: true

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file establish-global-forwarder.yml

Additional resources

• The README-dnsconfig.md file in the /usr/share/doc/ansible-freeipa/ directory

30.8. ENSURING THE PRESENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure the presence of a DNS global forwarder in IdM. In the example procedure below, the IdM administrator ensures the presence of a DNS global forwarder to a DNS server with an Internet Protocol (IP) v4 address of **7.7.9.9** and IP v6 address of **2001:db8::1:0** on port **53**.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- Open your inventory file and make sure that the IdM server that you want to configure is listed in the [ipaserver] section. For example, to instruct Ansible to configure server.idm.example.com, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the forwarders-absent.yml Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-presence-of-a-global-forwarder.yml
- 4. Open the **ensure-presence-of-a-global-forwarder.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the name variable for the playbook to Playbook to ensure the presence of a global forwarder in IdM DNS.
 - b. In the tasks section, change the name of the task to Ensure the presence of a DNS global forwarder to 7.7.9.9 and 2001:db8::1:0 on port 53.
 - c. In the **forwarders** section of the **ipadnsconfig** portion:

- i. Change the first **ip_address** value to the IPv4 address of the global forwarder: **7.7.9.9**.
- ii. Change the second **ip_address** value to the IPv6 address of the global forwarder: **2001:db8::1:0**.
- iii. Verify the **port** value is set to **53**.
- d. Change the **state** to **present**.

This the modified Ansible playbook file for the current example:

 name: Playbook to ensure the presence of a global forwarder in IdM DNS hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure the presence of a DNS global forwarder to 7.7.9.9 and 2001:db8::1:0 on port 53

ipadnsconfig:

forwarders:

- ip_address: 7.7.9.9

- ip_address: 2001:db8::1:0

port: 53 state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-presence-of-a-global-forwarder.yml

Additional resources

• The README-dnsconfig.md file in the /usr/share/doc/ansible-freeipa/ directory

30.9. ENSURING THE ABSENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure the absence of a DNS global forwarder in IdM. In the example procedure below, the IdM administrator ensures the absence of a DNS global forwarder with an Internet Protocol (IP) v4 address of **8.8.6.6** and IP v6 address of **2001:4860:4860:4860** on port **53**.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.

- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

Procedure

- Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the **forwarders-absent.yml** Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-absence-of-a-global-forwarder.yml
- 4. Open the ensure-absence-of-a-global-forwarder.yml file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to ensure the absence of a global forwarder in IdM DNS**.
 - b. In the tasks section, change the name of the task to Ensure the absence of a DNS global forwarder to 8.8.6.6 and 2001:4860:4860:8800 on port 53.
 - c. In the **forwarders** section of the **ipadnsconfig** portion:
 - i. Change the first ip address value to the IPv4 address of the global forwarder: 8.8.6.6.
 - ii. Change the second **ip_address** value to the IPv6 address of the global forwarder: **2001:4860:4860:8800**.
 - iii. Verify the **port** value is set to **53**.
 - d. Set the action variable to member.
 - e. Verify the state is set to absent.

This the modified Ansible playbook file for the current example:

- name: Playbook to ensure the absence of a global forwarder in IdM DNS hosts: ipaserver

vars files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure the absence of a DNS global forwarder to 8.8.6.6 and

2001:4860:4860::8800 on port 53

ipadnsconfig: forwarders:

- ip_address: 8.8.6.6

- ip address: 2001:4860:4860::8800

port: 53 action: member state: absent



IMPORTANT

If you only use the **state: absent** option in your playbook without also using **action: member**, the playbook fails.

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-absence-of-a-global-forwarder.yml

Additional resources

- The README-dnsconfig.md file in the /usr/share/doc/ansible-freeipa/ directory
- The **action: member** option in ipadnsconfig ansible-freeipa modules

30.10. ENSURING DNS GLOBAL FORWARDERS ARE DISABLED IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure DNS Global Forwarders are disabled in IdM. In the example procedure below, the IdM administrator ensures that the forwarding policy for the global forwarder is set to **none**, which effectively disables the global forwarder.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

• You know the IdM administrator password.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig

2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Verify the contents of the **disable-global-forwarders.yml** Ansible playbook file which is already configured to disable all DNS global forwarders. For example:

\$ cat disable-global-forwarders.yml

- name: Playbook to disable global DNS forwarders

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Disable global forwarders.

ipadnsconfig:

forward_policy: none

4. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file disable-global-forwarders.yml

Additional resources

• The README-dnsconfig.md file in the /usr/share/doc/ansible-freeipa/ directory

30.11. ENSURING THE PRESENCE OF A DNS FORWARD ZONE IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure the presence of a DNS Forward Zone in IdM. In the example procedure below, the IdM administrator ensures the presence of a DNS forward zone for **example.com** to a DNS server with an Internet Protocol (IP) address of **8.8.8.8**.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.

- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the secret.yml Ansible vault stores your ipaadmin_password.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the **forwarders-absent.yml** Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-presence-forwardzone.yml
- 4. Open the **ensure-presence-forwardzone.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to ensure the presence of a dnsforwardzone in IdM DNS**.
 - b. In the tasks section, change the name of the task to Ensure presence of a dnsforwardzone for example.com to 8.8.8.8.
 - c. In the tasks section, change the ipadnsconfig heading to ipadnsforwardzone.
 - d. In the **ipadnsforwardzone** section:
 - Add the ipaadmin_password variable and set it to your IdM administrator password.
 - ii. Add the **name** variable and set it to **example.com**.
 - iii. In the forwarders section:
 - A. Remove the **ip_address** and **port** lines.
 - B. Add the IP address of the DNS server to receive forwarded requests by specifying it after a dash:
 - 8.8.8.8
 - iv. Add the **forwardpolicy** variable and set it to **first**.

- v. Add the **skip_overlap_check** variable and set it to **true**.
- vi. Change the **state** variable to **present**.

This the modified Ansible playbook file for the current example:

```
-name: Playbook to ensure the presence of a dnsforwardzone in IdM DNS hosts: ipaserver

vars_files:
- /home/user_name/MyPlaybooks/secret.yml
tasks:
- name: Ensure the presence of a dnsforwardzone for example.com to 8.8.8.8 ipadnsforwardzone:
    ipaadmin_password: "{{ ipaadmin_password }}"
    name: example.com
    forwarders:
        - 8.8.8.8
    forwardpolicy: first
    skip_overlap_check: true
    state: present
```

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-presence-forwardzone.yml

Additional resources

• See the **README-dnsforwardzone.md** file in the /usr/share/doc/ansible-freeipa/ directory.

30.12. ENSURING A DNS FORWARD ZONE HAS MULTIPLE FORWARDERS IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure a DNS Forward Zone in IdM has multiple forwarders. In the example procedure below, the IdM administrator ensures the DNS forward zone for **example.com** is forwarding to **8.8.8.8** and **4.4.4.4**.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.

- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the [ipaserver] section. For example, to instruct Ansible to configure server.idm.example.com, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the **forwarders-absent.yml** Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-presence-multiple-forwarders.yml
- 4. Open the **ensure-presence-multiple-forwarders.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to ensure the presence of multiple forwarders in a dnsforwardzone in IdM DNS.**
 - b. In the tasks section, change the name of the task to Ensure presence of 8.8.8.8 and 4.4.4.4 forwarders in dnsforwardzone for example.com.
 - c. In the tasks section, change the ipadnsconfig heading to ipadnsforwardzone.
 - d. In the **ipadnsforwardzone** section:
 - i. Add the ipaadmin_password variable and set it to your IdM administrator password.
 - ii. Add the **name** variable and set it to **example.com**.
 - iii. In the forwarders section:
 - A. Remove the **ip_address** and **port** lines.
 - B. Add the IP address of the DNS servers you want to ensure are present, preceded by a dash:
 - 8.8.8.8 - 4.4.4.4
 - iv. Change the state variable to present.

This the modified Ansible playbook file for the current example:

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-presence-multiple-forwarders.yml

Additional resources

• See the **README-dnsforwardzone.md** file in the /usr/share/doc/ansible-freeipa/ directory.

30.13. ENSURING A DNS FORWARD ZONE IS DISABLED IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure a DNS Forward Zone is disabled in IdM. In the example procedure below, the IdM administrator ensures the DNS forward zone for **example.com** is disabled.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig

2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the forwarders-absent.yml Ansible playbook file. For example:

\$ cp forwarders-absent.yml ensure-disabled-forwardzone.yml

- 4. Open the **ensure-disabled-forwardzone.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to ensure a dnsforwardzone is disabled in IdM DNS**.
 - b. In the tasks section, change the name of the task to Ensure a dnsforwardzone for example.com is disabled.
 - c. In the tasks section, change the ipadnsconfig heading to ipadnsforwardzone.
 - d. In the **ipadnsforwardzone** section:
 - i. Add the **ipaadmin password** variable and set it to your IdM administrator password.
 - ii. Add the **name** variable and set it to **example.com**.
 - iii. Remove the entire forwarders section.
 - iv. Change the **state** variable to **disabled**.

This the modified Ansible playbook file for the current example:

- name: Playbook to ensure a dnsforwardzone is disabled in IdM DNS

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

tasks:

- name: Ensure a dnsforwardzone for example.com is disabled ipadnsforwardzone:

ipaadmin_password: "{{ ipaadmin_password }}"

name: example.com state: disabled

- 6. Save the file.
- 7. Run the playbook:

-

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-disabled-forwardzone.yml

Additional resources

• See the **README-dnsforwardzone.md** file in the /usr/share/doc/ansible-freeipa/ directory.

30.14. ENSURING THE ABSENCE OF A DNS FORWARD ZONE IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure the absence of a DNS Forward Zone in IdM. In the example procedure below, the IdM administrator ensures the absence of a DNS forward zone for **example.com**.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.

Procedure

- Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:
 - [ipaserver] server.idm.example.com
- 3. Make a copy of the **forwarders-absent.yml** Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-absence-forwardzone.yml
- 4. Open the **ensure-absence-forwardzone.yml** file for editing.
- 5. Adapt the file by setting the following variables:

- a. Change the **name** variable for the playbook to **Playbook to ensure the absence of a dnsforwardzone in IdM DNS**.
- b. In the tasks section, change the name of the task to Ensure the absence of a dnsforwardzone for example.com.
- c. In the **tasks** section, change the **ipadnsconfig** heading to **ipadnsforwardzone**.
- d. In the **ipadnsforwardzone** section:
 - i. Add the **ipaadmin_password** variable and set it to your IdM administrator password.
 - ii. Add the **name** variable and set it to **example.com**.
 - iii. Remove the entire forwarders section.
 - iv. Leave the state variable as absent.

This the modified Ansible playbook file for the current example:

- name: Playbook to ensure the absence of a dnsforwardzone in IdM DNS hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure the absence of a dnsforwardzone for example.com ipadnsforwardzone:

ipaadmin_password: "{{ ipaadmin_password }}"

name: example.com

state: absent

- 6. Save the file.
- 7. Run the playbook:

 $\$ \ ansible-playbook \ --vault-password-file=password_file \ -v \ -i \ inventory. file \ ensure-absence-forwardzone.yml$

Additional resources

• See the **README-dnsforwardzone.md** file in the /usr/share/doc/ansible-freeipa/ directory.

CHAPTER 31. USING ANSIBLE TO MANAGE DNS RECORDS IN IDM

This chapter describes how to manage DNS records in Identity Management (IdM) using an Ansible playbook. As an IdM administrator, you can add, modify, and delete DNS records in IdM. The chapter contains the following sections:

- Ensuring the presence of A and AAAA DNS records in IdM using Ansible
- Ensuring the presence of A and PTR DNS records in IdM using Ansible
- Ensuring the presence of multiple DNS records in IdM using Ansible
- Ensuring the presence of multiple CNAME records in IdM using Ansible
- Ensuring the presence of an SRV record in IdM using Ansible

31.1. DNS RECORDS IN IDM

Identity Management (IdM) supports many different DNS record types. The following four are used most frequently:

Α

This is a basic map for a host name and an IPv4 address. The record name of an A record is a host name, such as **www**. The **IP Address** value of an A record is an IPv4 address, such as **192.0.2.1**. For more information about A records, see RFC 1035.

AAAA

This is a basic map for a host name and an IPv6 address. The record name of an AAAA record is a host name, such as **www**. The **IP Address** value is an IPv6 address, such as **2001:DB8::1111**. For more information about AAAA records, see RFC 3596.

SRV

Service (SRV) resource records map service names to the DNS name of the server that is providing that particular service. For example, this record type can map a service like an LDAP directory to the server which manages it.

The record name of an SRV record has the format _service._protocol, such as _ldap._tcp. The configuration options for SRV records include priority, weight, port number, and host name for the target service.

For more information about SRV records, see RFC 2782.

PTR

A pointer record (PTR) adds a reverse DNS record, which maps an IP address to a domain name.



NOTE

All reverse DNS lookups for IPv4 addresses use reverse entries that are defined in the **in-addr.arpa.** domain. The reverse address, in human-readable form, is the exact reverse of the regular IP address, with the **in-addr.arpa.** domain appended to it. For example, for the network address **192.0.2.0/24**, the reverse zone is **2.0.192.in-addr.arpa**.

The record name of a PTR must be in the standard format specified in RFC 1035, extended in RFC 2317, and RFC 3596. The host name value must be a canonical host name of the host for which you want to create the record.



NOTE

Reverse zones can also be configured for IPv6 addresses, with zones in the .ip6.arpa. domain. For more information about IPv6 reverse zones, see RFC 3596.

When adding DNS resource records, note that many of the records require different data. For example, a CNAME record requires a host name, while an A record requires an IP address. In the IdM Web UI, the fields in the form for adding a new record are updated automatically to reflect what data is required for the currently selected type of record.

31.2. COMMON IPA DNSRECORD-* OPTIONS

You can use the following options when adding, modifying and deleting the most common DNS resource record types in Identity Management (IdM):

- A (IPv4)
- AAAA (IPv6)
- SRV
- PTR

In **Bash**, you can define multiple entries by listing the values in a comma-separated list inside curly braces, such as **--option={val1,val2,val3}**.

Table 31.1. General Record Options

Option	Description
ttl=number	Sets the time to live for the record.
structured	Parses the raw DNS records and returns them in a structured format.

Table 31.2. "A" record options

Option	Description .	Examples
a- rec=ARECORD	Passes a single A record or a list of A records.	ipa dnsrecord-add idm.example.com host1a- rec=192.168.122.123
	Can create a wildcard A record with a given IP address.	ipa dnsrecord-add idm.example.com "*"a-rec=192.168.122.123 [a]

Option	Description	Examples
a-ip- address=strin g	Gives the IP address for the record. When creating a record, the option to specify the A record value is a-rec . However, when modifying an A record, the a-rec option is used to specify the current value for the A record. The new value is set with thea-ip-address option.	ipa dnsrecord-mod idm.example.coma-rec 192.168.122.123a-ip- address 192.168.122.124
[a] The example creates a wildcard A record with the IP address of 192.0.2.123.		

Table 31.3. "AAAA" record options

Option	Description	Example
aaaa- rec=AAAAREC ORD	Passes a single AAAA (IPv6) record or a list of AAAA records.	ipa dnsrecord-add idm.example.com www aaaa-rec 2001:db8::1231:5675
aaaa-ip- address=strin g	Gives the IPv6 address for the record. When creating a record, the option to specify the A record value is aaaa-rec. However, when modifying an A record, theaaaa-rec option is used to specify the current value for the A record. The new value is set with the-a-ip-address option.	ipa dnsrecord-mod idm.example.comaaaa-rec 2001:db8::1231:5675aaaa- ip-address 2001:db8::1231:5676

Table 31.4. "PTR" record options

Option	Description	Example
ptr- rec=PTRRECO RD	Passes a single PTR record or a list of PTR records. When adding the reverse DNS record, the zone name used with the ipa dnsrecord-add command is reversed, compared to the usage for adding other DNS records. Typically, the host IP address is the last	ipa dnsrecord-add 122.168.192.in-addr.arpa 4 ptr-rec server4.idm.example.com.
	octet of the IP address in a given network. The first example on the right adds a PTR record for server4.idm.example.com with IPv4 address 192.168.122.4. The second example adds a reverse DNS entry to the 0.0.0.0.0.0.0.0.8.b.d.0.1.0.0.2.ip6.arpa. IPv6 reverse zone for the host server2.example.com with the IP address 2001:DB8::1111.	\$ ipa dnsrecord-add 0.0.0.0.0.0.0.0.8.b.d.0.1.0.0.2.i p6.arpa. 1.1.1.0.0.0.0.0.0.0.0.0.0.0.0 ptr-rec server2.idm.example.com.
ptr- hostname=stri ng	Gives the host name for the record.	

Table 31.5. "SRV" Record Options

Option	Description	Example
srv- rec=SRVRECORD	3	# ipa dnsrecord-add idm.example.com _ldaptcpsrv-rec="0 51 389 server1.idm.example.com."
priority, weight The weight val examples add the probability	priority, weight, port, and target values. The weight values of 51 and 49 in the examples add up to 100 and represent the probability, in percentages, that a particular record is used.	# ipa dnsrecord-add server.idm.example.com _ldaptcp srv-rec="1 49 389 server2.idm.example.com."
srv- priority=number	Sets the priority of the record. There can be multiple SRV records for a service type. The priority (0 - 65535) sets the rank of the record; the lower the number, the higher the priority. A service has to use the record with the highest priority first.	# ipa dnsrecord-mod server.idm.example.com _ldaptcp srv-rec="1 49 389 server2.idm.example.com."srv- priority=0
srv- weight=number	Sets the weight of the record. This helps determine the order of SRV records with the same priority. The set weights should add up to 100, representing the probability (in percentages) that a particular record is used.	# ipa dnsrecord-mod server.idm.example.com _ldaptcp srv-rec="0 49 389 server2.idm.example.com."srv- weight=60
srv- port=number	Gives the port for the service on the target host.	# ipa dnsrecord-mod server.idm.example.com _ldaptcp srv-rec="0 60 389 server2.idm.example.com."srv- port=636
srv- target=string	Gives the domain name of the target host. This can be a single period (.) if the service is not available in the domain.	

Additional resources

• Run ipa dnsrecord-add --help.

31.3. ENSURING THE PRESENCE OF A AND AAAA DNS RECORDS IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure that A and AAAA records for a particular IdM host are present. In the example used in the procedure below, an IdM administrator ensures the presence of A and AAAA records for **host1** in the **idm.example.com** DNS zone.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the ansible-freeipa package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.
- The idm.example.com zone exists and is managed by IdM DNS. For more information about adding a primary DNS zone in IdM DNS, see Using Ansible playbooks to manage IdM DNS zones.

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsrecord
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **ensure-A-and-AAAA-records-are-present.yml** Ansible playbook file. For example:

\$ cp ensure-A-and-AAAA-records-are-present.yml ensure-A-and-AAAA-records-are-present-copy.yml

- 4. Open the ensure-A-and-AAAA-records-are-present-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsrecord** task section:
 - Set the **ipaadmin password** variable to your IdM administrator password.
 - Set the **zone_name** variable to **idm.example.com**.
 - In the **records** variable, set the **name** variable to **host1**, and the **a_ip_address** variable to **192.168.122.123**.
 - In the **records** variable, set the **name** variable to **host1**, and the **aaaa_ip_address** variable to **::1**.

This is the modified Ansible playbook file for the current example:

- name: Ensure A and AAAA records are present

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure A and AAAA records are present

- name: Ensure that 'host1' has A and AAAA records.

ipadnsrecord:

ipaadmin_password: "{{ ipaadmin_password }}"

zone_name: idm.example.com

records: - name: host1

a_ip_address: 192.168.122.123

- name: host1

aaaa_ip_address: ::1

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-A-and-AAAA-records-are-present-copy.yml

Additional resources

- DNS records in IdM
- The README-dnsrecord.md file in the /usr/share/doc/ansible-freeipa/ directory
- Sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory

31.4. ENSURING THE PRESENCE OF A AND PTR DNS RECORDS IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure that an A record for a particular IdM host is present, with a corresponding PTR record. In the example used in the procedure below, an IdM administrator ensures the presence of A and PTR records for **host1** with an IP address of **192.168.122.45** in the **idm.example.com** zone.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

- You know the IdM administrator password.
- The idm.example.com DNS zone exists and is managed by IdM DNS. For more information about adding a primary DNS zone in IdM DNS, see Using Ansible playbooks to manage IdM DNS zones.

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsrecord

2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **ensure-dnsrecord-with-reverse-is-present.yml** Ansible playbook file. For example:

\$ cp ensure-dnsrecord-with-reverse-is-present.yml ensure-dnsrecord-with-reverse-is-present-copy.yml

- 4. Open the **ensure-dnsrecord-with-reverse-is-present-copy.yml** file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsrecord** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name** variable to **host1**.
 - Set the **zone name** variable to **idm.example.com**.
 - Set the **ip address** variable to **192.168.122.45**.
 - Set the create_reverse variable to true.
 This is the modified Ansible playbook file for the current example:

- name: Ensure DNS Record is present.
hosts: ipaserver
become: true
gather_facts: false

tasks:

Ensure that dns record is present

- ipadnsrecord:

ipaadmin_password: "{{ ipaadmin_password }}"

name: host1

zone_name: idm.example.com ip_address: 192.168.122.45

create_reverse: true

state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-dnsrecord-with-reverse-is-present-copy.yml

Additional resources

- DNS records in IdM
- The **README-dnsrecord.md** file in the /usr/share/doc/ansible-freeipa/ directory
- Sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory

31.5. ENSURING THE PRESENCE OF MULTIPLE DNS RECORDS IN IDM USING ANSIBLE

Follow this procedure to use an Ansible playbook to ensure that multiple values are associated with a particular IdM DNS record. In the example used in the procedure below, an IdM administrator ensures the presence of multiple A records for **host1** in the **idm.example.com** DNS zone.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.
- The idm.example.com zone exists and is managed by IdM DNS. For more information about adding a primary DNS zone in IdM DNS, see Using Ansible playbooks to manage IdM DNS zones.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsrecord
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the ensure-presence-multiple-records.yml Ansible playbook file. For example:

\$ cp ensure-presence-multiple-records.yml ensure-presence-multiple-records-copy.yml

- 4. Open the ensure-presence-multiple-records-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsrecord** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - In the **records** section, set the **name** variable to **host1**.
 - In the **records** section, set the **zone name** variable to **idm.example.com**.
 - In the **records** section, set the **a_rec** variable to **192.168.122.112** and to **192.168.122.122**.
 - Define a second record in the records section:
 - Set the **name** variable to **host1**.
 - Set the **zone_name** variable to **idm.example.com**.
 - Set the **aaaa_rec** variable to **::1**.

This is the modified Ansible playbook file for the current example:

--- name: Test multiple DNS Records are present.
hosts: ipaserver
become: true
gather_facts: false

tasks:
Ensure that multiple dns records are present
- ipadnsrecord:
 ipaadmin_password: "{{ ipaadmin_password }}"
 records:
 - name: host1
 zone_name: idm.example.com
 a_rec: 192.168.122.112
 a_rec: 192.168.122.122

zone_name: idm.example.com

- 6. Save the file.
- 7. Run the playbook:

- name: host1

aaaa_rec: ::1

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensurepresence-multiple-records-copy.yml

Additional resources

- DNS records in IdM
- The **README-dnsrecord.md** file in the /usr/share/doc/ansible-freeipa/ directory
- Sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory

31.6. ENSURING THE PRESENCE OF MULTIPLE CNAME RECORDS IN IDM USING ANSIBLE

A Canonical Name record (CNAME record) is a type of resource record in the Domain Name System (DNS) that maps one domain name, an alias, to another name, the canonical name.

You may find CNAME records useful when running multiple services from a single IP address: for example, an FTP service and a web service, each running on a different port.

Follow this procedure to use an Ansible playbook to ensure that multiple CNAME records are present in IdM DNS. In the example used in the procedure below, **host03** is both an HTTP server and an FTP server. The IdM administrator ensures the presence of the **www** and **ftp** CNAME records for the **host03** A record in the **idm.example.com** zone.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.
- The idm.example.com zone exists and is managed by IdM DNS. For more information about adding a primary DNS zone in IdM DNS, see Using Ansible playbooks to manage IdM DNS zones.
- The host03 A record exists in the idm.example.com zone.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsrecord
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **ensure-CNAME-record-is-present.yml** Ansible playbook file. For example:

\$ cp ensure-CNAME-record-is-present.yml ensure-CNAME-record-is-present-copy.yml

- 4. Open the ensure-CNAME-record-is-present-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsrecord** task section:
 - Optional: Adapt the description provided by the **name** of the play.
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **zone_name** variable to **idm.example.com**.
 - In the **records** variable section, set the following variables and values:
 - Set the **name** variable to **www**.
 - Set the **cname_hostname** variable to **host03**.
 - Set the **name** variable to **ftp**.
 - Set the **cname hostname** variable to **host03**.

This is the modified Ansible playbook file for the current example:

- name: Ensure that 'www.idm.example.com' and 'ftp.idm.example.com' CNAME records point to 'host03.idm.example.com'.

hosts: ipaserver become: true gather_facts: false

tasks:

- ipadnsrecord:

ipaadmin_password: "{{ ipaadmin_password }}"

zone name: idm.example.com

records:

- name: www

cname hostname: host03

- name: ftp

cname_hostname: host03

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-CNAME-record-is-present.yml

Additional resources

- See the **README-dnsrecord.md** file in the /usr/share/doc/ansible-freeipa/ directory.
- See sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory.

31.7. ENSURING THE PRESENCE OF AN SRV RECORD IN IDM USING ANSIBLE

A DNS service (SRV) record defines the hostname, port number, transport protocol, priority and weight of a service available in a domain. In Identity Management (IdM), you can use SRV records to locate IdM servers and replicas.

Follow this procedure to use an Ansible playbook to ensure that an SRV record is present in IdM DNS. In the example used in the procedure below, an IdM administrator ensures the presence of the **_kerberos._udp.idm.example.com** SRV record with the value of **10 50 88 idm.example.com** This sets the following values:

- It sets the priority of the service to 10.
- It sets the weight of the service to 50.
- It sets the port to be used by the service to 88.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
- You know the IdM administrator password.
- The idm.example.com zone exists and is managed by IdM DNS. For more information about adding a primary DNS zone in IdM DNS, see Using Ansible playbooks to manage IdM DNS zones.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsrecord
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **ensure-SRV-record-is-present.yml** Ansible playbook file. For example:

 $\$\ cp\ ensure-SRV\text{-}record\text{-}is\text{-}present.yml\ ensure-SRV\text{-}record\text{-}is\text{-}present\text{-}copy.yml}$

- 4. Open the **ensure-SRV-record-is-present-copy.yml** file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsrecord** task section:
 - Set the **ipaadmin password** variable to your IdM administrator password.
 - Set the **name** variable to **_kerberos._udp.idm.example.com**.
 - Set the **srv_rec** variable to '10 50 88 idm.example.com'.
 - Set the **zone_name** variable to **idm.example.com**.

 This the modified Ansible playbook file for the current example:

- name: Test multiple DNS Records are present.

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure a SRV record is present

- ipadnsrecord:

ipaadmin_password: "{{ ipaadmin_password }}"
name: _kerberos._udp.idm.example.com
srv_rec: '10 50 88 idm.example.com'
zone_name: idm.example.com

state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory.file ensure-SRV-record-is-present.yml

Additional resources

- DNS records in IdM
- The **README-dnsrecord.md** file in the /usr/share/doc/ansible-freeipa/ directory
- Sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory

CHAPTER 32. USING ANSIBLE TO AUTOMOUNT NFS SHARES FOR IDM USERS

Automount is a way to manage, organize, and access directories across multiple systems. Automount automatically mounts a directory whenever access to it is requested. This works well within an Identity Management (IdM) domain as it allows you to share directories on clients within the domain easily.

You can use Ansible to configure NFS shares to be mounted automatically for IdM users logged in to IdM clients in an IdM location.

The example in this chapter uses the following scenario:

- **nfs-server.idm.example.com** is the fully-qualified domain name (FQDN) of a Network File System (NFS) server.
- **nfs-server.idm.example.com** is an IdM client located in the **raleigh** automount location.
- The NFS server exports the **/exports/project** directory as read-write.
- Any IdM user belonging to the developers group can access the contents of the exported directory as /devel/project/ on any IdM client that is located in the same raleigh automount location as the NFS server.
- idm-client.idm.example.com is an IdM client located in the raleigh automount location.



IMPORTANT

If you want to use a Samba server instead of an NFS server to provide the shares for IdM clients, see the Red Hat Knowledgebase solution How do I configure kerberized CIFS mounts with Autofs in an IPA environment?.

32.1. AUTOFS AND AUTOMOUNT IN IDM

The **autofs** service automates the mounting of directories, as needed, by directing the **automount** daemon to mount directories when they are accessed. In addition, after a period of inactivity, **autofs** directs **automount** to unmount auto-mounted directories. Unlike static mounting, on-demand mounting saves system resources.

Automount maps

On a system that utilizes **autofs**, the **automount** configuration is stored in several different files. The primary **automount** configuration file is /**etc/auto.master**, which contains the master mapping of **automount** mount points, and their associated resources, on a system. This mapping is known as automount maps.

The /etc/auto.master configuration file contains the *master map*. It can contain references to other maps. These maps can either be direct or indirect. Direct maps use absolute path names for their mount points, while indirect maps use relative path names.

Automount configuration in IdM

While **automount** typically retrieves its map data from the local /etc/auto.master and associated files, it can also retrieve map data from other sources. One common source is an LDAP server. In the context of Identity Management (IdM), this is a 389 Directory Server.

If a system that uses **autofs** is a client in an IdM domain, the **automount** configuration is not stored in local configuration files. Instead, the **autofs** configuration, such as maps, locations, and keys, is stored

as LDAP entries in the IdM directory. For example, for the idm.example.com IdM domain, the default master map is stored as follows:

dn:

automountmapname=auto.master,cn=default,cn=automount,dc=idm,dc=example,dc=com

objectClass: automountMap

objectClass: top

automountMapName: auto.master

Additional resources

Mounting file systems on demand

32.2. SETTING UP AN NFS SERVER WITH KERBEROS IN A RED HAT ENTERPRISE LINUX IDENTITY MANAGEMENT DOMAIN

If you use Red Hat Enterprise Linux Identity Management (IdM), you can join your NFS server to the IdM domain. This enables you to centrally manage users and groups and to use Kerberos for authentication, integrity protection, and traffic encryption.

Prerequisites

- The NFS server is enrolled in a Red Hat Enterprise Linux Identity Management (IdM) domain.
- The NFS server is running and configured.

Procedure

1. Obtain a kerberos ticket as an IdM administrator:

kinit admin

2. Create a **nfs/<FQDN>** service principal:

ipa service-add nfs/nfs_server.idm.example.com

3. Retrieve the **nfs** service principal from IdM, and store it in the /etc/krb5.keytab file:

ipa-getkeytab -s idm_server.idm.example.com -p nfs/nfs_server.idm.example.com -k /etc/krb5.keytab

4. Optional: Display the principals in the /etc/krb5.keytab file:

klist -k /etc/krb5.keytab

Keytab name: FILE:/etc/krb5.keytab

KVNO Principal

- 1 nfs/nfs_server.idm.example.com@IDM.EXAMPLE.COM
- 1 nfs/nfs server.idm.example.com@IDM.EXAMPLE.COM
- 1 nfs/nfs_server.idm.example.com@IDM.EXAMPLE.COM
- 1 nfs/nfs_server.idm.example.com@IDM.EXAMPLE.COM
- 7 host/nfs server.idm.example.com@IDM.EXAMPLE.COM

7 host/nfs_server.idm.example.com@IDM.EXAMPLE.COM 7 host/nfs_server.idm.example.com@IDM.EXAMPLE.COM 7 host/nfs_server.idm.example.com@IDM.EXAMPLE.COM

By default, the IdM client adds the host principal to the /etc/krb5.keytab file when you join the host to the IdM domain. If the host principal is missing, use the ipa-getkeytab -s idm_server.idm.example.com -p host/nfs_server.idm.example.com -k /etc/krb5.keytab command to add it.

5. Use the **ipa-client-automount** utility to configure mapping of IdM IDs:

ipa-client-automount

Searching for IPA server... IPA server: DNS discovery

Location: default

Continue to configure the system with these values? [no]: yes

Configured /etc/idmapd.conf

Restarting sssd, waiting for it to become available.

Started autofs

6. Update your /etc/exports file, and add the Kerberos security method to the client options. For example:

/nfs/projects/ 192.0.2.0/24(rw,**sec=krb5i**)

If you want that your clients can select from multiple security methods, specify them separated by colons:

/nfs/projects/ 192.0.2.0/24(rw,**sec=krb5:krb5i:krb5p**)

7. Reload the exported file systems:

exportfs -r

32.3. CONFIGURING AUTOMOUNT LOCATIONS, MAPS, AND KEYS IN IDM BY USING ANSIBLE

As an Identity Management (IdM) system administrator, you can configure automount locations and maps in IdM so that IdM users in the specified locations can access shares exported by an NFS server by navigating to specific mount points on their hosts. Both the exported NFS server directory and the mount points are specified in the maps. In LDAP terms, a location is a container for such map entries.

The example describes how to use Ansible to configure the **raleigh** location and a map that mounts the **nfs-server.idm.example.com:/exports/project** share on the **/devel/project** mount point on the IdM client as a read-write directory.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.

- The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
- The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

1. On your Ansible control node, navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **automount-location-present.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/automount/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/automount/automount-location-present.yml automount-location-map-and-key-present.yml

- 3. Open the automount-location-map-and-key-present.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipaautomountlocation** task section:
 - Set the **ipaadmin password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **raleigh**.
 - Ensure that the **state** variable is set to **present**.
 This is the modified Ansible playbook file for the current example:

--- name: Automount location present example
hosts: ipaserver
vars_files:
- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure automount location is present ipaautomountlocation:

ipaadmin_password: "{{ ipaadmin_password }}"

name: raleigh state: present

- 5. Continue editing the automount-location-map-and-key-present.yml file:
 - a. In the tasks section, add a task to ensure the presence of an automount map:

```
[...]
  vars_files:
  - /home/user_name/MyPlaybooks/secret.yml
  tasks:
[...]
  - name: ensure map named auto.devel in location raleigh is created
  ipaautomountmap:
    ipaadmin_password: "{{ ipaadmin_password }}"
```

name: auto.devel location: raleigh state: present

b. Add another task to add the mount point and NFS server information to the map:

```
[...]
  vars_files:
  - /home/user_name/MyPlaybooks/secret.yml
  tasks:
[...]
  - name: ensure automount key /devel/project is present
  ipaautomountkey:
    ipaadmin_password: "{{ ipaadmin_password }}"
    location: raleigh
    mapname: auto.devel
    key: /devel/project
    info: nfs-server.idm.example.com:/exports/project
    state: present
```

c. Add another task to ensure **auto.devel** is connected to **auto.master**:

```
[...]
  vars_files:
  - /home/user_name/MyPlaybooks/secret.yml
  tasks:
[...]
- name: Ensure auto.devel is connected in auto.master:
  ipaautomountkey:
    ipaadmin_password: "{{ ipaadmin_password }}"
    location: raleigh
    mapname: auto.map
    key: /devel
    info: auto.devel
    state: present
```

- 6. Save the file.
- 7. Run the Ansible playbook and specify the playbook and inventory files:

 $\$ ansible-playbook --vault-password_file=password_file -v -i inventory automount-location-map-and-key-present.yml

32.4. USING ANSIBLE TO ADD IDM USERS TO A GROUP THAT OWNS NFS SHARES

As an Identity Management (IdM) system administrator, you can use Ansible to create a group of users that is able to access NFS shares, and add IdM users to this group.

This example describes how to use an Ansible playbook to ensure that the **idm_user** account belongs to the **developers** group, so that **idm_user** can access the **/exports/project** NFS share.

Prerequisites

- You have **root** access to the **nfs-server.idm.example.com** NFS server, which is an IdM client located in the **raleigh** automount location.
- On the control node:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.
 - In ~/MyPlaybooks/, you have created the automount-location-map-and-key-present.yml file that already contains tasks from Configuring automount locations, maps, and keys in IdM by using Ansible.

1. On your Ansible control node, navigate to the ~/MyPlaybooks/ directory:

```
$ cd ~/MyPlaybooks/
```

- 2. Open the automount-location-map-and-key-present.yml file for editing.
- 3. In the **tasks** section, add a task to ensure that the IdM **developers** group exists and **idm_user** is added to this group:

```
[...]
  vars_files:
  - /home/user_name/MyPlaybooks/secret.yml
  tasks:
[...]
  - ipagroup:
    ipaadmin_password: "{{ ipaadmin_password }}"
    name: developers
    user:
    - idm_user
    state: present
```

- 4. Save the file.
- 5. Run the Ansible playbook and specify the playbook and inventory files:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory automount-location-map-and-key-present.yml

6. On the NFS server, change the group ownership of the **/exports/project** directory to **developers** so that every IdM user in the group can access the directory:

chgrp developers /exports/project

32.5. CONFIGURING AUTOMOUNT ON AN IDM CLIENT

As an Identity Management (IdM) system administrator, you can configure automount services on an IdM client so that NFS shares configured for a location to which the client has been added are accessible to an IdM user automatically when the user logs in to the client. The example describes how to configure an IdM client to use automount services that are available in the **raleigh** location.

Prerequisites

- You have **root** access to the IdM client.
- You are logged in as IdM administrator.
- The automount location exists. The example location is raleigh.

Procedure

- On the IdM client, enter the ipa-client-automount command and specify the location. Use the -U option to run the script unattended:
 - # ipa-client-automount --location raleigh -U
- 2. Stop the autofs service, clear the SSSD cache, and start the autofs service to load the new configuration settings:
 - # systemctl stop autofs ; sss_cache -E ; systemctl start autofs

32.6. VERIFYING THAT AN IDM USER CAN ACCESS NFS SHARES ON AN IDM CLIENT

As an Identity Management (IdM) system administrator, you can test if an IdM user that is a member of a specific group can access NFS shares when logged in to a specific IdM client.

In the example, the following scenario is tested:

• An IdM user named idm_user belonging to the developers group can read and write the contents of the files in the /devel/project directory automounted on idm-client.idm.example.com, an IdM client located in the raleigh automount location.

Prerequisites

- You have set up an NFS server with Kerberos on an IdM host .
- You have configured automount locations, maps, and mount points in IdM in which you configured how IdM users can access the NFS share.
- You have used Ansible to add IdM users to the developers group that owns the NFS shares .
- You have configured automount on the IdM client.

Procedure

1. Verify that the IdM user can access the **read-write** directory:

a. Connect to the IdM client as the IdM user:

\$ ssh idm_user@idm-client.idm.example.com Password:

b. Obtain the ticket-granting ticket (TGT) for the IdM user:

\$ kinit idm_user

c. Optional: View the group membership of the IdM user:

\$ ipa user-show idm_user
User login: idm_user
[...]
Member of groups: developers, ipausers

d. Navigate to the /devel/project directory:

\$ cd /devel/project

e. List the directory contents:

\$ **Is** rw_file

f. Add a line to the file in the directory to test the **write** permission:

\$ echo "idm_user can write into the file" > rw_file

g. Optional: View the updated contents of the file:

\$ cat rw_file this is a read-write file idm_user can write into the file

The output confirms that idm_user can write into the file.

CHAPTER 33. USING ANSIBLE TO INTEGRATE IDM WITH NIS DOMAINS AND NETGROUPS

33.1. NIS AND ITS BENEFITS

In UNIX environments, the network information service (NIS) is a common way to centrally manage identities and authentication. NIS, which was originally named **Yellow Pages** (YP), centrally manages authentication and identity information such as:

- Users and passwords
- Host names and IP addresses
- POSIX groups

For modern network infrastructures, NIS is considered too insecure because, for example, it neither provides host authentication, nor is data sent encrypted over the network. To work around the problems, NIS is often integrated with other protocols to enhance security.

If you use Identity Management (IdM), you can use the NIS server plug-in to connect clients that cannot be fully migrated to IdM. IdM integrates netgroups and other NIS data into the IdM domain. Additionally, you can easily migrate user and host identities from a NIS domain to IdM.

Netgroups can be used everywhere that NIS groups are expected.

Additional resources

- NIS in IdM
- NIS netgroups in IdM
- Migrating from NIS to Identity Management

33.2. NIS IN IDM

NIS objects in IdM

NIS objects are integrated and stored in the Directory Server back end in compliance with RFC 2307. IdM creates NIS objects in the LDAP directory and clients retrieve them through, for example, System Security Services Daemon (SSSD) or **nss_ldap** using an encrypted LDAP connection.

IdM manages netgroups, accounts, groups, hosts, and other data. IdM uses a NIS listener to map passwords, groups, and netgroups to IdM entries.

NIS Plug-ins in IdM

For NIS support, IdM uses the following plug-ins provided in the slapi-nis package:

NIS Server Plug-in

The NIS Server plug-in enables the IdM-integrated LDAP server to act as a NIS server for clients. In this role, Directory Server dynamically generates and updates NIS maps according to the configuration. Using the plug-in, IdM serves clients using the NIS protocol as an NIS server.

Schema Compatibility Plug-in

The Schema Compatibility plug-in enables the Directory Server back end to provide an alternate

view of entries stored in part of the directory information tree (DIT). This includes adding, dropping, or renaming attribute values, and optionally retrieving values for attributes from multiple entries in the tree.

For further details, see the /usr/share/doc/slapi-nis-version/sch-getting-started.txt file.

33.3. NIS NETGROUPS IN IDM

NIS entities can be stored in netgroups. Compared to UNIX groups, netgroups provide support for:

- Nested groups (groups as members of other groups).
- Grouping hosts.

A netgroup defines a set of the following information: host, user, and domain. This set is called a **triple**. These three fields can contain:

- A value.
- A dash (-), which specifies "no valid value"
- No value. An empty field specifies a wildcard.

(host.example.com,,nisdomain.example.com) (-,user,nisdomain.example.com)

When a client requests a NIS netgroup, IdM translates the LDAP entry:

- To a traditional NIS map and sends it to the client over the NIS protocol by using the NIS plug-in.
- To an LDAP format that is compliant with RFC 2307 or RFC 2307bis.

33.4. USING ANSIBLE TO ENSURE THAT A NETGROUP IS PRESENT

You can use an Ansible playbook to ensure that an IdM netgroup is present. The example describes how to ensure that the **TestNetgroup1** group is present.

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package on the Ansible controller.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
 - You have stored your ipaadmin_password in the secret.yml Ansible vault.

Procedure

1. Create your Ansible playbook file **netgroup-present.yml** with the following content:

- name: Playbook to manage IPA netgroup.

hosts: ipaserver become: no

vars files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure netgroup members are present ipanetgroup:

ipaadmin_password: "{{ ipaadmin_password }}"

name: TestNetgroup1

2. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory_/netgroup-present.yml

Additional resources

- NIS in IdM
- /usr/share/doc/ansible-freeipa/README-netgroup.md
- /usr/share/doc/ansible-freeipa/playbooks/netgroup

33.5. USING ANSIBLE TO ENSURE THAT MEMBERS ARE PRESENT IN A NETGROUP

You can use an Ansible playbook to ensure that IdM users, groups, and netgroups are members of a netgroup. The example describes how to ensure that the **TestNetgroup1** group has the following members:

- The user1 and user2 IdM users
- The **group1** IdM group
- The admins netgroup
- An idmclient1 host that is an IdM client

Prerequisites

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package on the Ansible controller.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
 - You have stored your **ipaadmin password** in the **secret.yml** Ansible vault.
- The TestNetgroup1 IdM netgroup exists.

- The user1 and user2 IdM users exist.
- The group1 IdM group exists.
- The admins IdM netgroup exists.

1. Create your Ansible playbook file **IdM-members-present-in-a-netgroup.yml** with the following content:

--- name: Playbook to manage IPA netgroup.
hosts: ipaserver
become: no

vars_files:
- /home/user_name/MyPlaybooks/secret.yml
tasks:
- name: Ensure netgroup members are present
ipanetgroup:
 ipaadmin_password: "{{ ipaadmin_password }}"
 name: TestNetgroup1
 user: user1,user2
 group: group1
 host: idmclient1
 netgroup: admins
 action: member

2. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory_/ldM-members-present-in-a-netgroup.yml

Additional resources

- NIS in IdM
- /usr/share/doc/ansible-freeipa/README-netgroup.md
- /usr/share/doc/ansible-freeipa/playbooks/netgroup

33.6. USING ANSIBLE TO ENSURE THAT A MEMBER IS ABSENT FROM A NETGROUP

You can use an Ansible playbook to ensure that IdM users are members of a netgroup. The example describes how to ensure that the **TestNetgroup1** group does not have the **user1** IdM user among its members. netgroup

Prerequisites

You have configured your Ansible control node to meet the following requirements:

- You are using Ansible version 2.14 or later.
- You have installed the **ansible-freeipa** package on the Ansible controller.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
- You have stored your **ipaadmin password** in the **secret.yml** Ansible vault.
- The **TestNetgroup1** netgroup exists.

1. Create your Ansible playbook file **IdM-member-absent-from-a-netgroup.yml** with the following content:

name: Playbook to manage IPA netgroup.
hosts: ipaserver
become: no
vars_files:
 -/home/user_name/MyPlaybooks/secret.yml
tasks:
 - name: Ensure netgroup user, "user1", is absent
ipanetgroup:
 ipaadmin_password: "{{ ipaadmin_password }}"

user: "user1" action: member state: absent

name: TestNetgroup1

2. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory_/ldM-member-absent-from-a-netgroup.yml

Additional resources

- NIS in IdM
- /usr/share/doc/ansible-freeipa/README-netgroup.md
- /usr/share/doc/ansible-freeipa/playbooks/netgroup

33.7. USING ANSIBLE TO ENSURE THAT A NETGROUP IS ABSENT

You can use an Ansible playbook to ensure that a netgroup does not exist in Identity Management (IdM). The example describes how to ensure that the **TestNetgroup1** group does not exist in your IdM domain.

Prerequisites

You have configured your Ansible control node to meet the following requirements:

- You are using Ansible version 2.14 or later.
- You have installed the **ansible-freeipa** package on the Ansible controller.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
- You have stored your **ipaadmin_password** in the **secret.yml** Ansible vault.

1. Create your Ansible playbook file **netgroup-absent.yml** with the following content:

```
---
- name: Playbook to manage IPA netgroup.
hosts: ipaserver
become: no

vars_files:
- /home/user_name/MyPlaybooks/secret.yml
tasks:
- name: Ensure netgroup my_netgroup1 is absent
ipanetgroup:
    ipaadmin_password: "{{ ipaadmin_password }}"
    name: my_netgroup1
    state: absent
```

2. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory_/netgroupabsent.yml

Additional resources

- NIS in IdM
- /usr/share/doc/ansible-freeipa/README-netgroup.md
- /usr/share/doc/ansible-freeipa/playbooks/netgroup

CHAPTER 34. USING ANSIBLE TO CONFIGURE HBAC AND SUDO RULES IN IDM

Using host-based access control (HBAC) in Identity Management (IdM), you can define policies that restrict access to hosts or services based on the following:

- The user attempting to log in and this user's groups
- The host that a user is trying to access and the host groups to which that host belongs
- The service that is being used to access a host


Using **sudo**, a user can run programs as another user, with different privileges, for example **root** privileges. In IdM, you can manage sudo rules centrally. You can define **sudo** rules based on user groups, host groups and command groups, as well as individual users, hosts and commands.

Complete this procedure to ensure the presence of the following HBAC and **sudo** rules for IdM users:

- jane can only access host client01.idm.example.com.
- john can only access host client02.idm.example.com.
- Members of the admins group, which includes the default admin user as well as the regular alice user, can access any IdM host.
- Members of the **admins** group can run **sudo** with the following commands on any IdM host:
 - /usr/sbin/reboot
 - /usr/bin/less
 - /usr/sbin/setenforce

The following diagram represents the desired configuration described above:

Figure 34.1. IdM HBAC and SUDO rules diagram



NOTE

The procedure illustrates the use of an action group that simplifies the use of modules with **module_defaults**, which is only available in the **freeipa.ansible_freeipa** collection, not the **ansible-freeipa rpm**. You can set default values to be applied to all modules of the collection used in a playbook by using the **action_group** named **freeipa.ansible_freeipa.modules**. In the example, the IdM administrator password is defined in this way. The **ansible-freeipa-collection** is part of the **rhel-9-for-x86 64-appstream-rpms** repository in RHEL 9.5 and later.

Prerequisites

- On the control node:
 - You are using Ansible version 2.14 or later.
 - You are using RHEL version 9.5 or later.
 - You have installed the **ansible-freeipa-collection** subpackage.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server in the ~/MyPlaybooks/ directory.
 - You have stored your **ipaadmin password** in the **secret.yml** Ansible vault.
- The users jane, john and alice exist in IdM. Passwords are configured for these accounts.

Procedure

1. Create your Ansible playbook file **add-hbac-and-sudo-rules-to-idm.yml** with the following content:

- name: Playbook to manage IPA HBAC and SUDO rules hosts: ipaserver become: false gather_facts: false collections: freeipa.ansible_freeipa vars files: - /home/<user_name>/MyPlaybooks/secret.yml module defaults: group/freeipa.ansible freeipa.modules: ipaadmin_password: "{{ ipaadmin_password }}" tasks: - name: HBAC Rule for Jane - can log in to client01 ipahbacrule: # Creates the rule name: Jane_rule hbacsvc: - sshd - login host: # Host name - client01.idm.example.com user: - jane - name: HBAC Rule for John - can log in to client02 ipahbacrule: # Creates the rule name: john_rule hbacsvc: - sshd - login host: # Host name - client02.idm.example.com user: - john - name: Add user member alice to group admins ipagroup: name: admins action: member user: - alice - name: HBAC Rule for IdM administrators ipahbacrule: # Rule to allow admins full access name: admin access # Rule name servicecat: all # All services hostcat: all # All hosts group: # User group - admins - name: Add reboot command to SUDO ipasudocmd: name: /usr/sbin/reboot

state: present

357

- name: Add less command to SUDO

ipasudocmd:

name: /usr/bin/less state: present

- name: Add setenforce command to SUDO

ipasudocmd:

name: /usr/sbin/setenforce

state: present

- name: Create a SUDO command group

ipasudocmdgroup: name: cmd_grp_1

description: "Group of important commands"

sudocmd:

- /usr/sbin/setenforce
- /usr/bin/less
- /usr/sbin/reboot

action: sudocmdgroup

state: present

- name: Create a SUDO rule with a SUDO command group

ipasudorule:

name: sudo_rule_1 allow sudocmdgroup:

- cmd_grp_1 group: admins state: present

- name: Disable allow_all HBAC Rule

ipahbacrule: # Rule to allow admins full access

name: allow_all # Rule name

state: disabled # Disables rule to allow everyone the ability to login

2. Run the playbook:

\$ ansible-playbook --vault-password-file=password_file -i inventory add-hbac-and-sudo-rules-to-idm.yml

Verification

1. Connect to client01 as the jane user:

~]\$ ssh jane@client01

Password:

Last login: Fri Aug 11 15:32:18 2023 from 192.168.122.1 [jane@client01 ~]\$

The output verifies that jane has logged in to client01.

2. Try to connect to client02 as the jane user:

~]\$ ssh jane@client02

Password:

Connection closed by 192.168.122.47 port 22

The output verifies that jane cannot log in to client02.

3. Connect to client02 as the alice user:

```
~]$ ssh alice@client02
Password:
```

Last login: Fri Aug 10 16:13:43 2023 from 192.168.122.1

The output verifies that alice has logged in to client02.

4. Try to view the contents of the /etc/sssd/sssd.conf file using less without invoking the superuser privileges:

```
[alice@client02 ~]$ less /etc/sssd/sssd.conf /etc/sssd/sssd.conf: Permission denied
```

The attempt fails as the file is not readable by anyone except the owner of the file, which is root.

5. Invoke the **root** privileges to view the contents of the /etc/sssd/sssd.conf file using less:

```
[alice@client02 ~]$ sudo less /etc/sssd/sssd.conf
[sudo] password for alice:

[domain/idm.example.com]

id_provider = ipa
ipa_server_mode = True
[...]
```

The output verifies that alice can execute the less command on the /etc/sssd/sssd.conf file.

Additional resources

- Host-based access control rules in IdM
- Sudo access on an IdM client
- Using collections in a playbook

CHAPTER 35. USING ANSIBLE TO DELEGATE AUTHENTICATION FOR IDM USERS TO EXTERNAL IDENTITY PROVIDERS

You can use the **idp ansible-freeipa** module to associate users with external identity providers (IdP) that support the OAuth 2 device authorization flow. If an IdP reference and an associated IdP user ID exist, you can use them to enable IdP authentication for an IdM user with the **user ansible-freeipa** module.

Afterward, if these users authenticate with the SSSD version available in RHEL 9.1 or later, they receive RHEL Identity Management (IdM) single sign-on capabilities with Kerberos tickets after performing authentication and authorization at the external IdP.

35.1. THE BENEFITS OF CONNECTING IDM TO AN EXTERNAL IDP

As an administrator, you might want to allow users stored in an external identity source, such as a cloud services provider, to access RHEL systems joined to your Identity Management (IdM) environment. To achieve this, you can delegate the authentication and authorization process of issuing Kerberos tickets for these users to that external entity.

You can use this feature to expand IdM's capabilities and allow users stored in external identity providers (IdPs) to access Linux systems managed by IdM.

35.2. HOW IDM INCORPORATES LOGINS VIA EXTERNAL IDPS

SSSD 2.7.0 contains the **sssd-idp** package, which implements the **idp** Kerberos pre-authentication method. This authentication method follows the OAuth 2.0 Device Authorization Grant flow to delegate authorization decisions to external IdPs:

- 1. An IdM client user initiates OAuth 2.0 Device Authorization Grant flow, for example, by attempting to retrieve a Kerberos Ticket Granting Ticket (TGT) with the **kinit** utility at the command line.
- 2. A special code and website link are sent from the Authorization Server to the IdM Key Distribution Center (KDC) backend.
- 3. The IdM client displays the link and the code to the user. In this example, the IdM client outputs the link and code on the command line.
- 4. The user opens the website link in a browser, which can be on another host, a mobile phone, and so on:
 - a. The user enters the special code.
 - b. If necessary, the user logs in to the OAuth 2.0-based IdP.
 - c. The user is prompted to authorize the client to access information.
- 5. The user confirms access at the original device prompt. In this example, the user hits the **Enter** key at the command line.
- 6. The IdM KDC backend polls the OAuth 2.0 Authorization Server for access to user information.

What is supported:

- Logging in remotely via Secure Shell (SSH) with the **keyboard-interactive** authentication method enabled, which allows calling Pluggable Authentication Module (PAM) libraries.
- Logging in locally with the console via the **logind** service.
- Retrieving a Kerberos TGT with the **kinit** utility.

What is currently not supported:

- Logging in to the IdM WebUI directly. To log in to the IdM WebUI, you must first acquire a Kerberos ticket.
- Logging in to Cockpit WebUI directly. To log in to the Cockpit WebUI, you must first acquire a Kerberos ticket.

Additional resources

- Authentication against external Identity Providers
- RFC 8628: OAuth 2.0 Device Authorization Grant

35.3. USING ANSIBLE TO CREATE A REFERENCE TO AN EXTERNAL IDENTITY PROVIDER

To connect external identity providers (IdPs) to your Identity Management (IdM) environment, create IdP references in IdM. Complete this procedure to use the **idp ansible-freeipa** module to configure a reference to the **github** external IdP.

Prerequisites

- You have registered IdM as an OAuth application to your external IdP, and generated a client ID and client secret on the device that an IdM user will be using to authenticate to IdM. The example assumes that:
 - my_github_account_name is the github user whose account the IdM user will be using to authenticate to IdM.
 - The client ID is 2efe1acffe9e8ab869f4.
 - The client secret is 656a5228abc5f9545c85fa626aecbf69312d398c.
- Your IdM servers are using RHEL 9.1 or later.
- Your IdM servers are using SSSD 2.7.0 or later.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package on the Ansible controller.
 - You are using RHEL 9.4 or later.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.

• The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.

Procedure

1. On your Ansible control node, create an **configure-external-idp-reference.yml** playbook:

- name: Configure external IdP

hosts: ipaserver become: false gather_facts: false

tasks:

- name: Ensure a reference to github external provider is available

ipaidp:

ipaadmin_password: "{{ ipaadmin_password }}"

name: github_idp provider: github

client ID: 2efe1acffe9e8ab869f4

secret: 656a5228abc5f9545c85fa626aecbf69312d398c

idp_user_id: my_github_account_name

- 2. Save the file.
- 3. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory configure-external-idp-reference.yml

Verification

• On an IdM client, verify that the output of the **ipa idp-show** command shows the IdP reference you have created.

[idmuser@idmclient ~]\$ ipa idp-show github_idp

Next steps

• Using Ansible to enable an IdM user to authenticate via an external IdP

Additional resources

• The idp **ansible-freeipa** upstream documentation

35.4. USING ANSIBLE TO ENABLE AN IDM USER TO AUTHENTICATE VIA AN EXTERNAL IDP

You can use the **user ansible-freeipa** module to enable an Identity Management (IdM) user to authenticate via an external identity provider (IdP). To do that, associate the external IdP reference you have previously created with the IdM user account. Complete this procedure to use Ansible to associate

an external IdP reference named **github_idp** with the IdM user named **idm-user-with-external-idp**. As a result of the procedure, the user is able to use the **my_github_account_name** github identity to authenticate as **idm-user-with-external-idp** to IdM.

Prerequisites

- Your IdM client and IdM servers are using RHEL 9.1 or later.
- Your IdM client and IdM servers are using SSSD 2.7.0 or later.
- You have created a reference to an external IdP in IdM. See Using Ansible to create a reference to an external identity provider.
- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package on the Ansible controller.
 - You are using RHEL 9.4 or later.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.

Procedure

1. On your Ansible control node, create an **enable-user-to-authenticate-via-external-idp.yml** playbook:

```
- name: Ensure an IdM user uses an external IdP to authenticate to IdM
 hosts: ipaserver
 become: false
 gather_facts: false
 tasks:
 - name: Retrieve Github user ID
  ansible.builtin.uri:
   url: "https://api.github.com/users/my_github_account_name"
   method: GET
   headers:
    Accept: "application/vnd.github.v3+json"
  register: user data
 - name: Ensure IdM user exists with an external IdP authentication
  ipauser:
   ipaadmin_password: "{{ ipaadmin_password }}"
   name: idm-user-with-external-idp
   first: Example
   last: User
   userauthtype: idp
   idp: github_idp
   idp user id: my github account name
```

- 2. Save the file.
- 3. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory enable-user-to-authenticate-via-external-idp.yml

Verification

• Log in to an IdM client and verify that the output of the **ipa user-show** command for the **idm-user-with-external-idp** user displays references to the IdP:

\$ ipa user-show idm-user-with-external-idp

User login: idm-user-with-external-idp

First name: Example Last name: User

Home directory: /home/idm-user-with-external-idp

Login shell: /bin/sh

Principal name: idm-user-with-external-idp@idm.example.com Principal alias: idm-user-with-external-idp@idm.example.com Email address: idm-user-with-external-idp@idm.example.com

ID: 35000003 GID: 35000003

User authentication types: idp External IdP configuration: github

External IdP user identifier: idm-user-with-external-idp@idm.example.com

Account disabled: False

Password: False

Member of groups: ipausers Kerberos keys available: False

Additional resources

• The idp **ansible-freeipa** upstream documentation

35.5. RETRIEVING AN IDM TICKET-GRANTING TICKET AS AN EXTERNAL IDP USER

If you have delegated authentication for an Identity Management (IdM) user to an external identity provider (IdP), the IdM user can request a Kerberos ticket-granting ticket (TGT) by authenticating to the external IdP.

Complete this procedure to:

- 1. Retrieve and store an anonymous Kerberos ticket locally.
- 2. Request the TGT for the idm-user-with-external-idp user by using kinit with the -T option to enable Flexible Authentication via Secure Tunneling (FAST) channel to provide a secure connection between the Kerberos client and Kerberos Distribution Center (KDC).

Prerequisites

• Your IdM client and IdM servers use RHEL 9.1 or later.

- Your IdM client and IdM servers use SSSD 2.7.0 or later.
- You have created a reference to an external IdP in IdM. See Using Ansible to create a reference to an external identity provider.
- You have associated an external IdP reference with the user account. See Using Ansible to enable an IdM user to authenticate via an external IdP.
- The user that you are initially logged in as has write permissions on a directory in the local filesystem.

Procedure

1. Use Anonymous PKINIT to obtain a Kerberos ticket and store it in a file named ./fast.ccache.

\$ kinit -n -c ./fast.ccache

2. Optional: View the retrieved ticket:

\$ klist -c fast.ccache

Ticket cache: FILE:fast.ccache

Default principal: WELLKNOWN/ANONYMOUS@WELLKNOWN:ANONYMOUS

Valid starting Expires Service principal

03/03/2024 13:36:37 03/04/2024 13:14:28

krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM

3. Begin authenticating as the IdM user, using the **-T** option to enable the FAST communication channel.

[root@client ~]# kinit -T ./fast.ccache idm-user-with-external-idp
Authenticate at https://oauth2.idp.com:8443/auth/realms/master/device?user_code=YHMQ-XKTL and press ENTER.:

- 4. In a browser, authenticate as the user at the website provided in the command output.
- 5. At the command line, press the **Enter** key to finish the authentication process.

Verification

• Display your Kerberos ticket information and confirm that the line **config: pa_type** shows **152** for pre-authentication with an external IdP.

[root@client ~]# klist -C Ticket cache: KCM:0:58420

Default principal: idm-user-with-external-idp@IDM.EXAMPLE.COM

Valid starting Expires Service principal

05/09/22 07:48:23 05/10/22 07:03:07 krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM

config: fast_avail(krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM) = yes

08/17/2022 20:22:45 08/18/2022 20:22:43

krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM

config: pa_type(krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM) = 152

The **pa_type = 152** indicates external IdP authentication.

35.6. LOGGING IN TO AN IDM CLIENT VIA SSH AS AN EXTERNAL IDP USER

To log in to an IdM client via SSH as an external identity provider (IdP) user, begin the login process on the command linel. When prompted, perform the authentication process at the website associated with the IdP, and finish the process at the Identity Management (IdM) client.

Prerequisites

- Your IdM client and IdM servers are using RHEL 9.1 or later.
- Your IdM client and IdM servers are using SSSD 2.7.0 or later.
- You have created a reference to an external IdP in IdM. See Using Ansible to create a reference to an external identity provider.
- You have associated an external IdP reference with the user account. See Using Ansible to enable an IdM user to authenticate via an external IdP.

Procedure

1. Attempt to log in to the IdM client via SSH.

[user@client ~]\$ ssh idm-user-with-external-idp@client.idm.example.com (idm-user-with-external-idp@client.idm.example.com) Authenticate at https://oauth2.idp.com:8443/auth/realms/main/device?user_code=XYFL-ROYR and press ENTER.

- 2. In a browser, authenticate as the user at the website provided in the command output.
- 3. At the command line, press the **Enter** key to finish the authentication process.

Verification

Display your Kerberos ticket information and confirm that the line config: pa_type shows 152 for pre-authentication with an external IdP.

[idm-user-with-external-idp@client ~]\$ klist -C

Ticket cache: KCM:0:58420

Default principal: idm-user-with-external-idp@IDM.EXAMPLE.COM

Valid starting Expires Service principal

05/09/22 07:48:23 05/10/22 07:03:07 krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM

config: fast_avail(krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM) = yes

08/17/2022 20:22:45 08/18/2022 20:22:43

krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM

config: pa type(krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM) = 152

35.7. THE PROVIDER OPTION IN THE IPAIDP ANSIBLE MODULE

The following identity providers (IdPs) support OAuth 2.0 device authorization grant flow:

- Microsoft Identity Platform, including Azure AD
- Google
- GitHub
- Keycloak, including Red Hat Single Sign-On (SSO)
- Okta

When using the **idp ansible-freeipa** module to create a reference to one of these external IdPs, you can specify the IdP type with the **provider** option in your **ipaidp ansible-freeipa** playbook task, which expands into additional options as described below:

provider: microsoft

Microsoft Azure IdPs allow parametrization based on the Azure tenant ID, which you can specify with the **organization** option. If you need support for the live.com IdP, specify the option **organization common**.

Choosing **provider: microsoft** expands to use the following options. The value of the **organization** option replaces the string **\${ipaidporg}** in the table.

Option	Value
auth_uri: URI	https://login.microsoftonline.com/\${ipaidporg}/oauth2/v2.0/authorize
dev_auth_uri: URI	https://login.microsoftonline.com/\${ipaidporg}/oauth2/v2.0/devicecode
token_uri: URI	https://login.microsoftonline.com/\${ipaidporg}/oauth2/v2.0/t oken
userinfo_uri: URI	https://graph.microsoft.com/oidc/userinfo
keys_uri: URI	https://login.microsoftonline.com/common/discovery/v2.0/k eys
scope: STR	openid email
idp_user_id: STR	email

provider: google

Choosing **provider: google** expands to use the following options:

Option	Value
auth_uri: URI	https://accounts.google.com/o/oauth2/auth
dev_auth_uri: URI	https://oauth2.googleapis.com/device/code

Option	Value
token_uri: URI	https://oauth2.googleapis.com/token
userinfo_uri: URI	https://openidconnect.googleapis.com/v1/userinfo
keys_uri: URI	https://www.googleapis.com/oauth2/v3/certs
scope: STR	openid email
idp_user_id: STR	email

provider: github

Choosing **provider: github** expands to use the following options:

Option	Value
auth_uri: URI	https://github.com/login/oauth/authorize
dev_auth_uri: URI	https://github.com/login/device/code
token_uri: URI	https://github.com/login/oauth/access_token
userinfo_uri: URI	https://openidconnect.googleapis.com/v1/userinfo
keys_uri: URI	https://api.github.com/user
scope: STR	user
idp_user_id: STR	login

provider: keycloak

With Keycloak, you can define multiple realms or organizations. Since it is often a part of a custom deployment, both base URL and realm ID are required, and you can specify them with the **base_url** and **organization** options in your **ipaidp** playbook task:

- name: Playbook to manage IPA idp

hosts: ipaserver become: false

tasks

- name: Ensure keycloak idp my-keycloak-idp is present using provider

ipaidp:

ipaadmin_password: "{{ ipaadmin_password }}"

name: my-keycloak-idp provider: keycloak organization: main

base_url: keycloak.domain.com:8443/auth

client_id: my-keycloak-client-id

Choosing **provider: keycloak** expands to use the following options. The value you specify in the **base_url** option replaces the string **\${ipaidpbaseurl}** in the table, and the value you specify for the **organization `option replaces the string `\${ipaidporg}**.

Option	Value
auth_uri: URI	https://\${ipaidpbaseurl}/realms/\${ipaidporg}/protocol/openid-connect/auth
dev_auth_uri: URI	https://\${ipaidpbaseurl}/realms/\${ipaidporg}/protocol/openi d-connect/auth/device
token_uri: URI	https://\${ipaidpbaseurl}/realms/\${ipaidporg}/protocol/openi d-connect/token
userinfo_uri: URI	https://\${ipaidpbaseurl}/realms/\${ipaidporg}/protocol/openi d-connect/userinfo
scope: STR	openid email
idp_user_id: STR	email

provider: okta

After registering a new organization in Okta, a new base URL is associated with it. You can specify this base URL with the **base_url** option in the **ipaidp** playbook task:

- name: Playbook to manage IPA idp

hosts: ipaserver become: false

tasks:

- name: Ensure okta idp my-okta-idp is present using provider

ipaidp:

ipaadmin_password: "{{ ipaadmin_password }}"

name: my-okta-idp provider: okta

base_url: dev-12345.okta.com client_id: my-okta-client-id

Choosing **provider: okta** expands to use the following options. The value you specify for the **base_url** option replaces the string **\${ipaidpbaseurl}** in the table.

Option	Value
auth_uri: URI	https://\${ipaidpbaseurl}/oauth2/v1/authorize

Option	Value
dev_auth_uri: URI	https://\${ipaidpbaseurl}/oauth2/v1/device/authorize
token_uri: URI	https://\${ipaidpbaseurl}/oauth2/v1/token
userinfo_uri: URI	https://\${ipaidpbaseurl}/oauth2/v1/userinfo
scope: STR	openid email
idp_user_id: STR	email

Additional resources

• Pre-populated IdP templates

CHAPTER 36. USING CONSTRAINED DELEGATION IN IDM

Learn more about how you can use the constrained delegation feature in Identity Management (IdM):

- Constrained delegation in Identity Management describes how constrained delegation works.
- Configuring a web console to allow a user authenticated with a smart card to SSH to a remote
 host without being asked to authenticate again describes a use case for constrained delegation
 in the context of using the Red Hat Enterprise Linux web console to SSH to a remote host
 without requiring authentication.
- Using Ansible to configure a web console to allow a user authenticated with a smart card to SSH
 to a remote host without being asked to authenticate again describes a use case for constrained
 delegation in the context of using Ansible to configure the use of the Red Hat Enterprise Linux
 web console to SSH to a remote host without requiring authentication.
- Configuring a web console client to allow a user authenticated with a smart card to run sudo without being asked to authenticate describes a use case for constrained delegation in the context of using the Red Hat Enterprise Linux web console to run **sudo** without requiring authentication.
- Using Ansible to configure a web console to allow a user authenticated with a smart card to run sudo without being asked to authenticate again describes a use case for constrained delegation in the context of using Ansible to configure the use of the Red Hat Enterprise Linux web console to run **sudo** without requiring authentication.

36.1. CONSTRAINED DELEGATION IN IDENTITY MANAGEMENT

The Service for User to Proxy (**S4U2proxy**) extension provides a service that obtains a service ticket to another service on behalf of a user. This feature is known as **constrained delegation**. The second service is typically a proxy performing some work on behalf of the first service, under the authorization context of the user. Using constrained delegation eliminates the need for the user to delegate their full ticket-granting ticket (TGT).

Identity Management (IdM) traditionally uses the Kerberos **S4U2proxy** feature to allow the web server framework to obtain an LDAP service ticket on the user's behalf. The IdM-AD trust system also uses constrained delegation to obtain a **cifs** principal.

You can use the **S4U2proxy** feature to configure a web console client to allow an IdM user that has authenticated with a smart card to achieve the following:

- Run commands with superuser privileges on the RHEL host on which the web console service is running without being asked to authenticate again.
- Access a remote host using **SSH** and access services on the host without being asked to authenticate again.

Additional resources

- S4U2proxy
- Service constrained delegation

36.2. CONFIGURING THE WEB CONSOLE TO ALLOW A USER AUTHENTICATED WITH A SMART CARD TO SSH TO A REMOTE HOST WITHOUT BEING ASKED TO AUTHENTICATE AGAIN

After logging in to a user account on the RHEL web console, you can connect to remote machines by using the SSH protocol. You can use the constrained delegation feature to use **SSH** without being asked to authenticate again.

In the example procedure, the web console session runs on the **myhost.idm.example.com** host, and you configure the console to access the **remote.idm.example.com** host by using SSH on behalf of the authenticated user.

Prerequisites

- You have obtained an IdM **admin** ticket-granting ticket (TGT).
- You have **root** access to **remote.idm.example.com**.
- The **cockpit** service is running in IdM.
- The web console has created an **S4U2Proxy** Kerberos ticket in the user session. To verify it, log in to the web console as an IdM user, open the **Terminal** page, and enter:

\$ klist

Ticket cache: FILE:/run/user/1894000001/cockpit-session-3692.ccache

Default principal: user@IDM.EXAMPLE.COM

Valid starting Expires Service principal

07/30/21 09:19:06 07/31/21 09:19:06

HTTP/myhost.idm.example.com@IDM.EXAMPLE.COM

07/30/21 09:19:06 07/31/21 09:19:06 krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM

for client HTTP/myhost.idm.example.com@IDM.EXAMPLE.COM

Procedure

- 1. Create a list of the target hosts that the delegation rule can access:
 - a. Create a service delegation target:
 - \$ ipa servicedelegationtarget-add cockpit-target
 - b. Add the target host to the delegation target:
 - \$ ipa servicedelegationtarget-add-member cockpit-target \
 --principals=host/remote.idm.example.com@IDM.EXAMPLE.COM
- 2. Allow **cockpit** sessions to access the target host list by creating a service delegation rule and adding the HTTP service Kerberos principal to it:
 - a. Create a service delegation rule:
 - \$ ipa servicedelegationrule-add cockpit-delegation
 - b. Add the web console client to the delegation rule:

\$ ipa servicedelegationrule-add-member cockpit-delegation \ --principals=HTTP/myhost.idm.example.com@IDM.EXAMPLE.COM

c. Add the delegation target to the delegation rule:

\$ ipa servicedelegationrule-add-target cockpit-delegation \
--servicedelegationtargets=cockpit-target

- 3. Enable Kerberos authentication on the **remote.idm.example.com** host:
 - a. Connect through SSH to remote.idm.example.com as root.
 - b. Open the /etc/ssh/sshd_config file for editing.
 - c. Enable **GSSAPIAuthentication** by uncommenting the **GSSAPIAuthentication no** line and replacing it with **GSSAPIAuthentication yes**.
- 4. Restart the **sshd** service on **remote.idm.example.com** so that the changes take effect immediately:

\$ systemctl try-restart sshd.service

Additional resources

- Logging in to the web console with smart cards
- Constrained delegation in Identity Management

36.3. USING ANSIBLE TO CONFIGURE THE WEB CONSOLE TO ALLOW A USER AUTHENTICATED WITH A SMART CARD TO SSH TO A REMOTE HOST WITHOUT BEING ASKED TO AUTHENTICATE AGAIN

After logging in to a user account on the RHEL web console, you can connect to remote machines by using the SSH protocol. You can use the **servicedelegationrule** and **servicedelegationtarget** modules to configure the web console for the constrained delegation feature, which enables SSH connections without being asked to authenticate again.

In the example procedure, the web console session runs on the **myhost.idm.example.com** host and you configure it to access the **remote.idm.example.com** host by using SSH on behalf of the authenticated user.

Prerequisites

- The IdM **admin** password.
- root access to remote.idm.example.com.
- The web console service runs in IdM.
- The web console has created an **S4U2Proxy** Kerberos ticket in the user session. To verify it, log in to the web console as an IdM user, open the **Terminal** page, and enter:

\$ klist

Ticket cache: FILE:/run/user/1894000001/cockpit-session-3692.ccache

Default principal: user@IDM.EXAMPLE.COM

Valid starting Expires Service principal 07/30/21 09:19:06 07/31/21 09:19:06
HTTP/myhost.idm.example.com@IDM.EXAMPLE.COM 07/30/21 09:19:06 07/31/21 09:19:06 krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM for client HTTP/myhost.idm.example.com@IDM.EXAMPLE.COM

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

- 2. Create a web-console-smart-card-ssh.yml playbook with the following content:
 - a. Create a task that ensures the presence of a delegation target:

- name: Playbook to create a constrained delegation target

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure servicedelegationtarget web-console-delegation-target is present ipaservicedelegationtarget:

ipaadmin_password: "{{ ipaadmin_password }}"

name: web-console-delegation-target

- b. Add a task that adds the target host to the delegation target:
 - name: Ensure servicedelegationtarget web-console-delegation-target member principal host/remote.idm.example.com@IDM.EXAMPLE.COM is present ipaservicedelegationtarget:

ipaadmin_password: "{{ ipaadmin_password }}"

name: web-console-delegation-target

principal: host/remote.idm.example.com@IDM.EXAMPLE.COM

action: member

c. Add a task that ensures the presence of a delegation rule:

 name: Ensure servicedelegationrule delegation-rule is present ipaservicedelegationrule: ipaadmin_password: "{{ ipaadmin_password }}" name: web-console-delegation-rule

- d. Add a task that ensures that the Kerberos principal of the web console client service is a member of the constrained delegation rule:
 - name: Ensure the Kerberos principal of the web console client service is added to the servicedelegationrule web-console-delegation-rule

ipaservicedelegationrule:

ipaadmin_password: "{{ ipaadmin_password }}"

name: web-console-delegation-rule

principal: HTTP/myhost.idm.example.com

action: member

- e. Add a task that ensures that the constrained delegation rule is associated with the webconsole-delegation-target delegation target:
 - name: Ensure a constrained delegation rule is associated with a specific delegation arget

ipaservicedelegationrule:

ipaadmin_password: "{{ ipaadmin_password }}"

name: web-console-delegation-rule target: web-console-delegation-target

action: member

- 3. Save the file.
- 4. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory web-console-smart-card-ssh.yml

- 5. Enable Kerberos authentication on **remote.idm.example.com**:
 - a. Connect through SSH to remote.idm.example.com as root.
 - b. Open the /etc/ssh/sshd_config file for editing.
 - c. Enable **GSSAPIAuthentication** by uncommenting the **GSSAPIAuthentication no** line and replacing it with **GSSAPIAuthentication yes**.
- 6. Restart the **sshd** service on **remote.idm.example.com** so that the changes take effect immediately:

\$ systemctl try-restart sshd.service

Additional resources

- Logging in to the web console with smart cards
- Constrained delegation in Identity Management

- README-servicedelegationrule.md and README-servicedelegationtarget.md in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/servicedelegationtarget and /usr/share/doc/ansible-freeipa/playbooks/servicedelegationrule directories

36.4. CONFIGURING A WEB CONSOLE TO ALLOW A USER AUTHENTICATED WITH A SMART CARD TO RUN SUDO WITHOUT BEING ASKED TO AUTHENTICATE AGAIN

After you have logged in to a user account on the RHEL web console, as an Identity Management (IdM) system administrator you might need to run commands with superuser privileges. You can use the constrained delegation feature to run **sudo** on the system without being asked to authenticate again.

Follow this procedure to configure a web console to use constrained delegation. In the example below, the web console session runs on the **myhost.idm.example.com** host.

Prerequisites

- You have obtained an IdM **admin** ticket-granting ticket (TGT).
- The web console service is present in IdM.
- The myhost.idm.example.com host is present in IdM.
- You enabled **admin sudo** access to domain administrators on the IdM server. For details, see Enabling sudo access for IdM administrators on IdM hosts.
- The web console has created an **S4U2Proxy** Kerberos ticket in the user session. To verify that this is the case, log in to the web console as an IdM user, open the **Terminal** page, and enter:

\$ klist

Ticket cache: FILE:/run/user/1894000001/cockpit-session-3692.ccache

Default principal: user@IDM.EXAMPLE.COM

Valid starting Expires Service principal

07/30/21 09:19:06 07/31/21 09:19:06

HTTP/myhost.idm.example.com@IDM.EXAMPLE.COM

07/30/21 09:19:06 07/31/21 09:19:06 krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM for client HTTP/myhost.idm.example.com@IDM.EXAMPLE.COM

Procedure

- 1. Create a list of the target hosts that can be accessed by the delegation rule:
 - a. Create a service delegation target:
 - \$ ipa servicedelegationtarget-add cockpit-target
 - b. Add the target host to the delegation target:
 - \$ ipa servicedelegationtarget-add-member cockpit-target \
 --principals=host/myhost.idm.example.com@IDM.EXAMPLE.COM

- 2. Allow **cockpit** sessions to access the target host list by creating a service delegation rule and adding the **HTTP** service Kerberos principal to it:
 - a. Create a service delegation rule:
 - \$ ipa servicedelegationrule-add cockpit-delegation
 - b. Add the web console service to the delegation rule:
 - \$ ipa servicedelegationrule-add-member cockpit-delegation \
 --principals=HTTP/myhost.idm.example.com@IDM.EXAMPLE.COM
 - c. Add the delegation target to the delegation rule:
 - \$ ipa servicedelegationrule-add-target cockpit-delegation \
 --servicedelegationtargets=cockpit-target
- 3. Enable **pam_sss_gss**, the PAM module for authenticating users over the Generic Security Service Application Program Interface (GSSAPI) in cooperation with the System Security Services Daemon (SSSD):
 - a. Open the /etc/sssd/sssd.conf file for editing.
 - b. Specify that **pam_sss_gss** can provide authentication for the **sudo** and **sudo -i** commands in IdM your domain:

[domain/idm.example.com]
pam_gssapi_services = sudo, sudo-i

- c. Save and exit the file.
- d. Open the /etc/pam.d/sudo file for editing.
- e. Insert the following line to the top of the **#%PAM-1.0** list to allow, but not require, GSSAPI authentication for **sudo** commands:

auth sufficient pam_sss_gss.so

- f. Save and exit the file.
- 4. Restart the **SSSD** service so that the above changes take effect immediately:

\$ systemctl restart sssd

Additional resources

- Logging in to the web console with smart cards
- Constrained delegation in Identity Management

36.5. USING ANSIBLE TO CONFIGURE A WEB CONSOLE TO ALLOW A USER AUTHENTICATED WITH A SMART CARD TO RUN SUDO WITHOUT BEING ASKED TO AUTHENTICATE AGAIN

After you have logged in to a user account on the RHEL web console, as an Identity Management (IdM) system administrator you might need to run commands with superuser privileges. You can use the constrained delegation feature to run **sudo** on the system without being asked to authenticate again.

Follow this procedure to use the **ipaservicedelegationrule** and **ipaservicedelegationtarget ansible-freeipa** modules to configure a web console to use constrained delegation. In the example below, the web console session runs on the **myhost.idm.example.com** host.

Prerequisites

- You have obtained an IdM **admin** ticket-granting ticket (TGT) by authenticating to the web console session with a smart card..
- The web console service has been enrolled into IdM.
- The myhost.idm.example.com host is present in IdM.
- You enabled **admin sudo** access to domain administrators on the IdM server. For details, see Enabling sudo access for IdM administrators on IdM hosts .
- The web console has created an **S4U2Proxy** Kerberos ticket in the user session. To verify that this is the case, log in to the web console as an IdM user, open the **Terminal** page, and enter:

\$ klist

Ticket cache: FILE:/run/user/1894000001/cockpit-session-3692.ccache

Default principal: user@IDM.EXAMPLE.COM

Valid starting Expires Service principal

07/30/21 09:19:06 07/31/21 09:19:06

HTTP/myhost.idm.example.com@IDM.EXAMPLE.COM

07/30/21 09:19:06 07/31/21 09:19:06 krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM for client HTTP/myhost.idm.example.com@IDM.EXAMPLE.COM

- You have configured your Ansible control node to meet the following requirements:
 - You are using Ansible version 2.14 or later.
 - You have installed the **ansible-freeipa** package.
 - The example assumes that in the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring the constrained delegation.
 - The example assumes that the **secret.yml** Ansible vault stores your **ipaadmin_password**.
- The target node, that is the node on which the **ansible-freeipa** module is executed, is part of the IdM domain as an IdM client, server or replica.

Procedure

1. On your Ansible control node, navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

- 2. Create a web-console-smart-card-sudo.yml playbook with the following content:

a. Create a task that ensures the presence of a delegation target:

- name: Playbook to create a constrained delegation target

hosts: ipaserver

vars_files:

- /home/user_name/MyPlaybooks/secret.yml

- name: Ensure servicedelegationtarget named sudo-web-console-delegation-target is present

ipaservicedelegationtarget:

ipaadmin_password: "{{ ipaadmin_password }}"
name: sudo-web-console-delegation-target

- b. Add a task that adds the target host to the delegation target:
 - name: Ensure that a member principal named host/myhost.idm.example.com@IDM.EXAMPLE.COM is present in a service delegation target named sudo-web-console-delegation-target ipaservicedelegationtarget:

ipaadmin_password: "{{ ipaadmin_password }}"

name: sudo-web-console-delegation-target

principal: host/myhost.idm.example.com@IDM.EXAMPLE.COM

action: member

- c. Add a task that ensures the presence of a delegation rule:
 - name: Ensure servicedelegationrule named sudo-web-console-delegation-rule is present

ipaservicedelegationrule:

ipaadmin_password: "{{ ipaadmin_password }}"

- name: sudo-web-console-delegation-rule
- d. Add a task that ensures that the Kerberos principal of the web console service is a member of the constrained delegation rule:
 - name: Ensure the Kerberos principal of the web console service is added to the service delegation rule named sudo-web-console-delegation-rule

ipaservicedelegationrule:

ipaadmin_password: "{{ ipaadmin_password }}"
name: sudo-web-console-delegation-rule

principal: HTTP/myhost.idm.example.com

action: member

- e. Add a task that ensures that the constrained delegation rule is associated with the sudoweb-console-delegation-target delegation target:
 - name: Ensure a constrained delegation rule is associated with a specific delegation target

ipaservicedelegationrule:

ipaadmin_password: "{{ ipaadmin_password }}"

name: sudo-web-console-delegation-rule

target: sudo-web-console-delegation-target

action: member

3. Save the file.

4. Run the Ansible playbook. Specify the playbook file, the file storing the password protecting the **secret.yml** file, and the inventory file:

\$ ansible-playbook --vault-password-file=password_file -v -i inventory web-console-smart-card-sudo.yml

- 5. Enable **pam_sss_gss**, the PAM module for authenticating users over the Generic Security Service Application Program Interface (GSSAPI) in cooperation with the System Security Services Daemon (SSSD):
 - a. Open the /etc/sssd/sssd.conf file for editing.
 - b. Specify that **pam_sss_gss** can provide authentication for the **sudo** and **sudo -i** commands in IdM your domain:

[domain/idm.example.com]
pam_gssapi_services = sudo, sudo-i

- c. Save and exit the file.
- d. Open the /etc/pam.d/sudo file for editing.
- e. Insert the following line to the top of the **#%PAM-1.0** list to allow, but not require, GSSAPI authentication for **sudo** commands:

auth sufficient pam_sss_gss.so

- f. Save and exit the file.
- 6. Restart the **SSSD** service so that the above changes take effect immediately:

\$ systemctl restart sssd

Additional resources

- Constrained delegation in Identity Management
- README-servicedelegationrule.md and README-servicedelegationtarget.md in the /usr/share/doc/ansible-freeipa/ directory
- Sample playbooks in the /usr/share/doc/ansible-freeipa/playbooks/servicedelegationtarget and /usr/share/doc/ansible-freeipa/playbooks/servicedelegationrule directories

36.6. ADDITIONAL RESOURCES

• Managing remote systems in the web console

CHAPTER 37. JOINING RHEL SYSTEMS TO AN ACTIVE DIRECTORY BY USING RHEL SYSTEM ROLES

If your organization uses Microsoft Active Directory (AD) to centrally manage users, groups, and other resources, you can join your Red Hat Enterprise Linux (RHEL) host to this AD. For example, AD users can then log into RHEL and you can make services on the RHEL host available for authenticated AD users. By using the **ad_integration** RHEL system role, you can automate the integration of Red Hat Enterprise Linux system into an Active Directory (AD) domain.



NOTE

The **ad_integration** role is for deployments using direct AD integration without an Identity Management (IdM) environment. For IdM environments, use the **ansible-freeipa** roles.

The **ad_integration** system role is not included in the **ansible-freeipa** package. It is part of the **rhel-system-roles** package. You can install **rhel-system-roles** on systems with a **Red Hat Enterprise Linux Server** subscription attached.

37.1. JOINING RHEL TO AN ACTIVE DIRECTORY DOMAIN BY USING THE AD_INTEGRATION RHEL SYSTEM ROLE

You can use the **ad_integration** RHEL system role to automate the process of joining RHEL to an Active Directory (AD) domain.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The managed node uses a DNS server that can resolve AD DNS entries.
- Credentials of an AD account which has permissions to join computers to the domain.
- Ensure that the required ports are open:
 - Ports required for direct integration of RHEL systems into AD using SSSD

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

usr: administrator pwd: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
-name: Active Directory integration
hosts: managed-node-01.example.com
vars_files:
    - ~/vault.yml
tasks:
    - name: Join an Active Directory
    ansible.builtin.include_role:
    name: redhat.rhel_system_roles.ad_integration
vars:
    ad_integration_user: "{{ usr }}"
    ad_integration_password: "{{ pwd }}"
    ad_integration_realm: "ad.example.com"
    ad_integration_allow_rc4_crypto: false
    ad_integration_timesync_source: "time_server.ad.example.com"
```

The settings specified in the example playbook include the following:

ad_integration_allow_rc4_crypto: <true|false>

Configures whether the role activates the **AD-SUPPORT** crypto policy on the managed node. By default, RHEL does not support the weak RC4 encryption but, if Kerberos in your AD still requires RC4, you can enable this encryption type by setting

ad_integration_allow_rc4_crypto: true.

Omit this the variable or set it to false if Kerberos uses AES encryption.

ad_integration_timesync_source: <time_server>

Specifies the NTP server to use for time synchronization. Kerberos requires a synchronized time among AD domain controllers and domain members to prevent replay attacks. If you omit this variable, the **ad_integration** role does not utilize the **timesync** RHEL system role to configure time synchronization on the managed node.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ad_integration/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

• Check if AD users, such as **administrator**, are available locally on the managed node:

\$ ansible managed-node-01.example.com -m command -a 'getent passwd administrator@ad.example.com'

 $administrator@ad.example.com: \verb§^*:1450400500:1450400513:Administrator:/home/administrator@ad.example.com: \verb§^*:1450400500:1450400513:Administrator:/home/administra$

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ad_integration/README.md file
- /usr/share/doc/rhel-system-roles/ad_integration/ directory
- Ansible vault