MAGUS:

Machine learning And Graph theory assisted Universal structure Searcher

Junjie Wang, Hao Gao, Yu Han, Qiuhan Jia, Shuning Pan, Chi Ding, Yong Wang, Jian Sun

National Laboratory of Solid State Microstructures, School of Physics and Collaborative Innovation Center of Advanced Microstructures, Nanjing University, Nanjing, 210093, China

Manual

Version 1.6.2, October 27, 2023.

https://gitlab.com/bigd4/magus

Contents

1 Introduction		on	4	
	1.1	Overvi	iew	4
	1.2	Currer	nt Features	4
	1.3	Interfa	ace	5
	1.4	How to	o Get Access	5
	1.5	How to	o Cite	5
	1.6	Public	eations Using MAGUS	6
2	Inst	allatio	${f n}$	7
	2.1	Depen	$\operatorname{dency} \ldots \ldots \ldots \ldots \ldots \ldots \ldots \ldots \ldots $	7
	2.2	Prepar	ration	8
		2.2.1	Set up the ASE API with Vasp	8
		2.2.2	Set up Job System	9
		2.2.3	Machine Learning Package Installation (Optional)	9
		2.2.4	Build a Virtual Environment (Optional)	9
	2.3	Install	with pip	10
	2.4	Install	with Source Code	10
		2.4.1	Download Code	10
			2.4.1.1 Use git	10
			2.4.1.2 From Website	10
		2.4.2	Use pip to Install the Source Code	10
	2.5	Install	Offline	11
	2.6	Other	Settings	11
		2.6.1	Set up Environment Variables	11

Contents MAGUS 1.6.1

		2.6.2	Set up Auto Completion (Optional)	11
	2.7	Check	Installation	12
3	Exa	mples		13
	3.1	Examp	ple List	13
	3.2	Examp	ple Introductions	13
		3.2.1	Generate Structures	13
		3.2.2	Relax Structures	14
		3.2.3	3D Bulk Search	14
		3.2.4	Molecule Crystal Search	14
		3.2.5	Cluster Search	14
		3.2.6	Surface Reconstruct	14
		3.2.7	Machine Learning Search	15
		3.2.8	2D Bulk Search	15
4	Inp	ut		1 6
	4.1	Input	Files	16
	4.2	Comm	and lines	16
		4.2.1	search	17
		4.2.2	summary	18
		4.2.3	clean	20
		4.2.4	prepare	20
		4.2.5	calculate	20
		4.2.6	generate	21
		4.2.7	checkpack	22
		4.2.8	test	23
		4.2.9	update	23
		4.2.10	getslabtool	23
		4.2.11	mutate	24
	4.3	Input	Parameters	25
5	FAC	Ş		54
	5.1	How to	o Set Environment Variables	54

Contents	MAGUS 1.6.
Jontems	MAGUS 1.0.

5.2	How to Use Python Virtual Environment	55
5.3	PBS Job System Parallel Mode "qsub" Command Not Found	55

Chapter 1

Introduction

1.1 Overview

MAGUS is the abbreviation for Machine learning And Graph theory assisted Universal structure Searcher. It is a machine learning and graph theory assisted crystal structure prediction method developed by Prof. Jian Sun's group at the School of Physics at Nanjing University. The programming languages are mainly Python and C++ and it is built as a pip installable package. Users can use just a few commands to install the package. MAGUS has also the advantage of high modularity and extensibility. All source codes are transparent to users after installation, and users can modify particular parts according to their needs.

MAGUS has been used to study multiple systems. Several designed new materials have been synthesized experimentally, and a number of high-profile academic papers have been published. (Publications using MAGUS)

1.2 Current Features

- Generation of atomic structures for a given symmetry, support cluster, surface, 2D and 3D crystals including molecules, confined systems, etc
- Geometry optimization of a large number of structures with DFT or active learning machine learning potential
- Multi-target search for structures with fixed or variationally component
- API for VASP, CASTEP, Quantum ESPRESSO, ORCA, MTP, NEP, DeepMD, gulp, lammps, XTB, ASE, etc. Easy for extension.

1.3 Interface

MAGUS now supports the following packages to calculate the energy of structures, some of them are commercial or need registration to get the permission to use.

- VASP
- CASTEP
- Quantum ESPRESSO
- ORCA
- ASE built-in EMT & LJ
- MTP
- NEP
- DeepMD
- gulp
- lammps
- XTB

You can also write interfaces to connect MAGUS and other codes by add them in the /magus/calculators directory.

1.4 How to Get Access

MAGUS is free for non-commercial academic use. To get access to the source code, you need to register at the following link (https://www.wjx.top/vm/m5eWS0X.aspx). We will invite you into our gitlab project as soon as possible. Then you can see the whole project after logging in. Please contact us by email (magus@nju.edu.cn) if you have any questions concerning MAGUS.

1.5 How to Cite

Reference	Cite for What
1, 2	for any work that used MAGUS
3, 4	Graph theory
5	Surface reconstruction
6	Structure searching in confined space

- 1. Junjie Wang, Hao Gao, Yu Han, Chi Ding, Shuning Pan, Yong Wang, Qiuhan Jia, Hui-Tian Wang, Dingyu Xing, and Jian Sun, "MAGUS: machine learning and graph theory assisted universal structure searcher", Natl. Sci. Rev. 10, nwad128, (2023).
- 2. Kang Xia, Hao Gao, Cong Liu, Jianan Yuan, Jian Sun, Hui-Tian Wang, Dingyu Xing, "A novel superhard tungsten nitride predicted by machine-learning accelerated crystal structure search", Sci. Bull. 63, 817 (2018).
- 3. Hao Gao, Junjie Wang, Yu Han, Jian Sun, "Enhancing Crystal Structure Prediction by Decomposition and Evolution Schemes Based on Graph Theory", Fundamental Research 1, 466 (2021).
- 4. Hao Gao, Junjie Wang, Zhaopeng Guo, Jian Sun, "Determining dimensionalities and multiplicities of crystal nets" npj Comput. Mater. 6, 143 (2020).
- 5. Yu Han, Junjie Wang, Chi Ding, Hao Gao, Shuning Pan, Qiuhan Jia, and Jian Sun, "Prediction of surface reconstructions using MAGUS", J. Chem. Phys. 158, 174109 (2023).
- 6. Chi Ding, Junjie Wang, Yu Han, Jianan Yuan, Hao Gao, and Jian Sun, "High Energy Density Polymeric Nitrogen Nanotubes inside Carbon Nanotubes", Chin. Phys. Lett. 39, 036101 (2022). (Express Letter)

1.6 Publications Using MAGUS

See the full publication list here.

Chapter 2

Installation

2.1 Dependency

MAGUS needs python>=3.6 and gcc>=4.8. You should install pip before using it to install other packages. The following python packages are required:

```
numpy
scipy
scikit-learn
pyyaml>=6.0
ase>=3.18
networkx
spglib
pandas
prettytable
packaging
```

The following python packages are optional:

```
beautifulreport
plotly
QdsadadawfgjghjkqawQ
dscribe
networkx
pymatgen
```

If you want to use MTP, you need to install mlip.

2.2 Preparation

2.2.1 Set up the ASE API with Vasp

MAGUS does VASP calculation based on ASE API. Hence, you need to do the following preparations first.

1) Make a new file run_vasp.py:

```
import subprocess
exitcode = subprocess.call("<Your_vasp_command>",
shell=True)
```

<Your_vasp_command> is the command to run VASP on your cluster, e.g. mpirun
vasp_std .

Notice: remember to load the corresponding environment, such as ips or openmpi, if you want to run vasp in parallel (run a single vasp job with multiple cores). If you want to use parallel mode (run several vasp jobs at the same time), you also need to load environment in sub jobs by adding control lines after "preProcessing" option, see details in Sec. 5.1.

2) Make a new mypps dir to store vasp pseudopotentials. You can also use soft links:

```
mypps/
— potpaw
— potpaw_GGA
— potpaw_PBE
```

```
$ ln -s <your-path-to>/PBE-5.4 mypps/potpaw_PBE
```

Three sub directories correspond to LDA, PW91 and PBE, respectively. It is allowed to leave some of them nonexistent if you do not use these potentials. It is also allowed to add other pseudopotentials.

3) Set environment variables:

```
$ export VASP_SCRIPT=<your-path-to>/run_vasp.py
$ export VASP_PP_PATH=<your-path-to>h/mypps
```

More information in: ase manual for vasp calculator.

Notice: run_vasp.py and mypps should not be under magus dir.

2.2.2 Set up Job System

MAGUS is developed under LSF job system, which is the default setting. But we also add support to SLURM and PBS job systems. You need to set an environment variable if you are not using the default LSF job system:

```
$ export JOB_SYSTEM=<your-job-system>
```

<your-job-system> should be one of LSF, SLURM and PBS. Add this line into your
bashrc to make the setting work every time you log in.

Notice: in some PBS job system, "qsub" commond may not be under system path in compute nodes. See section 5.3 for solution.

2.2.3 Machine Learning Package Installation (Optional)

MLIP is a software for Machine Learning Interatomic Potentials. It has been developed at Skoltech (Moscow) by Alexander Shapeev, Evgeny Podryabinkin, Konstantin Gubaev, and Ivan Novikov.* You can follow the instructions in https://mlip.skoltech.ru/download/.

2.2.4 Build a Virtual Environment (Optional)

We highly recommend that you use Anaconda to build a virtual environment and install MAGUS in an isolated environment to avoid conflicts. After installing anaconda, it will automatically write several lines in your bashrc which are used to initialize anaconda environment. You should source bashrc or re-login to make anaconda activated. If you do the jobs correctly, your shell prompt should be modified to be started as (base), which means you are now in base environment of anaconda. Then, create a new virtual environment with

```
$ conda create -n <your-env-name> python=<python-version>
```

<your-env-name> is the name of the environment that you can define as you will, and <python-version> should be not less than 3.6. When you want to activate this environment, use

```
$ conda activate <your-env-name>
```

^{*}Novikov, Ivan S., et al. "The MLIP package: moment tensor potentials with MPI and active learning." Machine Learning: Science and Technology 2.2 (2020): 025002.

2.3 Install with pip

It is convenient to install with pip. It will automatically download the source code and install the required python packages. The install command is

```
$ pip install git+https://gitlab.com/bigd4/magus.git
```

You may need to type in your username and password of your gitlab account because the project is not public. Your git version should not be too low, or https connection may fail. And there should be gcc in your environment. If you want to install in a virtual environment, do not forget to activate the environment first. If you work in a cluster and do not have permission to install in the default location, you may add ——user parameter.

2.4 Install with Source Code

2.4.1 Download Code

2.4.1.1 Use git

Clone the project and submodules to local file system:

```
$ git clone --recursive https://gitlab.com/bigd4/magus.git
```

2.4.1.2 From Website

If you have problem downloading with git, you have the alternative choice to download the zipped package on our gitlab website. Notice that the submodules such as pybind11 will not be downloaded at the same time. You should download and extract them and replace the empty folders in the source code, respectively.

2.4.2 Use pip to Install the Source Code

After downloading the code, go into the directory and install with:

```
$ pip install -e .
```

pip will read setup.py in your current directory and install. The —e option means that python will import the module directly from the current path, but not copy

the codes to the default lib path and import the module there, which is convenient for modifying in the future. If you do not have the need, you can remove the option.

2.5 Install Offline

If you have no access to Internet and your cluster does not have a python pypi mirror, which means you cannot use pip to install packages. You have the alternative choose to download with our pre-built offline installation package. You can download it from here. Install with

```
$ ./magus-<version-number>.sh
```

Follow the instructions. It will build an isolated conda environment with all required packages. You should go into your install path. Then, add bin into PATH and add condalib into PYTHONPATH. Notice that this method will build a new conda. If have already installed a conda in your system, the new one will not merge into the old one, which may cause difficulties to switch conda environments. As a result, it is not recommended to install with this method if your pip works normally.

2.6 Other Settings

2.6.1 Set up Environment Variables

To run MAGUS in your console, you need to add such path variables in bashrc.

```
$ export PATH=<your_path_to_magus>:$PATH
$ export PYTHONPATH=<your_path_to_magus>:$PYTHONPATH
```

If you use anaconda to manage your environment, the above actions should be unnecessary for you. When you activate your env, the path variables are automatically set.

2.6.2 Set up Auto Completion (Optional)

We have prepared a shell completion script for MAGUS. Add the following line into bashrc:

```
$ source <your_path_to_magus>/auto_complete.sh
```

2.7 Check Installation

If MAGUS is properly installed, you can see the version number by the following command in console:

\$ magus -v 1.0.5

If you have installed other optional packages, you can check if they are properly installed using:

\$ magus checkpack

Chapter 3

Examples

We have prepared a series of examples which you can find in the examples folder in your MAGUS installation path. In each example, there is a README.md. You should follow the instructions in it. The input parameters and other needed input files are almost ready, but you should modify the computing queue in both job and input.yaml. If you use virtual environment, you should also write the control lines to activate your python environment (see section 5.2 for details).

3.1 Example List

number	target
01	Generate Structures
02	Relax Structures
03	3D Bulk Search
04	Molecule Crystal Search
05	Cluster Search
06	Surface Reconstruct
07	Machine Learning Search
08	2D Bulk Search

3.2 Example Introductions

3.2.1 Generate Structures

• 01--1-B12: Generate 3d periodic crystal structures of boron with 12 atoms per unit cell by symmetry.

• 01--2-NH4NO3: Generate 3d periodic crystal structures of molecule crystal with 8 NH4 and NO3 molecules per unit cell by symmetry Pccn (56).

3.2.2 Relax Structures

- 02--1-C8-VASP: Structure relaxation of diamond by vasp interface.
- 02--2-B12-MTP: Relax 2000 structures with MTP and VASP.

3.2.3 3D Bulk Search

- 03--1-Al-fix-EMT: GAsearch of fixed composition Al (12 atoms per cell) by EMT.
- 03--2-Al-fix-VASP: GAsearch of fixed composition Al (12 atoms per cell) by VASP.
- 03--3-Ti02-fix-VASP: GAsearch of fixed composition TiO₂ (12 atoms per cell).
- 03--4-MgAlO-fix-GULP: GAsearch of fixed composition MgAlO under high pressure by GULP.
- 03--5-Si-fix-Castep: GAsearch of fixed composition Si by Castep.
- 03--6-ZnOH-var-GULP: GAsearch of variable composition $Zn_x(OH)_y$.

3.2.4 Molecule Crystal Search

• 04--1-CH4-fix-VASP: GAsearch of molecule crystal CH4 with 4 molecules per unit cell.

3.2.5 Cluster Search

• 05--1-LJ26: Ground state of Lennard-Jones cluster of 26 atoms.

3.2.6 Surface Reconstruct

- $06--1-C_2\times1_100$: Surface Reconstruction of diamond $(100)-2\times1$.
- 06--2-Sn02_4x1_110: Surface Reconstruction of SnO₂ (110)-4×1.

3.2.7 Machine Learning Search

- $07-1-MgSiO_3-MTP$: Use mtp to search $MgSiO_3$ under high pressure.
- 07--2-Na-NEP: A toy example for use NEP to search sodium.

3.2.8 2D Bulk Search

• 08--1-graphene: GAsearch of 2D carbon (graphene) by VASP.

Chapter 4

Input

In magus we use inputs including command lines and parameter input file (in yaml format) to control programs.

If you are a new user of MAGUS (AND SINCERELY THANKS VERY MUCH FOR USING OUR PROGRAM!), before you read the full description about all inputs below, we recommand first taking a look at examples which are easier to follow.

4.1 Input Files

A typical structure search task needs the following input files:

- input.yaml: the basic input file that defines the main parameters in the task.
- inputFold: the folder containing the extra needed input files for calculators, such as INCAR for VASP and in.lammps for LAMMPS.
- Seeds: the folder containing seed structures.

4.2 Command lines

You can simply type

\$ magus -h

to see which commands are supported for magus. You will see

```
usage: magus [-h] [-v]
             {search, summary, clean, prepare, calculate,
             generate, checkpack, test, update, getslabtool,
             mutate,parmhelp}
Magus: Machine learning And Graph theory assisted
Universal structure Searcher
optional arguments:
  -h, --help
                        show this help message and exit
  -v, --version
                        print version
Valid subcommands:
  {search, summary, clean, prepare, calculate, generate,
  checkpack,test,update,getslabtool,mutate,parmhelp}
                        search structures
    search
                        summary the results
    summary
                        clean the path
    clean
                        generate InputFold etc to prepare
    prepare
    for the search
                        calculate many structures
    calculate
    generate
                        generate many structures
    checkpack
                        check full
    test
                        do unit test of magus
    update
                        update magus
    getslabtool
                        tools to getslab in surface search
    mode
    mutate
                        mutation test
```

which prints valid subcommands. You can also helps for each command line:

4.2.1 search

```
optional arguments:
  -h, --help
                         show this help message and exit
  -ll {DEBUG, INFO, WARNING, ERROR}, --log-level
  {DEBUG, INFO, WARNING, ERROR}
                         set verbosity level by strings:
                         ERROR, WARNING, INFO
                         and DEBUG (default: INFO)
  -lp LOG_PATH, --log-path LOG_PATH
                         set log file to log messages to
                         disk (default:
                         log.txt)
  -i INPUT_FILE, --input-file INPUT_FILE
                         the input parameter file in yaml
                         format (default:
                         input.yaml)
                         use ml to accelerate(?) the search
  -m, --use-ml
  (default: False)
  -r, --restart
                        Restart the searching. (default:
  False)
```

4.2.2 summary

```
optional arguments:
                        show this help message and exit
  -h, --help
  -p PREC, --prec PREC tolerance for symmetry finding
  (default: 0.1)
  -r, --reverse
                        whether to reverse sort (default:
  False)
  -s, --save
                        whether to save POSCARS (default:
  False)
  --need-sort
                        whether to sort (default: False)
  -o OUTDIR, --outdir OUTDIR
                        where to save POSCARS (default: .)
  -n SHOW_NUMBER, --show-number SHOW_NUMBER
                        number of show in screen (default:
                        100)
  -sb SORTED_BY [SORTED_BY ...], --sorted-by SORTED_BY
  [SORTED_BY ...]
                        sorted by which arg (default:
                        Default)
  -rm REMOVE_FEATURES [REMOVE_FEATURES ...],
  --remove-features REMOVE_FEATURES [REMOVE_FEATURES ...]
                        the features to be removed from
                        the show features
                        (default: [])
  -a ADD_FEATURES [ADD_FEATURES ...], --add-features
  ADD_FEATURES [ADD_FEATURES ...]
                        the features to be added to the
                        show features
                        (default: [])
  -v, --var
                        use variable composition mode
  (default: False)
  -b BOUNDARY [BOUNDARY ...], --boundary BOUNDARY
  [BOUNDARY ...]
                        in variable composition mode: add
                        boundary (default:
  -t {bulk,cluster}, --atoms-type {bulk,cluster}
```

4.2.3 clean

```
$ magus clean -h

usage: magus clean [-h] [-f]

optional arguments:
   -h, --help show this help message and exit
   -f, --force rua!!!! (default: False)
```

4.2.4 prepare

```
$ magus prepare -h
usage: magus prepare [-h] [-v] [-m]

optional arguments:
  -h, --help show this help message and exit
  -v, --var variable composition search (default: False)
  -m, --mol Molecule Crystal Search (default: False)
```

4.2.5 calculate

```
-ll {DEBUG, INFO, WARNING, ERROR}, --log-level
{DEBUG, INFO, WARNING, ERROR}
                      set verbosity level by strings:
                      ERROR, WARNING, INFO
                      and DEBUG (default: INFO)
-lp LOG_PATH, --log-path LOG_PATH
                      set log file to log messages to
                      disk (default:
                      log.txt)
-m {scf,relax}, --mode {scf,relax}
                      scf or relax (default: relax)
-i INPUT_FILE, --input-file INPUT_FILE
                      the input parameter file in yaml
                      format (default:
                      input.yaml)
-o OUTPUT_FILE, --output-file OUTPUT_FILE
                      output traj file (default:
                      out.traj)
-p PRESSURE, --pressure PRESSURE
                      add pressure (default: None)
```

4.2.6 generate

```
log.txt)
-i INPUT_FILE, --input-file INPUT_FILE
the input parameter file in yaml
format (default:
input.yaml)
-o OUTPUT_FILE, --output-file OUTPUT_FILE
where to save generated traj
(default: gen.traj)
-n NUMBER, --number NUMBER
generate number (default: 10)
```

4.2.7 checkpack

```
$ magus checkpack -h
usage: magus checkpack [-h] [-ll
{DEBUG, INFO, WARNING, ERROR}] [-lp LOG_PATH]
                        [{all,calculators,comparators,fingerprints}]
positional arguments:
  {all,calculators,comparators,fingerprints}
                         the package to check (default:
                         all)
optional arguments:
  -h, --help
                         show this help message and exit
  -ll {DEBUG, INFO, WARNING, ERROR}, --log-level
  {DEBUG, INFO, WARNING, ERROR}
                         set verbosity level by strings:
                         ERROR, WARNING, INFO
                         and DEBUG (default: INFO)
  -lp LOG_PATH, --log-path LOG_PATH
                         set log file to log messages to
                         disk (default:
                         log.txt)
```

4.2.8 test

4.2.9 update

```
$ magus update -h

usage: magus update [-h] [-u] [-f]
optional arguments:
  -h, --help show this help message and exit
  -u, --user add --user to pip install (default: False)
  -f, --force add --force-reinstall to pip install
  (default: False)
```

4.2.10 getslabtool

```
-s SLABFILE, --slabfile SLABFILE
slab file (default: slab.vasp)
```

4.2.11 mutate

```
$ magus mutate -h
usage: magus mutate [-h] [-i INPUT_FILE] [-s SEED_FILE]
[-o OUTPUT_FILE]
                     [--cutandsplice] [--replaceball]
                     [--soft] [--perm]
                     [--lattice] [--ripple] [--slip]
                     [--rotate] [--rattle]
                     [--formula] [--lyrslip] [--shell]
                     [--lyrsym] [--clusym]
optional arguments:
  -h, --help
                        show this help message and exit
  -i INPUT_FILE, --input_file INPUT_FILE
                        input_file (default: input.yaml)
  -s SEED_FILE, --seed_file SEED_FILE
                         seed_file (default: seed.traj)
  -o OUTPUT_FILE, --output_file OUTPUT_FILE
                        output_file (default: result)
  --cutandsplice
                        add option to use operation!
  (default: False)
  --replaceball
                        add option to use operation!
  (default: False)
  --soft
                        add option to use operation!
  (default: False)
                        add option to use operation!
  --perm
  (default: False)
  --lattice
                        add option to use operation!
  (default: False)
  --ripple
                        add option to use operation!
  (default: False)
  --slip
                        add option to use operation!
  (default: False)
```

```
--rotate
                      add option to use operation!
(default: False)
--rattle
                      add option to use operation!
(default: False)
--formula
                      add option to use operation!
(default: False)
--lyrslip
                       add option to use operation!
(default: False)
--shell
                       add option to use operation!
(default: False)
--lyrsym
                      add option to use operation!
(default: False)
--clusym
                      add option to use operation!
(default: False)
```

4.3 Input Parameters

A yaml format parameter file is also necessary. By default is 'input.yaml'. IN THE FUTURE we will add command line to easily export notes and default values by

```
$ magus parmhelp
```

to see help for which parameters you can set in 'input.yaml'. For current version they are:

```
parameter information for <class
'magus.parameters.magusParameters'>
+++++ Default parameters
                           +++++
formulaType
               : type of formula, choose from fix or var
                  default value: fix
              : structure type, choose from bulk, layer,
structureType
                  confined_bulk, cluster, surface
                  default value: bulk
               : spacegroup to generate random structures
spacegroup
                  default value: [1-230]
DFTRelax
               : DFTRelax
                  default value: False
initSize
               : size of first population
                  default value: =popSize
```

goodSize : number of good indivials per generation default value: =popSize molMode : search molecule clusters default value: False : use Machine learning relaxation mlRelax default value: False : tolerance for symmetry finding symprec default value: 0.1 : limitation to detect clusters bondRatio default value: 1.15 eleSize : used in variable composition mode, control how many boundary structures are generated default value: 0 volRatio : cell_volume/SUM(atom_ball_volume) when generating structures (around this number) default value: 2 dRatio : distance between each pair of two atoms in the structure is not less than (radius1+radius2)*d ratio default value: 0.7 molDetector : methods to detect mol, choose from 1 and 2. See Hao Gao, Junjie Wang, Zhaopeng Guo, Jian Sun, "Determining dimensionalities and multiplicities of crystal nets" npj Comput. Mater. 6, 143 (2020) [doi.org/10.1016/j.fmre.2021.06.005] for more details. default value: 0 addSym : whether to add symmetry before crossover and mutation default value: True : ratio of new generated random structures randRatio in next generation default value: 0.2 : use mol dectector chkMol default value: False

: check seeds chkSeed

default value: True

diffE : energy difference to determin structure

duplicates

default value: 0.01

: volume difference to determin structure diffV

duplicates

default value: 0.05

: comparator, type magus checkpack to see comparator

which comparators you have.

default value: nepdes

fp calc : fingerprints, type magus checkpack to see

which fingerprint method you have.

default value: nepdes

: number of good individuals per generation n_cluster

default value: =saveGood

: automantic GA operation ratio autoOpRatio

default value: False

autoRandomRatio: automantic random structure generation

ratio

default value: False

parameter information for <class

'magus.generators.random.MoleculeSPGGenerator'>

+++++ Requirement parameters +++++

input mols : input molecules

formula_type : type of formula, choose from fix or var symbols : atom symbols

formula : formula

min_n_atoms : minimum number of atoms per unit cell
max_n_atoms : maximum number of atoms per unit cell

+++++ Default parameters

: tolerance for symmetry finding for symprec

molucule

default value: 0.1

threshold_mol : distance between each pair of two

molecules in the structure is

not less than

(mol_radius1+mol_radius2)*threshold_mol

default value: 1.0

max_attempts : max attempts to generate a random structure default value: 50 p_pri : probability of generate primitive cell default value: 0.0 : cell_volume/SUM(atom_ball_volume) when volume_ratio generating structures (around this number) default value: 1.5 : split cell into n_split parts n_split default value: [1] dimension : dimension default value: 3 : number of single compontent structures to ele_size generate to decide hull boundarys in variable composition mode default value: 0 : min lattice min_lattice default value: [-1, -1, -1, -1, -1] : max lattice max_lattice default value: [-1, -1, -1, -1, -1] min_volume : min volume default value: -1 : max volume max_volume default value: -1 : minimum formula min_n_formula default value: None max_n_formula : maximum formula default value: None d ratio : distance between each pair of two atoms in the structure is not less than (radius1+radius2)*d ratio default value: 1.0 distance_matrix: distance between each pair of two atoms in the structure is not less than (radius1+radius2)*distance_matrix[1][2] default value: None

October 27, 2023 Page 28

default value: [1-230]

: spacegroup to generate random structures

spacegroup

: max formula ratio in variable max ratio composition mode, for example set 10 and Zn11(OH) is not allowed default value: 1000 full_ele : only Generate Structures with full elements default value: True parameter information for <class 'magus.generators.random.LayerSPGGenerator'> +++++ Requirement parameters +++++ min thickness : minimum thickness max_thickness : maximum thickness formula_type : type of formula, choose from fix or var symbols
formula
min_n_atoms
max_n_atoms
: atom symbols
: formula
: minimum number of atoms per unit cell
max_n_atoms
: maximum number of atoms per unit cell +++++ Default parameters symprec : symprec default value: 0.1 threshold_mol : threshold_mol default value: 1.0 : spg_type spg_type default value: layer vacuum_thickness: vacuum_thickness default value: 10 : max attempts to generate a random max_attempts structure default value: 50 : probability of generate primitive cell p_pri default value: 0.0 volume_ratio : cell_volume/SUM(atom_ball_volume) when generating structures (around this number) default value: 1.5 : split cell into n_split parts n_split default value: [1] dimension : dimension default value: 3 : number of single compontent structures to ele_size

```
generate to decide hull boundarys in
                variable composition mode
                 default value: 0
min_lattice
              : min lattice
                 default value: [-1, -1, -1, -1, -1]
              : max lattice
max_lattice
                 default value: [-1, -1, -1, -1, -1]
min_volume
              : min volume
                 default value: -1
max_volume
              : max volume
                 default value: -1
              : minimum formula
min_n_formula
                 default value: None
max_n_formula : maximum formula
                 default value: None
d_ratio
              : distance between each pair of two atoms
in the structure is
                not less than (radius1+radius2)*d ratio
                 default value: 1.0
distance_matrix: distance between each pair of two atoms
in the structure is
                not less than
                (radius1+radius2)*distance_matrix[1][2]
                 default value: None
spacegroup
              : spacegroup to generate random structures
                 default value: [1-230]
              : max formula ratio in variable
max ratio
composition mode, for example set 10 and Zn11(OH) is not
allowed
                 default value: 1000
full ele
              : only Generate Structures with full
elements
                 default value: True
parameter information for <class
'magus.reconstruct.generator.ClusterSPGGenerator'>
+++++ Requirement parameters +++++
formula_type : type of formula, choose from fix or var
symbols
              : atom symbols
formula : formula
min_n_atoms : minimum number of atoms per unit cell
```

```
: maximum number of atoms per unit cell
max n atoms
+++++ Default parameters
vacuum_thickness: vacuum thickness
                  default value: 10
parameter information for <class
'magus.generators.random.SPGGenerator'>
+++++ Requirement parameters +++++
formula_type : type of formula, choose from fix or var
symbols
               : atom symbols
formula
min_n_atoms
: formula
: minimum number of atoms per unit cell
max_n_atoms : maximum number of atoms per unit cell
+++++ Default parameters +++++
max attempts
              : max attempts to generate a random
structure
                  default value: 50
               : probability of generate primitive cell
p_pri
                  default value: 0.0
volume ratio
               : cell_volume/SUM(atom_ball_volume) when
generating structures (around this number)
                  default value: 1.5
               : split cell into n_split parts
n_split
                  default value: [1]
               : dimension
dimension
                  default value: 3
ele size
               : number of single compontent structures to
                 generate to decide hull boundarys in
                 variable composition mode
                  default value: 0
min lattice
               : min lattice
                  default value: [-1, -1, -1, -1, -1]
               : max lattice
max_lattice
                  default value: [-1, -1, -1, -1, -1, -1]
min_volume
               : min volume
                  default value: -1
max_volume
               : max volume
                  default value: -1
              : minimum formula
min_n_formula
                  default value: None
max_n_formula : maximum formula
```

```
default value: None
d ratio
               : distance between each pair of two atoms
in the structure is
                 not less than (radius1+radius2)*d_ratio
                  default value: 1.0
distance_matrix: distance between each pair of two atoms
in the structure is
                 not less than
                 (radius1+radius2)*distance_matrix[1][2]
                  default value: None
spacegroup
               : spacegroup to generate random structures
                  default value: [1-230]
                  max formula ratio in variable
max ratio
composition mode, for example set 10 and Zn11(OH) is not
allowed
                  default value: 1000
full_ele
               : only Generate Structures with full
elements
                  default value: True
parameter information for <class
'magus.reconstruct.generator.SurfaceGenerator'>
+++++ Requirement parameters +++++
formula_type : type of formula, choose from fix or var
symbols
               : atom symbols
formula
              : formula
min_n_atoms : minimum number of atoms per unit cell
max_n_atoms : maximum number of atoms per unit cell
+++++ Default parameters
                           +++++
randwalk_range : maximum range of random walk
                  default value: 0.5
randwalk_ratio : ratio of random walk atoms
                  default value: 0.3
               : size[x] of reconstruction
rcs_x
                  default value: [1]
               : size[y] of reconstruction
rcs_y
                  default value: [1]
buffer
               : use buffer layer
                  default value: True
               : formula of surface region
rcs_formula
                  default value: None
```

```
: generate with planegroup/layergroup
spg_type
                  default value: plane
+++++ slabinfo parameters +++++
bulk file
               : file of bulk structure
                  default value: None
cutslices
               : bulk_file contains how many atom layers
                  default value: 2
bulk_layernum
              : number of atom layers in substrate region
                  default value: 3
buffer_layernum: number of atom layers in buffer region
                  default value: 3
               : number of atom layers in top surface
rcs layernum
region
                  default value: 2
               : Miller indices of surface direction,
direction
i.e.[1,0,0]
                  default value: None
               : R
rotate
                  default value: 0
               : matrix notation
matrix
                  default value: None
               : passivate bottom surface with H
addH
                  default value: False
pcell
               : use primitive cell
                  default value: True
+++++ modification parameters +++++
adsorb
               : adsorb atoms to cleaved surface
                  default value: {}
               : clean cleaved surface
clean
                  default value: {}
defect
               : add defect to cleaved surface
                  default value: {}
parameter information for <class
'magus.populations.individuals.Bulk'>
+++++ Requirement parameters +++++
               : tolerance for symmetry finding
symprec
+++++ Default parameters +++++
mol_detector : methods to detect mol, choose from 1 and
2. See
```

```
Hao Gao, Junjie Wang, Zhaopeng Guo, Jian
                 Sun, "Determining dimensionalities and
                 multiplicities
                 of crystal nets" npj Comput. Mater. 6,
                 143 (2020)
                 [doi.org/10.1016/j.fmre.2021.06.005]
                 for more details.
                  default value: 0
n_repair_try
               : attempts to repair structures when doing
GA operation
                  default value: 5
max_attempts
               : maximum attempts
                  default value: 50
               : if check seeds
check_seed
                  default value: False
min_lattice
               : min_lattice
                  default value: [0.0, 0.0, 0.0, 45.0,
                  45.0, 45.0]
               : max_lattice
max_lattice
                  default value: [99, 99, 99, 135, 135,
d ratio
               : distance between each pair of two atoms
in the structure is
                 not less than (radius1+radius2)*d_ratio
                  default value: 1.0
distance_matrix: distance between each pair of two atoms
in the structure is
                 not less than
                 (radius1+radius2)*distance_matrix[1][2]
                  default value: None
radius
               : radius
                  default value: None
max_forces
               : if forces of a structure larger is than
this number it will be deleted.
                  default value: 50.0
               : if enthalpy of a structure is larger than
max_enthalpy
this number it will be deleted.
                  default value: 100.0
               : full_ele
full_ele
                  default value: True
```

```
max_length_ratio: if max-cell-length/min-cell-length of a
structure is larger than this number it will be deleted.
                  default value: 8
parameter information for <class
'magus.populations.individuals.Layer'>
+++++ Requirement parameters +++++
               : tolerance for symmetry finding
symprec
+++++ Default parameters +++++
vacuum_thickness: vacuum_thickness
                  default value: 10
bond_ratio
               : bond ratio
                  default value: 1.1
               : attempts to repair structures when doing
n_repair_try
GA operation
                  default value: 5
               : maximum attempts
max_attempts
                  default value: 50
               : if check seeds
check_seed
                  default value: False
               : min lattice
min_lattice
                  default value: [0.0, 0.0, 0.0, 45.0,
                  45.0, 45.0]
max_lattice
               : max_lattice
                  default value: [99, 99, 99, 135, 135,
                  135]
d ratio
               : distance between each pair of two atoms
in the structure is
                 not less than (radius1+radius2)*d_ratio
                  default value: 1.0
distance matrix: distance between each pair of two atoms
in the structure is
                 not less than
                 (radius1+radius2)*distance matrix[1][2]
                  default value: None
radius
               : radius
                  default value: None
max forces
              : if forces of a structure larger is than
this number it will be deleted.
                  default value: 50.0
```

```
max_enthalpy : if enthalpy of a structure is larger than
this number it will be deleted.
                  default value: 100.0
               : full ele
full ele
                  default value: True
max_length_ratio: if max-cell-length/min-cell-length of a
structure is larger than this number it will be deleted.
                  default value: 8
parameter information for <class
'magus.populations.individuals.ConfinedBulk'>
+++++ Requirement parameters +++++
               : tolerance for symmetry finding
symprec
                          +++++
+++++ Default parameters
vacuum thickness: vacuum thickness
                  default value: 10
               : attempts to repair structures when doing
n_repair_try
GA operation
                  default value: 5
               : maximum attempts
max_attempts
                  default value: 50
               : if check seeds
check_seed
                  default value: False
min_lattice
               : min_lattice
                  default value: [0.0, 0.0, 0.0, 45.0,
                  45.0, 45.0]
               : max_lattice
max_lattice
                  default value: [99, 99, 99, 135, 135,
                  135]
d ratio
               : distance between each pair of two atoms
in the structure is
                 not less than (radius1+radius2)*d_ratio
                  default value: 1.0
distance_matrix: distance between each pair of two atoms
in the structure is
                 not less than
                 (radius1+radius2)*distance_matrix[1][2]
                  default value: None
radius
               : radius
                  default value: None
```

```
max_forces
              : if forces of a structure larger is than
this number it will be deleted.
                  default value: 50.0
              : if enthalpy of a structure is larger than
max enthalpy
this number it will be deleted.
                  default value: 100.0
full ele
               : full ele
                  default value: True
max_length_ratio: if max-cell-length/min-cell-length of a
structure is larger than this number it will be deleted.
                  default value: 8
parameter information for <class
'magus.reconstruct.individuals.Surface'>
+++++ Requirement parameters +++++
               : tolerance for symmetry finding
symprec
+++++ Default parameters
                          +++++
vacuum thickness: vacuum thickness
                  default value: 10
buffer
               : use buffer region
                  default value: True
fixbulk
               : fix atom positions in substrate
                  default value: True
slices_file
               : file name for slices_file
                  default value: Ref/layerslices.traj
               : attempts to repair structures when doing
n_repair_try
GA operation
                  default value: 5
               : maximum attempts
max_attempts
                  default value: 50
check seed
               : if check seeds
                  default value: False
               : min_lattice
min_lattice
                  default value: [0.0, 0.0, 0.0, 45.0,
                  45.0, 45.0]
               : max_lattice
max_lattice
                  default value: [99, 99, 99, 135, 135,
d ratio
               : distance between each pair of two atoms
in the structure is
                 not less than (radius1+radius2)*d_ratio
```

```
default value: 1.0
distance_matrix: distance between each pair of two atoms
in the structure is
                 not less than
                 (radius1+radius2)*distance_matrix[1][2]
                  default value: None
radius
               : radius
                  default value: None
max_forces
               : if forces of a structure larger is than
this number it will be deleted.
                  default value: 50.0
max_enthalpy : if enthalpy of a structure is larger than
this number it will be deleted.
                  default value: 100.0
              : full ele
full ele
                  default value: True
max_length_ratio: if max-cell-length/min-cell-length of a
structure is larger than this number it will be deleted.
                  default value: 8
parameter information for <class
'magus.reconstruct.individuals.Cluster'>
+++++ Requirement parameters +++++
               : tolerance for symmetry finding
symprec
+++++ Default parameters +++++
vacuum_thickness: vacuum thickness surrounding cluster to
break pbc when runing calculation
                  default value: 10
               : two atoms are "connected" if their
cutoff
distance < cutoff*radius.
                  default value: 1.0
weighten
              : use weighten atoms when appending or
removing atoms
                  default value: True
               : attempts to repair structures when doing
n_repair_try
GA operation
                  default value: 5
max_attempts
              : maximum attempts
                  default value: 50
               : if check seeds
check_seed
                  default value: False
```

```
min_lattice
               : min_lattice
                  default value: [0.0, 0.0, 0.0, 45.0,
                  45.0, 45.0]
               : max lattice
max lattice
                  default value: [99, 99, 99, 135, 135,
                  135]
               : distance between each pair of two atoms
d ratio
in the structure is
                 not less than (radius1+radius2)*d_ratio
                  default value: 1.0
distance_matrix: distance between each pair of two atoms
in the structure is
                 not less than
                 (radius1+radius2)*distance_matrix[1][2]
                  default value: None
               : radius
radius
                  default value: None
              : if forces of a structure larger is than
max forces
this number it will be deleted.
                  default value: 50.0
              : if enthalpy of a structure is larger than
max_enthalpy
this number it will be deleted.
                  default value: 100.0
full_ele
               : full ele
                  default value: True
max_length_ratio: if max-cell-length/min-cell-length of a
structure is larger than this number it will be deleted.
                  default value: 8
parameter information for <class
'magus.reconstruct.individuals.AdClus'>
+++++ Requirement parameters +++++
               : tolerance for symmetry finding
symprec
+++++ Default parameters +++++
substrate
               : substrate file name
                  default value: substrate.vasp
dist_clus2surface: distance from cluster to surface
                  default value: 2
size
               : size
                  default value: [1, 1]
```

```
vacuum_thickness: vacuum thickness surrounding cluster to
break pbc when runing calculation
                  default value: 10
               : two atoms are "connected" if their
cutoff
distance < cutoff*radius.
                  default value: 1.0
               : use weighten atoms when appending or
weighten
removing atoms
                  default value: True
               : attempts to repair structures when doing
n_repair_try
GA operation
                  default value: 5
               : maximum attempts
max_attempts
                  default value: 50
               : if check seeds
check_seed
                  default value: False
               : min_lattice
min_lattice
                  default value: [0.0, 0.0, 0.0, 45.0,
                  45.0, 45.0]
               : max_lattice
max_lattice
                  default value: [99, 99, 99, 135, 135,
                  135]
               : distance between each pair of two atoms
d ratio
in the structure is
                 not less than (radius1+radius2)*d_ratio
                  default value: 1.0
distance_matrix: distance between each pair of two atoms
in the structure is
                 not less than
                 (radius1+radius2)*distance_matrix[1][2]
                  default value: None
               : radius
radius
                  default value: None
              : if forces of a structure larger is than
max forces
this number it will be deleted.
                  default value: 50.0
max_enthalpy : if enthalpy of a structure is larger than
this number it will be deleted.
                  default value: 100.0
               : full_ele
full_ele
                  default value: True
```

```
max_length_ratio: if max-cell-length/min-cell-length of a
structure is larger than this number it will be deleted.
                 default value: 8
parameter information for <class
'magus.populations.populations.FixPopulation'>
+++++ Requirement parameters +++++
results_dir : path for results
pop_size
              : population size
symbols
             : symbols
formula : formula
+++++ Default parameters +++++
check_seed : if check seed is turned on, we will check
your seeds and delete those donot meet requirements
                 default value: False
parameter information for <class
'magus.populations.populations.VarPopulation'>
+++++ Requirement parameters +++++
results_dir : path for results
pop_size
              : population size
symbols
          : symbols : formula
             : formula
formula
+++++ Default parameters +++++
check_seed : if check seed is turned on, we will check
your seeds and delete those donot meet requirements
                 default value: False
parameter information for <class
'magus.reconstruct.individuals.RcsPopulation'>
+++++ Requirement parameters +++++
results_dir : path for results
pop_size
             : population size
          : symbols : formula
symbols
formula
+++++ Default parameters +++++
check_seed : if check seed is turned on, we will check
your seeds and delete those donot meet requirements
                 default value: False
```

```
parameter information for <class
'magus.operations.crossovers.CutAndSplicePairing'>
+++++ Default parameters +++++
              : try attempts
tryNum
                 default value: 50
              : cut displacement
cut_disp
                 default value: 0
             : choose best match
best_match
                 default value: False
parameter information for <class
'magus.operations.crossovers.ReplaceBallPairing'>
+++++ Default parameters +++++
tryNum
              : try attempts
                 default value: 50
             : cut range
cut_range
                 default value: [1, 2]
parameter information for <class
'magus.operations.mutations.SoftMutation'>
+++++ Default parameters +++++
tryNum
              : tryNum
                 default value: 50
parameter information for <class
'magus.operations.mutations.PermMutation'>
+++++ Default parameters +++++
tryNum
              : try attempts
                 default value: 50
frac_swaps : possibility to swap
                 default value: 0.5
parameter information for <class
'magus.operations.mutations.LatticeMutation'>
+++++ Default parameters +++++
tryNum
              : try attempts
                 default value: 50
sigma
              : Gauss distribution standard deviation
                 default value: 0.1
cell_cut
              : coefficient of gauss distribution in cell
mutation
```

```
default value: 1
keep_volume : whether to keep the volume unchange
                  default value: True
parameter information for <class
'magus.operations.mutations.RippleMutation'>
+++++ Default parameters +++++
               : try attempts
tryNum
                  default value: 50
               : rho
rho
                  default value: 0.3
mu
               : mu
                  default value: 2
eta
               : eta
                  default value: 1
parameter information for <class
'magus.operations.mutations.SlipMutation'>
+++++ Default parameters +++++
tryNum
               : try attempts
                  default value: 50
               : cut position
cut
                  default value: 0.5
randRange
               : range of movement
                  default value: [0.5, 2]
parameter information for <class
'magus.operations.mutations.RotateMutation'>
+++++ Default parameters +++++
tryNum
               : try attempts
                  default value: 50
               : possibility
p
                  default value: 1
parameter information for <class
'magus.operations.mutations.RattleMutation'>
+++++ Default parameters +++++
tryNum
               : try attempts
                  default value: 50
               : possibility
p
                  default value: 0.25
```

```
rattle_range : range of rattle
                 default value: 4
d_ratio : d_ratio
                default value: 0.7
keep_sym : if keeps symmetry when rattles
                 default value: None
symprec : tolerance for symmetry finding
                 default value: 0.1
parameter information for <class
'magus.operations.mutations.FormulaMutation'>
+++++ Default parameters +++++
              : try attempts
tryNum
                 default value: 10
n_candidate : number of candidates
                 default value: 5
parameter information for <class
'magus.reconstruct.ga.LyrSlipMutation'>
+++++ Default parameters +++++
tryNum
              : tryNum
                 default value: 10
             : cut
cut
                 default value: 0.2
randRange : randRange
                 default value: [0, 1]
parameter information for <class
'magus.reconstruct.ga.ShellMutation'>
+++++ Default parameters +++++
tryNum
              : tryNum
                 default value: 10
              : d
d
                 default value: 0.23
parameter information for <class
'magus.reconstruct.ga.LyrSymMutation'>
+++++ Default parameters +++++
tryNum
        : tryNum
                 default value: 10
symprec
             : symprec
```

```
default value: 0.0001
parameter information for <class
'magus.reconstruct.ga.CluSymMutation'>
+++++ Default parameters +++++
tryNum
               : tryNum
                  default value: 10
               : symprec
symprec
                  default value: 0.0001
parameter information for <class
'magus.calculators.emt.EMTCalculator'>
+++++ Requirement parameters +++++
              : work dictionary
work_dir
job_prefix
              : calculation dictionary
+++++ Default parameters +++++
eps
               : convergence energy
                  default value: 0.05
               : maximum number of relax steps
max_step
                  default value: 100
               : optimizer method, choose from bfgs, fire,
optimizer
lbfgs
                  default value: bfgs
               : max range of movement
max_move
                  default value: 0.1
relax_lattice : if to relax lattice
                  default value: True
pressure
               : pressure
                  default value: 0.0
parameter information for <class
'magus.calculators.lammps.LammpsCalculator'>
+++++ Default parameters +++++
               : choose from parallel or serial
mode
                  default value: parallel
               : pressure
pressure
                  default value: 0.0
exe_cmd
               : command line to run lammps
                  default value:
               : save_traj
save_traj
                  default value: False
```

```
atomStyle : atomStyle
                 default value: atomic
job_prefix : job_prefix
                default value: Lammps
+++++ Requirement_parallel parameters +++++
queue_name : quene name
num core
             : num core
work_dir
             : work dictionary
job_prefix : calculation dictionary
+++++ Default_parallel parameters +++++
pre_processing : serves to add any sentence you wish when
submiting the job to change system variables, load modules
etc.
                 default value:
wait_time
             : wait time
                 default value: 200
verbose
              : verbose
                 default value: False
kill_time : kill_time
                 default value: 100000
num_parallel : num_parallel
                default value: 1
              : pressure
pressure
                 default value: 0.0
parameter information for <class
'magus.calculators.mtp.MTPNoSelectCalculator'>
+++++ Default parameters +++++
              : choose from parallel or serial
mode
                 default value: parallel
              : pressure
pressure
                 default value: 0.0
force_tolerance: force_tolerance
                 default value: 0.05
stress_tolerance: stress_tolerance
                 default value: 1.0
min_dist
             : min dist
                 default value: 0.5
n_epoch
           : n_epoch
                 default value: 200
job_prefix : job_prefix
```

```
default value: MTP
+++++ Requirement_parallel parameters +++++
queue_name : quene name
num core
              : num_core
work dir
              : work dictionary
job_prefix : calculation dictionary
+++++ Default_parallel parameters +++++
pre_processing : serves to add any sentence you wish when
submiting the job to change system variables, load modules
etc.
                 default value:
              : wait time
wait time
                 default value: 200
              : verbose
verbose
                 default value: False
kill_time
              : kill_time
                 default value: 100000
num_parallel : num_parallel
                 default value: 1
pressure
              : pressure
                 default value: 0.0
parameter information for <class
'magus.calculators.mtp.MTPSelectCalculator'>
+++++ Default parameters +++++
              : choose from parallel or serial
mode
                 default value: parallel
              : pressure
pressure
                 default value: 0.0
              : xc
хс
                 default value: PBE
weights
              : weights
                 default value: [1.0, 0.01, 0.001]
scaled_by_force: scaled_by_force
                 default value: 0.0
force_tolerance: force_tolerance
                 default value: 0.05
stress_tolerance: stress_tolerance
                 default value: 1.0
min_dist : min_dist
                 default value: 0.5
```

```
n_epoch
               : n_epoch
                  default value: 200
ignore_weights : ignore_weights
                 default value: True
               : iob prefix
job_prefix
                  default value: MTP
               : n fail
n_fail
                  default value: 0
+++++ Requirement_parallel parameters +++++
              : quene name
queue_name
num_core
               : num_core
work dir
              : work dictionary
job_prefix : calculation dictionary
+++++ Default_parallel parameters +++++
pre_processing : serves to add any sentence you wish when
submiting the job to change system variables, load modules
etc.
                  default value:
wait_time
               : wait_time
                  default value: 200
verbose
               : verbose
                  default value: False
               : kill time
kill time
                  default value: 100000
num_parallel
               : num_parallel
                  default value: 1
pressure
               : pressure
                  default value: 0.0
parameter information for <class
'magus.calculators.mtp.MTPLammpsCalculator'>
+++++ Default parameters +++++
mode
               : choose from parallel or serial
                  default value: parallel
               : pressure
pressure
                  default value: 0.0
хс
               : xc
                  default value: PBE
               : weights
weights
                  default value: [1.0, 0.01, 0.001]
scaled_by_force: scaled_by_force
```

```
default value: 0.0
force_tolerance: force_tolerance
                 default value: 0.05
stress_tolerance: stress_tolerance
                 default value: 1.0
               : min dist
min_dist
                 default value: 0.5
n_epoch
               : n epoch
                 default value: 200
ignore_weights : ignore_weights
                 default value: True
               : job_prefix
job_prefix
                 default value: MTP
n_fail
               : n fail
                 default value: 0
+++++ Requirement_parallel parameters +++++
queue_name
              : quene name
num core
              : num core
work_dir
              : work dictionary
job_prefix
              : calculation dictionary
+++++ Default_parallel parameters +++++
pre_processing : serves to add any sentence you wish when
submiting the job to change system variables, load modules
etc.
                 default value:
wait time
              : wait time
                 default value: 200
verbose
               : verbose
                 default value: False
kill_time
               : kill time
                 default value: 100000
num_parallel
              : num_parallel
                 default value: 1
pressure
               : pressure
                 default value: 0.0
parameter information for <class
'magus.calculators.quip.QUIPCalculator'>
+++++
       Requirement parameters +++++
work_dir
          : work dictionary
job_prefix : calculation dictionary
```

```
+++++ Default parameters +++++
              : convergence energy
eps
                 default value: 0.05
              : maximum number of relax steps
max_step
                 default value: 100
optimizer
               : optimizer method, choose from bfgs, fire,
lbfgs
                 default value: bfgs
               : max range of movement
max_move
                 default value: 0.1
relax_lattice : if to relax lattice
                 default value: True
              : pressure
pressure
                 default value: 0.0
parameter information for <class
'magus.calculators.vasp.VaspCalculator'>
+++++ Default parameters +++++
mode
               : choose from parallel or serial
                 default value: parallel
pressure
              : pressure
                 default value: 0.0
              : XC
ХC
                 default value: PBE
pp_label
              : pp_label
                 default value: None
job_prefix
              : job_prefix
                 default value: Vasp
+++++ Requirement_parallel parameters +++++
queue_name : quene name
num core
              : num core
work_dir
             : work dictionary
job_prefix : calculation dictionary
+++++ Default_parallel parameters +++++
pre_processing : serves to add any sentence you wish when
submiting the job to change system variables, load modules
etc.
                 default value:
wait_time
             : wait_time
                 default value: 200
verbose
               : verbose
```

```
default value: False
              : kill time
kill_time
                 default value: 100000
num_parallel
              : num_parallel
                 default value: 1
pressure
               : pressure
                 default value: 0.0
parameter information for <class
'magus.calculators.castep.CastepCalculator'>
+++++ Default parameters +++++
               : choose from parallel or serial
mode
                 default value: parallel
               : pressure
pressure
                 default value: 0.0
xc_functional : xc_functional
                 default value: PBE
              : pspot
pspot
                 default value: 00PBE
suffix
              : suffix
                 default value: usp
job_prefix : job_prefix
                 default value: Castep
kpts
               : kpts
                 default value: {'density': 10, 'gamma':
                 True, 'even': False}
castep_command : castep_command
                 default value: castep
castep_pp_path : castep_pp_path
                 default value: None
+++++ Requirement_parallel parameters +++++
queue_name : quene name
num_core
              : num_core
work dir
              : work dictionary
job_prefix : calculation dictionary
+++++ Default_parallel parameters +++++
pre_processing : serves to add any sentence you wish when
submiting the job to change system variables, load modules
etc.
                 default value:
wait_time
              : wait_time
```

```
default value: 200
               : verbose
verbose
                  default value: False
kill time
               : kill time
                  default value: 100000
num_parallel
               : num_parallel
                  default value: 1
               : pressure
pressure
                  default value: 0.0
parameter information for <class
'magus.calculators.lj.LJCalculator'>
+++++ Requirement parameters +++++
work_dir
               : work dictionary
              : calculation dictionary
job_prefix
+++++ Default parameters +++++
eps
               : convergence energy
                  default value: 0.05
               : maximum number of relax steps
max_step
                  default value: 100
               : optimizer method, choose from bfgs, fire,
optimizer
lbfgs
                  default value: bfgs
               : max range of movement
max_move
                  default value: 0.1
relax_lattice : if to relax lattice
                  default value: True
pressure
               : pressure
                  default value: 0.0
parameter information for <class
'magus.calculators.gulp.GulpCalculator'>
+++++ Default parameters +++++
               : choose from parallel or serial
mode
                  default value: parallel
               : pressure
pressure
                  default value: 0.0
exe_cmd
               : command line to run gulp
                  default value: gulp < input > output
job_prefix
               : job_prefix
                  default value: Gulp
```

```
+++++ Requirement_parallel parameters +++++
queue_name : quene name
num_core
             : num_core
work_dir
             : work dictionary
job_prefix : calculation dictionary
+++++ Default_parallel parameters +++++
pre_processing : serves to add any sentence you wish when
submiting the job to change system variables, load modules
etc.
                 default value:
wait_time : wait_time
                 default value: 200
verbose
              : verbose
                 default value: False
kill_time
             : kill time
                 default value: 100000
num_parallel
              : num_parallel
                 default value: 1
pressure
              : pressure
                 default value: 0.0
parameter information for <class
'magus.calculators.base.AdjointCalculator'>
+++++ Requirement parameters +++++
work_dir : work dictionary
             : calculation dictionary
job prefix
+++++ Default parameters +++++
pressure
              : pressure
                 default value: 0.0
parameter information for <class
'magus.calculators.mtp.TwoShareMTPCalculator'>
+++++ Requirement parameters +++++
           : work dictionary
work dir
job_prefix : calculation dictionary
+++++ Default parameters +++++
             : pressure
pressure
                 default value: 0.0
```

Chapter 5

FAQ

5.1 How to Set Environment Variables

There are two modes in MAGUS: serial mode and parallel mode, controlled by "mode" option.

In serial mode ("mode: serial"), only one main job runs. All sub calculations (such as vasp relaxations) will run under the computing resource you apply for the main job. Hence, you can modify environment variables in the main job and they will be effective to all calculations.

In parallel mode ("mode: parallel"), the main job only works for some simple calculations and submitting sub jobs into job system to do more time-consuming calculations, which means sub jobs take different environment variables from the main job. Generally, sub job submission scripts are generated automatically by MAGUS, but you should add some environment variables to make the scripts fit for your system. The most convenient way to do that is to add "preprocessing" option in <code>input.yaml</code> under each Calculator category. For example:

```
# general parameters
formulaType: fix

...

# calcultor parameters

MainCalculator:
   jobPrefix: Vasp
   ...
   preProcessing: |
    #BSUB -gpu "num=1"
    module purge
   module load ips/xxxx cuda/xxxx
```

Chapter 5. FAQ MAGUS 1.6.1

```
export PATH=$PATH:xxxx
```

or you can just write in a single line if your code is short:

```
preProcessing: module load ips; source activate myenv
```

MAGUS will concatenate these codes after preProcessing into the submission script.

TIPS: There is a trick that most job systems run a new submission job with a new shell which will execute your bashrc at first. As a result, you can add the frequently used codes, such as **module load ips**, into bashrc and then you need not add such codes in preProcessing.

5.2 How to Use Python Virtual Environment

If you install MAGUS in your default env and you can directly run MAGUS in your console and <code>import magus</code> in python, you need do nothing and it will all work fine. If you install MAGUS in another env, you should modify the input files to activate the env in jobs. Add

```
$ source activate <your-env-name>
```

in the submission job and add

```
preProcessing: source activate <your-env-name>
```

in the input.yaml under each Calculator category such as MainCalculator.

5.3 PBS Job System Parallel Mode "qsub" Command Not Found

In some PBS system, "qsub" command is not under system path in compute nodes, which causes "qsub command not found" error. To fix this error, you need to add the path of "qsub" in your parent batch job. You can use

```
which qsub
```

Chapter 5. FAQ MAGUS 1.6.1

to get the path. You will get the output <your-pbs-lib-dir>/qsub. Then add such line in you batch file before MAGUS commands: