# 4 Electromagnetic waves in material

Let's let everything move!

## 4.1 Displacement current

Conservation of charge

$$abla \cdot \mathbf{J_s} = -rac{\partial 
ho_f}{\partial t}$$

However, this is incompatible with

$$abla imes \mathbf{H} = \mathbf{J}_f$$

Lets take the divergence for both sides, we get

$$abla \cdot (
abla imes \mathbf{H}) = 0 = 
abla \cdot \mathbf{J} + rac{\partial}{\partial t} \underbrace{
abla \cdot \mathbf{D}}_{
ho_{\mathbf{f}}}$$

 $\Rightarrow$  add an additional term to the current density  $J_f = \nabla \times H$ 

$$\Rightarrow 
abla imes \mathbf{H} = \mathbf{J_f} + \underbrace{rac{\partial \mathbf{D}}{\partial t}}_{ ext{displacement curren}}$$

LHS: 
$$\nabla imes \left( \frac{\mathbf{B}}{\mu_0} - \mathbf{M} \right) = \frac{1}{\mu_0} \nabla imes \mathbf{B} - \underbrace{\nabla imes \mathbf{M}}_{\mathbf{J_b}}$$

Where  $\boldsymbol{J}_{\boldsymbol{b}}$  is the bound current density.

$$\text{RHS} = \mathbf{J_s} + \tfrac{\partial \mathbf{D}}{\partial t} = \mathbf{J_s} + \tfrac{\partial \mathbf{P}}{\partial t} + \epsilon_0 \tfrac{\partial \mathbf{E}}{\partial t}$$

$$\Rightarrow$$
 we could write  $abla imes {f B} = \mu_0 \left( {f J_f} + {f J_b} + {f J_p} 
ight) + \mu_0 \epsilon_0 rac{\partial {f E}}{\partial t}$ 

where  $J_p$  is the polarization current density. which equals  $\frac{\partial \mathbf{P}}{\partial t}$ 

Note that  $abla \cdot \mathbf{J_p} = -rac{\partial 
ho_p}{\partial t}$  from conservation of charge.

Thus the polarization current responds to changes to bound charge, and hence in  ${f P}$ 

# 4.2 Maxwell's equations in insulating linear dielectrics

Since it is insulating linear dielectrics, we have  ${f J}_f=0$  and  ${f J}_b=0$ 

Hence, we could get Maxwell's equation

$$abla \cdot \mathbf{D} = 0$$
  $\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$ 

$$\nabla \cdot \mathbf{B} = 0$$
  $\nabla \times \mathbf{H} = \frac{\partial \mathbf{D}}{\partial t}$ 

remember,  ${f D}=\epsilon_0\epsilon_r{f E}+{f P}$  and  ${f B}=\mu_0\mu_r{f H}$  which gives

$$abla \cdot \mathbf{E} = 0$$
  $\qquad \nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$ 

$$abla \cdot \mathbf{B} = 0$$
  $\nabla \times \mathbf{B} = \mu_0 \mu_r \epsilon_0 \epsilon_r \frac{\partial \mathbf{E}}{\partial t}$ 

Consider

$$egin{aligned} 
abla imes (
abla imes \mathbf{E}) &= 
abla (
abla \cdot \mathbf{E}) - 
abla^2 \mathbf{E} = -rac{\partial}{\partial t} 
abla imes \mathbf{B} \end{aligned}$$
 $\Rightarrow 
abla^2 \mathbf{E} = \underbrace{\mu_0 \mu_r \epsilon_0 \epsilon_r}_{rac{1}{2}} rac{\partial^2 \mathbf{E}}{\partial t^2}$ 

which is wave equation.

 $\Rightarrow v = rac{c}{n}$  where c =  $rac{1}{\sqrt{\epsilon_0 \mu_0}}$  and n =  $\sqrt{\epsilon_r \mu_r}$  where n is also called *refractive index* 

#### Plane waves solutions

Lets choose propagation parallel to z, and hence

$$\frac{\partial \Psi}{\partial \mathbf{x}} = \frac{\partial \Psi}{\partial \mathbf{y}} = 0$$

remember that 
$$\nabla \cdot \mathbf{E} = 0 \Rightarrow \frac{\partial E_z}{\partial z} = 0$$
 similarly,  $\nabla \cdot \mathbf{B} = 0 \Rightarrow \frac{\partial B_z}{\partial z} = 0$ 

we also have 
$$abla imes \mathbf{E} = -rac{\partial \mathbf{B}}{\partial t} \Rightarrow rac{\partial B_z}{\partial t} = 0$$

And 
$$abla extbf{X} extbf{B} = \mu_0 \mu_r \epsilon_0 \epsilon_r rac{\partial \mathbf{E}}{\partial t} \Rightarrow rac{\partial E_z}{\partial t} = 0$$

Hence,  $E_z$  and  $B_z$  are constant in z and t, they are not part of wave motion now analyze the x,y components of curl:

$$-\frac{\partial E_y}{\partial z} = -\frac{\partial B_x}{\partial t}, -\frac{\partial B_y}{\partial z} = \frac{1}{v^2} \frac{\partial E_x}{\partial t}$$

 $\Rightarrow E_x, B_y$  are solutions

Lets then take

$$egin{align} rac{\partial^2 E_x}{\partial t^2} &= rac{1}{v^2} rac{\partial^2 E_x}{\partial t^2} \ \Rightarrow E_x(z,t) &= E_{x0} e^{i(\pm kz - \omega t)} \mathbf{\hat{x}} \end{aligned}$$

Then, we could have

$$A\Rightarrow B(z,t)=B_0e^{i(\pm kz-\omega t)}\mathbf{\hat{y}}$$

And then we could get the wave travelling in  $\pm \mathbf{z}$  direction

$$\Rightarrow \mp kE_0 = -\omega B_0$$
 and  $\pm kB_0 = rac{\omega}{v^2}E_0$   $\Rightarrow rac{E_0}{B_0} = \pm rac{\omega}{k} = \pm v$ 

Define Impedance Z as

$$Z = \left|rac{E_0}{H_0}
ight| = \sqrt{rac{\mu_0\mu_r}{\epsilon_0\epsilon_r}}$$

remember that  $H_0=rac{B_0}{\mu_0\mu_r}$ 

The motivation of doing so is that  $v = -\int \mathbf{E} \cdot d\mathbf{l}$  and  $I = \oint \mathbf{H} \cdot d\mathbf{l}$ 

So dimension would work

For free space, then, 
$$\epsilon_r=\mu_r=1$$
 and  $Z=\sqrt{rac{\mu_0}{\epsilon_0}}=377\Omega$ 

Remember that  $abla imes {f E} = -{f \dot B}$ , and use E, B  $\propto e^{i({f k}\cdot{f r}-\omega t)}$ , we could get

$$egin{aligned} i\mathbf{k} imes\mathbf{E} &= -(-i\omega)\mathbf{B} \ &= i\omega\mu_0\mu_r\mathbf{H} \ \Rightarrow Z &= \left|rac{\mathbf{E}}{\mathbf{H}}
ight| = \sqrt{rac{\mu_0\mu_r\omega}{k}} \end{aligned}$$

Which gives the same answer because  $v=rac{c}{n}=rac{\omega}{k}=rac{1}{\sqrt{\epsilon_0\epsilon_r\mu_0\mu_r}}$  which is this wave

## 4.3 conductors

Remember that 
$$\nabla \cdot \mathbf{J_f} = -\frac{\partial \rho_f}{\partial t}$$
 
$$\nabla \cdot \mathbf{J_p} = -\frac{\partial \rho_p}{\partial t}$$
 
$$\nabla \cdot \mathbf{J_b} = 0$$

The last one is 0 because  $abla \cdot (
abla imes \mathbf{M}) = 0$ 

For conductors, we have

 $ho_f=0$  since there are no free charges in equilibrium

 $\mathbf{J}_f = \sigma \mathbf{E}$  from Ohm's law where  $\sigma$  is the conductivity

$$\mathbf{D} = \epsilon_0 \epsilon_r \mathbf{E}$$
 and  $\mathbf{B} = \mu_0 \mu_r \mathbf{H}$  from linearity

Then we could get Maxwell's equation in conductors

$$\nabla \cdot \mathbf{E} = 0$$

$$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$$

$$\nabla \cdot \mathbf{B} = 0$$

$$\nabla \times \mathbf{B} = \underbrace{\mu_0 \mu_r \sigma \mathbf{E}}_{\text{conduction } \mathbf{J}} + \underbrace{\mu_0 \mu_r \sigma_0 \sigma_r \frac{\partial \mathbf{E}}{\partial t}}_{\text{dispalcement } \mathbf{J}}$$

Free charge will decay to zero in a short time au, and it is easy to prove (said Blundell)

$$\nabla \cdot \mathbf{J} = \frac{\partial \rho}{\partial t}$$

Where  $\nabla \cdot \mathbf{J}$  is equal to  $\sigma \cdot \nabla \cdot \mathbf{E}$  from Ohm's law

and  $abla \cdot \mathbf{E}$  is equal to  $rac{
ho}{\epsilon_0 \epsilon_r}$  from Gauss's law

$$\Rightarrow 
ho(f) = 
ho(0) e^{-rac{t}{ au}}$$

Where  $au = rac{\epsilon_0 \epsilon_r}{\sigma}$ 

If the metal has great conductivity, then  $\tau$  is very small, and hence  $\rho(f)$  is very small.

Let's consider the electromagnetic wave having frequency  $\omega$ , so we would like to compare  $\frac{1}{\omega}$  with  $\tau$ :

Condition	Conductor Type	Charge Response	Conductivity
$\omega  au \ll 1$	Good conductor	Charges respond very quickly	$\sigma\gg\epsilon_0\epsilon_r\omega$ Conduction current dominates
$\omega au\gg 1$	Bad conductor	Charges respond very slowly	$\sigma \ll \epsilon_0 \epsilon_r \omega$ Displacement current dominates

Take real life examples

	$\sigma(\Omega m)$	$\epsilon_r$	$rac{\sigma}{\epsilon_0\epsilon_r}(S^{-1})$
metal	$10^7$	1	$10^{19}$
Silicon	$4\cdot 10^{-4}$	11.7	$10^{7}$
Glass	$10^{-10}$	5	10

Note that visible light would have frequency ~  $5\cdot 10^{14}~\mathrm{Hz}$ 

Let's now do some electromagnetism

$$\nabla \times (\nabla \times \mathbf{E}) = \underbrace{\nabla (\nabla \cdot \mathbf{E})}_{0} - \nabla^{2} \mathbf{E}$$

$$= -\frac{\partial}{\partial t} \nabla \times \mathbf{B}$$

$$\nabla^{2} \mathbf{E} = \mu_{0} \mu_{r} \sigma \frac{\partial \mathbf{E}}{\partial t} + \mu_{0} \mu_{r} \sigma_{0} \sigma_{r} \frac{\partial^{2} \mathbf{E}}{\partial t^{2}}$$

Again, this would yield transverse plane waves with  ${f E, B} \perp$  to each others

$$\Rightarrow \mathbf{E} = \mathbf{E}_0 \hat{\mathbf{x}} e^{i(\hat{\mathbf{k}} \cdot \mathbf{z} - \omega t)}$$

with 
$$\widetilde{\mathbf{k}}=\mathbf{k}+i\kappa$$

$$ightarrow \widetilde{k}^2 = i \underbrace{\mu_0 \mu_r \sigma \omega}_{\mu} + \underbrace{\mu_0 \mu_r \epsilon_0 \epsilon_r}_{\epsilon} \omega^2$$

$$(k+i\kappa)^2 = k^2 - \kappa^2 + 2ik\kappa$$

$$k^2 - \kappa^2 = \mu_0 \epsilon_0 \omega^2$$

$$egin{align} 2k\kappa &= \mu\sigma\omega \Rightarrow k = rac{\mu\sigma\omega}{2\kappa} \ 0 &= \left(rac{\mu\sigma\omega}{2}
ight)^2rac{1}{\kappa^2} - \kappa^2 - \mu\epsilon_0\omega^2 \ 0 &= (\kappa^2)^2 + \mu\epsilon\omega^2(\kappa^2) - \left(rac{\mu\sigma\omega}{2}
ight)^2 \ \end{cases}$$

$$\kappa^2 = -rac{\mu\epsilon\omega^2}{2} \pm \sqrt{\left(rac{\mu\epsilon\omega^2}{2}
ight)^2 + \left(rac{\mu\sigma\omega}{2}
ight)^2}$$

$$\kappa^2 = rac{\mu\epsilon\omega^2}{2} \left[ \pm \sqrt{1+\left(rac{\sigma}{\epsilon\omega}
ight)^2} - 1 
ight]$$

Taking the positive root

$$\Rightarrow \kappa = \sqrt{rac{\mu\epsilon}{2}}\omega\sqrt{\sqrt{1+\left(rac{\sigma}{\epsilon\omega}
ight)^2}-1}$$

Sub into original equation

$$k = \frac{\mu\sigma\omega}{2\kappa} = \sqrt{\frac{\mu\epsilon}{2}}\omega\sqrt{\sqrt{1+\left(\frac{\sigma}{\epsilon\omega}\right)^2+1}}$$
  
 $\Rightarrow \mathbf{E} = \mathbf{E}_0\hat{\mathbf{x}}\underbrace{e^{-\kappa z}}_{e^{-\frac{z}{\delta}}}e^{i(\mathbf{k}\cdot\mathbf{r}-\omega t)}$ 

Where  $\delta=\frac{1}{\kappa}$  is the skin depth

*Reminder.* Good conductors have  $\sigma\gg\epsilon\omega$ 

$$k=\kappa=\sqrt{rac{\mu\epsilon}{2}}\omega\sqrt{rac{\sigma}{\epsilon\omega}}=\sqrt{rac{\mu\omega\sigma}{2}}$$

We could therefore have

$$abla^2 \mathbf{E} = \mu \sigma rac{\partial \mathbf{E}}{\partial t} + \mu \epsilon rac{\partial^2 \mathbf{E}}{\partial t^2}$$

We could also neglect the last term, since  $\frac{\partial^2 \mathbf{E}}{\partial t^2} \ll \frac{\partial \mathbf{E}}{\partial t}$ 

$$\Rightarrow \widetilde{k}^2 = i\mu\sigma\omega$$

$$\Rightarrow \widetilde{k} = \frac{1+i}{\sqrt{2}}\sqrt{\mu\sigma\omega}$$

$$\Rightarrow \widetilde{k} = \kappa = \sqrt{\frac{\mu\sigma\omega}{2}}$$

Hence, we could have

$$\delta = \frac{1}{k} = \sqrt{\frac{2}{\mu\sigma\omega}}$$

For a typical metal,  $\delta$  is

 $\begin{cases} \text{few nm - visible light} \\ \text{few}\mu m \text{ - microwave} \\ \text{few mm - radio waves} \end{cases}$ 

Lets go to poor conductors

Poor conductors has  $\sigma \ll \epsilon \omega$ , hence

$$kpprox\sqrt{rac{\mu\epsilon}{2}}\omega\sqrt{2}=\sqrt{\mu\epsilon}\omega \ \kappa=\sqrt{rac{\mu\epsilon}{2}}\omega\Big(1+rac{1}{2}ig(rac{\sigma}{\epsilon\omega}ig)^2+\cdots-1\Big)^{rac{1}{2}}$$

which equals to  $\frac{\sigma}{2}\sqrt{\frac{\mu}{\epsilon}}$  which is independent to  $\omega$ 

In an insulating dielectric,  $\sigma=0$ , hence  $\kappa=0$ , and hence  $k=\frac{\omega}{v}$  as expected.

Lets return to previous equation

Lets consider the curl equation in the conductor

$$egin{aligned} rac{\partial \mathbf{E}_x}{\partial z} &= rac{\partial B_y}{\partial t} \ i(k+k)\mathbf{E}_0 &= i\omega \mathbf{B}_0 \ z &= rac{\mu E_0}{B_0} &= rac{\mu \omega}{k+i\kappa} \ \widetilde{k} &= rac{\mu \omega}{\sqrt{k^2 + \kappa^2}} e^{i\phi} \end{aligned}$$

If we expand,  $\phi$  would be

$$\phi = an^{-1} \left( rac{\sqrt{1 + (Q/\epsilon\omega)^2} - 1}{\sqrt{1 + (Q/\epsilon\omega)^2} + 1} 
ight)^{rac{1}{2}}$$

For a good conductor,  $\sigma\gg\epsilon\omega$ , hence  $\phi o an^{-1}1=rac{\pi}{4}$ 

So this means that B lags behind E in a metal

## 4.4 Poynting vectors

Work done on charge

$$egin{aligned} \delta q &= 
ho = \delta au \ \delta F &= \delta q (\mathbf{E} + \mathbf{v} imes \mathbf{B}) \ \delta \mathbf{F} \cdot \mathbf{dl} &= \delta q (\mathbf{E} + \mathbf{v} imes \mathbf{B}) \cdot \mathbf{v} \delta t \ &= \mathbf{E} \cdot \mathbf{J_f} \delta au \delta t \end{aligned}$$

where  $\mathbf{J}_f$  eaquals to  $\rho \mathbf{v}$ 

Rate of work on charges

$$egin{aligned} \mathbf{F} &= rac{dw}{dt} \ &= \mathbf{E} \cdot \mathbf{J_f} d au \ &= rac{d}{dt} \int \underbrace{u_{mech}}_{ ext{Energy density}} d au \end{aligned}$$

From Maxwell's equation:

$$\mathbf{J}_f = 
abla imes \mathbf{H} - rac{\partial \mathbf{D}}{\partial t}$$

We have

$$\mathbf{E} \cdot \mathbf{J_f} = \mathbf{E} \cdot \nabla \times \mathbf{H} - \mathbf{E} \cdot \frac{\partial \mathbf{D}}{\partial \mathbf{t}}$$

By dotting everything, and then

$$egin{aligned} 
abla \cdot (\mathbf{E} imes \mathbf{H}) &= \mathbf{H} \cdot 
abla imes \mathbf{E} - \mathbf{E} \cdot 
abla imes \mathbf{H} \\ \mathbf{E} \cdot \mathbf{J_f} &= \mathbf{H} \cdot \underbrace{
abla imes \mathbf{E}}_{-rac{\partial \mathbf{B}}{\partial t}} - \mathbf{E} \cdot rac{\partial \mathbf{D}}{\partial t} - 
abla \cdot (\mathbf{E} imes \mathbf{H}) \end{aligned}$$

Where we call  $\mathbf{H} \cdot \underbrace{\nabla \times \mathbf{E}}_{-\frac{\partial \mathbf{B}}{\partial t}} - \mathbf{E} \cdot \frac{\partial \mathbf{D}}{\partial t}$  " $\frac{\partial}{\partial t} u_{EM}$ " (remember that

 $u_{EM} = \frac{1}{2} (\mathbf{B} \cdot \mathbf{H} + \mathbf{E} \cdot \mathbf{D})$  which equals to energy stored in EM field per unit volume) and  $\nabla \cdot (\mathbf{E} \times \mathbf{H})$  as " $\mathbf{S} = \mathbf{E} \times \mathbf{H}$ " or Poynting vector.

How is this working?

Assume that we are using a linear media:

$$\begin{aligned} \mathbf{E} \cdot \frac{\partial \mathbf{D}}{\partial t} &= \frac{1}{2} \cdot \frac{\partial (\mathbf{E} \cdot \mathbf{D})}{\partial t} \\ \mathbf{H} \cdot \frac{\partial \mathbf{B}}{\partial t} &= \frac{1}{2} \cdot \frac{\partial (\mathbf{B} \cdot \mathbf{H})}{\partial t} \end{aligned}$$

Remember that

$$\frac{1}{2}\epsilon_0 E^2 = \frac{1}{2}DE$$

$$\frac{B^2}{2\mu_0} = \frac{1}{2}BH$$
In free space

Bringing everything together, we could get


$$\Rightarrow rac{d}{dt}(u_{
m mech}+u_{
m EM})+
abla\cdot{f S}=0$$

Where  ${f S}$  is the poyting vector, or equiviantly,

$$\frac{d}{dt}\int (u_{\mathrm{mech}} + u_{\mathrm{EM}})d au + \oint \mathbf{S} \cdot d\mathbf{a} = 0$$

We could say that, therefore  ${\bf S}$  is the energy flux density, or the rate of flow of energy per unit area in the direction of S.


Example: a capacitor



The stored energy increase at rate

$$\dot{U} = rac{Q}{C}rac{dQ}{dt} \quad U = rac{Q^2}{2C}$$

also:




Hence, we have

$$\dot{U} = S \cdot 2\pi r d = rac{Q}{c} rac{dQ}{dt}$$

where 
$$S=EH=rac{Q}{dc}rac{rac{dQ}{dt}}{2\pi r}$$

There is another example



$$H \cdot S\pi a = I$$
 
$$E = \frac{V}{l}$$
 
$$\Rightarrow S = \frac{V}{l} \frac{I}{2\pi a}$$
 
$$\int \mathbf{S} \cdot \mathbf{da} = -IV = -I^2 R$$

# 4.5 Radiation pressure

EM waves are made up of photons, and hecne they have momentum

$$E = pc$$

 $\Rightarrow$  Transport of energy is appoinated by transport of momentum

$$P_{rad} = rac{< S>}{c}$$

For a perfect absorber, where  $P_{rad}$  is the radiation pressure

**Example** For a plane EM wave in free space, we have

$$U = rac{1}{2}\epsilon_0 E^2 + frac12rac{B^2}{\mu_0}$$
but  $E = cB$ 
 $\Rightarrow U = \epsilon_0 E^2$ 
 $\mathbf{E} = rac{1}{2}E_0\cos(kz - \omega t)\hat{\mathbf{x}}$ 
 $= E_0\cos^2(kz - \omega t)$ 
 $< E^2 > = rac{1}{2}E_0^2$ 
 $\Rightarrow < u > = rac{1}{2}\epsilon_0 E_0^2$ 
 $< S > = rac{1}{2}\epsilon_0 E_0^2 c = I$ 

Where I is the intensity of wave

$$\Rightarrow P_{rad} = egin{cases} rac{1}{2} \epsilon_0 E_0^2 & ext{perfect absorber} \ \epsilon_0 E_0^2 & ext{perfect reflector} \end{cases}$$

Sunlight: I~
$$1kWm^{-2}$$
  $\Rightarrow P_{rad} = 10^{-5}Pa$  FYI,  $P_{atm} = 10^{5}Pa$ 

**Example** Consider a star which is growing by accretion

i.e. matter is falling onto it uniformly in all directions

The star has luminosity L (e.g.  $L_{sun}=4 imes10^{26}$  w)

Energy flux = 
$$\frac{L}{4\pi R^2}[Wm^{-2}]$$

Radiation pressure:  $\frac{L}{4\pi R^2 C}$ 

Outward:

Force/unit mass =  $k\frac{L}{4\pi R^2 C}$  where k is the opacity, which is area/unit mass, which is a constant


Inward: Force due to gravity/unit mass =  $\frac{GM}{R^2}$ 

Since they balance, we have

$$\Rightarrow L = \frac{4\pi CGM}{k}$$

which is called Eddington Limit (Upper limit of luminosity of stars that accrete (isotopically))

## 4.6 EM waves - reflection and refraction



$$E_i e^{i(k_1 z - \omega t)} + E_r e^{i(-k_1 z - \omega t)}$$

Right:

$$E_t e^{i(k_2 z - \omega t)}$$

Using electromagnetic boundary conditions, we could get

 $E^{\parallel}$  is continuous

$$E_i^\parallel + E_r^\parallel = E_t^\parallel$$

$$H^{\parallel}$$
 is continuous  $rac{E_i}{Z_1} - rac{E_r}{Z_1} = rac{E_t}{Z_2}$ 

Putting two equations together

$$\frac{E_r}{E_i} = \frac{Z_2 - Z_1}{Z_2 + Z_1}$$
  $\frac{E_t}{E_i} = \frac{2Z_2}{Z_2 + Z_1}$ 

Where 
$$Z=\sqrt{rac{\mu}{\epsilon}}$$

|Poyting vector| 
$$=S=|\mathbf{E} imes\mathbf{H}|=rac{E^2}{Z}$$

We expect  $S_{
m incident} = S_{
m reflected} + S_{
m transmitted}$ 


Where they equal to

$$\frac{E_i^2}{Z_1} + \frac{E_r^2}{Z_1} = \frac{E_t^2}{Z_2}$$

separately

Lets now have angles

$$\mathbf{E}_r e^{i(\mathbf{k_r} \cdot \mathbf{r} - \omega t)}$$



$$\mathbf{E_i}e^{i(\mathbf{k_i}\cdot\mathbf{r}-\omega t)}$$

$$\mathbf{E}_t e^{i(\mathbf{k_t} \cdot \mathbf{r} - \omega t)}$$

Choose  $\mathbf{k}_i$  in x-z plane

At z = 0,  $E_{\parallel}$  is continuous and this holds for all x y and t  $\Rightarrow \omega$  must be the same

$$\Rightarrow {f k_i \cdot r} = {f k_r \cdot r} = {f k_t \cdot r}$$
 for all x, y at z=0

Take 
$$\mathbf{r}=(0,y,0)$$

 $\Rightarrow {f k_i, k_r}$  and  ${f k_t}$  all lie in the xz plane (*the plane of incidence*)

Take 
$$\mathbf{r}=(x,0,0)$$
 so  $\mathbf{k_i}\cdot\mathbf{r}=k\sin\theta_x$ 

$$egin{aligned} |\mathbf{k_i}| &= |\mathbf{k_r}| = k_1 \ |\mathbf{k_t}| &= k_2 \ \mathrm{in}\, heta_i &= k_1\sin heta_r = k_2\sin heta_r \end{aligned}$$

$$\Rightarrow \underbrace{k_1 \sin heta_i = k_1 \sin heta_r}_{ heta_i = heta_r, ext{ law of reflection}} = k_2 \sin heta_t$$

Remember that  $\frac{\omega}{k}=\frac{c}{n}$ , And the last two would lead to

$$\frac{\sin \theta_t}{\sin \theta_i} = \frac{k_1}{k_2} = \frac{n_2}{n_1}$$
 law of refraction, or snell's law

Where 
$$n=\sqrt{\epsilon_r\mu_r}$$


#### **Fresnel equations**

Worring about polarization directions

We work in those steps

#### 1. ${f E}$ in the plane of incidence

Remid that  ${f E}, {f H}$  and  ${f k}$  form a right-handed system



	incident	reflected	transmitted
$E_x$	$E_i\cos heta_i$	$E_r \cos  heta_r$	$E_t \cos  heta_t$
$E_z$	$-E_i\sin heta_i$	$E_r\cos heta_r$	$-E_t\sin heta_t$
$H_y$	$rac{E_i}{Z_1}$	$-rac{E_r}{Z_1}$	$rac{E_t}{Z_2}$


 $E_{\parallel}$  continuous  $\Rightarrow E_x$  continuous  $\Rightarrow E_i \cos heta_i + E_r \cos heta_i = E_t \cos heta_t$ 

$$rac{E_r}{E_i} = rac{Z_2\cos heta_i - Z_1\cos heta_i}{Z_2\cos heta_1 + Z_1\cos heta_i} \ rac{E_t}{E_i} = rac{2Z_2\cos heta_i}{Z_2\cos heta_i + Z_1\cos heta_i}$$

Now look for Fresnel equations for p-polarizations

#### 2. ${f E}$ perpendicular to the plane of incidence

"s-like" s = senkrecht = perpendicular



	incident	reflected	transmitted
$E_y$	$E_i$	$E_r$	$E_t$
$H_x$	$-rac{E_i}{Z_1}{\cos heta_i}$	$rac{E_r}{Z_1}{\cos heta_r}$	$-rac{E_t}{Z_2}{\cos heta_t}$
$H_z$	$rac{E_i}{Z_1}{\sin heta_i}$	$rac{E_r}{Z_1}{\sin heta_r}$	$rac{E_t}{Z_2}{ m sin} heta_t$

 $E_{\parallel}$  continuous

$$\Rightarrow$$
  $E_y$ continuous  $E_i + E_r = E_t$ 

 $H_{\parallel}$  continuous

$$A_{\parallel} = H_{x} continuous$$
  $A_{x} = H_{x} continuous$   $A_{x} = H_{x} continuous$ 

Remember that

$$Z=\sqrt{rac{\mu_r\mu_0}{\epsilon_r\epsilon_0}}=rac{Z_0}{n}\quad n=\sqrt{\epsilon_r}$$
while  $\mu_r=1$ 

Let's set  $\mu_r=1$ 

Let's set 
$$\mu_r=1$$
 Then,  $Z=\sqrt{rac{\mu_r\mu_0}{\epsilon_r\epsilon_0}}=rac{Z_0}{n}$   $n=\sqrt{\epsilon_r}$ 

So we can replace  $Z_i$  with  $\frac{1}{n_i}$  in expressions involving ratios of Z's.

### e.g. Fresnel equations for p-polarization

$$egin{aligned} r = rac{E_r}{E_i} = rac{rac{1}{n_2}\cos heta_t - rac{1}{n_1}\cos heta_i}{rac{1}{n_2}\cos heta_t + rac{1}{n_1}\cos heta_i} \ = rac{n_1\cos heta_t - n_2\cos heta_i}{n_1\cos heta_t + n_2\cos heta_i} \end{aligned}$$

Use Snell's law

$$n_1 \sin heta_i = n_2 \sin heta_t \ \Rightarrow r = rac{\sin 2 heta_t - \sin 2 heta_i}{\sin 2 heta_t + \sin 2 heta_i} \ t = rac{4 \sin_t het a_t \cos heta_i}{\sin 2 heta_t + \sin 2 heta_i}$$

For s-polarization, we have

$$r = rac{\sin( heta_t - heta_i)}{\sin( heta_t + heta_i)} \ t = rac{2\sin heta_t\cos heta_i}{\sin( heta_t + heta_i)}$$

We also have

$$egin{aligned} n_1 \sin heta_i &= n_2 \sin heta_t \ \sin heta_t &= rac{n_1}{n_2} \sin heta_i \ \cos heta_t &= \sqrt{1 - \sin^2 heta_t} = \sqrt{1 - rac{n_1^2}{n_2^2} \sin^2 heta_i} \end{aligned}$$

Fresnel equations:

/  $n_1\cos heta_i$  on top and bottom

$$egin{aligned} lpha &= rac{\cos heta_t}{\cos heta_i} = rac{1}{\cos heta_i} \sqrt{1-(rac{n_1}{n_2}{\sin heta_i})^2} \ eta &= rac{n_2}{n_1} \end{aligned}$$

	$E^{\parallel}$ (p)	$E^{\perp}$ (s)
r	$\frac{\alpha-\beta}{\alpha+\beta}$	$\frac{1-lphaeta}{1+lphaeta}$
t	$\frac{2\alpha}{\alpha+\beta}$	$\frac{2}{1+lphaeta}$

Remember, EM waves have an energy flux given by

$$S = |\mathbf{E} imes \mathbf{H}| = rac{E^2}{Z}$$

Intensity coefficients

$$R=rac{I_r}{I_i}=|r|^2=egin{cases} (rac{lpha-eta}{lpha+eta})^2 & (p)\ (rac{1-lphaeta}{1+lphaeta})^2 & (s) \end{cases}$$

$$T=rac{I_t}{I_i}=|t|^2rac{n_2}{n_1}rac{\cos heta_t}{\cos heta_i}$$

where  $\frac{n_2}{n_1}$  is due to waves at ifferent speeds. And  $\frac{\cos\theta_t}{\cos\theta_i}$  is due to the wavesfronts at different angles.

$$T=|t|^2lphaeta=egin{cases} lphaeta(rac{2}{lpha+eta})^2 & (p)\ lphaeta(rac{2}{1+lphaeta})^2 & (s) \end{cases}$$

Lets check in certain cases

$$egin{align*} m{\bullet} \ \ \theta_i = 0 \Rightarrow \alpha = 1 \\ r_s = r_p = \frac{1-\beta}{1+\beta} = \frac{n_1-n_2}{n_1+n_2} \\ t_s = t_p = \frac{2}{1+\beta} = \frac{2n_1}{n_1+n_2} \\ R_s = R_p = (\frac{n_1-n_2}{n_1+n_2})^2 \\ T_s = T_p - \frac{n_2}{n_1} \frac{4n_1^2}{(n_1+n_2)^2} = \frac{4n_1n_2}{(n_1+n_2)^2} \end{aligned}$$

#### Example: air/glass interface

$$n_1 = 1$$
  $n_2 = 1.5$   $r_s = r_p = -0.2$   $T_s = T_p = 0.8$   $R_s = R_p = 0.04$   $T_s = T_p = 0.96$ 

 $\Rightarrow$  4% of light is reflected, 96% is transmitted

[If  $n_2$ , for example, = 1.75,  $R_s=R_p=0.074$ , which is sa problem]

Lets take another go at differnet angle

$$egin{aligned} ullet & heta_i=90^\circ ext{, and set } eta>1 \ & \sin heta_i=1 & \cos heta_i=0 \ & heta o \infty \ & r_p=1 & r_s=-1 \ & t_p=0 & t_s=0 \end{aligned}$$

• now consider  $\beta<1$ , we cna have total interal reflection for  $\theta_i>\theta_c$  where  $\theta_c$  is the critical angle =  $\beta=\frac{n_2}{n_1}$ 

At 
$$heta_c=\sin^{-1}eta$$
,  $lpha=rac{1}{\cos heta_c}\sqrt{1-(rac{\sin heta_c}{eta})^2}=0$ 

Hence, we have

$$egin{aligned} r_p &= -1 & r_s &= 1 \ t_p &= rac{2}{eta} & t_s &= 2 \ \sin heta_c &= eta \end{aligned}$$


 $r_p$  vanishes at the certain angle called **"Brewster's angle"**  $heta_B$ 

$$r_p=rac{lpha-eta}{lpha+eta}=0$$
 when  $lpha=eta=rac{n_2}{n_1}$   $rac{1}{cos heta_B}\sqrt{1-(rac{\sin heta_B}{eta})^2}=eta$ 

square both sides:

$$egin{aligned} \sec^2 heta_B - rac{1}{eta^2} an^2 heta_B = eta^2 \ (1 - rac{1}{eta^2}) an^2 heta_B = eta^2 - 1 \ rac{(eta^2 - 1)}{eta^2} an^2 heta_B = (eta^2 - 1) \ \Rightarrow an heta_B = eta \end{aligned}$$

#### Method of producing polarized light



Reflectted light polarized with  ${f E}$  perpendicular to the plane of incidence

Polarizing sunglasses with transmission axis vertical reduce glare because reflected light is mainly horizontally polarized.

#### **Total internal reflection**

$$n_1 \sin heta_i = n_2 \sin heta_t \ \sin heta_t = rac{\sin heta_i}{n_2/n_1}$$

Since  $n_2 < n_1$ , there will be total internal reflection when  $\sin heta_t > 1$ 

For transmitted wave, its like

$$\begin{array}{l} \bullet \quad e^{i(\mathbf{k}\cdot\mathbf{r}-\omega t)} \text{ in medium} \\ = e^{i(k_2[x\sin\theta_t+z\cos\theta_t]-\omega t)} \\ \text{ since } z\cos\theta t = 1-\sin^2\theta_t = \underbrace{e^{i(k_2x\sin\theta_t-\omega_t)}}_{wave} \underbrace{e^{-(\sin^2\theta_t-1)^{\frac{1}{2}}k_2z}}_{e^{-z/\delta}} \text{ where} \\ \delta = \frac{\lambda_2}{2\pi} \frac{1}{(\sin^2\theta_t-1)^{\frac{1}{2}}} \end{array}$$

This is called an evanescent wave

Lets now consider the Plane travelling wave

$$egin{aligned} E_x &= E_0 e^{i(kz-\omega t)} \ 
abla imes \mathbf{E} &= -\mathbf{\dot{B}} = i\omega B \ \mathbf{B} &= rac{1}{i\omega} igg| egin{aligned} \hat{\mathbf{i}} & \hat{\mathbf{j}} & \hat{\mathbf{k}} \ \partial x & \partial y & \partial z \ E_x & 0 & 0 \ \end{aligned} \ &= rac{1}{i\omega} igg( egin{aligned} \partial_z E_x \ -\partial_y E_x \ \end{pmatrix} \ &= rac{1}{i\omega} igg( ikE_x \ 0 \ \end{aligned} \ &= rac{1}{i\omega} igg( egin{aligned} \hat{\mathbf{j}} & \hat{\mathbf{j}} \ \\ &= rac{E_x}{\omega/k} \hat{\mathbf{y}} \ \end{aligned} \ &= rac{E_x}{c} \hat{\mathbf{y}} \end{aligned}$$

For s-polarization,  $\theta_i > \theta_c$ , we have

$$\sin \theta_t = \frac{\sin \theta_i}{n_2/n_1} > 1$$

$$\cos \theta_t = i\sqrt{\sin^2 \theta_t - 1}$$

$$r_s = \frac{n_1 \cos \theta_i - n_2 \cos \theta_t}{n_1 \cos \theta_i + n_2 \cos \theta_t}$$

$$= \frac{A - iB}{A + iB}$$

$$\Rightarrow R_s = |r_s|^2 = \frac{A^2 + B^2}{A^2 + B^2} = 1$$

$$t_s = \frac{2n_1 \cos \theta_i}{n_1 \cos \theta_i + n_2 \cos \theta_t} = \frac{2A}{A + iB}$$
So is complex
$$\Rightarrow \mathbf{E}_t = \mathbf{\hat{y}} t_s E_i e^{i(k_2[x \sin \theta_t - \omega t])} e^{-z/\delta}$$
where  $\delta = \frac{\lambda_2}{2\pi} \frac{1}{(\sin^2 \theta_t - 1)^{\frac{1}{2}}}$ 

$$\nabla \times \mathbf{E} = -\mathbf{\dot{B}} = i\omega \mathbf{B}$$

$$\mathbf{B} = \frac{1}{i\omega} \begin{vmatrix} \mathbf{\hat{i}} & \mathbf{\hat{j}} & \mathbf{\hat{k}} \\ \partial_x & \partial_y & \partial_z \\ 0 & E_t & 0 \end{vmatrix}$$

$$= \frac{1}{i\omega} \begin{pmatrix} -\partial_z E_t \\ 0 \\ \partial_x E_t \end{pmatrix}$$

$$= \begin{pmatrix} \frac{iE_t}{\omega\delta} \\ 0 \\ k_2 \sin \theta_t E_t/\omega \end{pmatrix}$$

 $\Rightarrow B_z$  is in phase with  $E_y$ 

 $\Rightarrow$  transport of energy along x

 $B_x$  is out of phase with  $E_y$ 

 $\Rightarrow$  no transport of energy along z

$$<\mathbf{S}>=<\mathbf{E}\times\mathbf{H}^*>$$

 $\mathbf{H}^*$  is the complex conjugate of H

#### **Reminder on conductors**

$$\nabla \times (\nabla \times \mathbf{E}) = \nabla(\nabla \cdot \mathbf{E}) - \nabla^{2}\mathbf{E} - \frac{\partial}{\partial t}\nabla \times \mathbf{B}$$

$$\mu_{0}\mu_{r}\sigma\mathbf{E} + \mu_{0}\mu_{r}\sigma_{0}\sigma_{r}\frac{\partial \mathbf{E}}{\partial t} = 0 \quad \text{if good conductor}$$

$$\nabla^{2}\mathbf{E} = \mu_{0}\sigma\frac{\partial \mathbf{E}}{\partial t}$$

$$-\tilde{k}^{2} = i\omega\mu_{0}\sigma$$

$$\Rightarrow \tilde{k} = k + i\kappa \quad k = \kappa = \sqrt{\frac{\mu_{0}\sigma\omega}{2}}$$

$$\nabla \times \mathbf{E} = -\dot{\mathbf{B}}$$

$$-\frac{\partial B_{y}}{\partial t} = (\nabla \times \mathbf{E})_{y} = \frac{\partial E_{x}}{\partial z}$$

$$i\omega B_{0} = i(k + i\kappa)E_{0}$$

$$Z = \frac{E_{0}}{H_{0}} = \frac{E_{0}}{B_{0}/\mu_{0}} = \frac{\mu_{0}\omega}{k + i\kappa}$$

$$= \sqrt{\frac{2\mu_{0}\omega}{\sigma}}\frac{1}{1 + i}$$

$$\Rightarrow Z = \sqrt{\frac{\mu_{0}\omega}{2\sigma}}(1 - i)$$

#### Reflection from a meatal surface

air	metal
$Z_1=\sqrt{rac{\mu_0}{\epsilon_0}}$	$Z_2 = \sqrt{rac{\mu_0 \omega}{2\sigma}} (1-i)$

 $|z_2| \ll |Z_1|$  for a good conductor because  $\sigma \gg \epsilon_0 \epsilon_r \omega$ 

write 
$$lpha=rac{\sqrt{rac{\mu_0\omega}{2\sigma}}}{\sqrt{rac{\mu_0}{\epsilon_0}}}=\sqrt{rac{\omega\epsilon_0}{2\sigma}}\ll 1$$

$$\begin{split} r &= \frac{E_r}{E_i} \quad \text{normal incidence} \\ &= \frac{Z_2 - Z_1}{Z_2 + Z_1} \\ &= \frac{Z_2/Z_1 - 1}{Z_2/Z - 1 + 1} \\ &= \frac{\alpha(1-i) - 1}{\alpha(1-i) + 1} \\ &\approx \frac{1 - 2\alpha + \cdots}{1 + 2\alpha + \cdots} \\ &= 1 - 4\alpha + O(\alpha^2) \\ &= 1 - \frac{2\omega\delta}{c} + O(\alpha^2) \\ &= 1 - \frac{4\pi\delta}{\lambda} + O(\alpha^2) \end{split}$$
 where  $\delta = \sqrt{\frac{2}{\omega\mu_0\sigma}}$  is the skin depth

- $\Rightarrow$  most of the EM wave intensity is reflected
- $\Rightarrow$  metals are shiny!

#### 4.7 Plasmas


Plasmas are neutral gas of charged particles, such as ions and free electrons (like metals)

#### Examples: where you can find plasma

- metal
- ionosphere
- stars
- fusion reactor
- interstellar gas /intergalactic medium
- supernova remnants
- radio galaxies / quasars
- lightening
- aurorae
- fire
- plasma displays

Its density varies from  $10^2-10^{35}kg/m^3$  , temperature is  $10^0-10^{13}k$ we would only focus on cold plasma

Lets consider a slab of plasma



having nnumber density n

the positive ions are fixed in place, and now lets move electrons by distance  $\xi$ 


$$ightarrow$$
 E field:  $E=rac{\sigma}{\epsilon_0}$  and  $\sigma=ne\xi$  
$$m\ddot{\xi}=-eE \quad {
m where} E=rac{ne\xi}{\epsilon_0}$$
  $\Rightarrow \ddot{\xi}+\omega_p^2\xi=0 \quad {
m which is SHM}$   ${
m where} \ \omega_p^2=rac{ne^2}{\epsilon_0 m}$ 

This is the SHM at the <u>plasma frequency</u>  $\omega_p$ 

Now, lets drive charges with EM wave  ${f E}e^{-i\omega t}$  (we could ignore B if  $v\ll c$ ) Hence, we could get  $\xi=\xi_0e^{-i\omega t}$ 

$$-m\omega^{2}\xi_{0} = -e\mathbf{E}$$
 $\mathbf{P} = -ne\xi_{0} = -\frac{ne^{2}}{m\omega^{2}}\mathbf{E}$ 
 $= (\epsilon_{r} - 1)\epsilon_{0}\mathbf{E}$ 
 $\Rightarrow \underbrace{\epsilon_{r}}_{\tilde{n}^{2}} = 1 - \frac{\omega_{p}^{2}}{\omega^{2}}$ 

where  $\tilde{n}^2$  is the refractive index, and that can be imaginary we could plot the relation between  $\omega$  and  $\epsilon_r$ 



at  $\omega>\omega_p,\,\tilde{n}$  is real, hence EM waves can propagate at  $\omega<\omega_p,\,\tilde{n}$  is imaginary, hence EM waves cant propagate

For example, metals are shiny, but only at optical frequencies. They will transport if it is going to much shorter wavelengths.

e.g. ionosphere

AM radios would be refracted + reflected (~ 1 MHz)

FM radio and TV radios would escape (~100MHz)


Lets look at the dispersion relation again

$$\frac{\omega}{k} = \frac{c}{n}$$

we could get

$$egin{aligned} ilde{n} &= 1 - rac{\omega_p^2}{\omega^2} = rac{c^2 k^2}{\omega^2} \ \Rightarrow \omega &= c^2 k^2 + \omega_p^2 \end{aligned}$$

The dispersion relationship would be like



Hence, we could conclude that

- waves are dispersive in plasma
- there are no propagating waves for  $\omega < \omega_p$
- ullet waves with  $\omegapprox\omega_p$  are slow  $v_g=rac{d\omega}{dk} o 0$  as  $\omega o\omega_p$

We have  $2\omega d\omega = 2c^2kdk$ 

$$\Rightarrow rac{d\omega}{dk} = rac{c^2k}{\omega} = c\sqrt{1-rac{\omega_p^2}{\omega^2}}$$

We could have end behaviors:

$$egin{array}{lll} v_g 
ightarrow 0 & {
m as} & \omega 
ightarrow \omega_p \ v_g 
ightarrow c & {
m as} & \omega 
ightarrow \infty \end{array}$$

Let's then take

$$\mathbf{E} = \mathbf{E}_0 e^{i(\mathbf{k} \cdot \mathbf{r} - \omega t)}$$

Choose  ${f k}$  to be (0,0,k), we have

$$\mathbf{P}=rac{-ne^2}{m\epsilon_0\omega^2}(\epsilon_0\mathbf{E})=-ig(rac{\omega_p}{\omega}ig)^2\epsilon_0\mathbf{E}$$

We could hence get Maxwell's equation

$$\nabla \times \mathbf{H} = \frac{\partial \dot{\mathbf{D}}}{\partial t} \quad \nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t} = -\mu_0 \frac{\partial \mathbf{H}}{\partial t}$$

$$\nabla \times (\nabla \times \mathbf{E}) = -\mu_0 \frac{\partial}{\partial t} \nabla \times \mathbf{H}$$

$$= 0\mu_0 \frac{\partial^2}{\partial t^2} \mathbf{D}$$

$$\mathbf{LHS} = \nabla(\nabla \cdot \mathbf{E}) - \nabla^2 \mathbf{E} = -\mu_0 \frac{\partial^2}{\partial t^2} (\epsilon_0 \mathbf{E} + \mathbf{P})$$


For the wave, we have

$$egin{aligned} 
abla & 
ightarrow i \mathbf{k} \ rac{\partial}{\partial t} & 
ightarrow -\omega^2 \mathbf{E} \ \Rightarrow k^2 \mathbf{E} - \underbrace{\mathbf{k} ig( \mathbf{k} \cdot \mathbf{E} ig)}_{k^2 E_z \mathbf{\hat{z}}} &= rac{\omega^2 - \omega_p^2}{c^2} \mathbf{E} \end{aligned}$$

Transverse solutions: 
$$\begin{pmatrix} 1 \\ 0 \\ 0 \end{pmatrix} \begin{pmatrix} 0 \\ 1 \\ 0 \end{pmatrix}$$
 we have  $\omega^2 = \omega_p^2 + c^2 k^2$ 

As for longitudinal solutions, we have  $\begin{pmatrix} 0 \\ 0 \\ 1 \end{pmatrix}$  , we have, hence,  $\omega^2 = \omega_p^2$ 

We can therefore classify waves in the  $\omega$  k graph




## 4.8 Dispersion

Refractive index changes with frequency

• classical theory of dispersion:


model electrons as a classical damped oscillator  $m\ddot{x}+m\gamma\dot{x}+m\omega_0^2x=qE_0e^{-i\omega t}$ 

Assume that 
$$x=x_0e^{-i\omega t}$$
 
$$(-\omega^2-i\omega\gamma+\omega_0^2)x_0=\frac{qE_0}{m}$$
 
$$P=nqx_0=\frac{nq^2}{m}E_0\frac{1}{\omega_0^2-\omega^2-i\omega\gamma}$$
 
$$=\epsilon_0(\tilde{\epsilon}_r-1)E_0$$
 
$$\tilde{\epsilon}_r=1+\frac{nq^2E_0}{\epsilon_0m}\frac{1}{\omega_0^2-\omega-i\omega\gamma}$$
 
$$\tilde{n}^2=\tilde{\epsilon}_r$$
 For a gas,  $\tilde{\epsilon}=1+$  small quantity 
$$\tilde{\epsilon}^{\frac{1}{2}}=1+\frac{1}{2} \text{small quantities}+\cdots$$
 
$$Re(\tilde{n})=1+\frac{nq^2}{2\epsilon_0m}\frac{\omega_0^2-\omega^2}{(\omega_0^2-\omega^2)^2+\omega^2\gamma^2}$$
 
$$Im(\tilde{n})=\frac{nq^2}{2\epsilon_0m}\frac{\gamma\omega}{(\omega_0^2-\omega^2)^2+\omega^2\gamma^2}$$



As  $\omega o 0$  ,  $Re( ilde{n}) o 1 + rac{nq^2}{2q_0\omega_0^2}$  ,  $Im( ilde{n}) o 0$ 

As  $\omega \to \infty$ ,  $Re(\tilde{n}) \to 1$ , we could get a better illustration, therefore, for the real part and imaginary part of  $\tilde{n}$ 



We can also conclude that  $Im(\tilde{n})$  corresponds to the absorption of light, and  $Re(\tilde{n})$  corresponds to the refraction of light and generally increases with frequency

The sharp drop in the real part of  $\tilde{n}$  in the real part of  $\tilde{n}$  near  $\omega_0$  is called <u>anomalous dispersion</u>