Potential

O1 拉普拉斯方程和他在笛卡尔坐标系下的解

拉普拉斯方程其人

开局先写一个假设什么东西都不动的麦克斯韦方程组

$$\nabla E = \frac{
ho}{\epsilon_0}$$

$$\nabla B = 0$$

$$\nabla \times E = 0$$

$$\nabla \times B = \mu_0 J$$

我们知道 $E=-\nabla V$,把这个带入第一个式子就可以得到著名的泊松equation

$$abla^2 V = -rac{
ho}{\epsilon_0}$$


而如果在一个范围内没有任何电荷出现的话 那就可以得到另一个叫做Laplace's equation 的东西

$$\nabla^2 V = 0$$

还挺优雅的 不是嘛

来解方程吧! 用一个具体的例子!

这篇文章主要就是要在笛卡尔坐标系下解这个方程,在大二第一学期我们主要使用 separation of variable来解,也就是说我们要假设这个V他是等于X(x)Y(y)Z(z)的。我们可以举一个具体的例子来熟悉这种方法



在x = \pm b时, $V=V_0$;然后y=0和a的那两个面是接地的。这也就是说Z(z)这一项没有什么用 不妨把他设成1.所以我们现在有

$$V = X(x)Y(y)$$

把他带入拉普拉斯方程中

$$0 = \frac{\partial^2 V}{\partial x^2} + \frac{\partial^2 V}{\partial y^2}$$

就可以得到

$$Y rac{\partial^2 X}{\partial x^2} + X rac{\partial^2 Y}{\partial y^2} = 0$$

两边同时除V

$$\frac{1}{X}\frac{\partial^2 X}{\partial x^2} + \frac{1}{Y}\frac{\partial^2 Y}{\partial y^2} = 0$$

因为第一项只和x有关,第二项只和另一个有关,所以只有这俩都是常数的情况,而且偏 微分可以写成全微分

先尝试**首项是负数**的情况

$$\frac{1}{X} \frac{d^2 X}{dx^2} = -\frac{1}{Y} \frac{d^2 Y}{dy^2} = -k^2$$

这个方程的解为 $X(x)=A_1\cos(kx)+A_2\sin(kx)$ 和 $Y(y)=B_1e^{ky}+B_2e^{-ky}$ 。我们有边界条件Y(0)=Y(a)=0,也就是说 $B_1+B_2=B_1e^{ka}+B_2e^{-ka}=0$,也就是说 $B_1(e^{ka}-e^{-ka})=0$,所以说 $2B_1\sinh(ka)=0$,也就是说 $B_1=B_2=0$ 这就是说所有地方的V都是0,这显然不是个解,也就是说我们要尝试一下**首项是正数的情况**

$$\frac{1}{X} \frac{d^2 X}{dx^2} = -\frac{1}{Y} \frac{d^2 Y}{dy^2} = k^2$$

解是 $Y(y)=A_1\cos(ky)+A_2\sin(ky)$ 和 $X(x)=B_1e^{kx}+B_2e^{-kx}$ (没错我就换了一下xy,甚至连顺序都懒得换)我们有

$$Y(0) = 0$$

也就是说 $A_1=0$,所以 $Y(a)=A_2\sin(ka)=0$, A_2 肯定不能等于0了,所以只能让 $\sin(ka)=0$,所以说 $ka=n\pi$,而 A_2 是随机常数。所以最终我们的解为

$$V(x,y) = \sum_{n=0}^{n} C_n \cosh\left(\frac{n\pi x}{a}\right) \sin\left(\frac{n\pi y}{a}\right)$$

好家伙 那 C_n 怎么搞?答案是用X(x)的边界条件

$$V(b,y) = \sum\limits_{i=0}^{n} C_n \cosh \left(rac{n \pi x}{a}
ight) \sin \left(rac{n \pi y}{a}
ight) = V_0$$

我们把左右两边各乘一个 $\sin\left(\frac{m\pi y}{a}\right)$,再对 γ 从0到 α 积分,可以得到

$$V(b,y) = \sum\limits_{i=0}^{n} C_n \coshig(rac{n\pi x}{a}ig) \int\limits_{0}^{a} \sinig(rac{n\pi y}{a}ig) \sinig(rac{m\pi y}{a}ig) dy = V_0 \int\limits_{0}^{a} sin(rac{m\pi y}{a}) dy$$

其中

$$\sin \frac{n\pi y}{a} \sin \frac{m\pi y}{a} = \frac{1}{2} \left[\cos \frac{(n-m)\pi y}{a} - \cos \frac{(n+m)\pi y}{a} \right]$$

所以我们知道只有在n=m时才不是0,其他的时候这个积分等于 $\frac{a}{2}$ 。所以说我们可以得到再m是偶数时, $C_m=0$,其余时间 $C_m=\frac{4V_0}{m\pi\cosh(\frac{m\pi b}{a})}$

最终 我们的解就是一个特别恐怖的式子

$$V(x,y) = rac{4V_0}{\pi} \sum_{i=0}^n rac{\coshrac{(2i+1)\pi x}{a}}{\coshrac{(2i+1)\pi b}{a}} a \sin\!\left(rac{i\pi y}{a}
ight)$$

结束!

O2 拉普拉斯方程在球坐标下的解

我们上次介绍了非常% 的拉普拉斯方程 $\nabla^2 V=0$ 并且算了算他在笛卡尔坐标系下的一个例子,这次来试一试球坐标

球坐标下的拉普拉斯方程

通过一些矢量微积分,我们可以知道

$$abla^2 V = rac{1}{r^2} rac{\partial}{\partial r} \left(r^2 rac{\partial V}{\partial r}
ight) + rac{1}{r^2 \sin heta} rac{\partial}{\partial heta} \left(\sin heta rac{\partial V}{\partial heta}
ight) + rac{1}{r^2 \sin^2 heta} rac{\partial^2 V}{\partial \phi^2} = 0$$

嗯。。。以我现在的知识还是看不出来这有什么优雅的

解方程!

一杯茶,一包烟,一道积分算一天! (虽然我不抽烟)

还是分离变量,假设 $abla^2=R(r)\Theta(heta)\Phi(\phi)$

两边同时乘 $\frac{r^2}{R\Theta\Phi}$,可以得到

$$\frac{1}{R} \frac{\partial}{\partial r} \left(r^2 \frac{\partial R}{\partial r} \right) + \frac{1}{\Theta \sin \theta} \frac{\partial}{\partial \theta} \left(\sin \theta \frac{\partial \Theta}{\partial \theta} \right) + \frac{1}{\Phi \sin^2 \theta} \frac{\partial^2 \Phi}{\partial \phi^2} = 0$$

左右两边再同时乘一个 $\sin^2\theta$ 的话,上面这个式子他的左边两项就会只和R和 θ 有关,而最后一项就会只和 ϕ 有关。所以我们可以说最后一个项乘个 $\sin^2\theta$ 是一个常数:

$$\frac{1}{\Phi} \frac{d^2 \Phi}{d^2 \phi} = K$$

如果说K>0的话,这个方程的解就是 $e^{\pm\sqrt{K}\phi}$ 的线性叠加了,我们在这里其实还是想要一个周期性的解,毕竟 ϕ 代表的是角度嘛,不能说 $\phi=\phi_0+2n\pi$ 里面对于任何一个n ϕ 的解都不一样。所以我们不如去把K设成一个负数,把它叫做 $-m^2$ 。这样子的话我们就可以得到

$$\Phi(\phi) = Ce^{im\phi}$$

其中的 ϕ 可以是正数也可以是负数 但必须要是整数。求个导的话就是

$$\frac{d^2\Phi}{d\phi^2} = -m^2\Phi$$

整个的式子就变成了这样子

$$\frac{1}{R} \frac{\partial}{\partial r} \left(r^2 \frac{\partial R}{\partial r} \right) + \frac{1}{\Theta \sin \theta} \frac{\partial}{\partial \theta} \left(\sin \theta \frac{\partial \Theta}{\partial \theta} \right) - \frac{m^2}{\sin^2 \theta} = 0$$

再找找有没有什么只和一个变量相关的东西?

(没错!)

(是第一项!)

(嘿嘿!)

那我们就可以把第一项设成常数了!

$$egin{aligned} rac{1}{R}rac{\partial}{\partial r}ig(r^2rac{\partial R}{\partial r}ig) &= l(l+1) \ rac{1}{\Theta\sin heta}rac{\partial}{\partial heta}ig(\sin hetarac{\partial\Theta}{\partial heta}ig) - rac{m^2}{\sin^2 heta} &= l(l+1) \end{aligned}$$

至于为什么把常数设计得这么怪,你之后就知道啦

我们可以把 $\cos \theta$ 设为x,那么下面的式子就变成了

$$rac{d}{dx} \left[(1-x^2) rac{d\Theta(x)}{dx}
ight] + \left[l(l+1) - rac{m^2}{1-x^2}
ight] \Theta(heta) = 0$$

苍天啊 大地啊 我都干什么啊! 这玩意怎么越写越长啊

别怕,这个方程在之后的数学物理方法中就可以学到 其实叫做Legendre equation。他的解叫做associated Legendre polynomials,可以写成这种形式

$$\Theta(x) = P_l^m(x)$$

其中的l是正整数,不然的话这个方程就又不是周期性的了,而且m也只能是从-l到+l

现在知道为啥把常数设成l(l+1)了吧

 Θ 和 Φ 的积还有一个名字,叫做球谐(spherical harmonic),用 Y_l^m 表示

$$Y_l^m = CP_l^m(\cos\theta)e^{im\phi}$$

然后就是这个式子了

$$\frac{1}{R} \frac{\partial}{\partial r} \left(r^2 \frac{\partial R}{\partial r} \right) = l(l+1)$$

求一下馬

$$l(l+1)=2rac{r}{R}rac{dR}{dr}+rac{r^2}{R}rac{d^2R}{dr^2}$$

试一下 $R = Cr^x$, 也就是说

$$l(l+1) = rac{2}{Cr^{x-1}} Cxr^{x-1} + rac{1}{Cr^{x-2}} Cx(x-1)r^{x-2}$$

$$l(l+1) = 2x + x(x-1)$$

$$l(l+1) = x(x+1)$$

所以说x等于l或者-l-1

所以说R就出来了

$$R(r) = lpha r^l + rac{eta}{r^{l+1}}$$

把三个东西乘起来 就可以得到

$$V(r, heta,\phi) = \sum\limits_{l=0}^{\infty}\sum\limits_{m=-l}^{l} \Big(lpha r^l + rac{eta}{r^{l+1}}\Big) Y_l^m(heta,\phi)$$

Legendre多项式的一个特点

P有一个很有用的特点,就是他们是正交的,也就是说我们有

$$\int_{-1}^1 P_n(x) P_m(x) dx = rac{2}{2n+1} \delta_{m,n}$$

这个东西可以让我们更简单地计算 α 和 β

一个对称的情况

例子 我喜欢例子 现在就让我算例子!!


通常情况下,我们做的题都和 ϕ 没有关系,所以说我们可以把球谐给写成单独一个关于 $\cos \theta$ 的Legendre多项式,也就是说整个的V可以写成

$$V(r, heta) = \sum_{l=0}^{\infty} \Big(lpha r^l + rac{eta}{r^{l+1}} \Big) P_l(\cos heta)$$

我们可以举一个例子:在一个三维空间里面,存在着一个空心导体球在原点,他的半径是 a。同时还存在一个沿着z轴向上的匀强电场E,求电势

首先啊,这是一个球,所以我们肯定会用球坐标来解这个方程

其次 我们看一下示意图



这个电势貌似和 ϕ 没有什么关系!那我们就可以用那个简化版的拉普拉斯方程的解

$$V(r, heta) = \sum\limits_{l=0}^{\infty} \Big(lpha r^l + rac{eta}{r^{l+1}} \Big) P_l(\cos heta)$$

我们首先可以看一看他的end behavior,也就是当r趋近于无穷大时,V应当等于 $-E\cos\theta$ 。我们看一下Legendre多项式的前几个方程:

$$P_0(x)=1$$
, $P_1(x)=x$, $P_2(x)=rac{1}{2}(3x^2-1)$, $P_3(x)=rac{1}{2}(5x^3-3x)\cdots$

从中我们可以大概看出来,满足上面的end behavior的情况应该是只有=1时 α 和 β 才不等于0

所以说就可以得到

$$V(r, heta) = \left(-Er + rac{eta_1}{r^2}
ight)\cos heta$$

还是一样的end behavior

就快要算出来了!

对于 eta_1 ,我们还有另外一个边界条件没有用,也就是 $r=\alpha$ 的情况:

$$V(a, heta)=(-Ea+rac{eta_1}{a^2})\cos heta=0$$

所以说 $\beta_1 = a^3 E$

综上所述,我们能算出来

$$V(r, heta) = -Er\cos heta + rac{a^3E\cos heta}{r^2}$$

可以看出来 其中第一项对应的是电场对应的电势,而后面哪一项就是磁场对应的电势了

完事收工!

Formal solution to Poisson's equation

Poisson's equation:

$$abla^2 V = -rac{
ho}{\epsilon_0}$$

Has solution

$$V(\overrightarrow{r})=rac{1}{4\pi\epsilon_0}\intrac{
ho(\overrightarrow{r'})}{|\overrightarrow{r'}-\overrightarrow{r}|}d au'$$

where au' is the volume

This also happens in Magnetism, $\overrightarrow{B} = \overrightarrow{\nabla} \times \overrightarrow{A}$, and A is called *magnetic vector potential*

This is valid because the divergence of B is 0

$$\overrightarrow{\nabla} \times (\overrightarrow{\nabla} \times A) = \mu_0 \overrightarrow{J}$$

$$\overrightarrow{
abla}(\overrightarrow{
abla}\cdot A) - \overrightarrow{
abla}^2\overrightarrow{A}$$

it has gauge freedom that we can choose taht it is divergence free

choose
$$\overrightarrow{
abla}\cdot A=0$$

$$\Rightarrow \nabla^2 \overrightarrow{A} = -\mu_0 \overrightarrow{J}$$

it looks like three independent Poisson equations

$$\Rightarrow \overrightarrow{A(r)} = rac{\mu_0}{4\pi} \int rac{\overrightarrow{J(r')}}{|\overrightarrow{r'}-\overrightarrow{r}|} d au'$$

Example: If we have a one dimentional current i.e. wire, this current will produce

$$\overrightarrow{A}(\overrightarrow{r}) = rac{\mu_0 I}{4\pi} \int rac{\overrightarrow{dl'}}{|\overrightarrow{r'}-\overrightarrow{r}|}$$

$$\overrightarrow{B}(\overrightarrow{r}) = \overrightarrow{
abla} imes \overrightarrow{A} = rac{\mu_0}{4\pi} \int rac{\overrightarrow{dl'} imes (\overrightarrow{r'} - \overrightarrow{r})}{|\overrightarrow{r'} - \overrightarrow{r}|^3}$$

Which is Biot-Savart law!

Multipole expansion

Laplace with azimuthal symmetry:


$$V(r, heta) = \sum_{l=0}^{\infty} [A_l r^l + rac{B_l}{r^{l+1}}] P_l(cos heta)$$

where P_l is Legendre polynomial

Apply to a point charge at $\overset{
ightarrow}{r'}$

$$V(\overrightarrow{r})=rac{1}{4\pi\epsilon_0}rac{q}{\stackrel{
ightarrow}{|\overrightarrow{r}-\overrightarrow{r'}|}}$$

(unit charge)



This has azimuthal symmetry, so we can use the above equation

If γ is zero, then $cos\theta=1$, then $P_l(cos\theta)=1$, then

$$V(r, heta)=rac{1}{4\pi\epsilon_0}rac{q}{|\overrightarrow{r'}-\overrightarrow{r'}|}=\sum_{l=0}^{\infty}A_lr^l+rac{B_l}{r^{l+1}}$$

Because $P_l(1)=1$

The expansion would be


$$rac{1}{|\overrightarrow{r'}-\overrightarrow{r|}|} = egin{cases} rac{1}{r}\sum_{l=0}^{\infty}(rac{r'}{r})^l & r > r' \ rac{1}{r'}\sum_{l=0}^{\infty}(rac{r}{r'})^l & r < r' \end{cases}$$

Choose the case r' < r

The general solutiuon would be

$$V=rac{1}{4\pi\epsilon_0}rac{q}{r}\sum_{l=0}^{\infty}(rac{r'}{r})^lP_l(cos heta)$$

Thus the general solution for \overrightarrow{r} outside a charge distribution is



$$V(\overrightarrow{r}) = rac{1}{4\pi\epsilon_0} \int_{l=0}^{\infty} (r')^l P_l(\cos(\gamma)) imes
ho(\overrightarrow{r'}) d au'$$

The leading term is the monopole term (I=0)

$$V(\overrightarrow{r})=rac{1}{4\pi\epsilon_0}\int
ho(r')d au'=rac{1}{4\pi\epsilon_0}rac{Q}{r}$$

Which is proportional to $\frac{1}{r}$

Next is the dipole term (I=1)

$$egin{aligned} V_1(\overrightarrow{r}) &= rac{1}{4\pi\epsilon_0} \int (r')\cos(\gamma)
ho(r')d au' \ &= rac{\overrightarrow{p\cdot r}}{4\pi\epsilon_0 r^3} \end{aligned}$$

Which is proportional to $\frac{1}{r^2}$

Where \overrightarrow{p} is the dipole moment $=\int\overrightarrow{r'}\rho(r')d au'$

and
$$rac{\overrightarrow{r\cdot r'}}{rr'}=\cos(\gamma)$$

Then the quadrupole term (I=2)

$$V_2(\overrightarrow{r}) = rac{1}{4\pi\epsilon_0}\int (r')^2rac{3\cos^2(\gamma)-1}{2}
ho(r')d au'$$

Now we can have a nice way of looking at field outside the charges using multipole expansion.

2. Electric polarization

Matter is not free space, it contains atoms

2.1 Bound charges

Electric field can induce a dipole moment in a neutral atom

Example 4.1. A primitive model for an atom consists of a point nucleus (+q) surrounded by a uniformly charged spherical cloud (-q) of radius a (Fig. 4.1). Calculate the atomic **polariz**ability of such an atom.



And the electric moment is defined as $\mathbf{p}=\alpha\mathbf{E}$ where α is the **polarizability** of the atom. A list of polarizability can be seen from the handout.

If, for example, the outside E ~ 10^6 V/m, then the displacement would be about 10^{-15} m, which is much less the size of an atom.

Also, there are polar molecules which already have a dipole moment, but they are randomized because of the present of inner energy K_BT





FIGURE 4.4

However, an E field can line them up

For a bok of aligned dipoles (per unit volume), define the polarization ${f P}$ as the dipole moment per unit volume as ${f P}=n{f p}$

If they are not aligned, then the polarization is zero.

Question: what is the electric potential produced by a box of dipoles?



$$V(\mathbf{R}) = \frac{1}{4\pi\epsilon_0} \int \frac{\mathbf{P}(\mathbf{r}) \cdot \mathbf{R}}{|R|^3} d^3 \tau'$$

$$= \frac{1}{4\pi\epsilon_0} \int \mathbf{P}(\mathbf{r}) \cdot \nabla \frac{1}{R} d\tau'$$

$$\nabla \frac{1}{R} = -\frac{\mathbf{R}}{R^3}$$

$$\nabla \frac{1}{|r - r'|} = -\frac{r - r'}{|r - r'|^3}$$

$$\nabla' \frac{1}{|r - r'|} = \frac{r - r \cdot r'}{|r - r'|^3}$$

Note that $abla \cdot (f\mathbf{F}) = f
abla \cdot \mathbf{F} + \mathbf{F} \cdot
abla f$

$$\Rightarrow V(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int \nabla' \frac{\mathbf{P}(\mathbf{r}')}{|\mathbf{R}|} d\tau' - \frac{1}{4\pi\epsilon_0} \int \frac{1}{R} \nabla \cdot \mathbf{P}(\mathbf{r}') d\tau'$$
$$= \frac{1}{4\pi\epsilon_0} \int_{s'} \frac{\sigma_b dS'}{R} + \frac{1}{4\pi\epsilon_0} \int_{\tau'} \frac{\rho_b d\tau'}{R}$$

where $\sigma_b = \mathbf{P} \cdot \mathbf{n}$ is the surface bounded charge density and $\rho_b = -\nabla \cdot \mathbf{P}$ is the volume bound charge density (the minus sign is because \mathbf{P} is defined as the dipole moment per unit volume).

The derivation can be seen from Griffiths' book page 176.

Remember to drop primes!

In bulk, Gauss's Law is
$$\nabla \cdot \mathbf{E} = \frac{\rho}{\epsilon_0}$$
, but $\rho = \rho_{free} + \rho_{bound}$ remember that $\rho_{bound} = -\nabla \cdot \mathbf{P}$ and hence $\nabla \cdot \mathbf{E} = \frac{\rho_{free}}{\epsilon_0} - \frac{\nabla \cdot \mathbf{P}}{\epsilon_0}$

We define electric displacement

$$\mathbf{D} = \epsilon_0 \mathbf{E} + \mathbf{P}$$
 $\Rightarrow
abla \cdot \mathbf{D} =
ho_{\mathit{free}}$

That is much easier, since it only depends on free charges.

The integral form is

$$\oint \mathbf{D} \cdot d\mathbf{a} = Q_{free}$$

Linear dielectrics

For a linear dielectric, $\mathbf{P} = \epsilon_0 \chi_e \mathbf{E}$ where χ_e is the electric susceptibility, which is dimensionless.

$$\Rightarrow$$
 D = ϵ_0 **E** + $P = \epsilon_0 (1 + \chi_e)$ **E**

 $(1+\chi_e)$ is the relative permitivity ϵ_r and it is dimensionless.

Example:

Field from a point charge in a linear dielectric:

$$egin{aligned} \int_s \mathbf{D} \cdot d\mathbf{s} &= Q_{free} \ \Rightarrow \mathbf{D} &= rac{Q_f}{4\pi r^2} \mathbf{\hat{r}} \ \Rightarrow \mathbf{E} &= rac{Q_f}{4\pi \epsilon_0 r^2} \mathbf{\hat{r}} \end{aligned}$$

Recap of lecture 5:

Polarization:
$$\overrightarrow{P} = n\overrightarrow{p}$$

Bound charges:
$$ho_b = -
abla \cdot \stackrel{
ightarrow}{P}, \, \sigma_b = \stackrel{
ightarrow}{P} \cdot \hat{n}$$

Electric displacement:
$$\overrightarrow{D}=\epsilon_0\overrightarrow{E}+\overrightarrow{P}=\epsilon_0\epsilon_r\overrightarrow{E}$$

Maxwell:
$$\nabla \cdot \overrightarrow{D} =
ho_f$$

Linear dielectric:
$$\overrightarrow{P} = \epsilon_0 \chi_e \overrightarrow{E}$$

Where
$$\chi_e$$
 is the electric susceptibility = ϵ_r-1

Question Has D solved everything?

-- No. The div equation is easier, but...

Reminder:
$$\overrightarrow{\nabla} \cdot \overrightarrow{E} = \frac{\rho_{tot}}{\epsilon_0}$$

And the equation for
$$\vec{D}$$
 is $\epsilon_0\vec{E}+\vec{P}=\epsilon_0\epsilon_r\vec{E}$

$$\overrightarrow{\nabla} \times \overrightarrow{E} = 0$$

$$\overrightarrow{
abla} imes \overrightarrow{D} = \epsilon \overrightarrow{
abla} imes \overrightarrow{E} + \overrightarrow{
abla} imes \overrightarrow{P}
eq 0$$

Boundrary conditions

 $E_{\it I/\it I}$ is continuous

$$\overrightarrow{
abla} imes\overrightarrow{E}=0$$

$$\oint \overrightarrow{E} \cdot \overrightarrow{dl} = 0$$

But $D_{//}$ is not continuous (if $abla imes \overrightarrow{P}
eq 0$ at interface) D_{\perp} is continuous

$$abla \cdot \overrightarrow{D} =
ho_f$$

$$\oint \overrightarrow{D} \cdot d\overrightarrow{a} = Q_f$$

but E_{\perp} may not be continuous if we have bound charges at the interface Example



$$\Rightarrow E_0//x$$

$$E_1=E_3=E_0$$

 D_{\perp} is continuous

$$\Rightarrow D_1 = D_3 = \epsilon_0 E_0 = D_2$$

$$D_2 = \epsilon_0 \epsilon_r E_2$$

$$\Rightarrow E_2 = \frac{E_0}{\epsilon_x}$$

So there is a smaller E field in the dielectric

$$P_2 = \epsilon_0(\epsilon_r - 1)E_2$$

= $\frac{\epsilon_0}{\epsilon_r}(\epsilon_r - 1)E_0$

$$(P_1 = P_3 = 0)$$

Since P_2 is constant, $abla imes \overrightarrow{P} = 0 \Rightarrow
ho_b = 0$

$$z = o, \sigma_b = \mathbf{P} \cdot \mathbf{n} = \frac{\epsilon_0}{\epsilon_r} (\epsilon_r - 1) E_0 \ z = d, \sigma_b = \mathbf{P} \cdot \mathbf{n} = \frac{\epsilon_0}{\epsilon_r} (\epsilon_r - 1) E_0$$

$$z=d, \sigma_b=\mathbf{P}\cdot\mathbf{n}=rac{arepsilon_0}{\epsilon_r}(\epsilon_r-1)E_0$$

Example:

There is dielectric sphere, with radius a and relative permittiaty \epsilon_r. The sphere is in a uniform electric field \mathbf{E}_0 . Find V.

We got to use Laplace's equation

General solution to Laplace's equation in spherical coordinates (with azimuthal symmetry) is

$$V(r, heta) = \sum_{l=0}^{\infty} \Big(A_l r^l + rac{B_l}{r}^{l+1}\Big) P_l(\cos heta)$$

where P_l is the Legendre polynomial.

Solve separatively for r > a and r < a

As
$$r \to \infty$$
, $V \to -E_0 r \cos \theta$

As r
ightarrow 0, V should be finite (not blow up)

$$\Rightarrow B_l = 0$$
 for r

case r<a:

$$V = V_{in} \sum_{l=0}^{\infty} A_l r^l P_l(\cos \theta)$$

And for r>a:

$$V=V_{out}=-E_0r\cos heta+\sum_{l=0}^{\infty}rac{B_l}{r^{l+1}}P_l(\cos heta)$$

As for r = a, $E_{//}, D_{\perp}, V$ are continuous

$$\sum_{l=0}^{\infty}A_{l}r^{l}P_{l}(\cos heta)=-E_{0}a\cos heta+\sum_{l=0}^{\infty}rac{B_{l}}{a^{l+1}}P_{l}(\cos heta)$$

$$\Rightarrow A_l = egin{cases} rac{B_l}{a^{l+1}} & l
eq 1 \ -E_0 + rac{B_1}{a^2} & l = 1 \end{cases}$$

$$E_0 = -rac{1}{r}rac{\partial V}{\partial heta}$$
 is continuous

 \rightarrow generates same expressions

That is not terribly useful, so we will try another one

$$\begin{split} D_{\perp} &= -\epsilon_0 \epsilon_r \frac{\partial V}{\partial r} \text{ is continuous} \\ &\Rightarrow -\epsilon_0 \epsilon_r \frac{\partial V}{\partial r}|_{r=a} = -\epsilon_0 \frac{\partial V_{out}}{\partial r}|_{r=a} \\ &\epsilon_r \sum_{l=0}^{\infty} l A_l a^{l-1} P_l(\cos \theta) = -E_0 \cos \theta + \sum_{l=0}^{\infty} -(l+1) \frac{B_l}{a^{l+2}} P_l(\cos \theta) \\ A_l &= \begin{cases} -\frac{1}{\epsilon_r} \frac{l+1}{l} \frac{B_l}{a^{2l+1}} & l \neq 1 \\ \frac{1}{\epsilon_r} (-E_0 - \frac{2B_l}{a^3}) & l = 1 \end{cases} \end{split}$$

Hence, we got two expressions for A in terms of I. They cant both be right unless $A_l=B_l=0$ for $l\neq 1$

On the other hand, we have

$$A_1 = \underbrace{-E_0 + \frac{B_1}{a^3}}_{\tiny{\scriptsize \textcircled{\tiny 1}}} = \underbrace{\frac{1}{\epsilon_r} \left(-E_0 - \frac{2B_0}{a^3} \right)}_{\tiny{\tiny \textcircled{\tiny 2}}}$$

$$\epsilon_r(\widehat{1}) - \widehat{2}) = 0$$

Hence

$$(1 - \epsilon_r)E_0 + (\epsilon_r + 2)\frac{B_1}{a^3} = 0$$

$$\Rightarrow B_1 = a^3 E_0 \left(\frac{\epsilon_r - 1}{\epsilon_r + 2}\right)$$

$$\rightarrow A_1 = -\frac{3E_0}{\epsilon_r + 2}$$

Now, put everything together

$$V = egin{cases} rac{rac{3}{\epsilon_r + 2} E_0 r \cos heta}{ ext{uniform field}} & r < a \ rac{3}{\epsilon_r + 2} E_0 r \cos heta & r < a \ rac{E_0 r \cos heta}{ ext{Uniform field}} + rac{\left(rac{E_r - 1}{E_r + 2} rac{E_0 a^3 \cos heta}{r^2}
ight)}{ ext{dipole field}} & r > a \end{cases}$$

Interestingly, we all have uniform fields applied inside and outside. And if in vacuum, we will have uniform field outside (dipole field vanishes)

P inside sphere:

$$P=\epsilon_0(\epsilon_r-1)E_{in}$$
 where $E_i n$ is $rac{3E_0}{\epsilon_r+2}$

Dipole moment of sphere

$$p=rac{4}{3}\pi a^3 P=rac{4\pi a^3\epsilon_0(\epsilon_r-1)E_0}{\epsilon_r+2}$$

Polarizability

$$lpha = rac{P}{E_0} \ = 4\pi a^3 \epsilon_0 rac{\epsilon_r - 1}{\epsilon_r + 2}$$

Bound charge on the surface

$$egin{aligned} \sigma_b &= \mathbf{P} \cdot \hat{\mathbf{n}} \ &= P \cos heta \ &= rac{3\epsilon_0(\epsilon_r - 1)}{\epsilon_r + 2} E_0 \cos heta \end{aligned}$$

3 Magnetization

3.1 Current Loop

From the handout, we have the following vector identity:


$$\oint \mathbf{\hat{r}} \cdot \mathbf{r}' d\mathbf{l}' = \left(\int d\mathbf{S}' \right) imes \mathbf{\hat{r}}$$

Start from Poisson's equation:

$$abla^2 A = rac{-\mu_0}{4\pi} \int \Big(rac{\mathbf{J}(\mathbf{r}')}{|\mathbf{r}-\mathbf{r}'|}\Big) d au'$$

Current loop:

$$A(r)=rac{\mu_0 I}{4\pi}\ointrac{1}{|{f r}-{f r}'|}d{f l}'$$



recall the expansion

$$\frac{1}{|\mathbf{r} - \mathbf{r}'|} = \frac{1}{r} \sum_{l=0}^{\infty} \left(\frac{r'}{r}\right)^{l} P_{l}(\cos \theta)$$

$$\Rightarrow A(r) = \frac{\mu_{0}I}{4\pi r} \sum_{l=0}^{\infty} \left(\frac{r'}{r}\right)^{l} \oint P_{l}(\cos \theta) d\mathbf{l}'$$

I = 0 term is zero

$$A_0(r)=rac{\mu_0I}{4\pi r}\oint d{f l}'=0$$

n = 1 term is the next most important term

$$A_1(r) = rac{\mu_0 I}{4\pi r} \left(rac{1}{r}
ight) \oint r' \cos heta d\mathbf{l}'$$

and
$$r'\cos\theta=\mathbf{r}'\cdot\mathbf{\hat{r}}$$

hence

$$A_1(r)=rac{\mu_0I}{4\pi r^2}\oint \mathbf{r}'\cdot\mathbf{\hat{r}}d\mathbf{l}'=rac{\mu_0I}{4\pi r^2}\mathbf{m} imes\mathbf{\hat{r}}$$

where

$$\mathbf{m} = I \int_{s} d\mathbf{S}'$$

$$= I\mathbf{S}'$$

Is the magnetic dipole moment of the current loop.


Lets stop the expansion before we get too complex stuff.

And that looks like a dipole right?

Put $\mathbf{m} \parallel z$ in spherical coordinates:

$$\mathbf{A}_1(\mathbf{r}) = rac{\mu_0}{4\pi r^2} m \sin(heta) \hat{\phi}$$

$$\mathbf{B}(\mathbf{r}) =
abla imes \mathbf{A} = rac{\mu_0}{4\pi r^3} m \sin(\theta) \hat{\mathbf{r}} - rac{\mu_0}{4\pi r^2} m \cos(\theta) \hat{\theta}$$
 which is same as electric dipole with $rac{P}{4\pi\epsilon_0}
ightarrow rac{\mu_0 m}{4\pi}$



Field patterns look the same at large r, but at small r, the magnetic field is not singular.

3.2 Magnetic Properties

In a field ${\bf B}$,a magnetic material will acquire a <u>magnetization</u> ${\bf M}=n{\bf m}$ where n is the number of magnetic dipole and ${\bf m}$ is the magnewtic moment of one atom


There are three main effects:

1. diamagnetism $ightarrow \mathbf{M} \propto -\mathbf{B}$ and that effect is very weak

All materials exihibits it!

2. Paramagnetism ightarrow $\mathbf{M} \propto +\mathbf{B}$ and it's stronger

That is often shown in materials with unpaired "spins"



 $(\mathbf{M} \propto \mathbf{B}$ but only at small B) Example: $CuSO_4 \cdot 5H_2O$

3. Ferromagnetism

Very strong QM effect E.g. Fe, Co, Ni It is a non-linear effect of M(B)

Recap to lecture 7:

Current loop $A(\mathbf{r}) = \frac{\mu_0}{4\pi r^2} \mathbf{m} imes \hat{\phi}$

Magnet moment $\mathbf{m} = I\mathbf{S}'$ where S is the vector area of the loop

Magnetization $\mathbf{M}=n\mathbf{m}$ where n is the number of magnetic dipole and \mathbf{m} is the magnewtic moment of one atom

3.3 Field due to a box of magnetic dipoles

When doing this, we start with some vector identities:

start with Divergence theorem:

$$\int_{V} \nabla \cdot \mathbf{u} d\tau = \oint_{S} \mathbf{u} \cdot d\tau$$

set $\mathbf{u} = \mathbf{v} \times \mathbf{c}$ where \mathbf{c} is a constant vector

LHS: $\int_s {f v} imes {f c} \cdot d{f S} = {f c} \cdot \int_s {f v} imes d{f S} = 0$ because ${f v} imes d{f S}$ is a vector perpendicular to ${f c}$

RHS:
$$\int_{\tau} \nabla \cdot (\mathbf{v} \times \mathbf{c}) d\tau = \int_{\tau} \mathbf{c} \cdot (\nabla \times \mathbf{v}) d\tau - \int_{\tau} \mathbf{v} \cdot (\underbrace{\nabla \times \mathbf{c}}_{0}) d\tau$$

Therefore, for any \mathbf{c} ,

$$\Rightarrow \int_{S} \mathbf{v} \times d\mathbf{S} = -\int_{ au}
abla imes \mathbf{v} d au$$



Assume there is a box of magnetic dipoles, and there is one dipole at position ${f r}'$

$$\mathbf{A}(\mathbf{r}) = rac{\mu_0}{4\pi} \int rac{\mathbf{M}(\mathbf{r}) imes(\mathbf{r}-\mathbf{r}')}{|\mathbf{r}-\mathbf{r}'|^3} d au'$$

which equals

$$rac{mu_0}{4\pi}\int \mathbf{M}(\mathbf{r}) imes
abla rac{1}{|r-r'|}d au'$$

We have

$$egin{aligned}
abla' imes \left(rac{\mathbf{M}}{\mathbf{r} - \mathbf{r}'}
ight) = \left(rac{1}{|r - r'|}
abla' imes \mathbf{M} - \mathbf{M} imes
abla' rac{1}{|r - r'|}
ight) \end{aligned}$$

Hence

$$A(\mathbf{r}) = rac{\mu_0}{4\pi} \int rac{
abla' imes \mathbf{M}(\mathbf{r})}{|\mathbf{r} - \mathbf{r}'|} - rac{
abla' imes \mathbf{M}(\mathbf{r})}{|\mathbf{r} - \mathbf{r}'|} d au'$$

The last term can be transformed into a surface integral:

$$\mathbf{A}(\mathbf{r}) = rac{\mu_0}{4\pi} \int rac{
abla' imes \mathbf{M}(\mathbf{r})}{|\mathbf{r} - \mathbf{r}'|} d au' + rac{\mu_0}{4\pi} \oint rac{\mathbf{M}(\mathbf{r}) imes d\mathbf{S}'}{|\mathbf{r} - \mathbf{r}'|}$$

This looks like

$$rac{\mu_0}{4\pi}\int_{ au}rac{\mathbf{J}(\mathbf{r})}{|r-r'|}d au+rac{\mu_0}{4\pi}\int_{s}rac{\mathbf{K}_b(\mathbf{r}')}{|r-r'|}dS'$$

Where $\mathbf{J} = \nabla \times \mathbf{M}$ is the bulk bound current density and $\mathbf{K}_b = \mathbf{M} \times \hat{\mathbf{n}}$ is the surface bound current density.

Remember to drop the prime!

Having done this, we can fix up Amperes law:

Amperes law: $\nabla \times \mathbf{B} = \mu_0 (\mathbf{J}_f + \mathbf{J}_b)$

Where \mathbf{J}_f is the free current density where you can connect or do sth like that; and \mathbf{J}_b is the bound current density, it can be written as the curl of M

Hence the expression for free current would be

$$\mathbf{J}_f =
abla imes (rac{\dot{\mathbf{B}}}{\mu_0} - \mathbf{M})$$

Stuff in the bracket is defined as the magnetic field H and hence the free current density has a simpler form

$$\mathbf{J}_f =
abla imes \mathbf{H}$$

Its integral form is

$$\oint \mathbf{H} \cdot d\mathbf{l} = I_f$$

However, $\nabla \cdot B = 0$ becomes

$$\nabla \cdot H = -\nabla \cdot M$$

The equtions to remember would be

$$\mathbf{D} = \epsilon_0 \mathbf{E} + \mathbf{P}$$

$$B = \mu_0(\mathbf{H} + \mathbf{M})$$

Linear materials

M is proportional to B

$$\mathbf{M}=\chi_m\mathbf{H}$$

where χ_m is the magnetic susceptibility


$$\mathbf{B} = \mu_0(\mathbf{H} + \mathbf{M}) = \mu_0 \underbrace{(1 + \chi_m)}_{\mu_r} \mathbf{H} = \mu_0 \mu_r \mathbf{H}$$

where $\mu_r=1+\chi_m$ is the relative permeability

If willing to be strict, H would be called magnetic field strength and B would be called magnetic flux density

3.4 Boundary conditions

one is not changed:



$$abla \cdot \mathbf{B} = 0 \Rightarrow B_1^{\perp} = B_2^{\perp}$$

Making this cylinder flater and flater, we can see that the B field is continuous However, $H_1^\perp=H_2^\perp$ is not true because the $\nabla\cdot H=-\nabla\cdot M$



 $abla imes \mathbf{H} = \mathbf{J}_f \Rightarrow H_1^{\parallel} - H_2^{\parallel}$ (Assuming there is no surface free currents)

But B^{\parallel} is not continuous because you can have bound surfce currents at interface and $abla imes {f B} = \mu_0 ({f J}_f + {f J}_b)$

$$\Rightarrow E^{\parallel}, D^{\perp}, H^{\parallel}, B^{\perp} are continuous$$

Assuming there is no surface free charges/currents

3.5 Magnetic scalar potential

If $\mathbf{J}_f = 0$ everywhere, then

$$abla imes \mathbf{H} = 0 \Rightarrow \mathbf{H} = -
abla \phi_m$$

where ϕ_m is the magnetic scalar potential

If, we are dealing wit linear material,

$$\mathbf{B} = -\mu_0 \mu_r \nabla \phi_m$$

If, in addition, $abla \cdot H = 0$

Then we can use the Laplace equation to solve for ϕ_m

3.6 Ferromagnetism

One way to define magnitization is = $\lim_{\delta v \to 0} \frac{\sum_{i \in \delta v} m_i}{\delta v}$


Microscopally, ferromaget has $M \neq 0$, even in B = 0

The reason for ferromagnetism is the (what will be learnt next term), the *exchange* interaction

Only in certain materials:

Fe, Co, Ni, Gd

There is an energy cost due to the stray field of the magnetic dipoles.




From the picture having stray field, it can be seen that on the tip and bottom of the field, there is a divergence of magnitization, leading to divergence in H. Meaning that field spreads out whenever you have magnetic moment going into the surface and not flowing out.


The energy cost would be

$$\int \frac{B^2}{2\mu_0} d au$$

 \Rightarrow It is energetic flavorable to form domains




This will cost low energy since there is no stray field and hence no divergence in H. (Average over the surface, M is zero)



When applying a B field, the correlated domain is expanded and finally they are all aligned.

So, the magnetization process involves moving domain walls.

- \Rightarrow The process is highly non-linear
- ⇒ hysterisis loop



States that is interesting

- 1. Saturation (right up)
- 2. Remanence (middle up)
- 3. Coercivity (left middle)

 Better picture is in handout

The field which is positive but M is zero is called coersive field.

We can modle this as

$$M=(\mu_r-1)H$$
 only if $\mu_r=\mu_r(H)$

and $\mu_r(H)$ is a multivalued function (because it depends on histroy)

Hard materials

 H_c , M_r are large

- difficult to move domain walls
- So it is hard to magnitize and demagnitize
- so it is used for permanent magnets

Soft materials

 H_c , M_r are small

- easy to move domain walls
- so it is used for transformers, motors, etc.

Example: Magnitization of a ring

Iron ring, radius r, and current I with N terms used to magnitize the ring



Have a Amperian loop around the ring, then use

$$\oint \mathbf{H} \cdot d\mathbf{l} = NI$$

Since H only depends on the free current, it is favorable for us to use it.


Continue the calculation

$$H \cdot 2\pi r = NI$$

$$H = \frac{NI}{2\pi r}$$

Hence B =
$$\mu_0\mu_r H = \mu_0\mu_r rac{NI}{2\pi r}$$

Now lets put a gap in the ring



The cutout, x, would much less than r

Lets use the same trick, ampere's law

$$\oint \mathbf{H} \cdot d\mathbf{l} = NI$$

$$H_{core}(2\pi r - x) + H_{gap}x = NI$$

 B_{\perp} Is continuous, \Rightarrow $B_{core}=B_{gap}$

Substitute in the function

$$rac{B_{core}}{\mu_0\mu_r}(2\pi r-x)+rac{B_{gap}}{\mu_0}(x)=NI$$

Rearrange that

$$B_{gap}=rac{\mu_0\mu_rNI}{(2\pi r-x)+\mu_rx}$$

If
$$\mu_r >> rac{2\pi r}{x}$$
 , then B_{gap} becomes about $rac{\mu_0 NI}{x}$

Is could be very large if x is small. But for that condition to work, you need mu_rNI to be very large.

4 Electromagnetic waves in material

Let's let everything move!

4.1 Displacement current

Conservation of charge

$$abla * \mathbf{J_s} = -rac{\partial
ho_f}{\partial t}$$

However, this is incompatible with

$$abla imes \mathbf{H} = \mathbf{J}_f$$

Lets take the divergence for both sides, we get

$$abla \cdot (
abla imes \mathbf{H}) = 0 =
abla \cdot \mathbf{J} + rac{\partial}{\partial t} \underbrace{
abla \cdot \mathbf{D}}_{
ho_F}$$

 \Rightarrow add an additional term to the current density $\boldsymbol{J_f} = \nabla \times \boldsymbol{H}$

$$ightarrow
abla imes \mathbf{H} = \mathbf{J_f} + \underbrace{rac{\partial \mathbf{D}}{\partial t}}_{ ext{displacement current}}$$

LHS:
$$\nabla imes \left(\frac{\mathbf{B}}{\mu_0} - \mathbf{M} \right) = \frac{1}{\mu_0} \nabla imes \mathbf{B} - \underbrace{\nabla imes \mathbf{M}}_{\mathbf{J}_{\mathbf{b}}}$$

Where J_b is the bound current density.

$$\text{RHS} = \mathbf{J_s} + \tfrac{\partial \mathbf{D}}{\partial t} = \mathbf{J_s} + \tfrac{\partial \mathbf{P}}{\partial t} + \epsilon_0 \tfrac{\partial \mathbf{E}}{\partial t}$$

$$\Rightarrow$$
 we could write $abla imes \mathbf{B} = \mu_0 \left(\mathbf{J_f} + \mathbf{J_b} + \mathbf{J_p} \right) + \mu_0 \epsilon_0 \frac{\partial \mathbf{E}}{\partial t}$

where J_p is the polarization current density. which equals $\frac{\partial \mathbf{P}}{\partial t}$

Note that $abla \cdot \mathbf{J_p} = -rac{\partial
ho_p}{\partial t}$ from conservation of charge.

Thus the polarization current responds to changes to bound charge, and hence in ${f P}$

4.2 Maxwell's equations in insulating linear dielectrics

Since it is insulating linear dielectrics, we have ${f J}_f=0$ and ${f J}_b=0$ Hence, we could get Maxwell's equation

$$abla \cdot \mathbf{D} = 0$$
 $\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$

$$\nabla \cdot \mathbf{B} = 0$$
 $\nabla \times \mathbf{H} = \frac{\partial \mathbf{D}}{\partial t}$

remember, $\mathbf{D}=\epsilon_0\epsilon_r\mathbf{E}+\mathbf{P}$ and $\mathbf{B}=\mu_0\mu_r\mathbf{H}$ which gives

$$abla \cdot \mathbf{E} = 0$$
 $\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$

$$abla \cdot \mathbf{B} = 0 \qquad
abla imes \mathbf{B} = \mu_0 \mu_r \epsilon_0 \epsilon_r rac{\partial \mathbf{E}}{\partial t}$$

Consider

$$egin{aligned}
abla imes (
abla imes \mathbf{E}) &=
abla (
abla \cdot \mathbf{E}) -
abla^2 \mathbf{E} = -rac{\partial}{\partial t}
abla imes \mathbf{B} \end{aligned}$$
 $\Rightarrow
abla^2 \mathbf{E} = \underbrace{\mu_0 \mu_r \epsilon_0 \epsilon_r}_{rac{1}{2}} rac{\partial^2 \mathbf{E}}{\partial t^2}$

which is wave equation.

$$\Rightarrow v=rac{c}{n}$$
 where c = $rac{1}{\sqrt{\epsilon_0\mu_0}}$ and n = $\sqrt{\epsilon_r\mu_r}$ where n is also called *refractive index*

Plane waves solutions

Lets choose propagation parallel to z, and hence

$$\frac{\partial \Psi}{\partial \mathbf{x}} = \frac{\partial \Psi}{\partial \mathbf{v}} = 0$$

remember that
$$\nabla \cdot \mathbf{E} = 0 \Rightarrow \frac{\partial E_z}{\partial z} = 0$$
 similarly, $\nabla \cdot \mathbf{B} = 0 \Rightarrow \frac{\partial B_z}{\partial z} = 0$

similarly,
$$abla \cdot {f B} = 0 \Rightarrow rac{\partial B_z}{\partial z} = 0$$

we also have
$$abla imes \mathbf{E} = -rac{\partial \mathbf{B}}{\partial t} \Rightarrow rac{\partial B_z}{\partial t} = 0$$

And
$$\nabla imes {f B} = \mu_0 \mu_r \epsilon_0 \epsilon_r rac{\partial {f E}}{\partial t} \Rightarrow rac{\partial E_z}{\partial t} = 0$$

Hence, E_z and B_z are constant in z and t, they are not part of wave motion now analyze the x,y components of curl:

$$-rac{\partial E_y}{\partial z} = -rac{\partial B_x}{\partial t}, -rac{\partial B_y}{\partial z} = rac{1}{v^2}rac{\partial E_x}{\partial t}$$

 $\Rightarrow E_x, B_y$ are solutions

Lets then take

$$egin{align} rac{\partial^2 E_x}{\partial t^2} &= rac{1}{v^2} rac{\partial^2 E_x}{\partial t^2} \ \Rightarrow E_x(z,t) &= E_{x0} e^{i(\pm kz - \omega t)} \mathbf{\hat{x}} \end{aligned}$$

Then, we could have

$$\Rightarrow B(z,t) = B_0 e^{i(\pm kz - \omega t)} \mathbf{\hat{y}}$$

And then we could get the wave travelling in $\pm \mathbf{z}$ direction

$$\Rightarrow \mp kE_0 = -\omega B_0$$
 and $\pm kB_0 = rac{\omega}{v^2}E_0$ $\Rightarrow rac{E_0}{B_0} = \pm rac{\omega}{k} = \pm v$

Define Impedance Z as

$$Z = \left|rac{E_0}{H_0}
ight| = \sqrt{rac{\mu_0\mu_r}{\epsilon_0\epsilon_r}}$$

remember that $H_0=rac{B_0}{\mu_0\mu_r}$

The motivation of doing so is that $v = -\int {f E} \cdot d{f l}$ and $I = \oint {f H} \cdot d{f l}$

So dimension would work


For free space, then,
$$\epsilon_r=\mu_r=1$$
 and $Z=\sqrt{rac{\mu_0}{\epsilon_0}}=377\Omega$

Remember that $abla imes {f E} = -{f \dot B}$, and use E, B $\propto e^{i({f k}\cdot{f r}-\omega t)}$, we could get

$$egin{aligned} i\mathbf{k} imes \mathbf{E} &= -(-i\omega)\mathbf{B} \ &= i\omega\mu_0\mu_r\mathbf{H} \ \Rightarrow z &= \left| rac{\mathbf{E}}{\mathbf{H}}
ight| = \sqrt{rac{\mu_0\mu_r\omega}{k}} \end{aligned}$$

Which gives the same answer because $v=rac{c}{n}=rac{\omega}{k}=rac{1}{\sqrt{\epsilon_0\epsilon_r\mu_0\mu_r}}$

which is this wave



4.3 conductors

Remember that

$$abla \cdot \mathbf{J_f} = -rac{\partial
ho_f}{\partial t}$$

$$\nabla \cdot \mathbf{J_p} = -\frac{\partial t}{\partial \rho_p}$$

$$\nabla \cdot \mathbf{J_h} = 0$$

The last one is 0 because $abla \cdot (
abla imes \mathbf{M}) = 0$

For conductors, we have

 $ho_f=0$ since there are no free charges in equilibrium

 $\mathbf{J}_f = \sigma \mathbf{E}$ from Ohm's law where σ is the conductivity

$$\mathbf{D} = \epsilon_0 \epsilon_r \mathbf{E}$$
 and $\mathbf{B} = \mu_0 \mu_r \mathbf{H}$ from linearity

Then we could get Maxwell's equation in conductors

$$abla \cdot \mathbf{E} = 0$$
 $abla \times \mathbf{E} = -rac{\partial \mathbf{B}}{\partial t}$

$$abla \cdot \mathbf{B} = 0 \qquad
abla imes \mathbf{B} = \underbrace{\mu_0 \mu_r \sigma \mathbf{E}}_{\mathrm{conduction } \mathbf{J}} + \underbrace{\mu_0 \mu_r \sigma_0 \sigma_r \frac{\partial \mathbf{E}}{\partial t}}_{\mathrm{dispalcement } \mathbf{J}}$$

Free charge will decay to zero in a short time au, and it is easy to prove (said Blundell)

$$\nabla \cdot \mathbf{J} = \frac{\partial \rho}{\partial t}$$

Where $abla \cdot \mathbf{J}$ is equal to $\sigma \cdot
abla \cdot \mathbf{E}$ from Ohm's law

and $abla \cdot \mathbf{E}$ is equal to $rac{
ho}{\epsilon_0 \epsilon_r}$ from Gauss's law

$$\Rightarrow
ho(f) =
ho(0) e^{-rac{t}{ au}}$$

Where
$$au = rac{\epsilon_0 \epsilon_r}{\sigma}$$

If the metal has great conductivity, then τ is very small, and hence $\rho(f)$ is very small.

Let's consider the electromagnetic wave having frequency ω , so we would like to compare $\frac{1}{\omega}$ with τ :

Condition	Conductor Type	Charge Response	Conductivity
$\omega au \ll 1$	Good conductor	Charges respond very quickly	$\sigma\gg\epsilon_0\epsilon_r\omega$ Conduction current dominates
$\omega au \gg 1$	Bad conductor	Charges respond very slowly	$\sigma \ll \epsilon_0 \epsilon_r \omega$ Displacement current dominates

Take real life examples

	$\sigma(\Omega m)$	ϵ_r	$rac{\sigma}{\epsilon_0\epsilon_r}(S^{-1})$
metal	10^7	1	10^{19}
Silicon	$4\cdot 10^{-4}$	11.7	10^{7}
Glass	10^{-10}	5	10

Note that visible light would have frequency ~ $5\cdot 10^{14}$ Hz

Let's now do some electromagnetism

$$egin{aligned}
abla imes (
abla imes \mathbf{E}) &= \underline{
abla (
abla \cdot \mathbf{E})} -
abla^2 \mathbf{E} \ &= -rac{\partial}{\partial t}
abla imes \mathbf{B} \ &= -rac{\partial}{\partial t}
abla imes \mathbf{B} \ &= \mu_0 \mu_r \sigma rac{\partial \mathbf{E}}{\partial t} + \mu_0 \mu_r \sigma_0 \sigma_r rac{\partial^2 \mathbf{E}}{\partial t^2} \end{aligned}$$

Again, this would yield transverse plane waves with ${f E}, {f B} \perp$ to each others

Again, this would yield mainsverse plane waves with
$$\begin{split} &\Rightarrow \mathbf{E} = \mathbf{E}_0 \hat{\mathbf{x}} e^{i(\widetilde{\mathbf{k}} \cdot \mathbf{z} - \omega t)} \\ &\text{with } \widetilde{\mathbf{k}} = \mathbf{k} + i \kappa \\ &\Rightarrow \widetilde{k}^2 = i \underbrace{\mu_0 \mu_r \sigma \omega}_{\mu} + \underbrace{\mu_0 \mu_r \epsilon_0 \epsilon_r \omega^2}_{\epsilon} \\ &(k+i\kappa)^2 = k^2 - \kappa^2 + 2ik\kappa \\ &k^2 - \kappa^2 = \mu_0 \epsilon_0 \omega^2 \\ &2k\kappa = \mu \sigma \omega \Rightarrow k = \frac{\mu \sigma \omega}{2\kappa} \\ &0 = \left(\frac{\mu \sigma \omega}{2}\right)^2 \frac{1}{k^2} - k^2 - \mu \epsilon_0 \omega^2 \\ &0 = (k^2)^2 + \mu \epsilon \omega^2 (k^2) - \left(\frac{\mu \sigma \omega}{2}\right)^2 \\ &\kappa^2 = -\frac{\mu \epsilon \omega^2}{2} \pm \sqrt{\left(\frac{\mu \epsilon \omega^2}{2}\right)^2 + \left(\frac{\mu \sigma \omega}{2}\right)^2} \\ &\kappa^2 = \frac{\mu \epsilon \omega^2}{2} \left[\pm \sqrt{1 + \left(\frac{\sigma}{\epsilon \omega}\right)^2} - 1 \right] \end{split}$$

Taking the positive root

$$ightarrow \kappa = \sqrt{rac{\mu\epsilon}{2}}\omega\sqrt{\sqrt{1+\left(rac{\sigma}{\epsilon\omega}
ight)^2}-1}$$

Sub into origional equation

$$k = rac{\mu\sigma\omega}{2\kappa} = \sqrt{rac{\mu\epsilon}{2}}\omega\sqrt{\sqrt{1+\left(rac{\sigma}{\epsilon\omega}
ight)}+1} \ \Rightarrow \mathbf{E} = \mathbf{E}_0\hat{\mathbf{x}}\underbrace{e^{-\kappa z}}_{e^{-rac{z}{\delta}}}e^{i(\mathbf{k}\cdot\mathbf{r}-\omega t)}$$

Where $\delta = \frac{1}{\kappa}$ is the *skin depth*

Reminder. Good conductors have $\sigma\gg\epsilon\omega$

$$k=\kappa=\sqrt{rac{\mu\epsilon}{2}}\omega\sqrt{rac{\sigma}{\epsilon\omega}}=\sqrt{rac{\mu\omega\sigma}{2}}$$

We could therefore have

$$abla^2 \mathbf{E} = \mu \sigma rac{\partial \mathbf{E}}{\partial t} + \mu \epsilon rac{\partial^2 \mathbf{E}}{\partial t^2}$$

We could also neglect the last term, since $\frac{\partial^2 E}{\partial t^2} \ll \frac{\partial E}{\partial t}$

$$egin{aligned} &\Rightarrow \widetilde{k}^2 = i\mu\sigma\omega \ &\Rightarrow \widetilde{k} = rac{1+i}{\sqrt{2}} sqrt\mu\sigma\omega \ &\Rightarrow \widetilde{k} = \kappa = \sqrt{rac{\mu\sigma\omega}{2}} \end{aligned}$$

Hence, we could have

$$\delta = \frac{1}{k} = \sqrt{\frac{2}{\mu\sigma\omega}}$$

For a typical metal, δ is

 $\begin{cases} \text{few nm - visible light} \\ \text{few}\mu m \text{ - microwave} \\ \text{few mm - radio waves} \end{cases}$

Lets go to poor conductors

Poor conductors has $\sigma \ll \epsilon \omega$, hence

$$egin{aligned} k &pprox \sqrt{rac{\mu\epsilon}{2}}\omega\sqrt{2} = \sqrt{\mu\epsilon}\omega \ \kappa &= \sqrt{rac{\mu\epsilon}{2}}\omega\Big(1 + rac{1}{2}ig(rac{\sigma}{\epsilon\omega}ig)^2 + \dots - 1\Big)^rac{1}{2} \end{aligned}$$

which equals to $\frac{\sigma}{2}\sqrt{\frac{\mu}{\epsilon}}$ which is independent to ω

In an insulating dielectric, $\sigma=0$, hence $\kappa=0$, and hence $k=rac{\omega}{v}$ as expected.

Lets return to previous equation

Lets consider the curl equation in the conductor

$$egin{aligned} rac{\partial \mathbf{E}_x}{\partial z} &= rac{\partial B_y}{\partial t} \ i(k+k)\mathbf{E}_0 &= i\omega \mathbf{B}_0 \ z &= rac{\mu E_0}{B_0} &= rac{\mu \omega}{k+i\kappa} \ \widetilde{k} &= rac{\mu \omega}{\sqrt{k^2+\kappa^2}} e^{i\phi} \end{aligned}$$

If we expand, ϕ would be

$$\phi= an^{-1}\left(rac{\sqrt{1+(Q/\epsilon\omega)^2}-1}{\sqrt{1+(Q/\epsilon\omega)^2}+1}
ight)^{rac{1}{2}}$$

For a good conductor, $\sigma\gg\epsilon\omega$, hence $\phi o an^{-1}1=rac{\pi}{4}$

So this means that B lags behind E in a metal

Poyting vectors

Work done on charge

$$egin{aligned} \delta q &=
ho = delta au \ \delta F &= \delta q(\mathbf{E} + \mathbf{V} imes \mathbf{B}) \ \delta \mathbf{F} \cdot \mathbf{dl} &= \delta q(\mathbf{E} + \mathbf{V} imes \mathbf{B}) \cdot \mathbf{v} \delta t \ &= \mathbf{E} \cdot \mathbf{J_f} \delta au \delta t \end{aligned}$$

where \mathbf{J}_f eaquals to $\rho \mathbf{v}$

Rate of work on charges

$$egin{aligned} \mathbf{F} &= rac{dw}{dt} \ &= \mathbf{E} \cdot \mathbf{J_f} d au \ &= rac{d}{dt} \int \underbrace{u_{mech}}_{ ext{Energy density}} d au \end{aligned}$$

From Maxwell's equation:

$$\mathbf{J}_f =
abla imes \mathbf{H} - rac{\partial \mathbf{D}}{\partial t}$$

We have

$$\mathbf{E} \cdot \mathbf{J_f} = \mathbf{E} \cdot \nabla \times \mathbf{H} - \mathbf{E} \cdot \frac{\partial \mathbf{D}}{\partial t}$$

By dotting everything, and then

$$\begin{array}{l} \nabla \cdot \left(\mathbf{E} \times \mathbf{H} \right) = \mathbf{H} \cdot \nabla \times \mathbf{E} - \mathbf{E} \cdot \nabla \times \mathbf{H} \\ \mathbf{E} \cdot \mathbf{J_f} = \mathbf{H} \cdot \underbrace{\nabla \times \mathbf{E}}_{-\frac{\partial \mathbf{B}}{\partial t}} - \mathbf{E} \cdot \frac{\partial \mathbf{D}}{\partial t} - \nabla \cdot \left(\mathbf{E} \times \mathbf{H} \right) \end{array}$$

Where we call $\mathbf{H} \cdot \underbrace{\nabla \times \mathbf{E}}_{-\frac{\partial \mathbf{B}}{\partial t}} - \mathbf{E} \cdot \frac{\partial \mathbf{D}}{\partial t}$ " $\frac{\partial}{\partial t} u_{EM}$ " (remember that

 $u_{EM} = \frac{1}{2} (\mathbf{B} \cdot \mathbf{H} + \mathbf{E} \cdot \mathbf{D})$ which equals to Energy stored in EM field per unit volume) and $\nabla \cdot (\mathbf{E} \times \mathbf{H})$ as " $\mathbf{S} = \mathbf{E} \times \mathbf{H}$ " or poyting vector.

How is this working?

Assume that we are using a linear media:

$$\mathbf{E} \cdot \frac{\partial \mathbf{D}}{\partial t} = \frac{1}{2} \mathbf{E} \cdot \frac{\partial (\mathbf{E} \cdot \mathbf{D})}{\partial t}$$

$$\mathbf{H} \cdot \frac{\partial \mathbf{B}}{\partial t} = \frac{1}{2} \mathbf{H} \cdot \frac{\partial (\mathbf{B} \cdot \mathbf{H})}{\partial t}$$

Remember that

$$\frac{1}{2}\epsilon_0 E^2 = \frac{1}{2}DE$$

$$\frac{B^2}{2\mu_0} = \frac{1}{2}BH$$
In free space

Brining everything together, we could get


$$\Rightarrow rac{d}{dt}(u_{
m mech}+u_{
m EM})+
abla\cdot{f S}=0$$

Where \mathbf{S} is the poyting vector, or equiviantly,

$$\frac{d}{dt}\int (u_{\mathrm{mech}} + u_{\mathrm{EM}})d\tau + \oint \mathbf{S} \cdot d\mathbf{a} = 0$$

We could say that, therefore ${\bf S}$ is the energy flux density, or the rate of flow of energty per unit area in the direction of S.


Example: a capacitor



The stored energy increase at rate

$$\dot{U} = \frac{Q}{C} \frac{dQ}{dt}$$
 $U = \frac{Q^2}{2C}$

also:




Hence, we have

$$\dot{U} = S \cdot 2\pi r d = rac{Q}{c} rac{dQ}{dt}$$

where
$$S=EH=rac{Q}{dc}rac{rac{dQ}{dt}}{2\pi r}$$

There is another example



$$H \cdot S\pi a = I$$

$$E = \frac{V}{l}$$

$$\Rightarrow S = \frac{V}{l} \frac{I}{2\pi a}$$

$$\int \mathbf{S} \cdot \mathbf{da} = -IV = -I^2 R$$

4.5 Radiation pressure

EM waves are made up of photons, and hecne they have momentum

$$E = pc$$

 \Rightarrow Transport of energy is appoinated by transport of momentum

$$P_{rad} = rac{< S>}{c}$$

For a perfect absorber, where P_{rad} is the radiation pressure

Example For a plane EM wave in free space, we have

$$U = \frac{1}{2}\epsilon_0 E^2 + frac12\frac{B^2}{\mu_0}$$
 but $E = cB$
$$\Rightarrow U = \epsilon_0 E^2$$

$$\mathbf{E} = \frac{1}{2}E_0\cos(kz - \omega t)\hat{\mathbf{x}}$$

$$= E_0\cos^2(kz - \omega t)$$

$$< E^2 > = \frac{1}{2}E_0^2$$

$$\Rightarrow < u > = \frac{1}{2}\epsilon_0 E_0^2$$


$$< S > = \frac{1}{2}\epsilon_0 E_0^2 c = I$$
 Where I is the intensity of wave
$$\Rightarrow P_r ad = \begin{cases} \frac{1}{2}\epsilon_0 E_0^2 & \text{perfect absorber} \\ \epsilon_0 E_0^2 & \text{perfect reflector} \end{cases}$$

Sunlight: I
$$\sim$$
1 kWm^{-2} $\Rightarrow P_{rad} = 10^{-5}Pa$ FYI, $P_{atm} = 10^{5}Pa$

Example Consider a star which is growing by accretion i.e. matter is falling onto it uniformly in all directions

The star has luminosity L

4.6 EM waves - reflection and refraction



Left:

$$E_i e^{i(k_1 x - \omega t)} + E_r e^{i(-k_1 - \omega t)}$$

Right:

$$E_t e^{i(k_2 x - \omega t)}$$

Using electrom boundery conditions, we could get

$$E^{\parallel}$$
 is continuous

$$E_i^\parallel + E_r^\parallel = E_t^\parallel$$

$$H^{\parallel}$$
 is continuous

$$\frac{E_i}{Z^1} - \frac{E_r}{Z_1} = \frac{E_f}{Z_2}$$

Putting two equations together

$$rac{E_r}{E_i} = rac{Z_2 - Z_1}{Z_2 + Z_1}$$
 $rac{E_t}{E_i} = rac{2Z_2}{Z_2 + Z_1}$

Where
$$Z=\sqrt{rac{\mu}{\epsilon}}$$

|Poyting vector|
$$=S=|\mathbf{E} imes\mathbf{H}|=rac{E^2}{Z}$$

We expect
$$S_{incident} = S_{reflected} + S_{transmitted}$$


Where they equal to

$$\frac{E_i^2}{Z_1} + \frac{E_r^2}{Z_1} = \frac{E_t^2}{Z_2}$$

separately

Lets now have angles

$$E_r e^{i(\mathbf{k_r} \cdot \mathbf{r} - \omega t)}$$



$$\mathbf{E_i}e^{i(\mathbf{k_i}\cdot\mathbf{r}\omega t)}$$

$$E_t e^{i(\mathbf{k_t} \cdot \mathbf{r} - \omega t)}$$

Choose \mathbf{k}_i in x-z plane

At z = 0, E_{\parallel} is cointinuous and this holds for all x y and t $\Rightarrow \omega$ must be the same

$$\Rightarrow {f k_i \cdot r} = {f k_r \cdot r} = {f k_t \cdot r}$$
 for all x, y at z=0

Take
$$\mathbf{r}=(0,y,0)$$

 \Rightarrow $\mathbf{k_i}, \mathbf{k_r}$ and \mathbf{k}_t all lie iin the xz plane (the plane of incidence)

Take
$$\mathbf{r} = (x,0,0)$$
 so $\mathbf{k_i} \cdot \mathbf{r} = k \sin \theta_x$

$$|\mathbf{k_i}| = \mathbf{k_r}| = k_1$$

$$|\mathbf{k_t}| = k_2$$

$$\Rightarrow \underbrace{k_1 \sin \theta_i = k_1 \sin \theta_r}_{\theta_i = \theta_r, \, \text{law of reflection}} = k_2 \sin \theta_t$$

Remember that $\frac{\omega}{k}=\frac{c}{n}$, And the last two would lead to $\frac{\sin\theta_t}{\sin\theta_i}=\frac{k_1}{k_2}=\frac{n_2}{n_1}$ -law of refraction, or snell's law Where $n=\sqrt{\epsilon_r\mu_r}$

Fresnel equations


Worring about polarization directions

We work in those steps

1. E in the plane of incidence

"parallel-like" = parallel

Remid that ${f E}, {f H}$ and ${f k}$ form a right-handed system



	incident	reflected	transmitted
E_x	$E_i\cos heta_i$	$E_r\cos heta_r$	$E_t \cos heta_t$
E_z	$-E_i\sin heta_i$	$E_r\cos heta_r$	$-E_t\sin heta_t$
H_y	$rac{E_i}{Z_1}$	$-rac{E_r}{Z_1}$	$rac{E_t}{Z_2}$


 E_{\parallel} continuous $\Rightarrow E_x$ continuous $\Rightarrow E_i \cos heta_i + E_r \cos heta_i = E_t \cos heta_t$

$$egin{split} rac{E_r}{E_i} &= rac{Z_2 \cos_t het a_i - Z_1 \cos heta_i}{Z_2 \cos heta_1 + Z_1 \cos heta_i} \ rac{E_t}{E_i} &= rac{2Z_2 \cos heta_i}{Z_2 \cos heta_i + Z_1 \cos heta_i} \end{split}$$

Now look for Fresned equations for p-polarizations

$2. \ \mathbf{E}$ perpendicular to the plane of incidence

"s-like" s = senkrecht = perpendicular



	incident	reflected	transmitted
E_y	E_i	E_r	E_t
H_x	$-rac{E_i}{Z_1}{\cos heta_i}$	$rac{E_r}{Z_1}{\cos heta_r}$	$-rac{E_t}{Z_2}{\cos heta_t}$
H_z	$rac{E_i}{Z_1}{ m sin} heta_i$	$rac{E_r}{Z_1}{\sin heta_r}$	$rac{E_t}{Z_2}{ m sin} heta_t$

 E_{\parallel} continuous

$$\Rightarrow E_y ext{continuous} \quad E_i + E_r = E_t$$

 H_{\parallel} continuous

$$\Rightarrow H_x continuous \quad -rac{E_i}{Z_1} cos \, heta_i + rac{E_r}{Z_1} cos \, heta_r = -rac{E_t}{Z_2} cos \, heta_t$$

Remember that

$$Z = \sqrt{rac{\mu_r \mu_0}{\epsilon_r \epsilon_0}} = rac{Z_0}{n} \quad n = \sqrt{\epsilon_r} ext{while } \mu_r = 1$$

Let's set
$$\mu_r=1$$

Then,
$$Z=\sqrt{rac{\mu_r\mu_0}{\epsilon_r\epsilon_0}}=rac{Z_0}{n}$$
 $n=\sqrt{\epsilon_r}$

So we can replace Z_i with $\frac{1}{n_i}$ in expressions involving ratios of Z's.

e.g. Fresnel equations for p-polarization

$$egin{aligned} r = rac{E_r}{E_i} = rac{rac{1}{n_2}\cos heta_t - rac{1}{n_1}\cos heta_i}{rac{1}{n_2}\cos heta_t + rac{1}{n_1}\cos heta_i} \ = rac{n_1\cos heta_t - n_2\cos heta_i}{n_1\cos heta_t + n_2\cos heta_i} \end{aligned}$$

Use Snell's law

$$egin{aligned} n_1 \sin heta_i &= n_2 \sin heta_t \ \Rightarrow r &= rac{\sin 2 heta_t - \sin 2 heta_i}{\sin 2 heta_t + \sin 2 heta_i} \ t &= rac{4 \sin_t het a_t \cos heta_i}{\sin 2 heta_t + \sin 2 heta_i} \end{aligned}$$

For s-polarization, we have

$$r = rac{\sin(heta_t - heta_i)}{\sin(heta_t + heta_i)} \ t = rac{2\sin heta_t\cos heta_i}{\sin(heta_t + heta_i)}$$

We also have

$$egin{aligned} n_1 \sin heta_i &= n_2 \sin heta_t \ \sin heta_t &= rac{n_1}{n_2} \sin heta_i \ \cos heta_t &= \sqrt{1 - \sin^2 heta_t} = \sqrt{1 - rac{n_1^2}{n_2^2} \sin^2 heta_i} \end{aligned}$$

Fresnel equations:

/ $n_1 \cos \theta_i$ on top and bottom

$$egin{aligned} lpha &= rac{\cos heta_t}{\cos heta_i} = rac{1}{\cos heta_i} \sqrt{1-(rac{n_1}{n_2}\!\sin heta_i)^2} \ eta &= rac{n_2}{n_1} \end{aligned}$$

	E^{\parallel} (p)	E^{\perp} (s)
r	$\frac{\alpha-\beta}{\alpha+\beta}$	$rac{1-lphaeta}{1+lphaeta}$
t	$\frac{2\alpha}{\alpha+eta}$	$\frac{2}{1+lphaeta}$

Remember, EM waves have an energy flux given by

$$S = |\mathbf{E} imes \mathbf{H}| = rac{E^2}{Z}$$

Intensify coefficients

$$T=rac{I_r}{I_i}=|r|^2=egin{cases} (rac{lpha-eta}{lpha+eta})^2 & (p)\ (rac{1-lphaeta}{1+lphaeta})^2 & (s) \end{cases}$$

$$T=rac{I_t}{I_i}=|t|^2rac{n_2}{n_1}rac{\cos heta_t}{\cos heta_i}$$

where $\frac{n_2}{n_1}$ is due to waves at ifferent speeds. And $\frac{\cos\theta_t}{\cos\theta_i}$ is due to the wavesfronts at different angles.

$$T=|t|^2lphaeta=egin{cases} lphaeta(rac{2}{lpha+eta})^2 & (p)\ lphaeta(rac{2}{1+lphaeta})^2 & (s) \end{cases}$$

Lets check in certain cases

$$egin{aligned} \bullet \ \ heta_i = 0 \Rightarrow \alpha = 1 \\ r_s = r_p = \dfrac{1-\beta}{1+\beta} = \dfrac{n_1-n_2}{n_1+n_2} \\ t_s = t_p = \dfrac{2}{1+\beta} = \dfrac{2n_1}{n_1+n_2} \\ R_s = R_p = (\dfrac{n_1-n_2}{n_1+n_2})^2 \\ T_s = T_p - \dfrac{n_2}{n_1} \dfrac{4n_1^2}{(n_1+n_2)^2} = \dfrac{4n_1n_2}{(n_1+n_2)^2} \end{aligned}$$

Example: air/glass interface

$$n_1 = 1$$
 $n_2 = 1.5$ $r_s = r_p = -0.2$ $T_s = T_p = 0.8$ $R_s = R_p = 0.04$ $T_s = T_p = 0.96$

 \Rightarrow 4% of light is reflected, 96% is transmitted

[If n_2 , for example, = 1.75, $R_s=R_p=0.074$, which is sa problem]

Lets take another go at differnet angle

$$egin{aligned} ullet & heta_i=90^\circ, ext{ and set } eta>1 \ & \sin heta_i=1 & \cos heta_i=0 \ & heta o \infty \ & r_p=1 & r_s=-1 \ & t_p=0 & t_s=0 \end{aligned}$$

• now consider $\beta<1$, we cna have total interal reflection for $\theta_i>\theta_c$ where θ_c is the critical angle = $\beta=\frac{n_2}{n_1}$

At
$$heta_c = \sin^{-1}eta$$
, $lpha = rac{1}{\cos heta_c}\sqrt{1-(rac{\sin heta_c}{eta})^2} = 0$

Hence, we have

$$egin{array}{ll} r_p = -1 & r_s = 1 \ t_p = rac{2}{eta} & t_s = 2 \end{array}$$

$$\sin \theta_c = \beta$$

 r_p vanishes at the certain angle called "Brewster's angle" θ_B

$$r_p = rac{lpha - eta}{lpha + eta} = 0 ext{ when } lpha = eta = rac{n_2}{n_1} \ rac{1}{cos heta_B} \sqrt{1 - (rac{\sin heta_B}{eta})^2} = eta$$

square both sides:

$$egin{aligned} \sec^2 heta_B - rac{1}{eta^2} an^2 heta_B = eta^2 \ (1 - rac{1}{eta^2}) an^2 heta_B = eta^2 - 1 \ rac{(eta^2 - 1)}{eta^2} an^2 heta_B = (eta^2 - 1) \ \Rightarrow an heta_B = eta \end{aligned}$$