# Chapter 6 The Link Layer and LANs


#### A note on the use of these Powerpoint slides:

We're making these slides freely available to all (faculty, students, readers). They're in PowerPoint form so you see the animations; and can add, modify, and delete slides (including this one) and slide content to suit your needs. They obviously represent a *lot* of work on our part. In return for use, we only ask the following:

- If you use these slides (e.g., in a class) that you mention their source (after all, we'd like people to use our book!)
- If you post any slides on a www site, that you note that they are adapted from (or perhaps identical to) our slides, and note our copyright of this material.

Thanks and enjoy! JFK/KWR

© All material copyright 1996-2016 J.F Kurose and K.W. Ross, All Rights Reserved



## Computer Networking: A Top Down Approach

7<sup>th</sup> edition
Jim Kurose, Keith Ross
Pearson/Addison Wesley
April 2016


## Link Layer

## Link layer: introduction

#### terminology:

- hosts and routers: nodes
- communication channels that connect adjacent nodes along communication path: links
  - wired links
  - wireless links
  - LANs
- layer-2 packet: frame, encapsulates datagram

data-link layer has responsibility of transferring datagram from one node to physically adjacent node over a link



## Link layer: context

- datagram transferred by different link protocols over different links:
  - e.g., Ethernet on first link, frame relay on intermediate links, 802.11 on last link
- each link protocol provides different services
  - e.g., may or may not provide rdt over link

#### transportation analogy:

- trip from Princeton to Lausanne
  - limo: Princeton to JFK
  - plane: JFK to Geneva
  - train: Geneva to Lausanne
- tourist = datagram
- transport segment = communication link
- transportation mode = link layer protocol
- travel agent = routing algorithm

## Link layer services


- framing, link access:
  - encapsulate datagram into frame, adding header, trailer
  - channel access if shared medium
  - "MAC" addresses used in frame headers to identify source, destination
    - different from IP address!
- reliable delivery between adjacent nodes
  - we learned how to do this already (chapter 3)!
  - seldom used on low bit-error link (fiber, some twisted pair)
  - wireless links: high error rates
    - Q: why both link-level and end-end reliability?

## Link layer services (more)


- flow control:
  - pacing between adjacent sending and receiving nodes
- error detection:
  - errors caused by signal attenuation, noise.
  - receiver detects presence of errors:
    - signals sender for retransmission or drops frame
- error correction:
  - receiver identifies and corrects bit error(s) without resorting to retransmission
- half-duplex and full-duplex
  - with half duplex, nodes at both ends of link can transmit, but not at same time

#### Where is the link layer implemented?

- in each and every host
- link layer implemented in "adaptor" (aka network interface card NIC) or on a chip
  - Ethernet card, 802.11 card; Ethernet chipset
  - implements link, physical layer
- attaches into host's system buses
- combination of hardware, software, firmware



## Adaptors communicating



- sending side:
  - encapsulates datagram in frame
  - adds error checking bits, rdt, flow control, etc.


- receiving side
  - looks for errors, rdt, flow control, etc.
  - extracts datagram, passes to upper layer at receiving side

#### **Error Detection and Correction**

#### **Error detection**

EDC= Error Detection and Correction bits (redundancy)


- D = Data protected by error checking, may include header fields
- Error detection not 100% reliable!
  - protocol may miss some errors, but rarely
  - larger EDC field yields better detection and correction



## Parity checking

#### single bit parity:

detect single bit errors



#### two-dimensional bit parity:

detect and correct single bit errors

correctable single bit error

<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose\_ross/interactive/

## Internet checksum (review)

goal: detect "errors" (e.g., flipped bits) in transmitted packet (note: used at transport layer only)

#### sender:


- treat segment contents as sequence of 16-bit integers
- checksum: addition (I's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

#### receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - NO error detected
  - YES no error detected.
     But maybe errors nonetheless?

#### Cyclic redundancy check

- more powerful error-detection coding
- view data bits, D, as a binary number
- choose r+1 bit pattern (generator), G
- goal: choose r CRC bits, R, such that
  - <D,R> exactly divisible by G (modulo 2)
  - receiver knows G, divides <D,R> by G. If non-zero remainder: error detected!
  - can detect all burst errors less than r+1 bits
- widely used in practice (Ethernet, 802.11 WiFi, ATM)



#### CRC example

#### want:

 $D \cdot 2^r XOR R = nG$ 


equivalently:

 $D \cdot 2^r = nG XOR R$ 

#### equivalently:

if we divide D.2<sup>r</sup> by G, want remainder R to satisfy:

$$R = remainder[\frac{D \cdot 2^r}{G}]$$



<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose\_ross/interactive/

#### Media Access Protocols

#### Multiple access links, protocols

#### two types of "links":

- point-to-point
  - PPP for dial-up access
  - point-to-point link between Ethernet switch, host
- broadcast (shared wire or medium)
  - old-fashioned Ethernet
  - upstream HFC
  - 802.11 wireless LAN



shared wire (e.g., cabled Ethernet)



shared RF (e.g., 802.11 WiFi)



shared RF (satellite)



humans at a cocktail party (shared air, acoustical)

## Multiple access protocols

- single shared broadcast channel
- two or more simultaneous transmissions by nodes: interference
  - collision if node receives two or more signals at the same time

#### multiple access protocol

- distributed algorithm that determines how nodes share channel, i.e., determine when node can transmit
- communication about channel sharing must use channel itself!
  - no out-of-band channel for coordination

## An ideal multiple access protocol

given: broadcast channel of rate R bps desiderata:

- I. when one node wants to transmit, it can send at rate R.
- 2. when M nodes want to transmit, each can send at average rate R/M
- 3. fully decentralized:
  - no special node to coordinate transmissions
  - no synchronization of clocks, slots
- 4. simple

## MAC protocols: taxonomy


#### three broad classes:

- channel partitioning
  - divide channel into smaller "pieces" (time slots, frequency, code)
  - allocate piece to node for exclusive use
- random access
  - channel not divided, allow collisions
  - "recover" from collisions
- "taking turns"
  - nodes take turns, but nodes with more to send can take longer turns

#### Channel partitioning MAC protocols: TDMA

#### TDMA: time division multiple access


- access to channel in "rounds"
- each station gets fixed length slot (length = packet transmission time) in each round
- unused slots go idle
- example: 6-station LAN, 1,3,4 have packets to send, slots 2,5,6 idle



#### Channel partitioning MAC protocols: FDMA

#### FDMA: frequency division multiple access

- channel spectrum divided into frequency bands
- each station assigned fixed frequency band
- unused transmission time in frequency bands go idle
- example: 6-station LAN, 1,3,4 have packet to send, frequency bands 2,5,6 idle



## Random access protocols

- when node has packet to send
  - transmit at full channel data rate R.
  - no a priori coordination among nodes
- two or more transmitting nodes → "collision",
- random access MAC protocol specifies:
  - how to detect collisions
  - how to recover from collisions (e.g., via delayed retransmissions)
- examples of random access MAC protocols:
  - slotted ALOHA
  - ALOHA
  - CSMA, CSMA/CD, CSMA/CA

## **ALOHA**

#### Slotted ALOHA


#### assumptions:

- all frames same size
- time divided into equal size slots (time to transmit I frame)
- nodes start to transmit only slot beginning
- nodes are synchronized
- if 2 or more nodes transmit in slot, all nodes detect collision

#### operation:

- when node obtains fresh frame, transmits in next slot
  - if no collision: node can send new frame in next slot
  - if collision: node retransmits frame in each subsequent slot with prob. p until success

#### Slotted ALOHA



#### **Pros:**

- single active node can continuously transmit at full rate of channel
- highly decentralized: only slots in nodes need to be in sync
- simple

#### Cons:

- collisions, wasting slots
- idle slots
- nodes may be able to detect collision in less than time to transmit packet
- clock synchronization

## Slotted ALOHA: efficiency

efficiency: long-run fraction of successful slots (many nodes, all with many frames to send)

- suppose: N nodes with many frames to send, each transmits in slot with probability p
- prob that given node has success in a slot =  $p(1-p)^{N-1}$
- prob that any node has a success =  $Np(1-p)^{N-1}$

- max efficiency: find p\* that maximizes
   Np(1-p)<sup>N-1</sup>
- for many nodes, take limit of  $Np*(I-p*)^{N-I}$  as N goes to infinity, gives:


max efficiency = 1/e = .37

at best: channel used for useful transmissions 37% of time!



## Pure (unslotted) ALOHA

- unslotted Aloha: simpler, no synchronization
- when frame first arrives
  - transmit immediately
- collision probability increases:
  - frame sent at  $t_0$  collides with other frames sent in  $\begin{bmatrix} t_0 1, t_0 + 1 \end{bmatrix}$



## Pure ALOHA efficiency

P(success by given node) = P(node transmits) ·

P(no other node transmits in  $[t_0-I,t_0]$  · P(no other node transmits in  $[t_0-I,t_0]$ 

$$= p \cdot (1-p)^{N-1} \cdot (1-p)^{N-1}$$
$$= p \cdot (1-p)^{2(N-1)}$$

... choosing optimum p and then letting  $n \longrightarrow \infty$ 

$$= 1/(2e) = .18$$

even worse than slotted Aloha!

## **CSMA**

#### CSMA (carrier sense multiple access)

**CSMA:** listen before transmit:

if channel sensed idle: transmit entire frame

 if channel sensed busy, defer transmission

human analogy: don't interrupt others!

#### **CSMA** collisions

- collisions can still occur: propagation delay means two nodes may not hear each other's transmission
- collision: entire packet transmission time wasted
  - distance & propagation delay play role in in determining collision probability






t<sub>1</sub>

## CSMA/CD (collision detection)

#### CSMA/CD: carrier sensing, deferral as in CSMA

- collisions detected within short time
- colliding transmissions aborted, reducing channel wastage
- collision detection:
  - easy in wired LANs: measure signal strengths, compare transmitted, received signals
  - difficult in wireless LANs: received signal strength overwhelmed by local transmission strength
- human analogy: the polite conversationalist

## CSMA/CD (collision detection)



## Ethernet CSMA/CD algorithm

- I. NIC receives datagram from network layer, creates frame
- 2. If NIC senses channel idle, starts frame transmission. If NIC senses channel busy, waits until channel idle, then transmits.
- 3. If NIC transmits entire frame without detecting another transmission, NIC is done with frame!

- 4. If NIC detects another transmission while transmitting, aborts and sends jam signal
- 5. After aborting, NIC enters binary (exponential) backoff:
  - after mth collision, NIC chooses K at random from {0,1,2,..., 2<sup>m</sup>-1}.
     NIC waits K:512 bit times, returns to Step 2
  - longer backoff interval with more collisions

## CSMA/CD efficiency

- T<sub>prop</sub> = max prop delay between 2 nodes in LAN
- t<sub>trans</sub> = time to transmit max-size frame

$$efficiency = \frac{1}{1 + 5t_{prop}/t_{trans}}$$

- efficiency goes to I
  - as  $t_{prop}$  goes to 0
  - as t<sub>trans</sub> goes to infinity
- better performance than ALOHA: and simple, cheap, decentralized!

## Token Passing

# "Taking turns" MAC protocols

#### channel partitioning MAC protocols:

- share channel efficiently and fairly at high load
- inefficient at low load: delay in channel access, I/N bandwidth allocated even if only I active node!

#### random access MAC protocols

- efficient at low load: single node can fully utilize channel
- high load: collision overhead


#### "taking turns" protocols

look for best of both worlds!

# "Taking turns" MAC protocols

#### polling:


- master node "invites" slave nodes to transmit in turn
- typically used with "dumb" slave devices
- concerns:
  - polling overhead
  - latency
  - single point of failure (master)




# "Taking turns" MAC protocols

#### token passing:

- control token passed from one node to next sequentially.
- token message
- concerns:
  - token overhead
  - latency
  - single point of failure (token)




#### Cable access network



- multiple 40Mbps downstream (broadcast) channels
  - single CMTS transmits into channels
- multiple 30 Mbps upstream channels
  - multiple access: all users contend for certain upstream channel time slots (others assigned)

#### Cable access network



#### DOCSIS: data over cable service interface spec

- FDM over upstream, downstream frequency channels
- TDM upstream: some slots assigned, some have contention
  - downstream MAP frame: assigns upstream slots
  - request for upstream slots (and data) transmitted random access (binary backoff) in selected slots

# Summary of MAC protocols

- channel partitioning, by time, frequency or code
  - Time Division, Frequency Division
- random access (dynamic),
  - ALOHA, S-ALOHA, CSMA, CSMA/CD
  - carrier sensing: easy in some technologies (wire), hard in others (wireless)
  - CSMA/CD used in Ethernet
  - CSMA/CA used in 802.11
- taking turns
  - polling from central site, token passing
  - Bluetooth, FDDI, token ring

## MAC and ARP


### MAC addresses and ARP

- 32-bit IP address:
  - network-layer address for interface
  - used for layer 3 (network layer) forwarding
- MAC (or LAN or physical or Ethernet) address:
  - function: used 'locally" to get frame from one interface to another physically-connected interface (same network, in IP-addressing sense)
  - 48 bit MAC address (for most LANs) burned in NIC ROM, also sometimes software settable
  - e.g.: IA-2F-BB-76-09-AD

hexadecimal (base 16) notation (each "numeral" represents 4 bits)

## LAN addresses and ARP

each adapter on LAN has unique LAN address




# LAN addresses (more)

- MAC address allocation administered by IEEE
- manufacturer buys portion of MAC address space (to assure uniqueness)
- analogy:
  - MAC address: like Social Security Number
  - IP address: like postal address
- MAC flat address → portability
  - can move LAN card from one LAN to another
- IP hierarchical address not portable
  - address depends on IP subnet to which node is attached

## ARP: address resolution protocol

Question: how to determine interface's MAC address, knowing its IP address?



ARP table: each IP node (host, router) on LAN has table

- IP/MAC address mappings for some LAN nodes:
  - < IP address; MAC address; TTL>
- TTL (Time To Live): time after which address mapping will be forgotten (typically 20 min)


## ARP protocol: same LAN

- A wants to send datagram to B
  - B's MAC address not in A's ARP table.
- A broadcasts ARP query packet, containing B's IP address
  - destination MAC address = FF-FF-FF-FF-FF
  - all nodes on LAN receive ARP query
- B receives ARP packet, replies to A with its (B's) MAC address
  - frame sent to A's MAC address (unicast)


- A caches (saves) IP-to-MAC address pair in its ARP table until information becomes old (times out)
  - soft state: information that times out (goes away) unless refreshed
- ARP is "plug-and-play":
  - nodes create their ARP tables without intervention from net administrator

#### walkthrough: send datagram from A to B via R


- focus on addressing at IP (datagram) and MAC layer (frame)
- assume A knows B's IP address
- assume A knows IP address of first hop router, R (how?)
- assume A knows R's MAC address (how?)




- A creates IP datagram with IP source A, destination B
- A creates link-layer frame with R's MAC address as destination address, frame contains A-to-B IP datagram




- frame sent from A to R
- frame received at R, datagram removed, passed up to IP




- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as destination address, frame contains A-to-B IP datagram



- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as destination address, frame contains A-to-B IP datagram



- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as dest, frame contains A-to-B IP datagram




<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose ross/interactive/

## **Ethernet**

# Ethernet


- "dominant" wired LAN technology:
- single chip, multiple speeds (e.g., Broadcom BCM5761)
- first widely used LAN technology
- simpler, cheap
- kept up with speed race: 10 Mbps 10 Gbps



Metcalfe's Ethernet sketch

## Ethernet: physical topology

- bus: popular through mid 90s
  - all nodes in same collision domain (can collide with each other)
- star: prevails today
  - active switch in center
  - each "spoke" runs a (separate) Ethernet protocol (nodes do not collide with each other)



### Ethernet frame structure

sending adapter encapsulates IP datagram (or other network layer protocol packet) in Ethernet frame type

preamble	dest. address	source address	·	data (payload)	CRC
----------	------------------	-------------------	---	-------------------	-----

#### preamble:

- 7 bytes with pattern 10101010 followed by one byte with pattern 10101011
- used to synchronize receiver, sender clock rates

### Ethernet frame structure (more)

- addresses: 6 byte source, destination MAC addresses
  - if adapter receives frame with matching destination address, or with broadcast address (e.g. ARP packet), it passes data in frame to network layer protocol
  - otherwise, adapter discards frame
- type: indicates higher layer protocol (mostly IP but others possible, e.g., Novell IPX, AppleTalk)
- CRC: cyclic redundancy check at receiver
  - error detected: frame is dropped




#### Ethernet: unreliable, connectionless


- connectionless: no handshaking between sending and receiving NICs
- unreliable: receiving NIC doesn't send acks or nacks to sending NIC
  - data in dropped frames recovered only if initial sender uses higher layer rdt (e.g., TCP), otherwise dropped data lost
- Ethernet's MAC protocol: unslotted CSMA/CD with binary backoff


#### 802.3 Ethernet standards: link & physical layers


- many different Ethernet standards
  - common MAC protocol and frame format
  - different speeds: 2 Mbps, 10 Mbps, 100 Mbps, 1Gbps, 10 Gbps, 40 Gbps
  - different physical layer media: fiber, cable

















#### Characteristics of selected wireless links







#### ad hoc mode

- no base stations
- nodes can only transmit to other nodes within link coverage
- nodes organize themselves into a network: route among themselves

## Wireless network taxonomy

	single hop	multiple hops
infrastructure (e.g., APs)	host connects to base station (WiFi, WiMAX, cellular) which connects to larger Internet	host may have to relay through several wireless nodes to connect to larger Internet: mesh net
no infrastructure	no base station, no connection to larger Internet (Bluetooth, ad hoc nets)	no base station, no connection to larger Internet. May have to relay to reach other a given wireless node MANET,VANET

### IEEE 802.11 Wireless LAN

#### 802.11b

- 2.4-5 GHz unlicensed spectrum
- up to 11 Mbps
- direct sequence spread spectrum (DSSS) in physical layer
  - all hosts use same chipping code

#### 802.11a

- 5-6 GHz range
- up to 54 Mbps

#### 802.11g


- 2.4-5 GHz range
- up to 54 Mbps

#### 802. I In: multiple antennae

- 2.4-5 GHz range
- up to 200 Mbps

- all use CSMA/CA for multiple access
- all have base-station and ad-hoc network versions

#### 802.11 LAN architecture




BSS 2


- wireless host communicates with base station
  - base station = access point (AP)
- Basic Service Set (BSS) (aka "cell") in infrastructure mode contains:
  - wireless hosts
  - access point (AP): base station
  - ad hoc mode: hosts only

## 802.11: Channels, association

- 802.11b: 2.4GHz-2.485GHz spectrum divided into 11 channels at different frequencies
  - AP admin chooses frequency for AP
  - interference possible: channel can be same as that chosen by neighboring AP!
- host: must associate with an AP
  - scans channels, listening for beacon frames containing AP's name (SSID) and MAC address
  - selects AP to associate with
  - may perform authentication [Chapter 8]
  - will typically run DHCP to get IP address in AP's subnet

# 802.11: passive/active scanning





#### passive scanning:


- (I) beacon frames sent from APs
- (2) association Request frame sent: H1 to selected AP
- (3) association Response frame sent from selected AP to HI


#### active scanning:

- (1) Probe Request frame broadcast from H1
- (2) Probe Response frames sent from APs
- (3) Association Request frame sent: H1 to selected AP
- (4) Association Response frame sent from selected AP to H1

## IEEE 802.11: multiple access

- avoid collisions: 2<sup>+</sup> nodes transmitting at same time
- 802.11: CSMA sense before transmitting
  - don't collide with ongoing transmission by other node
- 802.11: no collision detection!
  - difficult to receive (sense collisions) when transmitting due to weak received signals (fading)
  - can't sense all collisions in any case: hidden terminal, fading
  - goal: avoid collisions: CSMA/C(ollision)A(voidance)





#### IEEE 802.11 MAC Protocol: CSMA/CA

#### 802.11 sender

1 if sense channel idle for **DIFS** then transmit entire frame (no CD)

2 if sense channel busy then


start random backoff time
timer counts down while channel idle
transmit when timer expires
if no ACK, increase random backoff interval,

802.11 receiver

- if frame received OK

repeat 2

return ACK after **SIFS** (ACK needed due to hidden terminal problem)



## Avoiding collisions (more)

idea: allow sender to "reserve" channel rather than random access of data frames: avoid collisions of long data frames

- sender first transmits small request-to-send (RTS) packets to BS using CSMA
  - RTSs may still collide with each other (but they' re short)
- BS broadcasts clear-to-send CTS in response to RTS
- CTS heard by all nodes
  - sender transmits data frame
  - other stations defer transmissions

avoid data frame collisions completely using small reservation packets!