White Box Testing fits() Example

Software Testing and Quality Assurance Joseph Timoney

Source code for fits()

```
Status fits(int passengers, boolean comfortFlag)
          Status rv = FAILURE;
           int availableSeats = 120;
           if (comfortFlag)
         if (comfortFlag)
availableSeats = availableSeats - 40;
if ( (passengers>0) && (passengers<=availableSeats))
rv = SUCCESS;
else if (passengers<=0)
rv = ERROR;</pre>
          return rv;
11
```

Example- fits()

- · Specification:
- A plane has 120 seats. A flight can accommodate up to that number of passengers. If the passengers require extra comfort, the effective number of seats is reduced by 40 to ensure that every passenger has an empty seat next to them. The method fits() indicates whether a particular number of passengers can be accommodated with or without extra comfort.

CFG for fits() Node 1: Lines 1–5 • Node 2: Line 6 • Node 3: Line 7 Node 4: Line 8 Node 5: Line 9 Node 6: Line 10 Node 7: Line 11-12

Fits() specification

- Status fits(int passengers, boolean comfortFlag)
- **Inputs**

 - passengers: the number of passengers to be carried
 comfortFlag: flag to indicate whether extra comfort is required
- Outputs
- return value:
 - SUCCESS if passengers≤120 and !comfortFlag
 - SUCCESS if passengers ≤ 80 and comfortFlag
 - FAILURE if passengers>120, or if passengers>80 and comfortFlag
 - ERROR if any inputs are invalid (e.g. passengers<1)
- · Status is defined as follows:
 - enum Status { SUCCESS, FAILURE, ERROR };

Test Cases for Statement Coverage for fits()

Test Case	Node	Test
SC1	1	T5.1
SC2	2	T5.2
SC3	3	T5.1
SC4	4	T5.1
SC5	5	T5.2
SC6	6	T5.2
SC7	7	T5.1

Test Data for Statement Coverage for fits()

	ID	Test	Inputs		Exp. Output	
	ш	Cases Covered	passengers	comfortFlag	return value	
	T5.1	SC1,3,4,7	40	false	SUCCESS	
	T5.2	SC[1],2,[3],5,6,[7]	-100	true	ERROR	

Path Coverage

Six paths can be identified in the CFG for fits()

- Node 1-2-3-4-7
- Node 1–3–4–7
- $\bullet \ \ {\rm Node} \ 1\text{--}2\text{--}3\text{--}5\text{--}7$
- Node 1-3-5-7
- Node 1-2-3-5-6-7
- Node 1–3–5–6–7

Test Cases for Branch Coverage for fits()

Test Case	Edge	Test
BCa	a	T6.2
BCb	b	T6.1
BCc	c	T6.2
BCd	d	T6.2
BCe	e	T6.2
BCf	f	T6.1
BCg	g	T6.3
BCh	h	T6.2
BCi	i	T6.2

Test Cases for Path Coverage for fits()

Test Case	Nodes	Test
P1	1,2,3,4,7	T11.1
P2	1,3,4,7	T11.2
P3	1,2,3,5,7	T11.3
P4	1,3,5,7	T11.4
P5	1,2,3,5,6,7	T11.5
P6	1,3,5,6,7	T11.6

Test Data for Branch Coverage for fits()

ID	Test	Inputs		Exp. Output	
110	Cases Covered	passengers	comfortFlag	return value	
T6.1	BCb,d,f	40	false	SUCCESS	
T6.2	BCa,c,e,h,i	-100	true	ERROR	
T6.3	BC [b,e] g	200	false	FAILURE	

Test Data for Path Coverage for fits()

ID	Test Cases Covered	In	puts	Exp. Output
110		passengers	comfortFlag	return value
T11.1	P1	40	true	SUCCESS
T11.2	P2	40	false	SUCCESS
T11.3	P3	101	true	FAILURE
T11.4	P4	200	false	FAILURE
T11.5	P5	-100	true	ERROR
T11.6	P6	-100	false	ERROR

Definitions and uses in fits()

Variable	Definitions	Uses
passengers	1	7,9
comfortFlag	1	5
rv	3,8,10	11
availableSeats	4,6	6,7

Test Data for DU-pair testing for fits()

ID	Test	Inputs		Exp. Output	
110	Cases Covered	passengers	comfortFlag	return value	
	DUP1,3,5,8	40	false	SUCCESS	
T12.2	DUP [1] 2 [3] 4,7,9	101	true	FAILURE	
T12.3	DUP [1,2,3] 6 [8]	-100	false	ERROR	

DU-pairs

D	U
1	7
1	9



comfortFlag



Passengers



availableSeats

Final Test Data after elimination of duplicate tests

ID	Test	Inputs	Exp. Outp	
	Cases Covered	passengers	comfortFlag	return value
T1.1	EP2,5,7, TT4	40	false	SUCCESS
T1.2	EP3,6,8	100	true	FAILURE
T1.3	EP4 [5,8], TT1	200	false	FAILURE
T1.4	EP1*,9*	-100	false	ERROR
T2.1	BV3,9.11	1	false	SUCCESS
T2.2	BV4,10 [11]	80	true	SUCCESS
T2.3	BV5 [9.11]	81	false	SUCCESS
T2.4	BV6 [10] 12	120	true	FAILURE
T2.5	BV7 [10,12]	121	true	FAILURE
T2.6	BV8 [10,12]	Integer.MAX_VALUE	true	FAILURE
T2.7	BV1*,13*	Integer MIN_VALUE	false	ERROR
T2.8	BV2* [13*]	0	false	ERROR
T3.2	TT2	100	false	SUCCESS
T3.3	TT3	100	true	FAILURE
T4.1		16	false	SUCCESS
T4.2		46	true	SUCCESS
T4.3		-1974596984	true	ERROR
T4.4		-122368221	false	ERROR
T4.5		10	true	SUCCESS
T4.7		112	false	SUCCESS
T4.8		1950430522	true	FAILURE
T4.9		74	false	SUCCESS
T4.10		-1942749054	true	ERROR
T5.2	SC[1] 2 [3] 5,6 [7]	-100	true	ERROR
T8.1	DOCL3.5	40	true	SUCCESS

Test Cases for DU-pair testing for fits()

Test Case	Variable	D	U	Test		
DUP1	passengers	- 1	-7	T12.1		
DUP2	passengers	1	9	T12.2		
DUP3	comfortFlag	1	5	T12.1		
DUP4	rv	3	11	T12.2		
DUP5	rv	- 8	11	T12.1		
DUP6	rv	10	11	T12.3		
DUP7	availableSeats	4	6	T12.2		
DUP8	availableSeats	4	7	T12.1		
DUP9	availableSeats	6	7	T12.2		
1 Status fits(int passengers, boolean comfortFlag) 2 {						