QQDeBreathTool

Standalone 1.12 Stable · Illustrated user guide

Find the breaths. Decide how much to keep.



Figure 1 · Actual 1.12 interface; generated audio and manually placed regions.

Import > Analyze > Edit > Listen > Export

About this guide

For the Windows x64, Apple Silicon and Intel Mac standalone app. Work in its own window and export three aligned WAV stems. ARA, VST3, AU and DAW scanning are not involved.

Reading map

Installation 02 / Import and analyze 03 / Edit regions 04 / Monitor and display 05 / Fades and breath level 06 / Undo and session restore 07 / Export and troubleshooting 08.

About the illustrations

Screenshots render the actual 1.12 interface offscreen with generated audio and manually placed regions; they are not detection-accuracy evidence. The example uses -6 dB Breath Gain; the default is 0 dB.

02 / Install and upgrade

Keep the complete app together, with original audio and settings intact.

Windows x64 | Apple Silicon | Intel Mac

Windows: extract and run

Choose Windows-x64. Quit the old app and keep an old copy, then extract the complete QQDeBreathTool folder. Run QQDeBreathTool.exe. The _internal directory is required; do not copy the EXE alone or mix old and new runtime files. Python is not needed. Intended for Windows 10/11 x64.

Mac: choose the matching chip

Choose Apple-Silicon for M-series chips, or Intel for Intel Macs. Extract with Archive Utility and copy QQDeBreathTool.app to Applications, replacing the old app. Do not unpack on Windows first: symbolic links or executable permissions may be lost. See the release and installation guide for the verified minimum macOS version.

First launch on Mac

Mac builds are ad-hoc signed, without Developer ID notarization. After verifying the official source, use right-click Open or Privacy & Security if needed. The installation guide gives an app-specific quarantine remedy when that is the cause.

Official downloads

github.com/Ziqing-Gu/QQDeBreathTool/releases/tag/v1.12. Download the runnable package for your platform. Complete-Source.zip and GitHub Source code downloads are source, not apps.

03 / Import and analyze

Automatic analysis finds Breath. Mark Noise manually.




Figure 3 · Actual 1.12 interface; generated audio and manually placed regions.

1. Open a vocal recording

Click 打开/拖入音频 (Open / Drop Audio), or drag a file into the window. WAV, AIF/AIFF, FLAC, OGG and MP3 are offered; decoding depends on the file encoding. Check the sample rate, channel count and duration at the bottom. Convert unsupported material to PCM WAV if needed.

2. Click 分析 (Analyze)

Analysis covers the entire loaded file; zooming the waveform does not restrict its range. Wait for the progress window to finish before editing. This interface has no analysis-cancel button or adjustable detection-threshold control.

3. Review the blue regions

Blue marks Breath and amber marks Noise. Unmarked audio belongs to Vocal Only. Automatic results identify Breath only; consonants and breathy word tails may need correction. Audition before deciding what to remove.

Reanalysis and speed

Analyzing again replaces the current regions; Undo can restore them within the current session. Version 1.12 reduces repeated computation and exact-zero window work, but gains vary. Some Windows recordings improved from about 25-43 seconds to 5-9 seconds; those figures are not Mac benchmarks.

04 / Correct the regions

Zoom in and preserve the start and end of each word.




Figure 4 · Actual 1.12 interface; generated audio and manually placed regions.

Left: start | Middle: move | Right: end

Select and adjust

Click a region to select it. Drag its left or right edge to change the boundary; drag the middle to move the whole region. A white border shows selection. Double-click or right-click the region timecode at the bottom to copy it for review notes.

Create, reclassify and delete

Choose Breath or Noise in 类型 (Type), then Shift-drag to draw a region. With a region selected, B assigns Breath and N assigns Noise; right-click toggles the two types. Delete or 删除区块 removes the marking, returning that audio to Vocal Only. It does not cut samples from the original file.

Zoom and navigate

Use the wheel to zoom around the pointer. Shift-wheel pans horizontally; the bottom scrollbar also moves the view. 全览 (Fit) shows the full file. Left-clicking the waveform also sets the playhead. Zoom into a breath before editing its edges.

05 / Monitor and display

Listening selection, display scale and exported processing have different roles.




Figure 5 · Actual 1.12 interface; generated audio and manually placed regions.



Solo first, then combine

Combine Voice, Breath and Noise freely under Monitor. Listen to Breath alone to catch words inside the regions, then Voice alone to check word edges, then the combined result. The checkboxes also control which stem waveforms are displayed. Unchecking all three produces silence.

Playback, follow and return

Click 播放 (Play) or press Space to toggle playback; 停止 (Stop) ends it. 跟随 (Follow) scrolls the view with playback. 回起点 (Return to start) returns to the playback start when stopping or reaching the end, according to the app transport behavior.

Two easy-to-confuse controls

显示 (Display), 0.1-64x, changes only waveform height. 监听 (Monitor Gain), -20 to +20 dB, affects listening volume only, not exported files. Monitor checkboxes do not select which stems are exported: Export Three Stems always writes all three.

06 / Fades and breath level

These controls shape monitoring and exported stems.



Figure 6 · Actual 1.12 interface; generated audio and manually placed regions.

Fade > Peak normalize > Breath Gain

Fade: smooth the boundaries

When Fade is enabled, In and Out set global fade-in and fade-out times: 0-500 ms each, default 10 ms each. They are not per-selected-region settings. Adjacent regions share a crossfade. Start with short fades and listen for affected word edges.

Normalize Breath: per-region peaks

呼吸标准化 (Normalize Breath) scales each Breath region to the 目标 (Target) peak level. Target ranges from -60 to 0 dB, default -6 dB. This is peak normalization, not LUFS matching, compression or noise reduction.

Breath Gain: set the overall breath level

呼吸音量 (Breath Gain) ranges from -30 to +30 dB, default 0 dB. When normalization is on, gain follows normalization. Lower it to retain the breathing rhythm more subtly. A high target plus positive gain can clip; monitor the meter and listen.

Editing numeric values

Drag numeric values up or down; Shift-drag provides fine adjustment, Alt-click resets the default, and double-click opens numeric entry. The pictured -6 dB is a demonstration setting. Fades, normalization, target and Breath Gain affect export; Monitor Gain does not.

07 / Undo and session restore

Restoring edits is different from restoring the undo history.




Figure 7 · Actual 1.12 interface; generated audio and manually placed regions.

Current regions > Undo / Redo > Close: history clears

What Undo / Redo covers

The standalone app keeps up to 100 region-edit steps: analysis, creation, movement, boundary changes, type changes and deletion. Use the Undo / Redo buttons, or Ctrl+Z / Ctrl+Shift+Z on Windows. On Mac, the buttons are always the clearest route; key mapping follows platform behavior.

Parameters are outside region undo

Fades, normalization, target, Breath Gain, monitor checkboxes and Monitor Gain are outside this region history. Undo does not restore those values; use numeric entry or Alt-click reset as appropriate.

What returns after reopening


The app remembers the last audio path, its edited regions and common processing/monitor settings. The original file must remain at that path. Relaunching restores the last regions automatically; manually opening or switching files clears the current regions. All these actions clear Undo / Redo. Separate per-file histories are not retained.

A practical finish

When satisfied, export into a fresh folder and keep the original recording. Before reanalyzing, confirm whether you still need the current edits or be ready to Undo in the same session. Export before renaming or moving the source file.

08 / Export and troubleshoot

All three stems retain their original timeline positions.



Export Three Stems

Click the green 导出三轨 (Export Three Stems) button and select a folder. Vocal.wav produces Vocal_Vocal Only.wav, Vocal_Breath.wav and Vocal_Noise.wav. Each retains the full duration, sample rate and channel count for alignment at the same start point. Fades and breath processing are rendered into the result, so summing the processed stems may differ from the original.

Avoid overwrites and common issues

Exporting the same source to the same folder writes the same filenames again. Use a new folder for alternate versions. No sound: check Monitor selection, Monitor Gain and system output. Wrong detection: adjust boundaries, change the type or delete the marking and audition again. Missing runtime/model: extract the complete app package again.

What was verified for 1.12

Windows detection regions matched 1.11 on eight original recordings. Synthetic cases, floating-point restoration, offscreen GUI analysis/Undo/Redo and packaged EXE analysis passed. Mac build and automated-check results are in the release. These are not claims of real Mac desktop listening acceptance.

License, feedback and credits

Gu Ziqing / Qing Audio. Qing Audio Non-Commercial Source-Share License 1.0 applies: NO COMMERCIAL USE. Distribution requires complete corresponding source at no charge, attribution and notices, stated origin/changes and the same license. Third-party licenses remain applicable. For feedback, include version 1.12, OS/chip, reproduction steps and a short shareable sample. QQ group: 692973169.