Fields and Waves I

Lecture 25

Review

James D. Rees

Electrical, Computer, and Systems Engineering Department Rensselaer Polytechnic Institute, Troy, NY

Announcements

- End-of-Semester Survey
- Final Office Hours
- Free-Form Exam 3 Reworks

Review

Reflection Coefficient

$$\Gamma_{\perp} = \frac{E_{m1}^{-}}{E_{m1}^{+}} = \frac{\eta_2 \cos \theta_1 - \eta_1 \cos \theta_2}{\eta_2 \cos \theta_1 + \eta_1 \cos \theta_2}$$

$$1 + \Gamma_{\perp} = \tau_{\perp}$$

$$\Gamma_{\parallel} = \frac{\boldsymbol{\eta}_2 \, \cos \boldsymbol{\theta}_2 - \boldsymbol{\eta}_1 \, \cos \boldsymbol{\theta}_1}{\boldsymbol{\eta}_2 \, \cos \boldsymbol{\theta}_2 + \boldsymbol{\eta}_1 \, \cos \boldsymbol{\theta}_1}$$

$$1 + \Gamma_{||} = \tau_{||} \frac{\cos \theta_2}{\cos \theta_1}$$

Widget showing angular dependence of reflection coefficient

Critical Angle


$$K_1 \sin \Theta_c = K_2 \sin \Theta_2$$

 $\sin \Theta_2 = \sin 90^\circ = 1$
 $K_1 \sin \Theta_c = K_2$
 $\sin \Theta_c = \frac{K_2}{K_1}$

$$\sin \theta_c = \sqrt{\frac{\varepsilon_2}{\varepsilon_1}}$$

(Note that when $\varepsilon_2 > \varepsilon_1$, this will not have a real-valued answer.)


Note that the reflection varies with angle. Perpendicular reflects more than Parallel. There is also an angle for which there is no reflection for parallel polarization.



Fields and Waves I

Ulaby

Brewster's Angle



- At the Brewster's Angle or polarizing angle, the reflection coefficient is 0 for one polarization of light.
- This means that only polarized light is reflected.

Brewster's Angle

$$\Gamma_{\parallel} = \frac{\eta_2 \cos \theta_2 - \eta_1 \cos \theta_1}{\eta_2 \cos \theta_2 + \eta_1 \cos \theta_1}$$
 Set this equal to zero:

$$\eta_2 \cos \theta_i = \eta_1 \cos \theta_t.$$

... to derive this. Looks like Snell's law but with cosines instead of sines.

By once again combining the two equations, we get:

$$\sin \theta_{\mathrm{B}\parallel} = \sqrt{\frac{1 - (\epsilon_1 \mu_2 / \epsilon_2 \mu_1)}{1 - (\epsilon_1 / \epsilon_2)^2}} \ .$$

Note that there will be no Brewster angle if the permittivities are the same.

Brewster's Angle

Wikimedia Commons

When the permeabilities of the two materials are the same, this becomes

$$\theta_{\mathrm{B}\parallel} = \sin^{-1} \sqrt{\frac{1}{1 + (\epsilon_1/\epsilon_2)}}$$

$$= \tan^{-1} \sqrt{\frac{\epsilon_2}{\epsilon_1}} \qquad (\text{for } \mu_1 = \mu_2).$$

Brewster's Angle

The Brewster's angle is why glare from the surface of water can be easily blocked with sunglasses.



Wikipedia

Brewster Angle

$$n_1 \sin \theta_1 = n_2 \sin \theta_2$$

$$\eta_2 \cos \theta_i = \eta_1 \cos \theta_t.$$

$$\Gamma_{\perp} = \frac{E_{m1}^{-}}{E_{m1}^{+}} = \frac{\eta_2 \cos \theta_1 - \eta_1 \cos \theta_2}{\eta_2 \cos \theta_1 + \eta_1 \cos \theta_2}$$

Combining these two equations and setting the incident angle to be the Brewster angle, we get:

$$\sin \theta_{\rm B\perp} = \sqrt{\frac{1 - (\mu_1 \epsilon_2 / \mu_2 \epsilon_1)}{1 - (\mu_1 / \mu_2)^2}} \ .$$

(Ulaby pg. 375)

Brewster Angle

$$\sin \theta_{\rm B\perp} = \sqrt{\frac{1 - (\mu_1 \epsilon_2 / \mu_2 \epsilon_1)}{1 - (\mu_1 / \mu_2)^2}} \ .$$


Note that this is undefined when the permeabilities of the two materials are the same. But when they are different, some Brewster angle will exist.

T-Line Equations


What is the equivalent circuit of a transmission line (both the lossless and the lossy version)?

T-Line Equations

Lossless




Lossy



T-Line Equations

What parameters must be set to what values in order to turn this lossy t-line into a lossless t-line?



T-Line Equations


When can we approximate a lumped circuit model as being an accurate representation of a real transmission line?

T-Line Equations

- When can we approximate a lumped circuit model as being an accurate representation of a real transmission line?
- The model is accurate when the length that each lumped segment represents is much less than the wavelength of the signal on the line.

T-Line Equations

What parameters must be set to what values in order to turn this lossy t-line into a lossless t-line?



G = 0 (no series admittance) (note that we are setting this admittance of this to zero, NOT resistance, which would short our t-line!)

Transmission Lines

What are the telegrapher's equations, or transmission line equations?

T-Line Equations

$$v(z) = V + e^{-\gamma z} + V - e^{+\gamma z} \qquad v(z) = V + e^{-\gamma z} + V - e^{+\gamma z}$$

$$i(z) = I + e^{-\gamma z} + I - e^{+\gamma z} \qquad i(z) = \frac{V + e^{-\gamma z}}{Z_o} - \frac{V - e^{+\gamma z}}{Z_o} = V + V - e^{+\gamma z}$$

$$v(z) = V + \left(e^{-\gamma z} + \Gamma_L e^{+\gamma z}\right)$$

$$i(z) = \frac{V + e^{-\gamma z}}{Z_o} - \frac{V - e^{+\gamma z}}{Z_o} = V + \frac{V - e^$$

These equations represent the lossy case. The lossless case is a special sub-case of the lossy case. How could we derive the lossless equations from these lossy equations?

T-Line Equations

$$v(z) = V + e^{-j\beta z} + \Gamma_L V + e^{+j\beta z}$$

$$i(z) = \frac{V^{+}}{Z_{o}} e^{-j\beta z} - \frac{\Gamma_{L}V^{+}}{Z_{o}} e^{+j\beta z}$$

Lossless equations emerge when we set $\alpha=0$.

Reflection Coefficient for T-Lines

In plain English, what does the reflection coefficient represent?

Reflection Coefficient for T-Lines

In plain English, what does the reflection coefficient represent?

When a wave hits an interface that causes it to reflect, the reflection coefficient tells us the amplitude ratio between the incident forward-traveling wave and the reflected backward-traveling wave.

Reflection Coefficient for T-Lines

What does it mean when the reflection coefficient has a negative value?


What does it mean when the reflection coefficient has a complex value?

Reflection Coefficient for T-Lines

$$\Gamma = |\Gamma| e^{j\theta_r} = \Gamma_r + j\Gamma_i \qquad \Gamma_r = |\Gamma| \cos \theta_r$$

$$\Gamma_i = |\Gamma| \sin \theta_r$$

A negative Γ would mean that at the point of reflection, the reflected wave is 180 degrees out of phase with the incident wave.



Reflection Coefficient for T-Lines

$$\Gamma = |\Gamma| e^{j\theta_r} = \Gamma_r + j\Gamma_i \qquad \Gamma_r = |\Gamma| \cos \theta_r$$

$$\Gamma_i = |\Gamma| \sin \theta_r$$

A complex Γ would mean that at the point of reflection, the reflected wave phase-shifted from incident wave by some amount that is not 0 or 180 degrees.

Example

- Suppose that a transmission line has $Z_0 = 50$ and the amplitude of an incident voltage pulse is 10V with wavelength 20m. Choose a load that will cause this transmission line to have a real reflection coefficient that is not zero or infinity.
- Then calculate the reflection coefficient and draw the standing wave pattern. Calculate the standing wave ratio.

Example

$$V_{o} = 10_{V}$$
 $V_{o} + \Gamma V_{o} = 13.33 V$
 $V_{o} - \Gamma V_{o} = 6.67 V$

$$\frac{1 + 1\Gamma 1}{1 - 1\Gamma 1} = \frac{4}{3} = 2$$

Pulses on T-Lines

Now let's do transient analysis on this same line. Why information do we need that we don't have yet?

Pulses on T-Lines


Now let's do transient analysis on this same line. Why information do we need that we don't have yet?


We need to know the source impedance as well as the load impedance, and we need to know the time delay of the line.

Pulses on T-Lines

- Suppose we put a very short 10V pulse into this line. What will the bounce diagram look like if the source impedance is match to the line, and what will it look like if the source impedance is the same as the load? Suppose that the time delay is 20ms.
- How would the bounce diagram analysis be different if the short 10V pulse were replaced with switching on a 10V DC source?

Pulses on T-Lines






Matched Source

Source Equals Load

Lossy T-Lines

For a lossless system,
$$Z_0$$
 represents $=\frac{\hat{V}}{\hat{I}}$

$$Z_o = \sqrt{\frac{l}{c}}$$



Replace $j\omega l$ with $r + j\omega l$


Replace $j\omega c$ with $g + j\omega c$


Characteristic Impedance

$$Z_0 =$$

$$Z_0 = \sqrt{\frac{r + j\omega l}{g + j\omega c}}$$

Low-Loss T-Lines





Likewise, when the admittance of G is nonzero but much less than the admittance of C, we consider the t-line to be low-loss.

Low-Loss T-Lines

Using the Binomial Theorem $\sqrt{1+x} \approx 1 + \frac{x}{2}$ for x << 1.

$$Z_{o} = \sqrt{\frac{r + j\omega l}{g + j\omega c}} \approx \sqrt{\frac{r + j\omega l}{j\omega c}} \approx \sqrt{\frac{j\omega l}{j\omega c}} \sqrt{1 + \frac{r}{j\omega l}} \approx \sqrt{\frac{l}{c}} \left(1 - j\frac{r}{2\omega l}\right)$$

$$\gamma = \sqrt{(r + j\omega l)(g + j\omega c)} \approx \sqrt{(r + j\omega l)(j\omega c)} \approx \sqrt{(j\omega l)(j\omega c)} \sqrt{1 + \frac{r}{j\omega l}}$$

$$\gamma = \alpha + j\beta \approx j\omega\sqrt{lc}\left(1 - j\frac{r}{2\omega l}\right)$$

Fields and Waves I

Low-Loss T-Lines

• Using the Binomial Theorem $\sqrt{1+x} \approx 1 + \frac{x}{2}$ for x <<1.

$$Z_{o} = \sqrt{\frac{r + j\omega l}{g + j\omega c}} \approx \sqrt{\frac{r + j\omega l}{j\omega c}} \approx \sqrt{\frac{j\omega l}{j\omega c}} \sqrt{1 + \frac{r}{j\omega l}} \approx \sqrt{\frac{l}{c}} \left(1 - j\frac{r}{2\omega l}\right)$$

The above expression is useful if you need to calculate the small phase of Z_0 . However, if you only care about magnitude, you can say $Z_0 \approx \sqrt{\frac{l}{c}}$

Low-Loss T-Lines

The propagation and attenuation constants become

$$j\boldsymbol{\beta} \approx j\boldsymbol{\omega}\sqrt{lc} \qquad \alpha \approx \boldsymbol{\omega}\sqrt{lc}\left(\frac{r}{2\boldsymbol{\omega}l}\right) = \frac{r}{2\sqrt{\frac{l}{c}}} = \frac{r}{2Z_o}$$

Distortionless T-Lines

For practical lines, the conductance per unit length g is negligible. Thus, we will add loss between the conductors so that

$$\frac{r}{l} = \frac{g}{c}$$

This is called the **Heaviside condition** and it can be achieved with periodic lumped shunt resistors.

Example

- Suppose you have a lossy transmission line with:
 - $r' = 0.01 \Omega/m$
 - c' = 1nF / m
 - I = 500nH / m
 - Signal frequency = 1 MHz

Figure out α and β for this line, then come up with a value of parallel shunt resistor that would cause the line to behave in a distortionless manner. Since placing these resistors is essentially creating a lumped line t-line model, they must be placed such that the lumped line approximation is reasonable.

Is this line low-loss?

$$\frac{|r'|}{|j\omega l'|} = \frac{0.01}{2\% \cdot 10^6 \cdot 500 \cdot 10^{-9}} = 0.003 \sqrt{1000}$$

$$\frac{|r'|}{|j\omega l'|} = \frac{0.01}{2\% \cdot 10^6 \cdot 500 \cdot 10^{-9}} = 22.36 \Omega$$

$$\frac{|r'|}{|low l'|} = \frac{|r'|}{|low loss|} = \frac{|r'|}{|$$

We need DX between shant resistors
to be much less
than the wavelength (let's say 140)
$$\lambda = \frac{2\pi}{B} = 44.72 \text{ m}$$
So shant resistors should appear every
0.44 m.

We need
$$\frac{\Gamma'}{L'} = \frac{9'}{C'} \longrightarrow \frac{0.01}{500 \times 10^{-9}} = \frac{9'}{10^{-9}}$$

$$g' = 2 \times 10^{-5} \Omega^{-1} m^{-1}$$

$$g' \cdot 0.44m = 8.8 \times 10^{-6} \Omega^{-1}$$

$$\frac{1}{g' \cdot 0.44m} = 114 k\Omega$$

T-Line Input Impedance

What does the input impedance of a load look like through a half wavelength of transmission line?

How about a for quarter wavelength of transmission line?

How about other lengths of transmission line?

T-Line Input Impedance

What does the input impedance of a load look like through a half wavelength of transmission line?

It looks like the load impedance, as though the line isn't there.

- How about a for quarter wavelength of transmission line?
 - It looks like Z_0^2 / Z_L (an "impedance transformer").
- How about other lengths of transmission line?

$$Z_{in} = Z_o \frac{Z_L + jZ_o \tan \beta L}{Z_o + jZ_L \tan \beta L}$$

Smith Charts

 Explain, in plain English, what a Smith Chart is and how it can be used.


Smith Charts

 Explain, in plain English, what a Smith Chart is and how it can be used.

A Smith Chart allows you to graphically convert between reflection coefficient and impedance and account for how traveling through a length of transmission line will "transform" how either of these two quantities look at the input.

Smith Charts

- On this special chart, we normalize impedances as fractions of a t-line's characteristic impedance.
- Then we plot them on the special non-Cartesian grid made of of circles and arcs. We can then read off our reflection coefficient in Cartesian coordinates.



- Suppose a transmission line has $Z_0 = 50\Omega$. Pick some arbitrary load impedance, express it as a normalized impedance, plot it on the Smith chart, and read off the reflection coefficient.
- Then read off what this impedance would look like a quarter wavelength from the load.

- Let $Z_1 = 100\Omega$.
- Normalized impedance: $z_L = 100\Omega/50\Omega = 2$.
- A quarter wavelength away, this will look like $z'_1 = 0.5$, or $Z_1 = 25\Omega$.


Example

Now, match your chosen load with an open-circuit stub.

- First, calculate the normalized load admittance $y_L = 1/z_L = 0.5$
- Next, rotate y_L onto the matching circle. $y'_L = 1 + 0.7j$
- How long must an open circuit stub be to have input impedance -0.7j? About 0.401 wavelengths.


Field Math

Which these circles represent positive vs. negative vs. no flux?



Field Math


Explain where in this picture you see positive, negative, and zero divergence.



Field Math


	Cartesian Coordinates	Cylindrical Coordinates	Spherical Coordinates
Coordinate variables	<i>x</i> , <i>y</i> , <i>z</i>	r, ϕ, z	R, θ, ϕ
Vector representation A =	$\hat{\mathbf{x}}A_x + \hat{\mathbf{y}}A_y + \hat{\mathbf{z}}A_z$	$\hat{\mathbf{r}}A_r + \hat{\mathbf{\phi}}A_\phi + \hat{\mathbf{z}}A_z$	$\hat{\mathbf{R}}A_R + \hat{\mathbf{\theta}}A_\theta + \hat{\mathbf{\phi}}A_\phi$
Magnitude of A A =	$\sqrt[+]{A_x^2 + A_y^2 + A_z^2}$	$\sqrt[+]{A_r^2 + A_{\phi}^2 + A_z^2}$	$\sqrt[+]{A_R^2 + A_\theta^2 + A_\phi^2}$
Position vector $\overrightarrow{OP_1} =$	$\hat{\mathbf{x}}x_1 + \hat{\mathbf{y}}y_1 + \hat{\mathbf{z}}z_1,$ for $P(x_1, y_1, z_1)$	$\hat{\mathbf{r}}r_1 + \hat{\mathbf{z}}z_1$, for $P(r_1, \phi_1, z_1)$	$\hat{\mathbf{R}}R_1$, for $P(R_1, \boldsymbol{\theta}_1, \boldsymbol{\phi}_1)$
Base vectors properties	$\hat{\mathbf{x}} \cdot \hat{\mathbf{x}} = \hat{\mathbf{y}} \cdot \hat{\mathbf{y}} = \hat{\mathbf{z}} \cdot \hat{\mathbf{z}} = 1$ $\hat{\mathbf{x}} \cdot \hat{\mathbf{y}} = \hat{\mathbf{y}} \cdot \hat{\mathbf{z}} = \hat{\mathbf{z}} \cdot \hat{\mathbf{x}} = 0$ $\hat{\mathbf{x}} \times \hat{\mathbf{y}} = \hat{\mathbf{z}}$ $\hat{\mathbf{y}} \times \hat{\mathbf{z}} = \hat{\mathbf{x}}$ $\hat{\mathbf{z}} \times \hat{\mathbf{x}} = \hat{\mathbf{y}}$	$\hat{\mathbf{r}} \cdot \hat{\mathbf{r}} = \hat{\boldsymbol{\phi}} \cdot \hat{\boldsymbol{\phi}} = \hat{\mathbf{z}} \cdot \hat{\mathbf{z}} = 1$ $\hat{\mathbf{r}} \cdot \hat{\boldsymbol{\phi}} = \hat{\boldsymbol{\phi}} \cdot \hat{\mathbf{z}} = \hat{\mathbf{z}} \cdot \hat{\mathbf{r}} = 0$ $\hat{\mathbf{r}} \times \hat{\boldsymbol{\phi}} = \hat{\mathbf{z}}$ $\hat{\boldsymbol{\phi}} \times \hat{\mathbf{z}} = \hat{\mathbf{r}}$ $\hat{\mathbf{z}} \times \hat{\mathbf{r}} = \hat{\boldsymbol{\phi}}$	$\hat{\mathbf{R}} \cdot \hat{\mathbf{R}} = \hat{\mathbf{\theta}} \cdot \hat{\mathbf{\theta}} = \hat{\mathbf{\phi}} \cdot \hat{\mathbf{\phi}} = 1$ $\hat{\mathbf{R}} \cdot \hat{\mathbf{\theta}} = \hat{\mathbf{\theta}} \cdot \hat{\mathbf{\phi}} = \hat{\mathbf{\phi}} \cdot \hat{\mathbf{R}} = 0$ $\hat{\mathbf{R}} \times \hat{\mathbf{\theta}} = \hat{\mathbf{\phi}}$ $\hat{\mathbf{\theta}} \times \hat{\mathbf{\phi}} = \hat{\mathbf{R}}$ $\hat{\mathbf{\phi}} \times \hat{\mathbf{R}} = \hat{\mathbf{\theta}}$
Dot product $A \cdot B =$	$A_x B_x + A_y B_y + A_z B_z$	$A_r B_r + A_\phi B_\phi + A_z B_z$	$A_R B_R + A_{\theta} B_{\theta} + A_{\phi} B_{\phi}$
Cross product A × B =	$\left \begin{array}{ccc} \hat{\mathbf{X}} & \hat{\mathbf{y}} & \hat{\mathbf{z}} \\ A_x & A_y & A_z \\ B_x & B_y & B_z \end{array}\right $	$\begin{vmatrix} \hat{\mathbf{r}} & \hat{\boldsymbol{\phi}} & \hat{\mathbf{z}} \\ A_r & A_{\phi} & A_z \\ B_r & B_{\phi} & B_z \end{vmatrix}$	$\left \begin{array}{ccc} \hat{\mathbf{R}} & \hat{\mathbf{\theta}} & \hat{\boldsymbol{\phi}} \\ A_R & A_{\theta} & A_{\phi} \\ B_R & B_{\theta} & B_{\phi} \end{array}\right $
Differential length $dl =$	$\hat{\mathbf{x}} dx + \hat{\mathbf{y}} dy + \hat{\mathbf{z}} dz$	$\hat{\mathbf{r}}dr + \hat{\mathbf{\phi}}rd\phi + \hat{\mathbf{z}}dz$	$\hat{\mathbf{R}} dR + \hat{\mathbf{\theta}} R d\theta + \hat{\mathbf{\phi}} R \sin \theta d\theta$
Differential surface areas	$d\mathbf{s}_{x} = \hat{\mathbf{x}} dy dz$ $d\mathbf{s}_{y} = \hat{\mathbf{y}} dx dz$ $d\mathbf{s}_{z} = \hat{\mathbf{z}} dx dy$	$d\mathbf{s}_r = \hat{\mathbf{r}}r d\phi dz$ $d\mathbf{s}_\phi = \hat{\boldsymbol{\phi}} dr dz$ $d\mathbf{s}_z = \hat{\mathbf{z}}r dr d\phi$	$ds_R = \hat{\mathbf{R}}R^2 \sin \theta \ d\theta \ d\phi$ $ds_\theta = \hat{\mathbf{\theta}}R \sin \theta \ dR \ d\phi$ $ds_\phi = \hat{\mathbf{\phi}}R \ dR \ d\theta$
Differential volume dV =	dx dy dz	r dr dø dz	$R^2 \sin \theta \ dR \ d\theta \ d\phi$

Field Math



How do we describe the three possible types of surface differential elements in cylindrical coordinates?

Field Math



Fields and Waves I

Electrostatics

 Describe in plain English what "electrostatics" means.

Electrostatics

 Describe in plain English what "electrostatics" means.

A subset of Maxwell's equations in which all charge is at rest. This means no magnetic fields and no currents

Example

3. Charged Plane (12 points)

Consider an infinitely thin sheet of positive charge floating in space. It has an area of 10m by 10m and its charge density is one nanocoulomb per square centimeter.

- a.) (4 pts) What will the electric field (E) be for a point above the plane's surface and very close to it? (Hint: You are being asked for an effective approximation).
- b.) (4 pts) What will the electric field (E) be for a point very far (much greater than 10m) above the plane's surface? (*This is also an approximation*.)
- c.) (4 pts) Suppose that there is a conductive plane hovering below the charged plane as shown below. Both planes have the same dimensions in the x and y directions, and the conductive plane does not have any net charge. Assume that the distance from point P to either plane is very small compared to the dimensions of the plane. What is the electric field at point P? (Hint: how does a conductive plane respond to a charge above it?)

(3) Charged Plane

a.) Very close to the plane's surface, it looks like an infinite charged plane.

$$\vec{E} = \frac{6}{2\epsilon_0} \hat{z} \qquad (pointing up)$$

$$\vec{E} = 5.65 \times 10^5 \text{ V/m } \hat{z}^2$$

b.) At these distances, the plane can be approximated as a point with total charge Q.

$$Q = (1 \times 10^{-5} \, \text{C/m}^2) \cdot (10 \, \text{m})^2 = 0.001 \, \text{C}$$

$$\vec{E} = \frac{1}{4 \, \text{ME}_6} \, \frac{Q}{r^2} \, \hat{r} = \frac{1}{4 \, \text{ME}_6} \, \frac{0.001 \, \text{C}}{r^2} \, \hat{r}$$

$$\vec{E} = \left(\frac{8.987 \times 10^6}{z^2}\right) \hat{2} \, \text{V/m}$$

Example

$$\overrightarrow{E} = \frac{-6}{2\epsilon_0} \, \widehat{2} \quad (points down because we are below the plane)$$


The effect of the conductive plane can be determined using the method of images. The charged plane causes a negative charge to appear on the conducting plane's surface.

This charge looks like a plane of negative charge with density 6 below P.


Thus,

$$\frac{1}{E+o+} = \frac{-6}{2\epsilon_0} \hat{z} + \frac{(-6)}{2\epsilon_0} \hat{z}$$
Etot = -1.129 x10 6 \hat{z} V/M

(pointing down)



$$ec{E}=$$
- $abla V$



- Gradient points in the direction of largest change
- Therefore, E-field lines are perpendicular (normal) to constant V surfaces

Example

7. Capacitance (18 pts)

Consider a spherical capacitor with a layered structure. Its innermost layer is a grounded spherical conductor of radius 1mm. This is covered by a 1mm thick layer of dielectric with permittivity $3\varepsilon_0$, then a 1mm thick layer of permittivity $6\varepsilon_0$, a 1mm layer of permittivity $9\varepsilon_0$, and finally at the outermost layer, 1mm thick shell of conductor.

a.) (8 pts) Calculate the capacitance of this sphere.

Now we calculate voltage from the outer conductor to the inner:

$$V = -\int \vec{E} \cdot d\vec{l}$$
 $V = -\int \frac{0.003}{4\pi(9\epsilon_0)} \frac{Q}{+2} dr - \int \frac{1}{4\pi(6\epsilon_0)} \frac{Q}{+2} dr$
 0.003
 0.003
 0.003
 0.003

Permittivity

In plain English, what is permittivity?

Permittivity

In plain English, what is permittivity?

Permittivity describes how strong the E-field will be in a material in response to an external D-field.

$$\vec{D} = \epsilon \vec{E}$$

Magnetostatics

In plain English, what is magnetostatics?

Magnetostatics

In plain English, what is magnetostatics?

Magnetostatics is a subset of Maxwell's Equations in which charges move only as constant currents. This means that we have static electric fields and static magnetic fields.

Displacement Current

- What is displacement current, and how do you calculate it?
- What is skin depth, and how do you calculate it?

Maxwell's Equations

Full Version

Added term in curl H equation for time varying electric field that gives a magnetic field.

$$\oint \vec{H} \cdot \vec{dl} = \int \vec{J} \cdot \vec{dS} + \underbrace{\int \frac{\partial \vec{D}}{\partial t} \cdot \vec{dS}}_{}$$

$$\nabla imes \vec{H} = \vec{J} + \frac{\partial \vec{D}}{\partial t}$$

$$\oint \vec{B} \cdot \vec{dS} = 0$$

$$\nabla \cdot \vec{B} = 0$$

$$\oint \vec{E} \cdot \vec{dl} = -\frac{d}{dt} \int \vec{B} \cdot d\vec{S}$$

$$\nabla \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$$

$$\oint \vec{D} \cdot dS = \oint
ho dv = Q_{encl}$$

$$\nabla \cdot \vec{D} = \rho$$

First introduced by Maxwell in 1873

Fields and Waves I

Maxwell's Equations

The total displacement current between the capacitor plates

$$I_d = -\epsilon \int \frac{\partial}{\partial t} (-\frac{V(t)}{d}) \hat{z} \cdot d\vec{S} = \frac{\epsilon \pi a^2}{d} \frac{\partial V(t)}{\partial t}$$

Using phasor notation for the voltage and current

$$V(t) = \operatorname{Re}\left(V_{o}e^{j\omega t}\right) \qquad I_{D} = j\omega \frac{\varepsilon \pi a^{2}}{d}V_{o}$$

Lossy EM Waves

Skin Depth, δ_s

shows how well an electromagnetic wave can penetrate into a conducting medium

$$\delta_s = \frac{1}{\alpha}$$
 [m]

Perfect dielectric:

$$\sigma=0$$

$$\alpha = 0$$


$$\sigma=0$$
 $\alpha=0$ $\delta_s=\infty$

Perfect Conductor:

$$\alpha = \infty$$

$$\alpha = \infty$$

$$\delta_s = 0$$



Fields and Waves I

Ulaby

73

Plane Waves

- What is a plane wave?
- What is intrinsic impedance?
- What happens when a plane wave passes through two regions of different intrinsic impedance, and why?

Electromagnetic Waves

Some Typical Waves




Figure 1-10

Ulaby

Plane Waves

- What is a Poynting vector, and how do you calculate it?
- How do you calculate the average power in a Poynting vector?

EM Wave Power Transmission

Poynting Vector S , is defined

$$S = E \times H$$

 $S = E \times H$ [W/unit area]

S is along the propagation direction of the wave

Total power

$$P = \int_{A} S \cdot \hat{a}_{n} dA$$

$$OR P = S A \cos \theta \quad [W]$$

Average power density of the wave

 $[W/m^2]$

Ulaby

EM Power Transmission

Plane wave in a Lossless Medium

$$\widetilde{E}(z) = \widetilde{E}_{x}^{+}(z)\widehat{a}_{x} + \widetilde{E}_{y}^{+}(z)\widehat{a}_{y}$$

$$\widetilde{E}(z) = (E_{x0}\widehat{a}_x + E_{y0}\widehat{a}_y)e^{-jkz}$$

$$\widetilde{H}(z) = \frac{1}{\eta} \widehat{a}_{z} \times \widetilde{E} = \frac{1}{\eta} (-E_{y0} \widehat{a}_{x} + E_{x0} \widehat{a}_{y}) e^{-jkz}$$

$$S_{av} = \hat{a}_z \frac{1}{2 n} (|E_{x0}|^2 + |E_{y0}|^2)$$


$$S_{av} = \hat{a}_z \frac{\left| \tilde{E} \right|^2}{2 \eta}$$
 [W/m²]

Polarization

- What is the difference between linear, circular, and elliptical polarization?
- What is the difference between left-hand circular and right-hand circular polarization?

Electromagnetic Waves

Some Typical Waves




Source: Gfycat

Wave Polarization

Circular Polarization

A wave is said to be circularly polarized if

- •the magnitudes of $\tilde{E}_x(z)$ and $\tilde{E}_y(z)$ are equal and
- •The phase difference is $\delta = \pm \pi/2$



Fields and Waves I

81

Polarization

$$\tan 2\gamma = (\tan 2\psi_0)\cos\delta \quad (-\pi/2 \le \gamma \le \pi/2),$$

$$\sin 2\chi = (\sin 2\psi_0)\sin\delta \quad (-\pi/4 \le \chi \le \pi/4),$$


where ψ_0 is an *auxiliary angle* defined by

$$\tan \psi_0 = \frac{a_y}{a_x} \qquad \left(0 \le \psi_0 \le \frac{\pi}{2}\right).$$

Ulaby pg. 329

▶ Positive values of χ , corresponding to $\sin \delta > 0$, are associated with left-handed rotation, and negative values of χ , corresponding to $\sin \delta < 0$, are associated with right-handed rotation. \blacktriangleleft

Polarization



22.5° Left elliptical polarization



0° Linear polarization



--22.5° Right elliptical polarization



-45° Right circular polarization




Oblique Incidence

How do you calculate the reflection between two media of different intrinsic impedance?

Review

Lossless Media

two lossless, homogenous, dielectric media



k (or wavenumber) is often used for EM waves but it is functionally the same as β (phase constant)

Incident wave
$$\tilde{E}^{i}(z) = \hat{a}_{x} E_{0}^{i} e^{-jk_{1}z}$$

$$k_1 = \omega \sqrt{\mu_1 \varepsilon_1}$$

$$\eta_1 = \sqrt{\frac{\mu_1}{\varepsilon_1}}$$

EM Waves and Boundaries

Reflection and Transmission Coefficients

$$\Gamma = \frac{E_0^r}{E_0^i} = \frac{\eta_2 - \eta_1}{\eta_2 + \eta_1}$$
 Normally incident

$$\tau = \frac{E_0^t}{E_0^t} = \frac{2 \eta_2}{\eta_2 + \eta_1}$$
 Normally incident

 Γ and τ are real for lossless dielectric media

$$\tau = 1 + \Gamma$$
 Normally incident


For nonmagnetic media

$$\Gamma = \frac{E_0^r}{E_0^i} = \frac{\sqrt{\varepsilon_{r1}} - \sqrt{\varepsilon_{r2}}}{\sqrt{\varepsilon_{r1}} + \sqrt{\varepsilon_{r2}}}$$

Oblique Incidence

Parallel Polarization

- For the first choice,
 we can assume that
 the electric field is
 directed in the plane
 of incidence (in this
 case the x-z plane.)
- This is called parallel polarization since E is parallel to this plane.




Fields and Waves I

Ulaby

Oblique Incidence

Perpendicular Polarization

- For the second choice, we can assume that the electric field in directed out of the plane of incidence.
- This is called perpendicular polarization since E is perpendicular to this plane.
- Note that E is only tangential while H has both components.



Ulaby

Snell's Law

Reflection and Transmission Coefficients

By algebraically combining the E and H tangential boundary conditions we can get the following:

$$\Gamma_{\perp} = \frac{E_{m1}}{E_{m1}} = \frac{\eta_2 \cos \theta_1 - \eta_1 \cos \theta_2}{\eta_2 \cos \theta_1 + \eta_1 \cos \theta_2}$$

$$\tau_{\perp} = \frac{E_{m2}^{+}}{E_{m1}^{+}} = \frac{2 \eta_2 \cos \theta_1}{\eta_2 \cos \theta_1 + \eta_1 \cos \theta_2}$$

$$1 + \Gamma_{\perp} = \tau_{\perp}$$

Snell's Law

Reflection and Transmission Coefficients

Parallel Polarization:

$$\Gamma_{\parallel} = \frac{\eta_2 \cos \theta_2 - \eta_1 \cos \theta_1}{\eta_2 \cos \theta_2 + \eta_1 \cos \theta_1}$$

$$\boldsymbol{\tau}_{\parallel} = \frac{2 \boldsymbol{\eta}_2 \cos \boldsymbol{\theta}_1}{\boldsymbol{\eta}_2 \cos \boldsymbol{\theta}_2 + \boldsymbol{\eta}_1 \cos \boldsymbol{\theta}_1}$$

$$1 + \Gamma_{||} = \tau_{||} \frac{\cos\theta_2}{\cos\theta_1}$$

Special Angles


- What is a critical angle and how do you calculate it?
- What is a Brewster's angle and how do you calculate it?

Reflection Angular Dependence

Critical Angle

$$n_1 \sin \theta_1 = n_2 \sin \theta_2$$

- When transmission angle reaches 90 degrees, there will be no transmission.
- Beyond this angle, there will be total reflection.



Reflection Angular Dependence

Critical Angle

$$K_1 \sin \Theta_c = K_2 \sin \Theta_2$$


 $\sin \Theta_2 = \sin 90^\circ = 1$
 $K_1 \sin \Theta_c = K_2$
 $\sin \Theta_c = \frac{K_2}{K_1}$

$$\sin \theta_c = \sqrt{\frac{\varepsilon_2}{\varepsilon_1}}$$

(Note that when $\varepsilon_2 > \varepsilon_1$, this will not have a real-valued answer.)

Reflection Angular Dependence

Brewster's Angle



- At the Brewster's Angle or polarizing angle, the reflection coefficient is 0 for one polarization of light.
- This means that only polarized light is reflected.

Brewster's Angle

$$n_1 \sin \theta_1 = n_2 \sin \theta_2$$

$$\eta_2 \cos \theta_i = \eta_1 \cos \theta_t.$$

$$\Gamma_{\perp} = \frac{E_{m1}^{-}}{E_{m1}^{+}} = \frac{\eta_2 \cos \theta_1 - \eta_1 \cos \theta_2}{\eta_2 \cos \theta_1 + \eta_1 \cos \theta_2}$$

Combining these two equations and setting the incident angle to be the Brewster angle, we get:

$$\sin \theta_{\rm B\perp} = \sqrt{\frac{1 - (\mu_1 \epsilon_2 / \mu_2 \epsilon_1)}{1 - (\mu_1 / \mu_2)^2}} \ .$$

(Ulaby pg. 375)

Brewster's Angle

$$\sin \theta_{\rm B\perp} = \sqrt{\frac{1 - (\mu_1 \epsilon_2 / \mu_2 \epsilon_1)}{1 - (\mu_1 / \mu_2)^2}} \ .$$

Note that this is undefined when the permeabilities of the two materials are the same. But when they are different, some Brewster angle will exist.

Brewster's Angle

$$n_1 \sin \theta_1 = n_2 \sin \theta_2$$

$$\eta_2 \cos \theta_i = \eta_1 \cos \theta_t.$$

$$\Gamma_{\parallel} = \frac{\eta_2 \cos \theta_2 - \eta_1 \cos \theta_1}{\eta_2 \cos \theta_2 + \eta_1 \cos \theta_1}$$

By once again combining the two equations, we get:

$$\sin \theta_{\mathrm{B}\parallel} = \sqrt{\frac{1 - (\epsilon_1 \mu_2 / \epsilon_2 \mu_1)}{1 - (\epsilon_1 / \epsilon_2)^2}} \; .$$

Brewster's Angle

When the permeabilities of the two materials are the same, this becomes

$$\theta_{\mathrm{B}\parallel} = \sin^{-1} \sqrt{\frac{1}{1 + (\epsilon_1/\epsilon_2)}}$$

$$= \tan^{-1} \sqrt{\frac{\epsilon_2}{\epsilon_1}} \qquad (\text{for } \mu_1 = \mu_2).$$