Enroll and configure new device into Soti control

TESTTESTESTESTESTEST

1. **Enroll the device into PPG Soti with not SVG**
    a. For the enrollment, you need connect to a non PPG Wifi Hotspot .

    Wifi PPG Local doesn't allow the connection



    b. On Copy apps and Data screen, click on **Don't copy**



c. On Google Sign in screen, as email enter afw#mobicontrol



d. Enter Enrollment Code related to the OU Soti

Contact the SME WMS to know which package is assigned to which OU

Email : dl-EMEAWMSManufacturingInfrastructureSME@ppg.com

This will determine the OU code to enter at this level

Attention : Each OU has a different code and this will determine profiles and packages assigned to the device. Be sure that you know which applications you need before enrolling the machine.

Ex : MRL code is VDKKTY53



e. You need to allow Soti to access to the device

Switch the button to allow modifying system settings



f. If you need additional packages not defined into the OU , please open a ticket to GBL WMS Support in Infra and contact WMS SMEs with ticket number

2. **<u>Enroll the device into PPG Soti with SVG</u>**

3. **<u>Configure device in SOTI</u>**

Once the device is enrolled into SOTI, go to SOTI Mobicontrol

a. **<u>Check your device</u>**

Select the correct OU and the gun should appears.

PPG\Scanners\EUC\<Region>)\<Site>

Packages and profiles are assigned by default to OU

So be sure you select the correct OU for the device.

If you got doubt please contact SME WMS (GBL WMS Support)



You should see device(s) on the right panel



b. <u>Change the name of the device following PPG standard :</u>

- Click on 3 dots buttons on the top right



- Choose rename



- Name it following convention :
  - H for Handheld
  - 3 Code site (OU)
  - Add W if the device is in a Warehouse
  - Add G for Guns or M for Forklift mounted devices
  - Number with 3 digit (001 to 999)

c. <u>Define configuration</u>

- Click on the device you want to activate/assign packages
- Go to Custom attributes on Device Details tab
- You need to change some settings
- Click on the Pencil icon to edit attributes



- Change Migration status to True
- Select SBU
- Change Usage status to Active
- Save settings



The result should be like that :



d. <u>Synchronize the device with Soti</u>

- Click on Check-in button to sync with Mobicontrol and receive configuration

e. <u>Check if profiles and packages are synchronized on the device</u>

- Go to configuration tab
- Check if you receive Profiles and packages being installed



During this process of installing, the gun could restart.

Once packages and profiles installed, the gun is ready to use.