

PG-00000-002_V2.3 June, 2009 CUBLAS Library PG-00000-002_V2.3

Published by NVIDIA Corporation 2701 San Tomas Expressway Santa Clara, CA 95050

Notice

ALL NVIDIA DESIGN SPECIFICATIONS, REFERENCE BOARDS, FILES, DRAWINGS, DIAGNOSTICS, LISTS, AND OTHER DOCUMENTS (TOGETHER AND SEPARATELY, "MATERIALS") ARE BEING PROVIDED "AS IS." NVIDIA MAKES NO WARRANTIES, EXPRESSED, IMPLIED, STATUTORY, OR OTHERWISE WITH RESPECT TO THE MATERIALS, AND EXPRESSLY DISCLAIMS ALL IMPLIED WARRANTIES OF NONINFRINGEMENT, MERCHANTABILITY, AND FITNESS FOR A PARTICULAR PURPOSE.

Information furnished is believed to be accurate and reliable. However, NVIDIA Corporation assumes no responsibility for the consequences of use of such information or for any infringement of patents or other rights of third parties that may result from its use. No license is granted by implication or otherwise under any patent or patent rights of NVIDIA Corporation. Specifications mentioned in this publication are subject to change without notice. This publication supersedes and replaces all information previously supplied. NVIDIA Corporation products are not authorized for use as critical components in life support devices or systems without express written approval of NVIDIA Corporation.

Trademarks

NVIDIA, CUDA, and the NVIDIA logo are trademarks or registered trademarks of NVIDIA Corporation in the United States and other countries. Other company and product names may be trademarks of the respective companies with which they are associated.

Copyright

© 2005–2009 by NVIDIA Corporation. All rights reserved.

Portions of the SGEMM and DGEMM library routines were written by Vasily Volkov and are subject to the Modified Berkeley Software Distribution License as follows:

Copyright (c) 2007-2009, Regents of the University of California

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of the University of California, Berkeley nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

CUBLAS Library PG-00000-002_V2.3

Portions of the SGEMM and DGEMM library routines were written by Davide Barbieri and are subject to the Modified Berkeley Software Distribution License as follows:

Copyright (c) 2008-2009 Davide Barbieri @ University of Rome Tor Vergata.

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3- The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

CUBLAS Library PG-00000-002_V2.3

Table of Contents

1. The CUBLAS Library	1
CUBLAS Types	
CUBLAS Helper Functions	
Function cublasShutdown()	
Function cublasAlloc()	10
Function cublasSetVector()	11
Function cublasSetMatrix()	13
2. BLAS1 Functions	
Single-Precision BLAS1 Functions	
Function cublasIsamax()	
Function cublasIsamin()	
Function cublasSasum()	
Function cublasSaxpy()	
Function cublasScopy()	
Function cublasSdot()	
Function cublasSnrm2()	
Function cublasSrot()	
Function cublasSrotg()	
Function cublasSrotm()	
Function cublasSrotmg()	
Function cublasSscal()	
Function cublasSswap()	
Single-Precision Complex BLAS1 Functions	28
Function cublasCaxpy()	28
Function cublasCcopy()	29
Function cublasCdotc()	
Function cublasCdotu()	31
Function cublasCrot()	.32

Function cublasCrotg()
Function cublasCscal()34
Function cublasCsrot()
Function cublasCsscal()
Function cublasCswap()37
Function cublasIcamax()
Function cublasIcamin()
Function cublasScasum()
Function cublasScnrm2()
Double-Precision BLAS1 Functions
Function cublasIdamax()
Function cublastdamax()
Function cublastramin()
Function cubiasDaxpy()
Function cubiasDaxpy()
Function cublasDdot()
Function cubiasDaot()
Function cublasDrot()
Function cublasDrotg()
Function cubiasprotm()
Function cublasDrotmg()
Function cublasDscal()
Function cublasDswap()
Double-Precision Complex BLAS1 functions
Function cublasZdotu()
Function cublasZscal()
3. BLAS2 Functions
Single-Precision BLAS2 Functions
Function cublasSgbmv()
Function cublasSgemv()
Function cublasSger()
Function cublasSsbmv()
Function cublasSspmv()
Function cublasSspr()
Function cublasSspr2()
Function cublasSsymv()
Function cublasSsyr()
Function cublasSsyr()
Function cublasStbmv()
Function cubiasStomv()
Function cubiasStosv()
Function cubiasStpmv()
Function cublasStrmv()

Function cublasStrsv()
Single-Precision Complex BLAS2 Functions
Double-Precision BLAS2 Functions 7 Function cublasDgemv() 7 Function cublasDger() 8 Function cublasDsyr() 8 Function cublasDtrsv() 8
Double-Precision Complex BLAS2 functions
4. BLAS3 Functions
Single-Precision BLAS3 Functions 8 Function cublasSgemm() 8 Function cublasSsymm() 9 Function cublasSsyrk() 9 Function cublasSsyr2k() 9 Function cublasStrmm() 9 Function cublasStrsm() 9
Single-Precision Complex BLAS3 Functions
Double-Precision BLAS3 Functions 10 Function cublasDgemm() 10 Function cublasDsymm() 10 Function cublasDsyrk() 10 Function cublasDsyr2k() 10 Function cublasDtrmm() 10 Function cublasDtrsm() 11
Double-Precision Complex BLAS3 Functions 11 Function cublasZgemm() 11 Function cublasZsyrk() 11
A. CUBLAS Fortran Bindings11

CHAPTER

1

The CUBLAS Library

CUBLAS is an implementation of BLAS (Basic Linear Algebra Subprograms) on top of the NVIDIA CUDA (compute unified device architecture) driver. It allows access to the computational resources of NVIDIA GPUs. The library is self-contained at the API level, that is, no direct interaction with the CUDA driver is necessary. CUBLAS attaches to a single GPU and does not auto-parallelize across multiple GPUs.

The basic model by which applications use the CUBLAS library is to create matrix and vector objects in GPU memory space, fill them with data, call a sequence of CUBLAS functions, and, finally, upload the results from GPU memory space back to the host. To accomplish this, CUBLAS provides helper functions for creating and destroying objects in GPU space, and for writing data to and retrieving data from these objects.

For maximum compatibility with existing Fortran environments, CUBLAS uses column-major storage and 1-based indexing. Since C and C++ use row-major storage, applications cannot use the native array semantics for two-dimensional arrays. Instead, macros or inline functions should be defined to implement matrices on top of one-dimensional arrays. For Fortran code ported to C in mechanical fashion, one may chose to retain 1-based indexing to avoid the need to

transform loops. In this case, the array index of a matrix element in row i and column j can be computed via the following macro:

```
#define IDX2F(i,j,ld) ((((j)-1)*(ld))+((i)-1))
```

Here, 1d refers to the leading dimension of the matrix as allocated, which in the case of column-major storage is the number of rows. For natively written C and C++ code, one would most likely chose 0-based indexing, in which case the indexing macro becomes

```
\#define\ IDX2C(i,j,ld)\ (((j)*(ld))+(i))
```

Please refer to the code examples at the end of this section, which show a tiny application implemented in Fortran on the host (Example 1. "Fortran 77 Application Executing on the Host") and show versions of the application written in C using CUBLAS for the indexing styles described above (Example 2. "Application Using C and CUBLAS: 1-based Indexing" and Example 3. "Application Using C and CUBLAS: 0-based Indexing").

Because the CUBLAS core functions (as opposed to the helper functions) do not return error status directly (for reasons of compatibility with existing BLAS libraries), CUBLAS provides a separate function to aid in debugging that retrieves the last recorded error.

Currently, only a subset of the CUBLAS core functions is implemented.

The interface to the CUBLAS library is the header file cublas.h. Applications using CUBLAS need to link against the DSO cublas.so (Linux), the DLL cublas.dll (Windows), or the dynamic library cublas.dylib (Mac OS X) when building for the device, and against the DSO cublasemu.so (Linux), the DLL cublasemu.dll (Windows), or the dynamic library cublasemu.dylib (Mac OS X) when building for device emulation.

Following these three examples, the remainder of this chapter discusses "CUBLAS Types" on page 8 and "CUBLAS Helper Functions" on page 9.

The CUBLAS Library

Example 1. Fortran 77 Application Executing on the Host

```
subroutine modify (m, ldm, n, p, q, alpha, beta)
implicit none
integer ldm, n, p, q
real*4 m(ldm,*), alpha, beta
external sscal
call sscal (n-p+1, alpha, m(p,q), ldm)
call sscal (ldm-p+1, beta, m(p,q), 1)
return
end
program matrixmod
implicit none
integer M, N
parameter (M=6, N=5)
real*4 a(M,N)
integer i, j
do j = 1, N
  do i = 1, M
    a(i,j) = (i-1) * M + j
  enddo
enddo
call modify (a, M, N, 2, 3, 16.0, 12.0)
do j = 1, N
  do i = 1, M
    write(*,"(F7.0\$)") a(i,j)
  enddo
  write (*,*) ""
enddo
stop
end
```

Example 2. Application Using C and CUBLAS: 1-based Indexing

```
#include <stdio.h>
#include <stdlib.h>
#include <math.h>
#include "cublas.h"
#define IDX2F(i,j,ld) ((((j)-1)*(ld))+((i)-1))
void modify (float *m, int ldm, int n, int p, int q, float alpha,
             float beta)
    \verb|cublasSscal| (n-p+1, alpha, &m[IDX2F(p,q,ldm)], ldm); \\
    cublasSscal (ldm-p+1, beta, &m[IDX2F(p,q,ldm)], 1);
}
#define M 6
#define N 5
int main (void)
    int i, j;
    cublasStatus stat;
    float* devPtrA;
    float* a = 0;
    a = (float *)malloc (M * N * sizeof (*a));
    if (!a) {
        printf ("host memory allocation failed");
        return EXIT_FAILURE;
    for (j = 1; j \le N; j++) {
        for (i = 1; i <= M; i++) {
            a[IDX2F(i,j,M)] = (i-1) * M + j;
    cublasInit();
    stat = cublasAlloc (M*N, sizeof(*a), (void**)&devPtrA);
```

CHAPTER 1 The CUBLAS Library

Example 2. Application Using C and CUBLAS: 1-based Indexing (continued)

```
if (stat != CUBLAS_STATUS_SUCCESS) {
   printf ("device memory allocation failed");
    cublasShutdown();
   return EXIT_FAILURE;
stat = cublasSetMatrix (M, N, sizeof(*a), a, M, devPtrA, M);
if (stat != CUBLAS_STATUS_SUCCESS) {
    printf ("data download failed");
    cublasFree (devPtrA);
    cublasShutdown();
   return EXIT_FAILURE;
modify (devPtrA, M, N, 2, 3, 16.0f, 12.0f);
stat = cublasGetMatrix (M, N, sizeof(*a), devPtrA, M, a, M);
if (stat != CUBLAS_STATUS_SUCCESS) {
   printf ("data upload failed");
    cublasFree (devPtrA);
    cublasShutdown();
   return EXIT_FAILURE;
cublasFree (devPtrA);
cublasShutdown();
for (j = 1; j \le N; j++) {
    for (i = 1; i <= M; i++) {
        printf ("%7.0f", a[IDX2F(i,j,M)]);
   printf ("\n");
return EXIT_SUCCESS;
```

Example 3. Application Using C and CUBLAS: 0-based Indexing

```
#include <stdio.h>
#include <stdlib.h>
#include <math.h>
#include "cublas.h"
#define IDX2C(i,j,ld) (((j)*(ld))+(i))
void modify (float *m, int ldm, int n, int p, int q, float alpha,
             float beta)
    cublasSscal (n-p, alpha, &m[IDX2C(p,q,ldm)], ldm);
    cublasSscal (ldm-p, beta, &m[IDX2C(p,q,ldm)], 1);
}
#define M 6
#define N 5
int main (void)
    int i, j;
   cublasStatus stat;
    float* devPtrA;
    float* a = 0;
   a = (float *)malloc (M * N * sizeof (*a));
    if (!a) {
       printf ("host memory allocation failed");
        return EXIT_FAILURE;
    for (j = 0; j < N; j++) {
        for (i = 0; i < M; i++) {
            a[IDX2C(i,j,M)] = i * M + j + 1;
    cublasInit();
    stat = cublasAlloc (M*N, sizeof(*a), (void**)&devPtrA);
    if (stat != CUBLAS_STATUS_SUCCESS) {
```

Chapter 1 The CUBLAS Library

Example 3. Application Using C and CUBLAS: 0-based Indexing (continued)

```
printf ("device memory allocation failed");
    cublasShutdown();
   return EXIT_FAILURE;
stat = cublasSetMatrix (M, N, sizeof(*a), a, M, devPtrA, M);
if (stat != CUBLAS_STATUS_SUCCESS) {
   printf ("data download failed");
    cublasFree (devPtrA);
    cublasShutdown();
   return EXIT_FAILURE;
modify (devPtrA, M, N, 1, 2, 16.0f, 12.0f);
stat = cublasGetMatrix (M, N, sizeof(*a), devPtrA, M, a, M);
if (stat != CUBLAS_STATUS_SUCCESS) {
   printf ("data upload failed");
    cublasFree (devPtrA);
    cublasShutdown();
   return EXIT_FAILURE;
cublasFree (devPtrA);
cublasShutdown();
for (j = 0; j < N; j++) {
    for (i = 0; i < M; i++) {
        printf ("%7.0f", a[IDX2C(i,j,M)]);
   printf ("\n");
return EXIT_SUCCESS;
```

CUBLAS Types

The only CUBLAS type is cublasStatus.

Type cublasStatus

The type cublasstatus is used for function status returns. CUBLAS helper functions return status directly, while the status of CUBLAS core functions can be retrieved via cublasGetError(). Currently, the following values are defined:

cublasStatus Values

CUBLAS STATUS SUCCESS	operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	CUBLAS library not initialized
CUBLAS_STATUS_ALLOC_FAILED	resource allocation failed
CUBLAS_STATUS_INVALID_VALUE	unsupported numerical value was passed to function
CUBLAS_STATUS_ARCH_MISMATCH	function requires an architectural feature absent from the architecture of the device
CUBLAS_STATUS_MAPPING_ERROR	access to GPU memory space failed
CUBLAS_STATUS_EXECUTION_FAILED	GPU program failed to execute
CUBLAS_STATUS_INTERNAL_ERROR	an internal CUBLAS operation failed

CUBLAS Helper Functions

The following are the CUBLAS helper functions:

- □ "Function cublasInit()" on page 9
- □ "Function cublasShutdown()" on page 10
- □ "Function cublasGetError()" on page 10
- □ "Function cublasAlloc()" on page 10
- □ "Function cublasFree()" on page 11
- □ "Function cublasSetVector()" on page 11
- □ "Function cublasGetVector()" on page 12
- □ "Function cublasSetMatrix()" on page 13
- □ "Function cublasGetMatrix()" on page 13

Function cublasInit()

cublasStatus
cublasInit (void)

initializes the CUBLAS library and must be called before any other CUBLAS API function is invoked. It allocates hardware resources necessary for accessing the GPU. It attaches CUBLAS to whatever GPU is currently bound to the host thread from which it was invoked.

Return Values

CUBLAS_STATUS_ALLOC_FAILED if resources could not be allocated

CUBLAS_STATUS_SUCCESS if CUBLAS library initialized successfully

Function cublasShutdown()

cublasStatus cublasShutdown (void)

releases CPU-side resources used by the CUBLAS library. The release of GPU-side resources may be deferred until the application shuts down.

Return Values

CUBLAS STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS library shut down successfully

Function cublasGetError()

cublasStatus
cublasGetError (void)

returns the last error that occurred on invocation of any of the CUBLAS core functions. While the CUBLAS helper functions return status directly, the CUBLAS core functions do not, improving compatibility with those existing environments that do not expect BLAS functions to return status. Reading the error status via cublasGetError() resets the internal error state to CUBLAS_STATUS_SUCCESS.

Function cublasAlloc()

```
cublasStatus
cublasAlloc (int n, int elemSize, void **devicePtr)
```

creates an object in GPU memory space capable of holding an array of n elements, where each element requires elemSize bytes of storage. If the function call is successful, a pointer to the object in GPU memory space is placed in devicePtr. Note that this is a device pointer that cannot be dereferenced in host code. Function cublasAlloc() is a wrapper around cudaMalloc(). Device pointers returned by

10 PG-00000-002_V2.3 NVIDIA

cublasAlloc() can therefore be passed to any CUDA device kernels, not just CUBLAS functions.

Return Values

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if n <= 0 or elemSize <= 0
CUBLAS_STATUS_ALLOC_FAILED	if the object could not be allocated due to lack of resources.
CUBLAS_STATUS_SUCCESS	if storage was successfully allocated

Function cublasFree()

```
cublasStatus
cublasFree (const void *devicePtr)
```

destroys the object in GPU memory space referenced by devicePtr.

Return Values

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INTERNAL_ERROR	if the object could not be deallocated
CUBLAS_STATUS_SUCCESS	if object was deallocated successfully

Function cublasSetVector()

copies n elements from a vector x in CPU memory space to a vector y in GPU memory space. Elements in both vectors are assumed to have a size of elemSize bytes. Storage spacing between consecutive elements is incx for the source vector x and incy for the destination vector y. In general, y points to an object, or part of an object, allocated via cublasAlloc(). Column-major format for two-dimensional matrices is assumed throughout CUBLAS. If the vector is part of a matrix, a vector increment equal to 1 accesses a (partial) column of the matrix.

Similarly, using an increment equal to the leading dimension of the matrix accesses a (partial) row.

Return Values

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if incx, incy, or elemSize <= 0
CUBLAS_STATUS_MAPPING_ERROR	if error accessing GPU memory
CUBLAS_STATUS_SUCCESS	if operation completed successfully

Function cublasGetVector()

```
cublasStatus
```

copies n elements from a vector x in GPU memory space to a vector y in CPU memory space. Elements in both vectors are assumed to have a size of elemSize bytes. Storage spacing between consecutive elements is incx for the source vector x and incy for the destination vector y. In general, x points to an object, or part of an object, allocated via cublasAlloc(). Column-major format for two-dimensional matrices is assumed throughout CUBLAS. If the vector is part of a matrix, a vector increment equal to 1 accesses a (partial) column of the matrix. Similarly, using an increment equal to the leading dimension of the matrix accesses a (partial) row.

Return Values

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if incx, incy, or elemSize <= 0
CUBLAS_STATUS_MAPPING_ERROR	if error accessing GPU memory
CUBLAS_STATUS_SUCCESS	if operation completed successfully

12 PG-00000-002_V2.3 NVIDIA

Function cublasSetMatrix()

copies a tile of rowsxcols elements from a matrix A in CPU memory space to a matrix B in GPU memory space. Each element requires storage of elemSize bytes. Both matrices are assumed to be stored in column-major format, with the leading dimension (that is, the number of rows) of source matrix A provided in lda, and the leading dimension of destination matrix B provided in ldb. B is a device pointer that points to an object, or part of an object, that was allocated in GPU memory space via cublasAlloc().

Return Values

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	<pre>if rows or cols < 0; or elemSize, lda, or ldb <= 0</pre>
CUBLAS_STATUS_MAPPING_ERROR	if error accessing GPU memory
CUBLAS_STATUS_SUCCESS	if operation completed successfully

Function cublasGetMatrix()

int ldb)

copies a tile of rowsxcols elements from a matrix A in GPU memory space to a matrix B in CPU memory space. Each element requires storage of elemSize bytes. Both matrices are assumed to be stored in column-major format, with the leading dimension (that is, the number of rows) of source matrix A provided in lda, and the leading dimension of destination matrix B provided in ldb. A is a device

pointer that points to an object, or part of an object, that was allocated in GPU memory space via **cublasAlloc()**.

Return Values

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	<pre>if rows or cols < 0; or elemSize, lda, or ldb <= 0</pre>
CUBLAS_STATUS_MAPPING_ERROR	if error accessing GPU memory
CUBLAS_STATUS_SUCCESS	if operation completed successfully

CHAPTER

2

BLAS1 Functions

Level 1 Basic Linear Algebra Subprograms (BLAS1) are functions that perform scalar, vector, and vector-vector operations. The CUBLAS BLAS1 implementation is described in these sections:

- □ "Single-Precision BLAS1 Functions" on page 16
- □ "Single-Precision Complex BLAS1 Functions" on page 28
- □ "Double-Precision BLAS1 Functions" on page 41
- □ "Double-Precision Complex BLAS1 functions" on page 53

Single-Precision BLAS1 Functions

The single-precision BLAS1 functions are as follows:

- □ "Function cublasIsamax()" on page 16
- □ "Function cublasIsamin()" on page 17
- □ "Function cublasSasum()" on page 18
- □ "Function cublasSaxpy()" on page 18
- □ "Function cublasScopy()" on page 19
- □ "Function cublasSdot()" on page 20
- □ "Function cublasSnrm2()" on page 21
- □ "Function cublasSrot()" on page 22
- □ "Function cublasSrotg()" on page 23
- □ "Function cublasSrotm()" on page 24
- □ "Function cublasSrotmg()" on page 25
- □ "Function cublasSscal()" on page 26
- □ "Function cublasSswap()" on page 27

Function cublasIsamax()

int

```
cublasIsamax (int n, const float *x, int incx)
```

finds the smallest index of the maximum magnitude element of single-precision vector \mathbf{x} ; that is, the result is the first \mathbf{i} , \mathbf{i} = 0 to \mathbf{n} -1, that maximizes $abs(\mathbf{x}[1+\mathbf{i}*incx])$. The result reflects 1-based indexing for compatibility with Fortran.

Input

n	number of elements in input vector
x	single-precision vector with n elements
incx	storage spacing between elements of x
Output	

Output

returns the smallest index (returns zero if n <= 0 or incx <= 0)

Reference: http://www.netlib.org/blas/isamax.f

CHAPTER 2 BLAS1 Functions

Error status for this function can be retrieved via **cublasGetError()**. Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasIsamin()

int

```
cublasIsamin (int n, const float *x, int incx)
```

finds the smallest index of the minimum magnitude element of single-precision vector \mathbf{x} ; that is, the result is the first \mathbf{i} , \mathbf{i} = 0 to \mathbf{n} -1, that minimizes $\mathtt{abs}(\mathbf{x}[1+\mathbf{i}*\mathtt{incx}])$. The result reflects 1-based indexing for compatibility with Fortran.

Input

n	number of elements in input vector
x	single-precision vector with n elements
incx	storage spacing between elements of x
Output	

Reference: http://www.netlib.org/scilib/blass.f

returns the smallest index (returns zero if n <= 0 or incx <= 0)

Error status for this function can be retrieved via cublasGetError().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasSasum()

float

```
cublasSasum (int n, const float *x, int incx)
```

computes the sum of the absolute values of the elements of single-precision vector \mathbf{x} ; that is, the result is the sum from $\mathbf{i} = 0$ to $\mathbf{n} - 1$ of $abs(\mathbf{x}[1+\mathbf{i}*incx])$.

Input

•	
n	number of elements in input vector
x	single-precision vector with n elements
incx	storage spacing between elements of x

Output

returns the single-precision sum of absolute values (returns zero if n <= 0 or incx <= 0, or if an error occurred)

Reference: http://www.netlib.org/blas/sasum.f

Error status for this function can be retrieved via cublasGetError().

Frror Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasSaxpy()

void

multiplies single-precision vector x by single-precision scalar alpha and adds the result to single-precision vector y; that is, it overwrites single-precision y with single-precision alpha * x + y.

```
For i = 0 to n-1, it replaces
```

```
y[ly+i*incy] with alpha *x[lx+i*incx]+y[ly+i*incy],
```

CHAPTER 2 BLAS1 Functions

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1-n) * incx;
```

ly is defined in a similar way using incy.

Input

-	
n	number of elements in input vectors
alpha	single-precision scalar multiplier
х	single-precision vector with n elements
incx	storage spacing between elements of x
У	single-precision vector with n elements
incy	storage spacing between elements of y

Output

y single-precision result (unchanged if n <= 0)

Reference: http://www.netlib.org/blas/saxpy.f

Error status for this function can be retrieved via **cublasGetError()**.

Frror Status

CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU

Function cublasScopy()

void

copies the single-precision vector \mathbf{x} to the single-precision vector \mathbf{y} . For i = 0 to n-1, it copies

```
x[lx+i*incx] to y[ly+i*incy],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1-n) * incx;
```

PG-00000-002_V2.3 NVIDIA

ly is defined in a similar way using incy.

Input

n	number of elements in input vectors
x	single-precision vector with n elements
incx	storage spacing between elements of x
У	single-precision vector with n elements
incy	storage spacing between elements of y

Output

У	contains single-precision vector x	

Reference: http://www.netlib.org/blas/scopy.f

Error status for this function can be retrieved via cublasGetError().

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasSdot()

float

computes the dot product of two single-precision vectors. It returns the dot product of the single-precision vectors x and y if successful, and 0.0f otherwise. It computes the sum for i = 0 to n-1 of

```
x[lx+i*incx]*y[ly+i*incy],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1-n) * incx;
```

ly is defined in a similar way using incy.

Input

n	number of elements in input vectors
x	single-precision vector with n elements

CHAPTER 2 BLAS1 Functions

Input (continued)

incx	storage spacing between elements of x
У	single-precision vector with n elements
incy	storage spacing between elements of y

Output

returns single-precision dot product (returns zero if n <= 0)

Reference: http://www.netlib.org/blas/sdot.f

Error status for this function can be retrieved via cublasGetError().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to execute on GPU

Function cublasSnrm2()

float

cublasSnrm2 (int n, const float *x, int incx)

computes the Euclidean norm of the single-precision n-vector x (with storage increment incx). This code uses a multiphase model of accumulation to avoid intermediate underflow and overflow.

Input

n	number of elements in input vector
x	single-precision vector with n elements
incx	storage spacing between elements of x

Output

returns the Euclidian norm (returns zero if n <= 0, incx <= 0, or if an error occurred)

Reference: http://www.netlib.org/blas/snrm2.f

Reference: http://www.netlib.org/slatec/lin/snrm2.f

Error status for this function can be retrieved via **cublasGetError()**. Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasSrot()

void

multiplies a 2×2 matrix
$$\begin{bmatrix} \texttt{sc ss} \\ -\texttt{ss sc} \end{bmatrix}$$
 with the 2×n matrix $\begin{bmatrix} \texttt{x}^T \\ \texttt{y}^T \end{bmatrix}$.

The elements of x are in x[1x+i*incx], i = 0 to n-1, where

$$1x = 1 \text{ if incx} >= 0, \text{ else}$$

 $1x = 1 + (1-n) * \text{incx};$

y is treated similarly using ly and incy.

Input

n	number of elements in input vectors
x	single-precision vector with n elements
incx	storage spacing between elements of x
У	single-precision vector with n elements
incy	storage spacing between elements of y
sc	element of rotation matrix
SS	element of rotation matrix

Output

х	rotated vector x (unchanged if n <= 0)
У	rotated vector y (unchanged if n <= 0)

Reference: http://www.netlib.org/blas/srot.f

CHAPTER 2 BLAS1 Functions

Error status for this function can be retrieved via **cublasGetError()**. Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasSrotg()

void

cublasSrotg (float *sa, float *sb, float *sc, float *ss) constructs the Givens transformation

$$G = \begin{bmatrix} sc ss \\ -ss sc \end{bmatrix}, \quad sc^2 + ss^2 = 1$$

which zeros the second entry of the 2-vector $\begin{bmatrix} sa & sb \end{bmatrix}^T$.

The quantity $r = \pm \sqrt{sa^2 + sb^2}$ overwrites sa in storage. The value of sb is overwritten by a value z which allows sc and ss to be recovered by the following algorithm:

if
$$z = 1$$
 set $sc = 0.0$ and $ss = 1.0$.
if $abs(z) < 1$ set $sc = \sqrt{1 - z^2}$ and $ss = z$.
if $abs(z) > 1$ set $sc = 1/z$ and $ss = \sqrt{1 - sc^2}$.

The function **cublasSrot**(n, x, incx, y, incy, sc, ss) normally is called next to apply the transformation to a $2 \times n$ matrix.

Input

sa	single-precision scalar
sb	single-precision scalar
Output	
sa	single-precision r
sb	single-precision z
sc	single-precision result
ss	single-precision result

Reference: http://www.netlib.org/blas/srotg.f

This function does not set any error status.

Function cublasSrotm()

applies the modified Givens transformation, h, to the $2\times n$ matrix $\begin{bmatrix} x^T \\ y^T \end{bmatrix}$

The elements of x are in x[lx+i*incx], i = 0 to n-1, where

$$1x = 1$$
 if incx >= 0, else
 $1x = 1 + (1 - n) * incx;$

y is treated similarly using ly and incy.

With sparam[0] = sflag, h has one of the following forms:

Input

n	number of elements in input vectors.
x	single-precision vector with n elements.
incx	storage spacing between elements of x.
У	single-precision vector with n elements.
incy	storage spacing between elements of y.
sparam	5-element vector. sparam[0] is sflag described above. sparam[1] through sparam[4] contain the 2×2 rotation matrix h: sparam[1] contains sh00, sparam[2] contains sh10, sparam[3] contains sh01, and sparam[4] contains sh11.

24 PG-00000-002_V2.3 NVIDIA

CHAPTER 2 BLAS1 Functions

Output

х	rotated vector x (unchanged if n <= 0)
У	rotated vector y (unchanged if n <= 0)

Reference: http://www.netlib.org/blas/srotm.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasSrotmg()

void

constructs the modified Givens transformation matrix h which zeros the second component of the 2-vector $(\sqrt{\text{sd1}}*\text{sx1}, \sqrt{\text{sd2}}*\text{sy1})^T$.

With sparam[0] = sflag, h has one of the following forms:

sparam[1] through sparam[4] contain sh00, sh10, sh01, and sh11, respectively. Values of 1.0f, -1.0f, or 0.0f implied by the value of sflag are not stored in sparam.

Input

sd1	single-precision scalar.
sd2	single-precision scalar.
sx1	single-precision scalar.
sy1	single-precision scalar.

Οι	ıtr	ııt.
\mathcal{O}_{L}	ıιμ	·uι

sd1	changed to represent the effect of the transformation.
sd2	changed to represent the effect of the transformation.
sx1	changed to represent the effect of the transformation.
sparam	5-element vector. sparam[0] is sflag described above. sparam[1] through sparam[4] contain the 2×2 rotation matrix h: sparam[1] contains sh00, sparam[2] contains sh10, sparam[3] contains sh01, and sparam[4] contains sh11.

Reference: http://www.netlib.org/blas/srotmg.f

This function does not set any error status.

Function cublasSscal()

void

```
cublasSscal (int n, float alpha, float *x, int incx)
```

replaces single-precision vector $\mathbf x$ with single-precision alpha * $\mathbf x$. For i = 0 to n-1, it replaces

$$x[lx+i*incx]$$
 with alpha * $x[lx+i*incx]$,

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1-n) * incx.
```

Input

n	number of elements in input vector
alpha	single-precision scalar multiplier
x	single-precision vector with n elements
incx	storage spacing between elements of x

Output

х	single-precision result (unchanged if n <= 0 or incx <= 0)	

Reference: http://www.netlib.org/blas/sscal.f

CHAPTER 2 BLAS1 Functions

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasSswap()

void

interchanges single-precision vector \mathbf{x} with single-precision vector \mathbf{y} . For $\mathbf{i} = 0$ to $\mathbf{n} - 1$, it interchanges

```
x[lx+i*incx] with y[ly+i*incy],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1-n) * incx;
```

ly is defined in a similar manner using incy.

Input

n	number of elements in input vectors
x	single-precision vector with n elements
incx	storage spacing between elements of x
У	single-precision vector with n elements
incy	storage spacing between elements of y

Output

х	input vector y (unchanged if n <= 0)
У	input vector x (unchanged if n <= 0)

Reference: http://www.netlib.org/blas/sswap.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

PG-00000-002_V2.3 NVIDIA

Single-Precision Complex BLAS1 Functions

The single-precision complex BLAS1 functions are as follows:

```
□ "Function cublasCaxpy()" on page 28
```

- □ "Function cublasCcopy()" on page 29
- □ "Function cublasCdotc()" on page 30
- □ "Function cublasCdotu()" on page 31
- □ "Function cublasCrot()" on page 32
- □ "Function cublasCrotg()" on page 33
- □ "Function cublasCscal()" on page 34
- □ "Function cublasCsrot()" on page 35
- □ "Function cublasCsscal()" on page 36
- □ "Function cublasCswap()" on page 37
- □ "Function cublasIcamax()" on page 37
- □ "Function cublasIcamin()" on page 38
- □ "Function cublasScasum()" on page 39
- □ "Function cublasScnrm2()" on page 40

Function cublasCaxpy()

```
void
```

multiplies single-precision complex vector \mathbf{x} by single-precision complex scalar alpha and adds the result to single-precision complex vector \mathbf{y} ; that is, it overwrites single-precision complex \mathbf{y} with single-precision complex alpha * $\mathbf{x} + \mathbf{y}$.

```
For i = 0 to n-1, it replaces
    y[ly + i * incy] with alpha * x[lx + i * incx] + y[ly + i * incy],
where
    lx = 0 if incx >= 0, else
    lx = 1 + (1-n) * incx;
```

28 PG-00000-002_V2.3 NVIDIA

ly is defined in a similar way using incy.

Input

-		
n	number of elements in input vectors	
alpha	single-precision complex scalar multiplier	
x	single-precision complex vector with n elements	
incx	storage spacing between elements of x	
У	single-precision complex vector with n elements	
incy	storage spacing between elements of y	

Output

У	single-precision complex result (unchanged if n <= 0)	

Reference: http://www.netlib.org/blas/caxpy.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasCcopy()

```
void
```

copies the single-precision complex vector \mathbf{x} to the single-precision complex vector \mathbf{y} .

```
For i = 0 to n-1, it copies
    x[lx + i * incx] to y[ly + i * incy],
where
    lx = 1 if incx >= 0, else
    lx = 1 + (1 - n) * incx;
```

ly is defined in a similar way using incy.

Input

n	number of elements in input vectors
x	single-precision complex vector with n elements
incx	storage spacing between elements of x
У	single-precision complex vector with n elements
incy	storage spacing between elements of y
-	

Output

				1	
V	contains	sinole.	-nrecision	complex v	rector x
4	COIICUIIIO	OIIIGIC	PICCIOIOII	COLLIDICAL V	CCCCI 21

Reference: http://www.netlib.org/blas/ccopy.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasCdotc()

```
cuComplex
```

computes the dot product of two single-precision complex vectors, the first of which is conjugated. It returns the dot product of the complex conjugate of single- precision complex vector \mathbf{x} and the single-precision complex vector \mathbf{y} if successful, and complex zero otherwise. For $\mathbf{i} = 0$ to $\mathbf{n} - 1$, it sums the products

```
\overline{x[1x+i*incx]} * y[1y+i*incy],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1-n) * incx;
```

ly is defined in a similar way using incy.

Input

-	
n	number of elements in input vectors
x	single-precision complex vector with n elements
incx	storage spacing between elements of x
У	single-precision complex vector with n elements
incy	storage spacing between elements of y

Output

returns single-precision complex dot product (zero if $n \le 0$)

Reference: http://www.netlib.org/blas/cdotc.f

Error status for this function can be retrieved via cublasGetError().

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS_STATUS_ALLOC_FAILED if function could not allocate reduction buffer

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasCdotu()

```
cuComplex
```

```
cublasCdotu (int n, const cuComplex *x, int incx, const cuComplex *y, int incy)
```

computes the dot product of two single-precision complex vectors. It returns the dot product of the single-precision complex vectors \mathbf{x} and \mathbf{y} if successful, and complex zero otherwise. For $\mathbf{i} = 0$ to $\mathbf{n} - 1$, it sums the products

```
x[lx+i*incx] * y[ly+i*incy],
where
lx = 1 if incx >= 0, else
lx = 1+(1-n)*incx;
```

ly is defined in a similar way using incy.

Input

n	number of elements in input vectors
x	single-precision complex vector with n elements
incx	storage spacing between elements of x
У	single-precision complex vector with n elements
incy	storage spacing between elements of y

Output

returns single-precision complex dot product (returns zero if $n \le 0$)

Reference: http://www.netlib.org/blas/cdotu.f

Error status for this function can be retrieved via cublasGetError().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS STATUS EXECUTION FAILED	if function failed to launch on GPU

Function cublasCrot()

void

multiplies a 2×2 matrix
$$\begin{bmatrix} sccs \\ -cssc \end{bmatrix}$$
 with the 2×n matrix $\begin{bmatrix} x^T \\ y^T \end{bmatrix}$.

The elements of x are in x[1x + i * incx], i = 0 to n-1, where

$$1x = 1$$
 if incx >= 0, else
 $1x = 1 + (1-n) * incx;$

y is treated similarly using ly and incy.

Input

n number of elements in input vectorsx single-precision complex vector with n elements

Input (continued)

incx	storage spacing between elements of x
У	single-precision complex vector with n elements
incy	storage spacing between elements of y
sc	single-precision cosine component of rotation matrix
CS	single-precision complex sine component of rotation matrix

Output

х	rotated vector x (unchanged if n <= 0)
У	rotated vector y (unchanged if n <= 0)

Reference: http://netlib.org/lapack/explore-html/crot.f.html

Error status for this function can be retrieved via **cublasGetError()**. Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasCrotg()

void

constructs the complex Givens transformation

$$G = \begin{bmatrix} sc cs \\ -cs sc \end{bmatrix}, sc*sc+cs*cs = 1$$

which zeros the second entry of the complex 2-vector $\begin{bmatrix} ca & cb \end{bmatrix}^T$.

The quantity ca/|ca|*||ca, cb|| overwrites ca in storage. In this case,

$$||ca, cb|| = scale * \sqrt{|ca/scale|^2 + |cb/scale|^2}$$
, where $|scale| = |ca| + |cb|$.

The function **cublasCrot** (n, x, incx, y, incy, sc, cs) normally is called next to apply the transformation to a $2 \times n$ matrix.

Input

•	
ca	single-precision complex scalar
cb	single-precision complex scalar
Output	
са	single-precision complex ca/ ca * ca, cb
sc	single-precision cosine component of rotation matrix
CS	single-precision complex sine component of rotation matrix

Reference: http://www.netlib.org/blas/crotg.f

This function does not set any error status.

Function cublasCscal()

void

replaces single-precision complex vector \mathbf{x} with single-precision complex alpha * \mathbf{x} .

For i = 0 to n-1, it replaces

```
x[lx+i*incx] with alpha * x[lx+i*incx],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1-n) * incx.
```

Input

n	number of elements in input vector
alpha	single-precision complex scalar multiplier
x	single-precision complex vector with n elements
incx	storage spacing between elements of x

Output

x single-precision complex result (unchanged if n <= 0 or incx <= 0)

Reference: http://www.netlib.org/blas/cscal.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU

Function cublasCsrot()

void

multiplies a 2×2 matrix
$$\begin{bmatrix} sc ss \\ -ss sc \end{bmatrix}$$
 with the 2×n matrix $\begin{bmatrix} x^T \\ y^T \end{bmatrix}$.

The elements of x are in x[lx+i*incx], i = 0 to n-1, where

$$1x = 1$$
 if incx >= 0, else
 $1x = 1 + (1-n) * incx;$

y is treated similarly using ly and incy.

Input

n	number of elements in input vectors
x	single-precision complex vector with n elements
incx	storage spacing between elements of x
У	single-precision complex vector with n elements
incy	storage spacing between elements of y
sc	single-precision cosine component of rotation matrix
ss	single-precision sine component of rotation matrix

Output

x	rotated vector x (unchanged if n <= 0)
У	rotated vector y (unchanged if n <= 0)

Reference: http://www.netlib.org/blas/csrot.f

Error status for this function can be retrieved via **cublasGetError()**. Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasCsscal()

void

cublasCsscal (int n, float alpha, cuComplex *x, int incx) replaces single-precision complex vector x with single-precision complex alpha * x. For i = 0 to n-1, it replaces

```
x[lx+i*incx] with alpha * x[lx+i*incx],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1-n) * incx.
```

Input

n	number of elements in input vector
alpha	single-precision scalar multiplier
x	single-precision complex vector with n elements
incx	storage spacing between elements of x

Output

x single-precision complex result (unchanged if n <= 0 or incx <= 0)

Reference: http://www.netlib.org/blas/csscal.f

Error status for this function can be retrieved via **cublasGetError()**. Error Status

CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU

Function cublasCswap()

void

interchanges the single-precision complex vector \mathbf{x} with the single-precision complex vector \mathbf{y} . For $\mathbf{i} = 0$ to $\mathbf{n} - 1$, it interchanges

```
x[1x+i*incx] with y[1y+i*incy],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1 - n) * incx;
```

ly is defined in a similar way using incy.

Input

n	number of elements in input vectors
x	single-precision complex vector with n elements
incx	storage spacing between elements of x
У	single-precision complex vector with n elements
incy	storage spacing between elements of y

Output

х	contains-single-precision complex vector y
У	contains-single-precision complex vector x

Reference: http://www.netlib.org/blas/cswap.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU

Function cublasIcamax()

int

```
cublasIcamax (int n, const cuComplex *x, int incx)
```

finds the smallest index of the maximum magnitude element of single-precision complex vector x; that is, the result is the first i, i = 0 to n-1,

that maximizes abs(x[1+i*incx]). The result reflects 1-based indexing for compatibility with Fortran.

Input

n	number of elements in input vector
x	single-precision complex vector with n elements
incx	storage spacing between elements of x

Output

returns the smallest index (returns zero if n <= 0 or incx <= 0)

Reference: http://www.netlib.org/blas/icamax.f

Error status for this function can be retrieved via cublasGetError().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasIcamin()

int

cublasIcamin (int n, const cuComplex *x, int incx)

finds the smallest index of the minimum magnitude element of single-precision complex vector \mathbf{x} ; that is, the result is the first \mathbf{i} , $\mathbf{i} = 0$ to $\mathbf{n} - 1$, that minimizes $\mathtt{abs}(\mathbf{x}[1+\mathbf{i}*\mathtt{incx}])$. The result reflects 1-based indexing for compatibility with Fortran.

Input

mpat	
n	number of elements in input vector
x	single-precision complex vector with n elements
incx	storage spacing between elements of x
Output	
returns	the smallest index (returns zero if n <= 0 or incx <= 0)

Reference: Analogous to http://www.netlib.org/blas/icamax.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasScasum()

float

```
cublasScasum (int n, const cuDouble *x, int incx)
```

takes the sum of the absolute values of a complex vector and returns a single-precision result. Note that this is not the L1 norm of the vector. The result is the sum from 0 to n-1 of

```
abs(real(x[lx+i*incx])) + abs(imag(x[lx+i*incx])),
```

where

```
1x = 1 if incx <= 0, else

1x = 1 + (1-n) * incx.
```

Input

n	number of elements in input vector
х	single-precision complex vector with n elements
incx	storage spacing between elements of x

Output

returns the single-precision sum of absolute values of real and imaginary parts (returns zero if n <= 0, incx <= 0, or if an error occurred)

Reference: http://www.netlib.org/blas/scasum.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasScnrm2()

float

cublasScnrm2 (int n, const cuComplex *x, int incx)

computes the Euclidean norm of single-precision complex n-vector x. This implementation uses simple scaling to avoid intermediate underflow and overflow.

Input

•	
n	number of elements in input vector
x	single-precision complex vector with n elements
incx	storage spacing between elements of x

Output

```
returns the Euclidian norm
(returns zero if n <= 0, incx <= 0, or if an error occurred)
```

Reference: http://www.netlib.org/blas/scnrm2.f

Error status for this function can be retrieved via cublasGetError().

Frror Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Double-Precision BLAS1 Functions

Note: Double-precision functions are only supported on GPUs with double-precision hardware.

The double-precision BLAS1 functions are as follows:

- □ "Function cublasIdamax()" on page 41
- □ "Function cublasIdamin()" on page 42
- □ "Function cublasDasum()" on page 43
- □ "Function cublasDaxpy()" on page 44
- □ "Function cublasDcopy()" on page 45
- □ "Function cublasDdot()" on page 46
- □ "Function cublasDnrm2()" on page 47
- □ "Function cublasDrot()" on page 47
- □ "Function cublasDrotg()" on page 48
- □ "Function cublasDrotm()" on page 49
- □ "Function cublasDrotmg()" on page 51
- □ "Function cublasDscal()" on page 52
- □ "Function cublasDswap()" on page 52

Function cublasIdamax()

int

```
cublasIdamax (int n, const double *x, int incx)
```

finds the smallest index of the maximum magnitude element of double-precision vector x; that is, the result is the first i, i = 0 to n-1, that maximizes abs(x[1+i*incx]). The result reflects 1-based indexing for compatibility with Fortran.

Input

n	number of elements in input vector
x	double-precision vector with n elements
incx	storage spacing between elements of x

Output

Reference: http://www.netlib.org/blas/idamax.f

Error status for this function can be retrieved via cublasGetError().

Frror Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasIdamin()

int

cublasIdamin (int n, const double *x, int incx)

finds the smallest index of the minimum magnitude element of double-precision vector \mathbf{x} ; that is, the result is the first \mathbf{i} , \mathbf{i} = 0 to n-1, that minimizes abs($\mathbf{x}[1+\mathbf{i}*incx]$). The result reflects 1-based indexing for compatibility with Fortran.

Input

n	number of elements in input vector
x	double-precision vector with n elements
incx	storage spacing between elements of x

Output

returns the smallest index (returns zero if n <= 0 or incx <= 0)

Analogous to http://www.netlib.org/blas/idamax.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer

Error Status (continued)

CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDasum()

double

cublasDasum (int n, const double *x, int incx)

computes the sum of the absolute values of the elements of double-precision vector \mathbf{x} ; that is, the result is the sum from $\mathbf{i} = 0$ to n-1 of $abs(\mathbf{x}[1+\mathbf{i}*incx])$.

Input

n	number of elements in input vector
x	double-precision vector with n elements
incx	storage spacing between elements of x

Output

returns the double-precision sum of absolute values (returns zero if n <= 0 or incx <= 0, or if an error occurred)

Reference: http://www.netlib.org/blas/dasum.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDaxpy()

void

multiplies double-precision vector \mathbf{x} by double-precision scalar alpha and adds the result to double-precision vector \mathbf{y} ; that is, it overwrites double-precision \mathbf{y} with double-precision alpha * $\mathbf{x} + \mathbf{y}$.

For i = 0 to n-1, it replaces

```
y[ly+i*incy] with alpha * x[lx+i*incx]+y[ly+i*incy],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1 - n) * incx;
```

ly is defined in a similar way using incy.

Input

n	number of elements in input vectors
alpha	double-precision scalar multiplier
х	double-precision vector with n elements
incx	storage spacing between elements of x
У	double-precision vector with n elements
incy	storage spacing between elements of y

Output

У	double-precision result (unchanged if n <= 0)
---	-----------------------------------------------

Reference: http://www.netlib.org/blas/daxpy.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS_STATUS_ARCH_MISMATCH if function invoked on device that does not support double precision

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasDcopy()

void

copies the double-precision vector \mathbf{x} to the double-precision vector \mathbf{y} . For $\mathbf{i} = 0$ to $\mathbf{n}-1$, it copies

```
x[lx+i*incx] to y[ly+i*incy],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1 - n) * incx;
```

ly is defined in a similar way using incy.

Input

n	number of elements in input vectors
x	double-precision vector with n elements
incx	storage spacing between elements of x
У	double-precision vector with n elements
incy	storage spacing between elements of y

Output

y contains double-precision vector x

Reference: http://www.netlib.org/blas/dcopy.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDdot()

double

computes the dot product of two double-precision vectors. It returns the dot product of the double-precision vectors x and y if successful, and 0.0 otherwise. It computes the sum for i = 0 to n-1 of

```
x[lx+i*incx]*y[ly+i*incy],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1-n) * incx;
```

ly is defined in a similar way using incy.

Input

•	
n	number of elements in input vectors
x	double-precision vector with n elements
incx	storage spacing between elements of x
У	double-precision vector with n elements
incy	storage spacing between elements of y

Output

returns double-precision dot product (returns zero if n <= 0)

Reference: http://www.netlib.org/blas/ddot.f

Error status for this function can be retrieved via cublasGetError().

Frror Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDnrm2()

double

cublasDnrm2 (int n, const double *x, int incx)

computes the Euclidean norm of the double-precision n-vector x (with storage increment incx). This code uses a multiphase model of accumulation to avoid intermediate underflow and overflow.

Input

n	number of elements in input vector
х	double-precision vector with n elements
incx	storage spacing between elements of x

Output

returns the Euclidian norm (returns zero if n <= 0, incx <= 0, or if an error occurred)

Reference: http://www.netlib.org/blas/dnrm2.f

Reference: http://www.netlib.org/slatec/lin/dnrm2.f

Error status for this function can be retrieved via cublasGetError().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDrot()

void

multiplies a 2×2 matrix
$$\begin{bmatrix} dc & ds \\ -ds & dc \end{bmatrix}$$
 with the 2×n matrix $\begin{bmatrix} x^T \\ y^T \end{bmatrix}$.

The elements of x are in x[1x + i * incx], i = 0 to n-1, where

$$1x = 1$$
 if incx >= 0, else
 $1x = 1 + (1-n) * incx;$

y is treated similarly using ly and incy.

Input

•	
n	number of elements in input vectors
x	double-precision vector with n elements
incx	storage spacing between elements of x
У	double-precision vector with n elements
incy	storage spacing between elements of y
dc	element of rotation matrix
ds	element of rotation matrix

Output

х	rotated vector x (unchanged if n <= 0)
У	rotated vector y (unchanged if n <= 0)

Reference: http://www.netlib.org/blas/drot.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDrotg()

void

constructs the Givens transformation

$$G = \begin{bmatrix} dc & ds \\ -ds & dc \end{bmatrix}, \qquad dc^2 + ds^2 = 1$$

which zeros the second entry of the 2-vector $\begin{bmatrix} da & db \end{bmatrix}^T$.

The quantity $r = \pm \sqrt{da^2 + db^2}$ overwrites da in storage. The value of db is overwritten by a value z which allows dc and ds to be recovered by the following algorithm:

```
if z = 1 set dc = 0.0 and ds = 1.0.

if abs(z) < 1 set dc = \sqrt{1-z^2} and ds = z.

if abs(z) > 1 set dc = 1/z and ds = \sqrt{1-dc^2}.
```

The function **cublasDrot**(n, x, incx, y, incy, dc, ds) normally is called next to apply the transformation to a $2 \times n$ matrix.

Input

da	double-precision scalar
db	double-precision scalar
Output	
da	double-precision r
db	double-precision z
dc	double-precision result
ds	double-precision result

Reference: http://www.netlib.org/blas/drotg.f

This function does not set any error status.

Function cublasDrotm()

void

applies the modified Givens transformation, h, to the $2 \times n$ matrix $\begin{bmatrix} x^T \\ y^T \end{bmatrix}$

The elements of x are in x[1x+i*incx], i = 0 to n-1, where

$$lx = 1 \text{ if incx} >= 0, else$$

 $lx = 1 + (1-n) * incx;$

y is treated similarly using ly and incy.

With dparam[0] = dflag, h has one of the following forms:

$$\begin{array}{ll} \mbox{dflag} = -1.0 & \mbox{dflag} = 0.0 \\ \mbox{h} = \begin{bmatrix} \mbox{dh00 dh01} \\ \mbox{dh10 dh11} \end{bmatrix} & \mbox{h} = \begin{bmatrix} \mbox{1.0 dh01} \\ \mbox{dh10 1.0} \end{bmatrix} \\ \mbox{dflag} = 1.0 & \mbox{dflag} = -2.0 \\ \mbox{h} = \begin{bmatrix} \mbox{dh00 1.0} \\ \mbox{-1.0 dh11} \end{bmatrix} & \mbox{h} = \begin{bmatrix} \mbox{1.0 0.0} \\ \mbox{0.0 1.0} \end{bmatrix} \end{array}$$

Input

n	number of elements in input vectors.
x	double-precision vector with n elements.
incx	storage spacing between elements of x.
У	double-precision vector with n elements.
incy	storage spacing between elements of y.
dparam	5-element vector. dparam[0] is dflag described above. dparam[1] through dparam[4] contain the 2×2 rotation matrix h: dparam[1] contains dh00, dparam[2] contains dh10, dparam[3] contains dh01, and dparam[4] contains dh11.

Output

x	rotated vector x (unchanged if n <= 0)
У	rotated vector y (unchanged if n <= 0)

Reference: http://www.netlib.org/blas/drotm.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDrotmg()

void

constructs the modified Givens transformation matrix h which zeros the second component of the 2-vector $(\sqrt{dd1}*dx1, \sqrt{dd2}*dy1)^T$.

With dparam[0] = dflag, h has one of the following forms:

$$\begin{array}{ll} \text{dflag} = -1.0 & \text{dflag} = 0.0 \\ \text{h} = \begin{bmatrix} \text{dh00 dh01} \\ \text{dh10 dh11} \end{bmatrix} & \text{h} = \begin{bmatrix} 1.0 & \text{dh01} \\ \text{dh10} & 1.0 \end{bmatrix} \\ \text{dflag} = 1.0 & \text{dflag} = -2.0 \\ \text{h} = \begin{bmatrix} \text{dh00 1.0} \\ -1.0 & \text{dh11} \end{bmatrix} & \text{h} = \begin{bmatrix} 1.0 & 0.0 \\ 0.0 & 1.0 \end{bmatrix} \end{array}$$

dparam[1] through dparam[4] contain dh00, dh10, dh01, and dh11, respectively. Values of 1.0, -1.0, or 0.0 implied by the value of dflag are not stored in dparam.

Input

-	
dd1	double-precision scalar
dd2	double-precision scalar
dx1	double-precision scalar
dy1	double-precision scalar

Output

dd1	changed to represent the effect of the transformation
dd2	changed to represent the effect of the transformation
dx1	changed to represent the effect of the transformation
dparam	5-element vector. dparam[0] is dflag described above. dparam[1] through dparam[4] contain the 2×2 rotation matrix h: dparam[1] contains dh00, dparam[2] contains dh10, dparam[3] contains dh01, and dparam[4] contains dh11.

Reference: http://www.netlib.org/blas/drotmg.f

This function does not set any error status.

Function cublasDscal()

void

cublasDscal (int n, double alpha, double *x, int incx)

replaces double-precision vector \mathbf{x} with double-precision alpha * \mathbf{x} . For \mathbf{i} = 0 to n-1, it replaces

```
x[1x+i*incx] with alpha * x[1x+i*incx],
```

where

```
lx = 1 if incx >= 0, else
```

$$lx = 1 + (1 - n) * incx.$$

Input

·-	
n	number of elements in input vector
alpha	double-precision scalar multiplier
x	double-precision vector with n elements
incx	storage spacing between elements of x

Output

X	double-precision result (unchanged if n <= 0 or incx <= 0)	

Reference: http://www.netlib.org/blas/dscal.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDswap()

void

interchanges double-precision vector \mathbf{x} with double-precision vector \mathbf{y} . For $\mathbf{i} = 0$ to $\mathbf{n}-1$, it interchanges

```
x[lx+i*incx] with y[ly+i*incy],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1 - n) * incx;
```

ly is defined in a similar manner using incy.

Input

n	number of elements in input vectors
x	double-precision vector with n elements
incx	storage spacing between elements of x
У	double-precision vector with n elements
incy	storage spacing between elements of y

Output

х	input vector y (unchanged if n <= 0)
У	input vector x (unchanged if n <= 0)

Reference: http://www.netlib.org/blas/dswap.f

Error status for this function can be retrieved via **cublasGetError()**.

Frror Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Double-Precision Complex BLAS1 functions

Note: Double-precision functions are only supported on GPUs with double-precision hardware.

Two double-precision complex BLAS1 functions are implemented:

- □ "Function cublasZdotu()" on page 54
- □ "Function cublasZscal()" on page 55

Function cublasZdotu()

cuDoubleComplex

computes the dot product of two double-precision complex vectors. It returns the dot product of the double-precision complex vectors \mathbf{x} and \mathbf{y} if successful, and complex zero otherwise. For $\mathbf{i} = 0$ to $\mathbf{n} - 1$, it sums the products

```
x[lx+i*incx]*y[ly+i*incy],
```

where

```
1x = 1 if incx >= 0, else

1x = 1 + (1-n) * incx;
```

ly is defined in a similar way using incy.

Input

n	number of elements in input vectors
х	double-precision complex vector with n elements
incx	storage spacing between elements of x
У	double-precision complex vector with n elements
incy	storage spacing between elements of y

Output

returns double-precision complex dot product (returns zero if n <= 0)

Reference: http://www.netlib.org/blas/zdotu.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	if function could not allocate reduction buffer
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasZscal()

void

```
cublasZscal (int n, cuDoubleComplex alpha,
             cuDoubleComplex *x, int incx)
```

replaces double-precision complex vector x with double-precision complex alpha * x.

```
For i = 0 to n-1, it replaces
```

```
x[1x+i*incx] with alpha * x[1x+i*incx],
```

where

```
1x = 1 if incx >= 0, else
1x = 1 + (1 - n) * incx.
```

Input

n	number of elements in input vector
alpha	double-precision complex scalar multiplier
x	double-precision complex vector with n elements
incx	storage spacing between elements of x

Output

double-precision complex result (unchanged if n <= 0 or incx <= 0) х

Reference: http://www.netlib.org/blas/zscal.f

Error status for this function can be retrieved via cublasGetError(). **Error Status**

CUBLAS_STATUS_NOT_INITIALIZED CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU CUBLAS STATUS ARCH MISMATCH

if CUBLAS library was not initialized if function invoked on device that does not support double precision

CHAPTER

3

BLAS2 Functions

The Level 2 Basic Linear Algebra Subprograms (BLAS2) are functions that perform matrix-vector operations. The CUBLAS implementations are described in the following sections:

- □ "Single-Precision BLAS2 Functions" on page 57
- □ "Single-Precision Complex BLAS2 Functions" on page 78 (*Not yet implemented*)
- □ "Double-Precision BLAS2 Functions" on page 79
- □ "Double-Precision Complex BLAS2 functions" on page 84

Single-Precision BLAS2 Functions

The single-precision BLAS2 functions are as follows:

- □ "Function cublasSgbmv()" on page 57
- □ "Function cublasSgemv()" on page 59
- □ "Function cublasSger()" on page 60
- □ "Function cublasSsbmv()" on page 61
- □ "Function cublasSspmv()" on page 63
- □ "Function cublasSspr()" on page 64
- □ "Function cublasSspr2()" on page 65
- □ "Function cublasSsymv()" on page 66
- □ "Function cublasSsyr()" on page 67
- □ "Function cublasSsyr2()" on page 68
- □ "Function cublasStbmv()" on page 70
- □ "Function cublasStbsv()" on page 71
- □ "Function cublasStpmv()" on page 73
- □ "Function cublasStpsv()" on page 74
- □ "Function cublasStrmv()" on page 75
- □ "Function cublasStrsv()" on page 77

Function cublasSgbmv()

alpha and beta are single-precision scalars, and x and y are single-precision vectors. A is an $m \times n$ band matrix consisting of single-precision elements with kl subdiagonals and ku superdiagonals.

Input

У

```
trans
         specifies op(A). If trans == 'N' or 'n', op(A) = A.
         If trans == 'T', 't', 'C', or 'c', op(A) = A^{T}.
         the number of rows of matrix A; m must be at least zero.
m
n
         the number of columns of matrix A; n must be at least zero.
kl
         the number of subdiagonals of matrix A; k1 must be at least zero.
ku
         the number of superdiagonals of matrix A; ku must be at least zero.
alpha
         single-precision scalar multiplier applied to op (A).
Α
         single-precision array of dimensions (lda, n). The leading
          (kl + ku + 1) \times n part of array A must contain the band matrix A,
         supplied column by column, with the leading diagonal of the matrix in
         row ku+1 of the array, the first superdiagonal starting at position 2 in
         row ku, the first subdiagonal starting at position 1 in row ku+2, and so
         on. Elements in the array A that do not correspond to elements in the
         band matrix (such as the top left ku×ku triangle) are not referenced.
lda
         leading dimension of A; 1da must be at least kl + ku + 1.
x
         single-precision array of length at least (1 + (n-1) * abs(incx))
         when trans == 'N' or 'n', and at least (1 + (m-1) * abs(incx))
         otherwise.
incx
         storage spacing between elements of x; incx must not be zero.
beta
         single-precision scalar multiplier applied to vector y. If beta is zero, y
         is not read.
         single-precision array of length at least (1 + (m-1) * abs(incy))
У
         when trans == 'N' or 'n' and at least (1 + (n-1) * abs(incy))
         otherwise. If beta is zero, y is not read.
incy
         storage spacing between elements of y; incy must not be zero.
Output
```

updated according to y = alpha * op(A) * x + beta * y.

Reference: http://www.netlib.org/blas/sgbmv.f

Error status for this function can be retrieved via **cublasGetError()**. Error Status

Function cublasSgemv()

```
void
```

performs one of the matrix-vector operations

```
y = alpha * op(A) * x + beta * y,
where op(A) = A or op(A) = A^{T},
```

alpha and beta are single-precision scalars, and x and y are single-precision vectors. A is an $m \times n$ matrix consisting of single-precision elements. Matrix A is stored in column-major format, and lda is the leading dimension of the two-dimensional array in which A is stored.

Input

```
trans
         specifies op (A). If trans == 'N' or 'n', op (A) = A.
         If trans == 'T', 't', 'C', or 'c', op(A) = A^{T}.
         specifies the number of rows of matrix A; m must be at least zero.
m
         specifies the number of columns of matrix A; n must be at least zero.
n
alpha
         single-precision scalar multiplier applied to op (A).
Α
         single-precision array of dimensions (lda, n) if trans == 'N' or
         'n', of dimensions (lda, m) otherwise; lda must be at least
         \max(1, m) if trans == 'N' or 'n' and at least \max(1, n) otherwise.
lda
         leading dimension of two-dimensional array used to store matrix A.
         single-precision array of length at least (1 + (n-1) * abs(incx)) if
х
         trans == 'N' or 'n', else at least (1 + (m-1) * abs(incx)).
incx
         specifies the storage spacing for elements of x; incx must not be zero.
beta
         single-precision scalar multiplier applied to vector y. If beta is zero, y
         is not read.
```

Input (continued)

У	single-precision array of length at least $(1 + (m-1) * abs(incy))$ if trans == 'N' or 'n', else at least $(1 + (n-1) * abs(incy))$.
incy	the storage spacing between elements of y; incy must not be zero.

Output

```
y updated according to y = alpha * op(A) * x + beta * y.
```

Reference: http://www.netlib.org/blas/sgemv.f

Error status for this function can be retrieved via cublasGetError().

Error Status

Function cublasSger()

void

performs the symmetric rank 1 operation

```
A = alpha * x * y^T + A
```

where alpha is a single-precision scalar, x is an m-element single-precision vector, y is an n-element single-precision vector, and A is an m×n matrix consisting of single-precision elements. Matrix A is stored in column-major format, and lda is the leading dimension of the two-dimensional array used to store A.

Input

m	specifies the number of rows of the matrix A; m must be at least zero.
n	specifies the number of columns of matrix A; n must be at least zero.
alpha	single-precision scalar multiplier applied to $x * y^T$.
x	single-precision array of length at least $(1 + (m-1) * abs(incx))$.
incx	the storage spacing between elements of x; incx must not be zero.

Input (continued)

У	single-precision array of length at least $(1 + (n-1) * abs(incy))$.
incy	the storage spacing between elements of y; incy must not be zero.
A	single-precision array of dimensions (lda, n).
lda	leading dimension of two-dimensional array used to store matrix A.

Output

```
A updated according to A = alpha * x * y^T + A.
```

Reference: http://www.netlib.org/blas/sger.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

Function cublasSsbmv()

void

performs the matrix-vector operation

```
y = alpha * A * x + beta * y,
```

where alpha and beta are single-precision scalars, and x and y are n-element single-precision vectors. A is an $n \times n$ symmetric band matrix consisting of single-precision elements, with k superdiagonals and the same number of subdiagonals.

Input

•	
uplo	specifies whether the upper or lower triangular part of the symmetric
	band matrix A is being supplied. If uplo == 'U' or 'u', the upper
	triangular part is being supplied. If uplo == 'L' or 'l', the lower
	triangular part is being supplied.
n	specifies the number of rows and the number of columns of the
	symmetric matrix A; n must be at least zero.

Input (continued)

k	specifies the number of superdiagonals of matrix A. Since the matrix is symmetric, this is also the number of subdiagonals; k must be at least zero.
alpha	single-precision scalar multiplier applied to A * x.
Α	single-precision array of dimensions (lda, n). When uplo == 'U' or 'u', the leading (k+1)×n part of array A must contain the upper triangular band of the symmetric matrix, supplied column by column, with the leading diagonal of the matrix in row k+1 of the array, the first superdiagonal starting at position 2 in row k, and so on. The top left k×k triangle of the array A is not referenced. When uplo == 'L' or 'l', the leading (k+1)×n part of the array A must contain the lower triangular band part of the symmetric matrix, supplied column by column, with the leading diagonal of the matrix in row 1 of the array, the first subdiagonal starting at position 1 in row 2, and so on. The bottom right k×k triangle of the array A is not referenced.
lda	leading dimension of A; 1da must be at least k+1.
х	single-precision array of length at least $(1 + (n-1) * abs(incx))$.
incx	storage spacing between elements of x; incx must not be zero.
beta	single-precision scalar multiplier applied to vector y. If beta is zero, y is not read.
У	single-precision array of length at least $(1+(n-1)*abs(incy))$. If beta is zero, y is not read.
incy	storage spacing between elements of y; incy must not be zero.
Output	

y updated according to y = alpha * A * x + beta * y.

Reference: http://www.netlib.org/blas/ssbmv.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if k < 0, n < 0, incx == 0, or incy == 0
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasSspmv()

```
void
```

performs the matrix-vector operation

```
y = alpha * A * x + beta * y,
```

where alpha and beta are single-precision scalars, and x and y are n-element single-precision vectors. A is a symmetric $n \times n$ matrix that consists of single-precision elements and is supplied in packed form.

Input

•	
uplo	specifies whether the matrix data is stored in the upper or the lower triangular part of array AP. If uplo == 'U' or 'u', the upper triangular part of A is supplied in AP. If uplo == 'L' or 'l', the lower triangular part of A is supplied in AP.
n	the number of rows and columns of matrix A; n must be at least zero.
alpha	single-precision scalar multiplier applied to A * x.
AP	single-precision array with at least $(n * (n+1))/2$ elements. If uplo == 'U' or 'u', array AP contains the upper triangular part of the symmetric matrix A, packed sequentially, column by column; that is, if $i <= j$, A[i,j] is stored in AP[i+(j*(j+1)/2)]. If uplo == 'L' or 'l', the array AP contains the lower triangular part of the symmetric matrix A, packed sequentially, column by column; that is, if $i >= j$, A[i,j] is stored in AP[i+((2*n-j+1)*j)/2].
x	single-precision array of length at least $(1 + (n-1) * abs(incx))$.
incx	storage spacing between elements of x; incx must not be zero.
beta	single-precision scalar multiplier applied to vector y. If beta is zero, y is not read.
У	single-precision array of length at least $(1+(n-1)*abs(incy))$. If beta is zero, y is not read.
incy	storage spacing between elements of y; incy must not be zero.

Output

```
y updated according to y = alpha * A * x + beta * y.
```

Reference: http://www.netlib.org/blas/sspmv.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if n < 0, incx == 0, or incy == 0
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasSspr()

void

performs the symmetric rank 1 operation

$$A = alpha * x * x^T + A$$
,

where alpha is a single-precision scalar, and x is an n-element single-precision vector. A is a symmetric $n \times n$ matrix that consists of single-precision elements and is supplied in packed form.

Input

uplo	specifies whether the matrix data is stored in the upper or the lower triangular part of array AP. If uplo == 'U' or 'u', the upper triangular part of A is supplied in AP. If uplo == 'L' or 'l', the lower triangular part of A is supplied in AP.
n	the number of rows and columns of matrix A; n must be at least zero.
alpha	single-precision scalar multiplier applied to $\mathbf{x} * \mathbf{x}^T$.
x	single-precision array of length at least $(1+(n-1)*abs(incx))$.
incx	storage spacing between elements of x; incx must not be zero.
AP	single-precision array with at least $(n * (n+1))/2$ elements. If uplo == 'U' or 'u', array AP contains the upper triangular part of the symmetric matrix A, packed sequentially, column by column; that is, if $i <= j$, A[i,j] is stored in AP[i+(j*(j+1)/2)]. If uplo == 'L' or 'l', the array AP contains the lower triangular part of the symmetric matrix A, packed sequentially, column by column; that is, if $i >= j$, A[i,j] is stored in AP[i+((2*n-j+1)*j)/2].

Output

A updated according to $A = alpha * x * x^T + A$.

Reference: http://www.netlib.org/blas/sspr.f

PG-00000-002_V2.3

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if n < 0 or incx == 0
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasSspr2()

void

performs the symmetric rank 2 operation

```
A = alpha * x * y^{T} + alpha * y * x^{T} + A,
```

where alpha is a single-precision scalar, and x and y are n-element single-precision vectors. A is a symmetric $n \times n$ matrix that consists of single-precision elements and is supplied in packed form.

```
uplo
         specifies whether the matrix data is stored in the upper or the lower
         triangular part of array A. If uplo == 'U' or 'u', only the upper
         triangular part of A may be referenced and the lower triangular part of
         A is inferred. If uplo == 'L' or 'l', only the lower triangular part of
         A may be referenced and the upper triangular part of A is inferred.
         the number of rows and columns of matrix A; n must be at least zero.
n
alpha
         single-precision scalar multiplier applied to x * y^T + alpha * y * x^T.
х
         single-precision array of length at least (1 + (n-1) * abs(incx)).
incx
         storage spacing between elements of x; incx must not be zero.
         single-precision array of length at least (1 + (n-1) * abs(incy)).
У
incy
         storage spacing between elements of y; incy must not be zero.
ΑP
         single-precision array with at least (n * (n + 1))/2 elements. If
         uplo == 'U' or 'u', array AP contains the upper triangular part of the
         symmetric matrix A, packed sequentially, column by column; that is, if
         i \le j, A[i,j] is stored in AP[i+(j*(j+1)/2)]. If uplo == 'L'
         or '1', the array AP contains the lower triangular part of the
         symmetric matrix A, packed sequentially, column by column; that is, if
         i >= j, A[i,j] is stored in AP[i + ((2 * n - j + 1) * j)/2].
```

Output

A	updated according to $A = alpha * x * y^T + alpha * y * x^T + A$.
---	--------------------------------------------------------------------

Reference: http://www.netlib.org/blas/sspr2.f

Error status for this function can be retrieved via cublasGetError().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if n < 0, incx == 0, or incy == 0
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasSsymv()

void

performs the matrix-vector operation

```
y = alpha * A * x + beta * y,
```

where alpha and beta are single-precision scalars, and x and y are n-element single-precision vectors. A is a symmetric $n \times n$ matrix that consists of single-precision elements and is stored in either upper or lower storage mode.

Input

uplo	specifies whether the upper or lower triangular part of the array A is referenced. If uplo == 'U' or 'u', the symmetric matrix A is stored in upper storage mode; that is, only the upper triangular part of A is referenced while the lower triangular part of A is inferred. If uplo == 'L' or 'l', the symmetric matrix A is stored in lower storage mode; that is, only the lower triangular part of A is referenced while the upper triangular part of A is inferred.
	thangular part of A is interfed.
n	specifies the number of rows and the number of columns of the symmetric matrix A; n must be at least zero.
alpha	single-precision scalar multiplier applied to A * x.

Input (continued)

A	single-precision array of dimensions (lda, n). If uplo == 'U' or 'u', the leading $n \times n$ upper triangular part of the array A must contain the upper triangular part of the symmetric matrix and the strictly lower triangular part of A is not referenced. If uplo == 'L' or 'l', the leading $n \times n$ lower triangular part of the array A must contain the lower triangular part of the symmetric matrix and the strictly upper triangular part of A is not referenced.
lda	leading dimension of A; 1da must be at least max(1, n).
x	single-precision array of length at least $(1+(n-1)*abs(incx))$.
incx	storage spacing between elements of x; incx must not be zero.
beta	single-precision scalar multiplier applied to vector y. If beta is zero, y is not read.
У	single-precision array of length at least $(1+(n-1)*abs(incy))$. If beta is zero, y is not read.
incy	storage spacing between elements of y; incy must not be zero.

Output

```
Y updated according to y = alpha * A * x + beta * y.
```

Reference: http://www.netlib.org/blas/ssymv.f

Error status for this function can be retrieved via **cublasGetError()**. Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS_STATUS_INVALID_VALUE if n < 0, incx == 0, or incy == 0

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasSsyr()

where alpha is a single-precision scalar, x is an n-element single-precision vector, and A is an $n \times n$ symmetric matrix consisting of single-

precision elements. A is stored in column-major format, and 1da is the leading dimension of the two-dimensional array containing A.

Input

uplo	specifies whether the matrix data is stored in the upper or the lower triangular part of array A. If uplo == 'U' or 'u', only the upper triangular part of A is referenced. If uplo == 'L' or 'l', only the lower triangular part of A is referenced.
n	the number of rows and columns of matrix A; n must be at least zero.
alpha	single-precision scalar multiplier applied to $x * x^T$.
x	single-precision array of length at least $(1 + (n-1) * abs(incx))$.
incx	the storage spacing between elements of x; incx must not be zero.
A	single-precision array of dimensions (lda, n). If uplo == 'U' or 'u', A contains the upper triangular part of the symmetric matrix, and the strictly lower triangular part is not referenced. If uplo == 'L' or 'l', A contains the lower triangular part of the symmetric matrix, and the strictly upper triangular part is not referenced.
lda	leading dimension of the two-dimensional array containing A; lda must be at least $max(1, n)$.

Output

```
A updated according to A = alpha * x * x^T + A.
```

Reference: http://www.netlib.org/blas/ssyr.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS_STATUS_INVALID_VALUE if n < 0 or incx == 0

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasSsyr2()

performs the symmetric rank 2 operation

```
A = alpha * x * y^T + alpha * y * x^T + A,
```

where alpha is a single-precision scalar, x and y are n-element single-precision vectors, and A is an $n \times n$ symmetric matrix consisting of single-precision elements.

Input

uplo	specifies whether the matrix data is stored in the upper or the lower triangular part of array A. If uplo == 'U' or 'u', only the upper triangular part of A is referenced and the lower triangular part of A is inferred. If uplo == 'L' or 'l', only the lower triangular part of A is referenced and the upper triangular part of A is inferred.
n	the number of rows and columns of matrix A; n must be at least zero.
alpha	single-precision scalar multiplier applied to $\mathbf{x} \star \mathbf{y}^T + \mathbf{y} \star \mathbf{x}^T$.
х	single-precision array of length at least $(1 + (n-1) * abs(incx))$.
incx	storage spacing between elements of x; incx must not be zero.
У	single-precision array of length at least $(1 + (n-1) * abs(incy))$.
incy	storage spacing between elements of y; incy must not be zero.
A	single-precision array of dimensions (lda, n). If uplo == 'U' or 'u', A contains the upper triangular part of the symmetric matrix, and the strictly lower triangular part is not referenced. If uplo == 'L' or 'l', A contains the lower triangular part of the symmetric matrix, and the strictly upper triangular part is not referenced.
lda	leading dimension of A; 1da must be at least max(1, n).

Output

```
A updated according to A = alpha * x * y^T + alpha * y * x^T + A.
```

Reference: http://www.netlib.org/blas/ssyr2.f

Error status for this function can be retrieved via **cublasGetError()**. Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS_STATUS_INVALID_VALUE if n < 0, incx == 0, or incy == 0

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasStbmv()

void

performs one of the matrix-vector operations

```
x = op(A) * x,
where op(A) = A or op(A) = A^{T},
```

x is an n-element single-precision vector, and A is an $n \times n$, unit or non-unit, upper or lower, triangular band matrix consisting of single-precision elements.

Input

```
uplo
         specifies whether the matrix A is an upper or lower triangular band
         matrix. If uplo == 'U' or 'u', A is an upper triangular band matrix. If
         uplo == 'L' or 'l', A is a lower triangular band matrix.
trans
         specifies op (A). If trans == 'N' or 'n', op (A) = A.
         If trans == 'T', 't', 'C', or 'c', op(A) = A<sup>T</sup>.
diag
         specifies whether or not matrix A is unit triangular. If diag == 'U' or
          'u', A is assumed to be unit triangular. If diag == 'N' or 'n', A is
         not assumed to be unit triangular.
         specifies the number of rows and columns of the matrix A; n must be
n
         at least zero. In the current implementation n must not exceed 4070.
k
         specifies the number of superdiagonals or subdiagonals. If uplo ==
          'U' or 'u', k specifies the number of superdiagonals. If uplo == 'L'
         or '1' k specifies the number of subdiagonals; k must at least be zero.
Α
         single-precision array of dimension (lda, n). If uplo == 'U' or 'u',
         the leading (k+1) \times n part of the array A must contain the upper
         triangular band matrix, supplied column by column, with the leading
         diagonal of the matrix in row k+1 of the array, the first superdiagonal
         starting at position 2 in row k, and so on. The top left kxk triangle of
         the array A is not referenced. If uplo == 'L' or 'l', the leading
          (k+1) \times n part of the array A must contain the lower triangular band
         matrix, supplied column by column, with the leading diagonal of the
         matrix in row 1 of the array, the first subdiagonal starting at position 1
         in row 2, and so on. The bottom right kxk triangle of the array is not
         referenced.
lda
         is the leading dimension of A; 1da must be at least k+1.
```

Input (continued)

single-precision array of length at least $(1 + (n-1) * abs(incx))$.
On entry, x contains the source vector. On exit, x is overwritten with
the result vector.

incx specifies the storage spacing for elements of x; incx must not be zero.

Output

```
x updated according to x = op(A) * x.
```

Reference: http://www.netlib.org/blas/stbmv.f

Error status for this function can be retrieved via cublasGetError().

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS_STATUS_INVALID_VALUE if n < 0, n > 4070, k < 0, or
incx == 0

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasStbsv()

```
void
```

solves one of the systems of equations

```
op(A) * x = b,
where op(A) = A \text{ or } op(A) = A^{T},
```

b and x are n-element vectors, and A is an $n \times n$, unit or non-unit, upper or lower, triangular band matrix with k+1 diagonals.

No test for singularity or near-singularity is included in this function. Such tests must be performed before calling this function.

```
uplo specifies whether the matrix is an upper or lower triangular band matrix: If uplo == 'U' or 'u', A is an upper triangular band matrix. If uplo == 'L' or 'l', A is a lower triangular band matrix.

trans specifies op(A). If trans == 'N' or 'n', op(A) = A.

If trans == 'T', 't', 'C', or 'c', op(A) = A<sup>T</sup>.
```

Input (continued)

diag	specifies whether A is unit triangular. If diag == 'U' or 'u', A is	
	assumed to be unit triangular; that is, diagonal elements are not read	
	and are assumed to be unity. If diag == 'N' or 'n', A is not assumed	
	to be unit triangular.	

- n the number of rows and columns of matrix A; n must be at least zero.
- k specifies the number of superdiagonals or subdiagonals. If uplo == 'U' or 'u', k specifies the number of superdiagonals. If uplo == 'L' or 'l', k specifies the number of subdiagonals; k must be at least zero.
- single-precision array of dimension (lda, n). If uplo == 'U' or 'u', the leading (k+1) ×n part of the array A must contain the upper triangular band matrix, supplied column by column, with the leading diagonal of the matrix in row k+1 of the array, the first superdiagonal starting at position 2 in row k, and so on. The top left k×k triangle of the array A is not referenced. If uplo == 'L' or 'l', the leading (k+1) ×n part of the array A must contain the lower triangular band matrix, supplied column by column, with the leading diagonal of the matrix in row 1 of the array, the first sub-diagonal starting at position 1 in row 2, and so on. The bottom right k×k triangle of the array is not referenced.
- x single-precision array of length at least (1+(n-1)*abs(incx)). On entry, x contains the n-element right-hand side vector b. On exit, it is overwritten with the solution vector x.
- incx storage spacing between elements of x; incx must not be zero.

Output

 \times updated to contain the solution vector \times that solves op(A) * \times = b.

Reference: http://www.netlib.org/blas/stbsv.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if incx == 0, n < 0, or n > 4070
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasStpmv()

void

performs one of the matrix-vector operations

```
x = op(A) * x,
where op(A) = A or op(A) = A^{T},
```

x is an n-element single-precision vector, and A is an $n \times n$, unit or non-unit, upper or lower, triangular matrix consisting of single-precision elements.

Input

•	
uplo	specifies whether the matrix A is an upper or lower triangular matrix. If uplo == 'U' or 'u', A is an upper triangular matrix. If uplo == 'L' or 'l', A is a lower triangular matrix.
trans	specifies op(A). If trans == 'N' or 'n', op(A) = A. If trans == 'T', 't', 'C', or 'c', op(A) = A^{T} .
diag	specifies whether or not matrix A is unit triangular. If diag == 'U' or 'u', A is assumed to be unit triangular. If diag == 'N' or 'n', A is not assumed to be unit triangular.
n	specifies the number of rows and columns of the matrix A; n must be at least zero. In the current implementation n must not exceed 4070.
АР	single-precision array with at least $(n * (n + 1))/2$ elements. If $uplo == 'U' or 'u'$, the array AP contains the upper triangular part of the symmetric matrix A, packed sequentially, column by column; that is, if $i <= j$, A[i,j] is stored in AP[i+(j*(j+1)/2)]. If $uplo == 'L' or 'l'$, array AP contains the lower triangular part of the symmetric matrix A, packed sequentially, column by column; that is, if $i >= j$, A[i,j] is stored in AP[i+((2*n-j+1)*j)/2].
х	single-precision array of length at least $(1 + (n-1) * abs(incx))$. On entry, x contains the source vector. On exit, x is overwritten with the result vector.
incx	specifies the storage spacing for elements of x; incx must not be zero.

Output

```
x updated according to x = op(A) * x.
```

Reference: http://www.netlib.org/blas/stpmv.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if incx == 0, n < 0, or n > 4070
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasStpsv()

void

solves one of the systems of equations

```
op(A) * x = b,
where op(A) = A \text{ or } op(A) = A^{T},
```

b and x are n-element single-precision vectors, and A is an $n \times n$, unit or non-unit, upper or lower, triangular matrix.

No test for singularity or near-singularity is included in this function. Such tests must be performed before calling this function.

Input

uplo	specifies whether the matrix is an upper or lower triangular matrix. If uplo == 'U' or 'u', A is an upper triangular matrix. If uplo == 'L' or 'l', A is a lower triangular matrix.
trans	specifies op(A). If trans == 'N' or 'n', op(A) = A. If trans == 'T', 't', 'C', or 'c', op(A) = A^{T} .
diag	specifies whether A is unit triangular. If diag == 'U' or 'u', A is assumed to be unit triangular; that is, diagonal elements are not read and are assumed to be unity. If diag == 'N' or 'n', A is not assumed to be unit triangular.
n	specifies the number of rows and columns of the matrix A; n must be at least zero. In the current implementation n must not exceed 4070.

74 PG-00000-002_V2.3

Input (continued)

AP	single-precision array with at least $(n * (n + 1))/2$ elements. If	
	uplo == 'U' or 'u', array AP contains the upper triangular matrix A,	
	packed sequentially, column by column; that is, if i <= j, A[i,j] is	
	stored in $AP[i + (j * (j + 1)/2)]$. If uplo == 'L' or 'l', array AP	
	contains the lower triangular matrix A, packed sequentially, column by	
	column; that is, if $i \ge j$, A[i,j] is stored in	
	AP[i + ((2 * n - j + 1) * j)/2]. When diag == 'U' or 'u', the diagonal elements of A are not referenced and are assumed to be unity.	
x	single-precision array of length at least $(1 + (n-1) * abs(incx))$. On entry, x contains the n-element right-hand side vector b. On exit, it is overwritten with the solution vector x.	
incx	storage spacing between elements of x; incx must not be zero.	

Output

x updated to contain the solution vector x that solves op (A) *x = b.

Reference: http://www.netlib.org/blas/stpsv.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS_STATUS_INVALID_VALUE if incx == 0, n < 0, or n > 4070

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasStrmv()

void

performs one of the matrix-vector operations

```
x = op(A) * x,
where op(A) = A or op(A) = A^T,
```

x is an n-element single-precision vector, and A is an $n \times n$, unit or non-unit, upper or lower, triangular matrix consisting of single-precision elements.

Input

uplo	specifies whether the matrix A is an upper or lower triangular matrix. If uplo == 'U' or 'u', A is an upper triangular matrix. If uplo == 'L' or 'l', A is an lower triangular matrix.
trans	specifies op(A). If trans == 'N' or 'n', op(A) = A. If trans == 'T', 't', 'C', or 'c', op(A) = A^{T} .
diag	specifies whether or not A is a unit triangular matrix. If $diag == 'U'$ or 'u', A is assumed to be unit triangular. If $diag == 'N'$ or 'n', A is not assumed to be unit triangular.
n	specifies the number of rows and columns of the matrix A; n must be at least zero. In the current implementation, n must not exceed 4070.
A	single-precision array of dimensions (lda, n). If uplo == 'U' or 'u', the leading n×n upper triangular part of the array A must contain the upper triangular matrix, and the strictly lower triangular part of A is not referenced. If uplo == 'L' or 'l', the leading n×n lower triangular part of the array A must contain the lower triangular matrix, and the strictly upper triangular part of A is not referenced. When diag == 'U' or 'u', the diagonal elements of A are not referenced either, but are assumed to be unity.
lda	leading dimension of A; lda must be at least $max(1, n)$.
х	single-precision array of length at least $(1+(n-1)*abs(incx))$. On entry, x contains the source vector. On exit, x is overwritten with the result vector.
incx	the storage spacing between elements of x; incx must not be zero.

Output

```
x updated according to x = op(A) * x.
```

Reference: http://www.netlib.org/blas/strmv.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS_STATUS_INVALID_VALUE if incx == 0, n < 0, or n > 4070

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

76 PG-00000-002_V2.3

Function cublasStrsv()

void

solves a system of equations

```
op(A) * x = b,
where op(A) = A \text{ or } op(A) = A^{T},
```

b and x are n-element single-precision vectors, and A is an $n \times n$, unit or non-unit, upper or lower, triangular matrix consisting of single-precision elements. Matrix A is stored in column-major format, and lda is the leading dimension of the two-dimensional array containing A.

No test for singularity or near-singularity is included in this function. Such tests must be performed before calling this function.

```
uplo
         specifies whether the matrix data is stored in the upper or the lower
         triangular part of array A. If uplo == 'U' or 'u', only the upper
         triangular part of A may be referenced. If uplo == 'L' or 'l', only
         the lower triangular part of A may be referenced.
trans
         specifies op(A). If trans == 'N' or 'n', op(A) = A.
         If trans == 'T', 't', 'C', or 'c', op(A) = A<sup>T</sup>.
diag
         specifies whether or not A is a unit triangular matrix.
         If diag == 'U' or 'u', A is assumed to be unit triangular.
         If diag == 'N' or 'n', A is not assumed to be unit triangular.
         specifies the number of rows and columns of the matrix A; n must be
n
         at least zero. In the current implementation, n must not exceed 4070.
Α
         single-precision array of dimensions (lda, n). If uplo == 'U' or 'u',
         A contains the upper triangular part of the symmetric matrix, and the
         strictly lower triangular part is not referenced. If uplo == 'L' or 'l',
         A contains the lower triangular part of the symmetric matrix, and the
         strictly upper triangular part is not referenced.
lda
         leading dimension of the two-dimensional array containing A;
         1da must be at least max(1, n).
         single-precision array of length at least (1 + (n-1) * abs(incx)).
X
         On entry, x contains the n-element, right-hand-side vector b. On exit,
         it is overwritten with the solution vector x.
incx
         the storage spacing between elements of x; incx must not be zero.
```

Output

x updated to contain the solution vector x that solves op(A) * x = b.

Reference: http://www.netlib.org/blas/strsv.f

Error status for this function can be retrieved via cublasGetError().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized

CUBLAS_STATUS_INVALID_VALUE if incx == 0, n < 0, or n > 4070

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU

Single-Precision Complex BLAS2 Functions

These functions have not been implemented yet.

Double-Precision BLAS2 Functions

Note: Double-precision functions are only supported on GPUs with double-precision hardware.

The double-precision BLAS2 functions are as follows:

- □ "Function cublasDgemv()" on page 79
- □ "Function cublasDger()" on page 80
- □ "Function cublasDsyr()" on page 81
- □ "Function cublasDtrsv()" on page 83

Function cublasDgemv()

void

performs one of the matrix-vector operations

```
y = alpha * op(A) * x + beta * y,
where op(A) = A or op(A) = A^{T},
```

alpha and beta are double-precision scalars, and x and y are double-precision vectors. A is an $m \times n$ matrix consisting of double-precision elements. Matrix A is stored in column-major format, and lda is the leading dimension of the two-dimensional array in which A is stored.

```
specifies op(A). If trans == 'N' or 'n', op(A) = A.

If trans == 'T', 't', 'C', or 'c', op(A) = A<sup>T</sup>.

m specifies the number of rows of matrix A; m must be at least zero.

n specifies the number of columns of matrix A; n must be at least zero.

alpha double-precision scalar multiplier applied to op(A).

A double-precision array of dimensions (lda, n) if trans == 'N' or 'n', of dimensions (lda, m) otherwise; lda must be at least max(1, m) if trans == 'N' or 'n' and at least max(1, n) otherwise.

lda leading dimension of two-dimensional array used to store matrix A.
```

Input (continued)

х	double-precision array of length at least $(1+(n-1)*abs(incx))$ if trans == 'N' or 'n', else at least $(1+(m-1)*abs(incx))$.
incx	specifies the storage spacing for elements of x; incx must not be zero.
beta	double-precision scalar multiplier applied to vector y. If beta is zero, y is not read.
У	double-precision array of length at least $(1 + (m-1) * abs(incy))$ if trans == 'N' or 'n', else at least $(1 + (n-1) * abs(incy))$.
incy	the storage spacing between elements of y; incy must not be zero.

Output

```
y updated according to y = alpha * op(A) * x + beta * y.
```

Reference: http://www.netlib.org/blas/dgemv.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if m < 0, n < 0, incx == 0, or incy == 0
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDger()

void

performs the symmetric rank 1 operation

```
A = alpha * x * y^T + A,
```

where alpha is a double-precision scalar, x is an m-element double-precision vector, y is an n-element double-precision vector, and A is an m×n matrix consisting of double-precision elements. Matrix A is stored

in column-major format, and lda is the leading dimension of the twodimensional array used to store A.

Input

m	specifies the number of rows of the matrix A; m must be at least zero.
n	specifies the number of columns of matrix A; n must be at least zero.
alpha	double-precision scalar multiplier applied to $x * y^T$.
x	double-precision array of length at least $(1 + (m-1) * abs(incx))$.
incx	the storage spacing between elements of x; incx must not be zero.
У	double-precision array of length at least $(1+(n-1)*abs(incy))$.
incy	the storage spacing between elements of y; incy must not be zero.
A	double-precision array of dimensions (lda, n).
lda	leading dimension of two-dimensional array used to store matrix A.
incy A	the storage spacing between elements of y; incy must not be zero. double-precision array of dimensions (lda, n).

Output

A updated according to $A = alpha * x * y^T + A$.

Reference: http://www.netlib.org/blas/dger.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if m < 0, n < 0, incx == 0, or incy == 0
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDsyr()

performs the symmetric rank 1 operation

$$A = alpha * x * x^{T} + A,$$

where alpha is a double-precision scalar, x is an n-element double-precision vector, and A is an $n \times n$ symmetric matrix consisting of double-precision elements. A is stored in column-major format, and lda is the leading dimension of the two-dimensional array containing A.

Input

uplo	specifies whether the matrix data is stored in the upper or the lower triangular part of array A. If uplo == 'U' or 'u', only the upper triangular part of A is referenced. If uplo == 'L' or 'l', only the lower triangular part of A is referenced.
n	the number of rows and columns of matrix A; n must be at least zero.
alpha	double-precision scalar multiplier applied to $\mathbf{x} * \mathbf{x}^{T}$.
x	double-precision array of length at least $(1 + (n-1) * abs(incx))$.
incx	the storage spacing between elements of x; incx must not be zero.
A	double-precision array of dimensions (lda, n). If uplo == 'U' or 'u', A contains the upper triangular part of the symmetric matrix, and the strictly lower triangular part is not referenced. If uplo == 'L' or 'l', A contains the lower triangular part of the symmetric matrix, and the strictly upper triangular part is not referenced.
lda	leading dimension of the two-dimensional array containing A; lda must be at least $max(1, n)$.

Output

A	updated according to $A = alpha * x * x^T + A$.	
---	--------------------------------------------------	--

Reference: http://www.netlib.org/blas/dsyr.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if n < 0 or incx == 0
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDtrsv()

void

solves a system of equations

```
op(A) * x = b,
where op(A) = A \text{ or } op(A) = A^{T},
```

b and x are n-element double-precision vectors, and A is an $n \times n$, unit or non-unit, upper or lower, triangular matrix consisting of double-precision elements. Matrix A is stored in column-major format, and lda is the leading dimension of the two-dimensional array containing A.

No test for singularity or near-singularity is included in this function. Such tests must be performed before calling this function.

```
specifies whether the matrix data is stored in the upper or the lower
uplo
         triangular part of array A. If uplo == 'U' or 'u', only the upper
         triangular part of A may be referenced. If uplo == 'L' or 'l', only
         the lower triangular part of A may be referenced.
         specifies op(A). If trans == 'N' or 'n', op(A) = A.
trans
         If trans == 'T', 't', 'C', or 'c', op(A) = A^{T}.
diag
         specifies whether or not A is a unit triangular matrix.
         If diag == 'U' or 'u', A is assumed to be unit triangular.
         If diag == 'N' or 'n', A is not assumed to be unit triangular.
n
         specifies the number of rows and columns of the matrix A; n must be
         at least zero. In the current implementation, n must not exceed 2040.
Α
         double-precision array of dimensions (lda, n). If uplo == 'U' or
         'u', A contains the upper triangular part of the symmetric matrix, and
         the strictly lower triangular part is not referenced. If uplo == 'L' or
         '1', A contains the lower triangular part of the symmetric matrix, and
         the strictly upper triangular part is not referenced.
lda
         leading dimension of the two-dimensional array containing A;
         1da must be at least max(1, n).
```

x	double-precision array of length at least $(1 + (n-1) * abs(incx))$. On entry, x contains the n-element, right-hand-side vector b. On exit, it is overwritten with the solution vector x.
incx	the storage spacing between elements of x; incx must not be zero.
Output	•

updated to contain the solution vector x that solves op(A) * x = b.

Reference: http://www.netlib.org/blas/dtrsv.f

Error status for this function can be retrieved via cublasGetError().

Error Status

Input (continued)

```
CUBLAS_STATUS_NOT_INITIALIZED
                                     if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE
                                     if incx == 0, n < 0, or n > 2040
CUBLAS_STATUS_ARCH_MISMATCH
                                     if function invoked on device that
                                     does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED
                                     if function failed to launch on GPU
```

Double-Precision Complex BLAS2 functions

Note: Double-precision functions are only supported on GPUs with doubleprecision hardware.

Only one double-precision complex BLAS2 function is implemented.

Function cublasZgemv()

```
void
cublasZgemv (char trans, int m, int n,
             cuDoubleComplex alpha,
             const cuDoubleComplex *A, int lda,
             const cuDoubleComplex *x, int incx,
             cuDoubleComplex beta, cuDoubleComplex *y,
             int incy)
```

performs one of the matrix-vector operations

```
y = alpha * op(A) * x + beta * y,
where op(A) = A or op(A) = A^{T},
```

alpha and beta are double-precision complex scalars, and x and y are double-precision complex vectors. A is an $m \times n$ matrix consisting of double-precision complex elements. Matrix A is stored in column-major format, and lda is the leading dimension of the two-dimensional array in which A is stored.

Input

```
trans
         specifies op (A). If trans == 'N' or 'n', op (A) = A.
         If trans == 'T', 't', 'C', or 'c', op(A) = A^{T}.
m
         specifies the number of rows of matrix A; m must be at least zero.
n
         specifies the number of columns of matrix A; n must be at least zero.
alpha
         double-precision complex scalar multiplier applied to op (A).
Α
         double-precision complex array of dimensions (lda, n) if trans ==
         'N' or 'n', of dimensions (lda, m) otherwise; lda must be at least
         \max(1, m) if trans == 'N' or 'n' and at least \max(1, n) otherwise.
lda
         leading dimension of two-dimensional array used to store matrix A.
х
         double-precision complex array of length at least
         (1+(n-1)*abs(incx)) if trans == 'N' or 'n', else at least
         (1 + (m-1) * abs(incx)).
incx
         specifies the storage spacing for elements of x; incx must not be zero.
beta
         double-precision complex scalar multiplier applied to vector y. If beta
         is zero, y is not read.
         double-precision complex array of length at least
У
         (1+(m-1)*abs(incy)) if trans == 'N' or 'n', else at least
         (1+(n-1)*abs(incy)).
         the storage spacing between elements of y; incy must not be zero.
incy
```

Output

```
y updated according to y = alpha * op(A) * x + beta * y.
```

Reference: http://www.netlib.org/blas/zgemv.f

Error status for this function can be retrieved via **cublasGetError()**. Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if m < 0, n < 0, incx == 0, or incy == 0
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

CHAPTER

4

BLAS3 Functions

Level 3 Basic Linear Algebra Subprograms (BLAS3) perform matrix-matrix operations. The CUBLAS implementations are described in the following sections:

- □ "Single-Precision BLAS3 Functions" on page 88
- □ "Single-Precision Complex BLAS3 Functions" on page 99
- □ "Double-Precision BLAS3 Functions" on page 101
- □ "Double-Precision Complex BLAS3 Functions" on page 113

Single-Precision BLAS3 Functions

The single-precision BLAS3 functions are listed below:

- □ "Function cublasSgemm()" on page 88
- □ "Function cublasSsymm()" on page 90
- □ "Function cublasSsyrk()" on page 92
- □ "Function cublasSsyr2k()" on page 93
- □ "Function cublasStrmm()" on page 95
- □ "Function cublasStrsm()" on page 97

Function cublasSgemm()

void

computes the product of matrix A and matrix B, multiplies the result by scalar alpha, and adds the sum to the product of matrix C and scalar beta. It performs one of the matrix-matrix operations:

```
C = alpha * op(A) * op(B) + beta * C,
where op(X) = X or op(X) = X^T,
```

and alpha and beta are single-precision scalars. A, B, and C are matrices consisting of single-precision elements, with op(A) an $m \times k$ matrix, op(B) a $k \times n$ matrix, and C an $m \times n$ matrix. Matrices A, B, and C are stored in column-major format, and lda, ldb, and ldc are the leading dimensions of the two-dimensional arrays containing A, B, and C.

Input

CHAPTER 4 **BLAS3 Functions**

Input (continued)

n	number of columns of matrix op(B) and number of columns of C; n must be at least zero.
k	number of columns of matrix op(A) and number of rows of op(B); k must be at least zero.
alpha	single-precision scalar multiplier applied to $op(A) * op(B)$.
A	single-precision array of dimensions (lda, k) if transa == 'N' or 'n', and of dimensions (lda, m) otherwise. If transa == 'N' or 'n', lda must be at least max(1, m); otherwise, lda must be at least max(1, k).
lda	leading dimension of two-dimensional array used to store matrix A.
В	single-precision array of dimensions (ldb, n) if transb == 'N' or 'n', and of dimensions (ldb, k) otherwise. If transb == 'N' or 'n', ldb must be at least $\max(1, k)$; otherwise, ldb must be at least $\max(1, n)$.
ldb	leading dimension of two-dimensional array used to store matrix B.
beta	single-precision scalar multiplier applied to C. If zero, C does not have to be a valid input.
С	single-precision array of dimensions ($1dc, n$); $1dc$ must be at least $max (1, m)$.
ldc	leading dimension of two-dimensional array used to store matrix C.
Output	
С	updated based on C = alpha * op(A) * op(B) + beta * C.

Reference: http://www.netlib.org/blas/sgemm.f

Error status for this function can be retrieved via cublasGetError().

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED
                                    if CUBLAS library was not initialized
                                    if m < 0, n < 0, or k < 0
CUBLAS_STATUS_INVALID_VALUE
                                    if function failed to launch on GPU
CUBLAS STATUS EXECUTION FAILED
```

Function cublasSsymm()

void

performs one of the matrix-matrix operations

```
C = alpha * A * B + beta * C  or C = alpha * B * A + beta * C ,
```

where alpha and beta are single-precision scalars, A is a symmetric matrix consisting of single-precision elements and is stored in either lower or upper storage mode. B and C are $m \times n$ matrices consisting of single-precision elements.

Input

```
side
         specifies whether the symmetric matrix A appears on the left-hand side
         or right-hand side of matrix B.
         If side == 'L' or 'l', C = alpha * A * B + beta * C.
         If side == 'R' or 'r', C = alpha * B * A + beta * C.
uplo
         specifies whether the symmetric matrix A is stored in upper or lower
         storage mode. If uplo == 'U' or 'u', only the upper triangular part
         of the symmetric matrix is referenced, and the elements of the strictly
         lower triangular part are inferred from those in the upper triangular
         part. If uplo == 'L' or 'l', only the lower triangular part of the
         symmetric matrix is referenced, and the elements of the strictly upper
         triangular part are inferred from those in the lower triangular part.
m
         specifies the number of rows of matrix C, and the number of rows of
         matrix B. It also specifies the dimensions of symmetric matrix A when
         side == 'L' or 'l'; m must be at least zero.
n
         specifies the number of columns of matrix C, and the number of
         columns of matrix B. It also specifies the dimensions of symmetric
         matrix A when side == 'R' or 'r'; n must be at least zero.
alpha
         single-precision scalar multiplier applied to A * B or B * A.
```

Input (continued)

A	single-precision array of dimensions (lda, ka), where ka is m when side == 'L' or 'l' and is n otherwise. If side == 'L' or 'l', the leading m×m part of array A must contain the symmetric matrix, such that when uplo == 'U' or 'u', the leading m×m part stores the upper triangular part of the symmetric matrix, and the strictly lower triangular part of A is not referenced; and when uplo == 'L' or 'l', the leading m×m part stores the lower triangular part of the symmetric matrix and the strictly upper triangular part is not referenced. If side == 'R' or 'r', the leading n×n part of array A must contain the symmetric matrix, such that when uplo == 'U' or 'u', the leading n×n part stores the upper triangular part of the symmetric matrix and the strictly lower triangular part of A is not referenced; and when uplo == 'L' or 'l', the leading n×n part stores the lower triangular part of the symmetric matrix and the strictly upper triangular part is not referenced.
lda	leading dimension of A. When $side == 'L'$ or 'l', it must be at least $max(1, m)$ and at least $max(1, n)$ otherwise.
В	single-precision array of dimensions (1db, n). On entry, the leading $m \times n$ part of the array contains the matrix B.
ldb	leading dimension of B; 1db must be at least max(1, m).
beta	single-precision scalar multiplier applied to C. If beta is zero, C does not have to be a valid input.
С	single-precision array of dimensions (ldc, n).
ldc	leading dimension of C ; 1dc must be at least $max(1, m)$.

Output

C updated according to C = alpha * A * B + beta * C or C = alpha * B * A + beta * C.

Reference: http://www.netlib.org/blas/ssymm.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

Function cublasSsyrk()

void

performs one of the symmetric rank k operations

```
C = alpha * A * A^{T} + beta * C  or C = alpha * A^{T} * A + beta * C,
```

where alpha and beta are single-precision scalars. C is an $n \times n$ symmetric matrix consisting of single-precision elements and is stored in either lower or upper storage mode. A is a matrix consisting of single-precision elements with dimensions of $n \times k$ in the first case, and $k \times n$ in the second case.

uplo	specifies whether the symmetric matrix C is stored in upper or lower
upio	storage mode. If uplo == 'U' or 'u', only the upper triangular part of the symmetric matrix is referenced, and the elements of the strictly lower triangular part are inferred from those in the upper triangular part. If uplo == 'L' or 'l', only the lower triangular part of the symmetric matrix is referenced, and the elements of the strictly upper triangular part are inferred from those in the lower triangular part.
trans	specifies the operation to be performed. If trans == 'N' or 'n', $C = \text{alpha} * A * A^T + \text{beta} * C$. If trans == 'T', 't', 'C', or 'c', $C = \text{alpha} * A^T * A + \text{beta} * C$.
n	specifies the number of rows and the number columns of matrix C. If trans == 'N' or 'n', n specifies the number of rows of matrix A. If trans == 'T', 't', 'C', or 'c', n specifies the number of columns of matrix A; n must be at least zero.
k	If trans == 'N' or 'n', k specifies the number of columns of matrix A. If trans == 'T', 't', 'C', or 'c', k specifies the number of rows of matrix A; k must be at least zero.
alpha	single-precision scalar multiplier applied to $A * A^T$ or $A^T * A$.
A	single-precision array of dimensions (lda, ka), where ka is k when trans == 'N' or 'n', and is n otherwise. When trans == 'N' or 'n', the leading $n \times k$ part of array A contains the matrix A; otherwise, the leading $k \times n$ part of the array contains the matrix A.
lda	leading dimension of A. When trans $==$ 'N' or 'n', lda must be at least max(1, n). Otherwise lda must be at least max(1, k).

beta	single-precision scalar multiplier applied to C. If beta is zero, C is not read.
С	single-precision array of dimensions (ldc, n). If uplo == 'U' or 'u', the leading n×n triangular part of the array C must contain the upper triangular part of the symmetric matrix C, and the strictly lower triangular part of C is not referenced. On exit, the upper triangular part of C is overwritten by the upper triangular part of the updated matrix. If uplo == 'L' or 'l', the leading n×n triangular part of the array C must contain the lower triangular part of the symmetric matrix C, and the strictly upper triangular part of C is not referenced. On exit, the lower triangular part of C is overwritten by the lower triangular part of the updated matrix.

ldc leading dimension of C; ldc must be at least max(1, n).

Output

```
C updated according to C = alpha * A * A^T + beta * C or C = alpha * A^T * A + beta * C.
```

Reference: http://www.netlib.org/blas/ssyrk.f

Error status for this function can be retrieved via cublasGetError().

Error Status

```
 \begin{array}{ll} \textbf{CUBLAS\_STATUS\_NOT\_INITIALIZED} & \text{if CUBLAS library was not initialized} \\ \textbf{CUBLAS\_STATUS\_INVALID\_VALUE} & \text{if } n < 0 \text{ or } k < 0 \\ \textbf{CUBLAS\_STATUS\_EXECUTION\_FAILED} & \text{if function failed to launch on GPU} \\ \end{array}
```

Function cublasSsyr2k()

void

performs one of the symmetric rank 2k operations

```
C = alpha * A * B^{T} + alpha * B * A^{T} + beta * C  or 

C = alpha * A^{T} * B + alpha * B^{T} * A + beta * C,
```

where alpha and beta are single-precision scalars. C is an $n \times n$ symmetric matrix consisting of single-precision elements and is stored

in either lower or upper storage mode. A and B are matrices consisting of single-precision elements with dimension of $n \times k$ in the first case, and $k \times n$ in the second case.

•	
uplo	specifies whether the symmetric matrix C is stored in upper or lower storage mode. If uplo == 'U' or 'u', only the upper triangular part of the symmetric matrix is referenced, and the elements of the strictly lower triangular part are inferred from those in the upper triangular part. If uplo == 'L' or 'l', only the lower triangular part of the symmetric matrix is referenced, and the elements of the strictly upper triangular part are inferred from those in the lower triangular part.
trans	specifies the operation to be performed. If trans == 'N' or 'n', $C = \text{alpha} * A * B^T + \text{alpha} * B * A^T + \text{beta} * C$. If trans == 'T', 't', 'C', or 'c', $C = \text{alpha} * A^T * B + \text{alpha} * B^T * A + \text{beta} * C$.
n	specifies the number of rows and the number columns of matrix C. If trans == 'N' or 'n'', n specifies the number of rows of matrix A. If trans == 'T', 't', 'C', or 'c', n specifies the number of columns of matrix A; n must be at least zero.
k	If trans == 'N' or 'n', k specifies the number of columns of matrix A. If trans == 'T', 't', 'C', or 'c', k specifies the number of rows of matrix A; k must be at least zero.
alpha	single-precision scalar multiplier.
A	single-precision array of dimensions (lda, ka), where ka is k when trans == 'N' or 'n', and is n otherwise. When trans == 'N' or 'n', the leading $n \times k$ part of array A must contain the matrix A, otherwise the leading $k \times n$ part of the array must contain the matrix A.
lda	leading dimension of A. When trans $==$ 'N' or 'n', lda must be at least max(1, n). Otherwise lda must be at least max(1, k).
В	single-precision array of dimensions (lda, kb), where kb = k when trans == 'N' or 'n', and k = n otherwise. When trans == 'N' or 'n', the leading $n \times k$ part of array B must contain the matrix B, otherwise the leading $k \times n$ part of the array must contain the matrix B.
ldb	leading dimension of B. When trans $==$ 'N' or 'n', ldb must be at least max(1, n). Otherwise ldb must be at least max(1, k).
beta	single-precision scalar multiplier applied to C. If beta is zero, C does not have to be a valid input.

Input (continued)

Single-precision array of dimensions (ldc, n). If uplo == 'U' or 'u', the leading n×n triangular part of the array C must contain the upper triangular part of the symmetric matrix C, and the strictly lower triangular part of C is not referenced. On exit, the upper triangular part of C is overwritten by the upper triangular part of the updated matrix. If uplo == 'L' or 'l', the leading n×n triangular part of the array C must contain the lower triangular part of the symmetric matrix C, and the strictly upper triangular part of C is not referenced. On exit, the lower triangular part of C is overwritten by the lower triangular part of the updated matrix.

ldc leading dimension of C; idc must be at least max(1, n).

Output

```
Updated according to
C = \text{alpha} * A * B^{T} + \text{alpha} * B * A^{T} + \text{beta} * C \text{ or}
C = \text{alpha} * A^{T} * B + \text{alpha} * B^{T} * A + \text{beta} * C.
```

Reference: http://www.netlib.org/blas/ssyr2k.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

Function cublasStrmm()

```
void
```

performs one of the matrix-matrix operations

```
B = alpha * op(A) * B or B = alpha * B * op(A),
where op(A) = A or op(A) = A^{T},
```

alpha is a single-precision scalar, B is an $m \times n$ matrix consisting of single-precision elements, and A is a unit or non-unit, upper or lower triangular matrix consisting of single-precision elements.

Matrices A and B are stored in column-major format, and 1da and 1db are the leading dimensions of the two-dimensional arrays that contain A and B, respectively.

Input

```
side
         specifies whether op (A) multiplies B from the left or right.
         If side == 'L' or 'l', B = alpha * op(A) * B.
         If side == 'R' \text{ or 'r'}, B = \text{alpha * B * op(A)}.
uplo
         specifies whether the matrix A is an upper or lower triangular matrix.
         If uplo == 'U' or 'u', A is an upper triangular matrix.
         If uplo == 'L' or 'l', A is a lower triangular matrix.
transa specifies the form of op (A) to be used in the matrix multiplication.
         If transa == 'N' or 'n', op(A) = A.
         If transa == 'T', 't', 'C', or 'c', op(A) = A^{T}.
diag
         specifies whether or not A is a unit triangular matrix. If diag == 'U'
         or 'u', A is assumed to be unit triangular. If diag == 'N' or 'n', A is
         not assumed to be unit triangular.
m
         the number of rows of matrix B; m must be at least zero.
n
         the number of columns of matrix B; n must be at least zero.
alpha
         single-precision scalar multiplier applied to op(A)*B or B*op(A),
         respectively. If alpha is zero, no accesses are made to matrix A, and
         no read accesses are made to matrix B.
Α
         single-precision array of dimensions (lda, k). If side == 'L' or 'l',
         k = m. If side == 'R' or 'r', k = n. If uplo == 'U' or 'u', the
         leading kxk upper triangular part of the array A must contain the
         upper triangular matrix, and the strictly lower triangular part of A is
         not referenced. If uplo == 'L' or 'l', the leading kxk lower
         triangular part of the array A must contain the lower triangular matrix,
         and the strictly upper triangular part of A is not referenced. When
         diag == 'U' or 'u', the diagonal elements of A are not referenced
         and are assumed to be unity.
lda
         leading dimension of A. When side == 'L' or 'l', it must be at least
         max(1, m) and at least max(1, n) otherwise.
В
         single-precision array of dimensions (1db, n). On entry, the leading
         m×n part of the array contains the matrix B. It is overwritten with the
         transformed matrix on exit.
ldb
         leading dimension of B; 1db must be at least max(1, m).
```

Output

```
B updated according to B = alpha * op(A) * B Or
 B = alpha * B * op(A).
```

Reference: http://www.netlib.org/blas/strmm.f

Error status for this function can be retrieved via **cublasGetError()**.

Error Status

```
CUBLAS_STATUS_NOT_INITIALIZED if CUBLAS library was not initialized if m < 0 or n < 0

CUBLAS_STATUS_EXECUTION_FAILED if function failed to launch on GPU
```

Function cublasStrsm()

void

solves one of the matrix equations

```
op(A) * X = alpha * B or X * op(A) = alpha * B,
where op(A) = A or op(A) = A^{T},
```

alpha is a single-precision scalar, and X and B are $m \times n$ matrices that consist of single-precision elements. A is a unit or non-unit, upper or lower, triangular matrix.

The result matrix X overwrites input matrix B; that is, on exit the result is stored in B. Matrices A and B are stored in column-major format, and lda and ldb are the leading dimensions of the two-dimensional arrays that contain A and B, respectively.

```
side specifies whether op(A) appears on the left or right of X:

side == 'L' or 'l' indicates solve op(A) * X = alpha * B;

side == 'R' or 'r' indicates solve X * op(A) = alpha * B.

uplo specifies whether the matrix A is an upper or lower triangular matrix:

uplo == 'U' or 'u' indicates A is an upper triangular matrix;

uplo == 'L' or 'l' indicates A is a lower triangular matrix.

transa specifies the form of op(A) to be used in matrix multiplication.

If transa == 'N' or 'n', op(A) = A.

If transa == 'T', 't', 'C', or 'c', op(A) = A<sup>T</sup>.

diag specifies whether or not A is a unit triangular matrix.

If diag == 'U' or 'u', A is assumed to be unit triangular.

If diag == 'N' or 'n', A is not assumed to be unit triangular.
```

Input (continued)

m	specifies the number of rows of B; m must be at least zero.
n	specifies the number of columns of B; n must be at least zero.
alpha	single-precision scalar multiplier applied to B. When alpha is zero, A is not referenced and B does not have to be a valid input.
A	single-precision array of dimensions (lda, k), where k is m when side == 'L' or 'l', and is n when side == 'R' or 'r'. If uplo == 'U' or 'u', the leading k×k upper triangular part of the array A must contain the upper triangular matrix, and the strictly lower triangular matrix of A is not referenced. When uplo == 'L' or 'l', the leading k×k lower triangular part of the array A must contain the lower triangular matrix, and the strictly upper triangular part of A is not referenced. Note that when diag == 'U' or 'u', the diagonal elements of A are not referenced and are assumed to be unity.
lda	leading dimension of the two-dimensional array containing A. When side == 'L' or 'l', lda must be at least max(1, m). When side == 'R' or 'r', lda must be at least max(1, n).
В	single-precision array of dimensions (1db, n); 1db must be at least $\max(1,m)$. The leading $m \times n$ part of the array B must contain the right-hand side matrix B. On exit B is overwritten by the solution matrix X.
ldb	leading dimension of the two-dimensional array containing B; 1db must be at least $max(1, m)$.

Output

B contains the solution matrix X satisfying op(A) * X = alpha * B or X * op(A) = alpha * B.

Reference: http://www.netlib.org/blas/strsm.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if m < 0 or n < 0
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Single-Precision Complex BLAS3 Functions

The only single-precision complex BLAS3 function is cublasCgemm().

Function cublasCgemm()

```
void
```

performs one of the matrix-matrix operations

```
C = alpha * op(A) * op(B) + beta * C,
where op(X) = X, op(X) = X^{T}, or op(X) = X^{H};
```

and alpha and beta are single-precision complex scalars. A, B, and C are matrices consisting of single-precision complex elements, with op(A) an $m \times k$ matrix, op(B) a $k \times n$ matrix and C an $m \times n$ matrix.

Input

```
transa specifies op (A). If transa == 'N' or 'n', op (A) = A.
         If transa == 'T' or 't', op(A) = A^{T}.
         If transa == 'C' or 'c', op(A) = A^{H}.
transb specifies op(B). If transb == 'N' or 'n', op(B) = B.
         \overline{\text{If}} \text{ transb} == 'T' \text{ or 't', op(B)} = B^T.
         If transb == 'C' or 'c', op(B) = B^H.
         number of rows of matrix op (A) and rows of matrix C;
m
         m must be at least zero.
         number of columns of matrix op (B) and number of columns of C;
n
         n must be at least zero.
k
         number of columns of matrix op (A) and number of rows of op (B);
         k must be at least zero.
         single-precision complex scalar multiplier applied to op(A)*op(B).
Α
         single-precision complex array of dimension (lda, k) if transa ==
          'N' or 'n', and of dimension (lda, m) otherwise.
lda
         leading dimension of A. When transa == 'N' or 'n', it must be at
         least max(1, m) and at least max(1, k) otherwise.
```

Input (continued)

В	single-precision complex array of dimension (ldb, n) if transb == 'N' or 'n', and of dimension (ldb, k) otherwise.
ldb	leading dimension of B. When transb == 'N' or 'n', it must be at least $max(1, k)$ and at least $max(1, n)$ otherwise.
beta	single-precision complex scalar multiplier applied to C. If beta is zero, C does not have to be a valid input.
C	single-precision array of dimensions (ldc, n).
ldc	leading dimension of C ; idc must be at least $max(1, m)$.

Output

```
Updated according to C = alpha * op(A) * op(B) + beta * C.
```

Reference: http://www.netlib.org/blas/cgemm.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if m < 0, n < 0, or k < 0
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Double-Precision BLAS3 Functions

Note: Double-precision functions are only supported on GPUs with double-precision hardware.

The double-precision BLAS3 functions are listed below:

- □ "Function cublasDgemm()" on page 101
- □ "Function cublasDsymm()" on page 103
- □ "Function cublasDsyrk()" on page 105
- □ "Function cublasDsyr2k()" on page 107
- □ "Function cublasDtrmm()" on page 109
- □ "Function cublasDtrsm()" on page 111

Function cublasDgemm()

```
void
```

computes the product of matrix A and matrix B, multiplies the result by scalar alpha, and adds the sum to the product of matrix C and scalar beta. It performs one of the matrix-matrix operations:

```
C = alpha * op(A) * op(B) + beta * C,
where op(X) = X or op(X) = X^{T},
```

and alpha and beta are double-precision scalars. A, B, and C are matrices consisting of double-precision elements, with op(A) an $m \times k$ matrix, op(B) a $k \times n$ matrix, and C an $m \times n$ matrix. Matrices A, B, and C are stored in column-major format, and lda, ldb, and ldc are the

> leading dimensions of the two-dimensional arrays containing A, B, and C.

Input

```
transa specifies op(A). If transa == 'N' or 'n', op(A) = A.
         If transa == 'T', 't', 'C', or 'c', op(A) = A^{T}.
transb specifies op(B). If transb == 'N' or 'n', op(B) = B.
         \overline{\text{If}} \text{ transb} == 'T', 't', 'C', \text{ or 'c', op(B)} = B^T.
         number of rows of matrix op (A) and rows of matrix C; m must be at
m
         least zero.
         number of columns of matrix op (B) and number of columns of C;
n
         n must be at least zero.
k
         number of columns of matrix op (A) and number of rows of op (B);
         k must be at least zero.
alpha
         double-precision scalar multiplier applied to op(A) * op(B).
Α
         double-precision array of dimensions (lda, k) if transa == 'N' or
          'n', and of dimensions (lda, m) otherwise. If transa == 'N' or
          'n', 1da must be at least max(1, m); otherwise, 1da must be at least
         \max(1, k).
lda
         leading dimension of two-dimensional array used to store matrix A.
В
         double-precision array of dimensions (ldb, n) if transb == 'N' or
          'n', and of dimensions (ldb, k) otherwise. If transb == 'N' or
          'n', ldb must be at least max(1, k); otherwise, ldb must be at least
         \max(1, n).
ldb
         leading dimension of two-dimensional array used to store matrix B.
beta
         double-precision scalar multiplier applied to C. If zero, C does not have
         to be a valid input.
C
         double-precision array of dimensions (ldc, n); ldc must be at least
         \max (1, m).
ldc
         leading dimension of two-dimensional array used to store matrix C.
Output
С
         updated based on C = alpha * op(A) * op(B)
                                                             + beta * C.
```

Reference: http://www.netlib.org/blas/dgemm.f

Error status for this function can be retrieved via cublasGetError(). **Error Status**

```
CUBLAS STATUS NOT INITIALIZED
                                     if CUBLAS library was not initialized
CUBLAS STATUS INVALID VALUE
                                     if m < 0, n < 0, or k < 0
```

CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDsymm()

void

performs one of the matrix-matrix operations

```
C = alpha * A * B + beta * C Or C = alpha * B * A + beta * C,
```

where alpha and beta are double-precision scalars, A is a symmetric matrix consisting of double-precision elements and is stored in either lower or upper storage mode. B and C are $m \times n$ matrices consisting of double-precision elements.

Input

```
side
         specifies whether the symmetric matrix A appears on the left-hand side
         or right-hand side of matrix B.
         If side == 'L' or 'l', C = alpha * A * B + beta * C.
         If side == 'R' or 'r', C = alpha * B * A + beta * C.
uplo
         specifies whether the symmetric matrix A is stored in upper or lower
         storage mode. If uplo == 'U' or 'u', only the upper triangular part
         of the symmetric matrix is referenced, and the elements of the strictly
         lower triangular part are inferred from those in the upper triangular
         part. If uplo == 'L' or 'l', only the lower triangular part of the
         symmetric matrix is referenced, and the elements of the strictly upper
         triangular part are inferred from those in the lower triangular part.
         specifies the number of rows of matrix C, and the number of rows of
m
         matrix B. It also specifies the dimensions of symmetric matrix A when
         side == 'L' or 'l'; m must be at least zero.
n
         specifies the number of columns of matrix C, and the number of
         columns of matrix B. It also specifies the dimensions of symmetric
         matrix A when side == 'R' or 'r'; n must be at least zero.
alpha
         double-precision scalar multiplier applied to A * B or B * A.
```

Input (continued)

A	double-precision array of dimensions (lda, ka), where ka is m when side == 'L' or 'l' and is n otherwise. If side == 'L' or 'l', the leading m×m part of array A must contain the symmetric matrix, such that when uplo == 'U' or 'u', the leading m×m part stores the upper triangular part of the symmetric matrix, and the strictly lower triangular part of A is not referenced; and when uplo == 'L' or 'l', the leading m×m part stores the lower triangular part of the symmetric matrix and the strictly upper triangular part is not referenced. If side == 'R' or 'r', the leading n×n part of array A must contain the symmetric matrix, such that when uplo == 'U' or 'u', the leading n×n part stores the upper triangular part of the symmetric matrix and the strictly lower triangular part of A is not referenced; and when uplo == 'L' or 'l', the leading n×n part stores the lower triangular part of the symmetric matrix and the strictly upper triangular part is not referenced.
lda	leading dimension of A. When side $== 'L'$ or '1', it must be at least $max(1, m)$ and at least $max(1, n)$ otherwise.
В	double-precision array of dimensions (ldb, n). On entry, the leading $m \times n$ part of the array contains the matrix B.
ldb	leading dimension of B; 1db must be at least max(1, m).
beta	double-precision scalar multiplier applied to C. If beta is zero, C does not have to be a valid input.
С	double-precision array of dimensions (ldc, n).
ldc	leading dimension of C; ldc must be at least max(1, m).

Output

C	updated according to C = alpha * A * B + beta * C 0r	
	C = alpha * B * A + beta * C.	

Reference: http://www.netlib.org/blas/dsymm.f

Error status for this function can be retrieved via cublasGetError().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if m < 0, n < 0, or k < 0
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDsyrk()

void

performs one of the symmetric rank k operations

```
C = alpha * A * A^T + beta * C  or C = alpha * A^T * A + beta * C ,
```

where alpha and beta are double-precision scalars. C is an $n \times n$ symmetric matrix consisting of double-precision elements and is stored in either lower or upper storage mode. A is a matrix consisting of double-precision elements with dimensions of $n \times k$ in the first case, and $k \times n$ in the second case.

Input

lda

uplo	specifies whether the symmetric matrix C is stored in upper or lower storage mode. If uplo == 'U' or 'u', only the upper triangular part of the symmetric matrix is referenced, and the elements of the strictly lower triangular part are inferred from those in the upper triangular part. If uplo == 'L' or 'l', only the lower triangular part of the symmetric matrix is referenced, and the elements of the strictly upper triangular part are inferred from those in the lower triangular part.
trans	specifies the operation to be performed. If trans == 'N' or 'n', $C = \text{alpha} * A * A^T + \text{beta} * C$. If trans == 'T', 't', 'C', or 'c', $C = \text{alpha} * A^T * A + \text{beta} * C$.
n	specifies the number of rows and the number columns of matrix C. If trans == 'N' or 'n', n specifies the number of rows of matrix A. If trans == 'T', 't', 'C', or 'c', n specifies the number of columns of matrix A; n must be at least zero.
k	If trans == 'N' or 'n', k specifies the number of columns of matrix A. If trans == 'T', 't', 'C', or 'c', k specifies the number of rows of matrix A; k must be at least zero.
alpha	double-precision scalar multiplier applied to $A * A^T$ or $A^T * A$.
A	double-precision array of dimensions (lda, ka), where ka is k when

trans == 'N' or 'n', and is n otherwise. When trans == 'N' or 'n', the leading $n \times k$ part of array A contains the matrix A; otherwise,

leading dimension of A. When trans == 'N' or 'n', lda must be at

PG-00000-002_V2.3 NVIDIA

the leading kxn part of the array contains the matrix A.

least max(1, n). Otherwise 1da must be at least max(1, k).

Input ((continued)
IIIPGL 1	(COLLINIACA)

beta	double-precision scalar multiplier applied to C. If beta is zero, C is not read.
С	double-precision array of dimensions (ldc, n). If uplo == 'U' or 'u', the leading n×n triangular part of the array C must contain the upper triangular part of the symmetric matrix C, and the strictly lower triangular part of C is not referenced. On exit, the upper triangular part of C is overwritten by the upper triangular part of the updated matrix. If uplo == 'L' or 'l', the leading n×n triangular part of the array C must contain the lower triangular part of the symmetric matrix C, and the strictly upper triangular part of C is not referenced. On exit, the lower triangular part of C is overwritten by the lower triangular part of the updated matrix.
ldc	leading dimension of C; $1dc$ must be at least $max(1, n)$.

Output

```
Updated according to C = alpha * A * A^T + beta * C or C = alpha * A^T * A + beta * C.
```

Reference: http://www.netlib.org/blas/dsyrk.f

Error status for this function can be retrieved via cublasGetError().

Error status for this function can be retrieved via **cublasGetError()**. Error Status

```
      CUBLAS_STATUS_NOT_INITIALIZED
      if CUBLAS library was not initialized

      CUBLAS_STATUS_INVALID_VALUE
      if m < 0, n < 0, or k < 0</td>

      CUBLAS_STATUS_ARCH_MISMATCH
      if function invoked on device that does not support double precision

      CUBLAS_STATUS_EXECUTION_FAILED
      if function failed to launch on GPU
```

Function cublasDsyr2k()

void

performs one of the symmetric rank 2k operations

```
C = alpha * A * B^{T} + alpha * B * A^{T} + beta * C  or 

C = alpha * A^{T} * B + alpha * B^{T} * A + beta * C,
```

where alpha and beta are double-precision scalars. C is an $n \times n$ symmetric matrix consisting of double-precision elements and is stored in either lower or upper storage mode. A and B are matrices consisting of double-precision elements with dimension of $n \times k$ in the first case, and $k \times n$ in the second case.

Input

uplo specifies whether the symmetric matrix C is stored in upper or lower storage mode. If uplo == 'U' or 'u', only the upper triangular part of the symmetric matrix is referenced, and the elements of the strictly lower triangular part are inferred from those in the upper triangular part. If uplo == 'L' or 'l', only the lower triangular part of the symmetric matrix is referenced, and the elements of the strictly upper triangular part are inferred from those in the lower triangular part. trans specifies the operation to be performed. If trans == 'N' or 'n', $C = alpha * A * B^{T} + alpha * B * A^{T} + beta * C. If trans == 'T',$ 't', 'C', or 'c', $C = alpha * A^T * B + alpha * B^T * A + beta * C$. specifies the number of rows and the number columns of matrix C. If n trans == 'N' or 'n', n specifies the number of rows of matrix A. If trans == 'T', 't', 'C', or 'c', n specifies the number of columns of matrix A; n must be at least zero. k If trans == 'N' or 'n', k specifies the number of columns of matrix A. If trans == 'T', 't', 'C', or 'c', k specifies the number of rows of matrix A; k must be at least zero. alpha double-precision scalar multiplier. Α double-precision array of dimensions (lda, ka), where ka is k when trans == 'N' or 'n', and is n otherwise. When trans == 'N' or 'n', the leading n×k part of array A must contain the matrix A,

otherwise the leading $k \times n$ part of the array must contain the matrix A.

Input ((continued)
IIIPGL 1	(COLLINIACA)

lda	leading dimension of A. When trans $==$ 'N' or 'n', lda must be at least max(1, n). Otherwise lda must be at least max(1, k).
В	double-precision array of dimensions (lda, kb), where kb = k when trans == 'N' or 'n', and k = n otherwise. When trans == 'N' or 'n', the leading $n \times k$ part of array B must contain the matrix B, otherwise the leading $k \times n$ part of the array must contain the matrix B.
ldb	leading dimension of B. When trans $==$ 'N' or 'n', ldb must be at least max(1, n). Otherwise ldb must be at least max(1, k).
beta	double-precision scalar multiplier applied to C. If beta is zero, C does not have to be a valid input.
С	double-precision array of dimensions (ldc, n). If uplo == 'U' or 'u', the leading n×n triangular part of the array C must contain the upper triangular part of the symmetric matrix C, and the strictly lower triangular part of C is not referenced. On exit, the upper triangular part of C is overwritten by the upper triangular part of the updated matrix. If uplo == 'L' or 'l', the leading n×n triangular part of the array C must contain the lower triangular part of the symmetric matrix C, and the strictly upper triangular part of C is not referenced. On exit, the lower triangular part of C is overwritten by the lower triangular part of the updated matrix.
ldc	leading dimension of C; idc must be at least $max(1, n)$.

Output

```
Updated according to
C = \text{alpha} * A * B^{T} + \text{alpha} * B * A^{T} + \text{beta} * C \text{ or}
C = \text{alpha} * A^{T} * B + \text{alpha} * B^{T} * A + \text{beta} * C.
```

Reference: http://www.netlib.org/blas/dsyr2k.f

Error status for this function can be retrieved via **cublasGetError()**. Error Status

CUBLAS_STATUS_NOT_INITIALIZEDif CUBLAS library was not initializedCUBLAS_STATUS_INVALID_VALUEif m < 0, n < 0, or k < 0</th>CUBLAS_STATUS_ARCH_MISMATCHif function invoked on device that does not support double precisionCUBLAS_STATUS_EXECUTION_FAILEDif function failed to launch on GPU

Function cublasDtrmm()

void

performs one of the matrix-matrix operations

```
B = alpha * op(A) * B or B = alpha * B * op(A),
where op(A) = A or op(A) = A^{T},
```

alpha is a double-precision scalar, B is an $m \times n$ matrix consisting of double-precision elements, and A is a unit or non-unit, upper or lower triangular matrix consisting of double-precision elements.

Matrices A and B are stored in column-major format, and 1da and 1db are the leading dimensions of the two-dimensional arrays that contain A and B, respectively.

Input

```
side
         specifies whether op (A) multiplies B from the left or right.
         If side == 'L' or 'l', B = alpha * op(A) * B.
         If side == 'R' or 'r', B = alpha * B * op(A).
uplo
         specifies whether the matrix A is an upper or lower triangular matrix.
         If uplo == 'U' or 'u', A is an upper triangular matrix.
         If uplo == 'L' or 'l', A is a lower triangular matrix.
transa specifies the form of op (A) to be used in the matrix multiplication.
         If transa == 'N' or 'n', op(A) = A.
         If transa == 'T', 't', 'C', or 'c', op(A) = A^{T}.
diag
         specifies whether or not A is a unit triangular matrix. If diag == 'U'
         or 'u', A is assumed to be unit triangular. If diag == 'N' or 'n', A is
         not assumed to be unit triangular.
m
         the number of rows of matrix B: m must be at least zero.
n
         the number of columns of matrix B: n must be at least zero.
alpha
         double-precision scalar multiplier applied to op(A)*B or B*op(A),
         respectively. If alpha is zero, no accesses are made to matrix A, and
         no read accesses are made to matrix B.
```

Input (continued)

A	double-precision array of dimensions (lda, k). If side == 'L' or 'l', k = m. If side == 'R' or 'r', k = n. If uplo == 'U' or 'u', the leading k×k upper triangular part of the array A must contain the upper triangular matrix, and the strictly lower triangular part of A is not referenced. If uplo == 'L' or 'l', the leading k×k lower triangular part of the array A must contain the lower triangular matrix, and the strictly upper triangular part of A is not referenced. When diag == 'U' or 'u', the diagonal elements of A are not referenced
	and are assumed to be unity.
lda	leading dimension of A. When side $== 'L'$ or 'l', it must be at least $max(1, m)$ and at least $max(1, n)$ otherwise.
В	double-precision array of dimensions (1db, n). On entry, the leading $m \times n$ part of the array contains the matrix B. It is overwritten with the transformed matrix on exit.
ldb	leading dimension of B; 1db must be at least max(1, m).

Output

```
B updated according to B = alpha * op(A) * B  or B = alpha * B * op(A).
```

Reference: http://www.netlib.org/blas/dtrmm.f

Error status for this function can be retrieved via **cublasGetError()**. Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if m < 0, n < 0, or k < 0
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasDtrsm()

void

solves one of the matrix equations

```
op(A) * X = alpha * B  or  X * op(A) = alpha * B,
where op(A) = A  or op(A) = A^{T},
```

alpha is a double-precision scalar, and X and B are $m \times n$ matrices that consist of double-precision elements. A is a unit or non-unit, upper or lower, triangular matrix.

The result matrix X overwrites input matrix B; that is, on exit the result is stored in B. Matrices A and B are stored in column-major format, and lda and ldb are the leading dimensions of the two-dimensional arrays that contain A and B, respectively.

Input

```
side
         specifies whether op (A) appears on the left or right of X:
         side == 'L' or 'l' indicates solve op(A) * X = alpha * B;
         side == 'R' or 'r' indicates solve X * op(A) = alpha * B.
uplo
         specifies whether the matrix A is an upper or lower triangular matrix:
         uplo == 'U' or 'u' indicates A is an upper triangular matrix;
         uplo == 'L' or 'l' indicates A is a lower triangular matrix.
transa specifies the form of op(A) to be used in matrix multiplication.
         If transa == 'N' or 'n', op(A) = A.
         If transa == 'T', 't', 'C', or 'c', op(A) = A^{T}.
diag
         specifies whether or not A is a unit triangular matrix.
         If diag == 'U' or 'u', A is assumed to be unit triangular.
         If diag == 'N' or 'n', A is not assumed to be unit triangular.
         specifies the number of rows of B; m must be at least zero.
m
         specifies the number of columns of B; n must be at least zero.
n
alpha
         double-precision scalar multiplier applied to B. When alpha is zero, A
         is not referenced and B does not have to be a valid input.
```

Input (continued)

A	double-precision array of dimensions (lda, k), where k is m when
	side == 'L' or 'l', and is n when side == 'R' or 'r'. If uplo ==
	'U' or 'u', the leading k×k upper triangular part of the array A must
	contain the upper triangular matrix, and the strictly lower triangular
	matrix of A is not referenced. When uplo == 'L' or 'l', the leading
	k×k lower triangular part of the array A must contain the lower
	triangular matrix, and the strictly upper triangular part of A is not
	referenced. Note that when diag == 'U' or 'u', the diagonal
	elements of A are not referenced and are assumed to be unity.
lda	leading dimension of the two-dimensional array containing A. When $side == 'L' or 'l'$, lda must be at least $max(1, m)$. When $side == 'R' or 'r'$, lda must be at least $max(1, n)$.
В	double-precision array of dimensions (ldb, n); ldb must be at least $\max(1, m)$. The leading $m \times n$ part of the array B must contain the right-hand side matrix B. On exit, B is overwritten by the solution matrix X.
ldb	leading dimension of the two-dimensional array containing B; 1db must be at least $max(1, m)$.

Output

B contains the solution matrix X satisfying op(A) * X = alpha * B Or X * op(A) = alpha * B.

Reference: http://www.netlib.org/blas/dtrsm.f

Error status for this function can be retrieved via **cublasGetError()**. Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if m < 0, n < 0, or k < 0
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Double-Precision Complex BLAS3 Functions

Note: Double-precision functions are only supported on GPUs with double-precision hardware.

There are two double-precision complex BLAS3 functions:

- □ "Function cublasZgemm()" on page 113
- □ "Function cublasZsyrk()" on page 115

Function cublasZgemm()

performs one of the matrix-matrix operations

```
C = alpha * op(A) * op(B) + beta * C,
where op(X) = X, op(X) = X^{T}, or op(X) = X^{H};
```

and alpha and beta are double-precision complex scalars. A, B, and C are matrices consisting of double-precision complex elements, with op(A) an $m \times k$ matrix, op(B) a $k \times n$ matrix and C an $m \times n$ matrix.

Input

```
transa specifies op(A). If transa == 'N' or 'n', op(A) = A.

If transa == 'T' or 't', op(A) = A<sup>T</sup>.

If transa == 'C' or 'c', op(A) = A<sup>H</sup>.

transb specifies op(B). If transb == 'N' or 'n', op(B) = B.

If transb == 'T' or 't', op(B) = B<sup>T</sup>.

If transb == 'C' or 'c', op(B) = B<sup>H</sup>.

m number of rows of matrix op(A) and rows of matrix C;

m must be at least zero.

n number of columns of matrix op(B) and number of columns of C;

n must be at least zero.
```

Input (continued)

k	number of columns of matrix op(A) and number of rows of op(B); k must be at least zero.
alpha	double-precision complex scalar multiplier applied to $op(A)*op(B)$.
A	double-precision complex array of dimension (lda, k) if transa == 'N' or 'n', and of dimension (lda, m) otherwise.
lda	leading dimension of A. When transa == 'N' or 'n', it must be at least $max(1, m)$ and at least $max(1, k)$ otherwise.
В	double-precision complex array of dimension (ldb, n) if transb == 'N' or 'n', and of dimension (ldb, k) otherwise.
ldb	leading dimension of B. When transb == 'N' or 'n', it must be at least $max(1, k)$ and at least $max(1, n)$ otherwise.
beta	double-precision complex scalar multiplier applied to C. If beta is zero, C does not have to be a valid input.
C	double-precision array of dimensions (ldc, n).
ldc	leading dimension of C; idc must be at least max(1, m).

Output

```
C updated according to C = alpha * op(A) * op(B) + beta * C.
```

Reference: http://www.netlib.org/blas/zgemm.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if m < 0, n < 0, or k < 0
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

Function cublasZsyrk()

void

performs one of the symmetric rank k operations

```
C = alpha * A * A^{T} + beta * C  or C = alpha * A^{T} * A + beta * C,
```

where alpha and beta are double-precision complex scalars. C is an $n \times n$ symmetric matrix consisting of double-precision complex elements and is stored in either lower or upper storage mode. A is a matrix consisting of double-precision complex elements with dimensions of $n \times k$ in the first case, and $k \times n$ in the second case.

Input

- specifies whether the symmetric matrix C is stored in upper or lower storage mode. If uplo == 'U' or 'u', only the upper triangular part of the symmetric matrix is referenced, and the elements of the strictly lower triangular part are inferred from those in the upper triangular part. If uplo == 'L' or 'l', only the lower triangular part of the symmetric matrix is referenced, and the elements of the strictly upper triangular part are inferred from those in the lower triangular part.
- specifies the operation to be performed. If trans == 'N' or 'n',

 C = alpha * A * A^T + beta * C. If trans == 'T', 't', 'C', or 'c',

 C = alpha * A^T * A + beta * C.
- n specifies the number of rows and the number columns of matrix C. If trans == 'N' or 'n', n specifies the number of rows of matrix A. If trans == 'T', 't', 'C', or 'c', n specifies the number of columns of matrix A; n must be at least zero.
- k If trans == 'N' or 'n', k specifies the number of columns of matrix A. If trans == 'T', 't', 'C', or 'c', k specifies the number of rows of matrix A; k must be at least zero.
- alpha double-precision complex scalar multiplier applied to $A * A^T$ or $A^T * A$.
- A double-precision complex array of dimensions (1da, ka), where ka is k when trans == 'N' or 'n', and is n otherwise. When trans == 'N' or 'n', the leading n×k part of array A contains the matrix A; otherwise, the leading k×n part of the array contains the matrix A.

Input (continued)

lda	leading dimension of A. When trans $==$ 'N' or 'n', lda must be at least max(1, n). Otherwise lda must be at least max(1, k).
beta	double-precision complex scalar multiplier applied to C. If beta is zero, C is not read.
С	double-precision complex array of dimensions (ldc, n). If uplo == 'U' or 'u', the leading n×n triangular part of the array C must contain the upper triangular part of the symmetric matrix C, and the strictly lower triangular part of C is not referenced. On exit, the upper triangular part of C is overwritten by the upper triangular part of the updated matrix. If uplo == 'L' or 'l', the leading n×n triangular part of the array C must contain the lower triangular part of the symmetric matrix C, and the strictly upper triangular part of C is not referenced. On exit, the lower triangular part of C is overwritten by the lower triangular part of the updated matrix.
ldc	leading dimension of C; 1dc must be at least max(1, n).

Output

```
C updated according to C = alpha * A * A^T + beta * C  or C = alpha * A^T * A + beta * C.
```

Reference: http://www.netlib.org/blas/zsyrk.f

Error status for this function can be retrieved via ${\tt cublasGetError}$ ().

Error Status

CUBLAS_STATUS_NOT_INITIALIZED	if CUBLAS library was not initialized
CUBLAS_STATUS_INVALID_VALUE	if n < 0 or k < 0
CUBLAS_STATUS_ARCH_MISMATCH	if function invoked on device that does not support double precision
CUBLAS_STATUS_EXECUTION_FAILED	if function failed to launch on GPU

APPENDIX



CUBLAS Fortran Bindings

CUBLA is implemented using the C-based CUDA toolchain and thus provides a C-style API. This makes interfacing to applications written in C or C++ trivial. In addition, there are many applications implemented in Fortran that would benefit from using CUBLAS. CUBLAS uses 1-based indexing and Fortran-style column-major storage for multidimensional data to simplify interfacing to Fortran applications. Unfortunately, Fortran-to-C calling conventions are not standardized and differ by platform and toolchain. In particular, differences may exist in the following areas:

- □ Symbol names (capitalization, name decoration)
- □ Argument passing (by value or reference)
- □ Passing of string arguments (length information)
- □ Passing of pointer arguments (size of the pointer)
- □ Returning floating-point or compound data types (for example, single-precision or complex data types)

To provide maximum flexibility in addressing those differences, the CUBLAS Fortran interface is provided in the form of wrapper functions. These wrapper functions, written in C, are located in the file fortran.c, whose code needs to be compiled into an application for it to call the CUBLAS API functions. Providing source code allows users to make any changes necessary for a particular platform and toolchain.

The code in fortran.c has been used to demonstrate interoperability with the compilers g77 3.2.3 on 32-bit Linux, g77 3.4.5 on 64-bit Linux, Intel Fortran 9.0 and Intel Fortran 10.0 on 32-bit and 64-bit Microsoft Windows XP, and g77 3.4.0 on Mac OS X.

Note that for g77, use of the compiler flag -fno-second-underscore is required to use these wrappers as provided. Also, the use of the default calling conventions with regard to argument and return value passing is expected. Using the flag -fno-f2c changes the default calling convention with respect to these two items.

Two kinds of wrapper functions are provided. The thunking wrappers allow interfacing to existing Fortran applications without any changes to the applications. During each call, the wrappers allocate GPU memory, copy source data from CPU memory space to GPU memory space, call CUBLAS, and finally copy back the results to CPU memory space and deallocate the GPU memory. As this process causes very significant call overhead, these wrappers are intended for light testing, not for production code. By default, non-thunking wrappers are used for production code. To enable the thunking wrappers, symbol CUBLAS_USE_THUNKING must be defined for the compilation of fortran.c.

The non-thunking wrappers, intended for production code, substitute device pointers for vector and matrix arguments in all BLAS functions. To use these interfaces, existing applications need to be modified slightly to allocate and deallocate data structures in GPU memory space (using CUBLAS_ALLOC and CUBLAS_FREE) and to copy data between GPU and CPU memory spaces (using CUBLAS_SET_VECTOR, CUBLAS_GET_VECTOR, CUBLAS_GET_MATRIX, and CUBLAS_GET_MATRIX). The sample wrappers provided in fortran.c map device pointers to 32-bit integers on the Fortran side, regardless of whether the host platform is a 32-bit or 64-bit platform.

One approach to deal with index arithmetic on device pointers in Fortran code is to use C-style macros, and use the C preprocessor to expand these, as shown in the example below. On Linux and Mac OS X, one way of pre-processing is to invoke 'g77 -E -x f77-cpp-input'. On Windows platforms with Microsoft Visual C/C++, using 'c1 -EP' achieves similar results.

When traditional fixed-form Fortran 77 code is ported to CUBLAS, line length often increases when the BLAS calls are exchanged for CUBLAS calls. Longer function names and possible macro expansion are contributing factors. Inadvertently exceeding the maximum line length can lead to run-time errors that are difficult to find, so care should be taken not to exceed the 72-column limit if fixed form is retained.

The following examples show a small application implemented in Fortran 77 on the host (Example A.1., "Fortran 77 Application Executing on the Host" on page 120), and show the same application using the non-thunking wrappers after it has been ported to use CUBLAS (Example A.2., "Fortran 77 Application Ported to Use CUBLAS" on page 121).

Example A.1. Fortran 77 Application Executing on the Host

```
subroutine modify (m, ldm, n, p, q, alpha, beta)
implicit none
integer ldm, n, p, q
real*4 m(ldm,*), alpha, beta
external sscal
call sscal (n-p+1, alpha, m(p,q), ldm)
call sscal (ldm-p+1, beta, m(p,q), 1)
return
end
program matrixmod
implicit none
integer M, N
parameter (M=6, N=5)
real*4 a(M,N)
integer i, j
do j = 1, N
  do i = 1, M
    a(i,j) = (i-1) * M + j
  enddo
enddo
call modify (a, M, N, 2, 3, 16.0, 12.0)
do j = 1, N
  do i = 1, M
    write(*,"(F7.0\$)") a(i,j)
  enddo
  write (*,*) ""
enddo
stop
end
```

Example A.2. Fortran 77 Application Ported to Use CUBLAS

```
#define IDX2F(i,j,ld) ((((j)-1)*(ld))+((i)-1))
      subroutine modify (devPtrM, ldm, n, p, q, alpha, beta)
      implicit none
      integer sizeof_real
      parameter (sizeof_real=4)
      integer ldm, n, p, q, devPtrM
     real*4 alpha, beta
      call cublas_sscal (n-p+1, alpha,
     1
                         devPtrM+IDX2F(p,q,ldm)*sizeof_real,
                         ldm)
     call cublas_sscal (ldm-p+1, beta,
                         devPtrM+IDX2F(p,q,ldm)*sizeof_real,
                         1)
     return
      end
      program matrixmod
      implicit none
      integer M, N, sizeof_real, devPtrA
      parameter (M=6, N=5, sizeof_real=4)
      real*4 a(M,N)
      integer i, j, stat
      external cublas_init, cublas_set_matrix, cublas_get_matrix
      external cublas shutdown, cublas alloc
      integer cublas_alloc, cublas_set_matrix, cublas_get_matrix
      do j = 1, N
       do i = 1, M
          a(i,j) = (i-1) * M + j
        enddo
      enddo
      call cublas_init
      stat = cublas_alloc(M*N, sizeof_real, devPtrA)
      if (stat .NE. 0) then
```

Example A.2. Fortran 77 Application Ported to Use CUBLAS (continued)

```
write(*,*) "device memory allocation failed"
  call cublas_shutdown
  stop
endif
stat = cublas_set_matrix (M, N, sizeof_real, a, M, devPtrA, M)
if (stat .NE. 0) then
  call cublas free (devPtrA)
  write(*,*) "data download failed"
  call cublas shutdown
  stop
endif
call modify (devPtrA, M, N, 2, 3, 16.0, 12.0)
stat = cublas_get_matrix (M, N, sizeof_real, devPtrA, M, a, M)
if (stat .NE. 0) then
  call cublas free (devPtrA)
  write(*,*) "data upload failed"
  call cublas_shutdown
  stop
endif
call cublas_free (devPtrA)
call cublas_shutdown
do j = 1, N
  do i = 1, M
    write(*,"(F7.0\$)") a(i,j)
  enddo
  write (*,*) ""
enddo
stop
end
```