Operating System: Chap8 Memory Management

National Tsing Hua University 2021, Fall Semester



Overview

- Background
- Swapping
- Contiguous Allocation
- Paging
- Segmentation
- Segmentation with Paging



Background

- Main memory and registers are the only storage
 CPU can access directly
- Collection of processes are waiting on disk to be brought into memory and be executed
- Multiple programs are brought into memory to improve resource utilization and response time to users
- A process may be moved between disk and memory during its execution





Outline

- How to refer memory in a program?
 - > address binding
- How to load a program into memory ?
 - static/dynamic loading and linking
- How to move a program between mem. & disk?
 - > swap
- How to allocate memory?
 - > paging, segment




Multistep Processing of a User Program






- Program is written as symbolic code
- Compiler translates symbolic code into absolute code
- If starting location changes → recompile
- Example: MS-DOS .COM format binary






- Compiler translates symbolic code into relocatable code
- Relocatable code:
 - Machine language that can be run from any memory location
- If starting location changes → reload the code




Source Program

Disk Image

Memory Content




- Compiler translates symbolic code into logical-address (i.e. virtual-address) code
- Special hardware (i.e. MMU) is needed for this scheme
- Most general-purpose OS use this method





Memory-Management Unit (MMU)

- Hardware device that maps virtual to physical address
- The value in the relocation register is added to every address generated by a user process at the time it is sent to memory





Logical vs. Physical Address

- Logical address generated by CPU
 - >a.k.a. virtual address
- Physical address seen by the memory module
- compile-time & load-time address binding
 - ▶ logical addr = physical addr
- Execution-time address binding
 - ▶ logical addr ≠ physical addr
- The user program deals with logical addresses; it never sees the real physical addresses



Outline

- How to refer memory in a program?
 - > address binding
- How to load a program into memory ?
 - static/dynamic loading and linking
- How to move a program between mem. & disk?
 - > swap
- How to allocate memory?
 - > paging, segment



Dynamic Loading

- The entire program must be in memory for it to execute?
- No, we can use dynamic-loading
 - > A routine is loaded into memory when it is called
- Better memory-space utilization
 - unused routine is never loaded
 - Particularly useful when large amounts of code are infrequently used (e.g., error handling code)
- No special support from OS is required implemented through program (library, API calls)



Dynamic Loading Example in C

- dlopen(): opens a library and prepares it for use
- dlsym(): looks up the value of a symbol in a given (opened) library.
- dlclose(): closes a DL library

```
#include <dlfcn.h>
int main() {
  double (*cosine)(double);
  void* handle = dlopen ("/lib/libm.so.6", RTLD_LAZY);
  cosine = dlsym(handle, "cos");
  printf ("%f\n", (*cosine)(2.0));
  dlclose(handle);
}
```

Dynamic Loading

Disk image Memory content After B() called After C() called After C() ends Init Function A() { **Function A() Function A() Function A() B()**; Function A() Function B() { **C()**; Function B() Function B() Function B() Function C() { Function C()



Static Linking

- Static linking: libraries are combined by the loader into the program inmemory image
 - > Waste memory: duplicated code
 - > Faster during execution time
- *Static linking + Dynamic loading
 - > Still can't prevent duplicated code

Program A Program B Program C

main () main ()


Libc.lib Libc.lib Libc.lib

Memory main () Libc.lib main () Libc.lib main () Libc.lib



Dynamic Linking

- Dynamic linking: Linking postponed until execution time
 - Only one code copy in memory and shared by everyone
 - ➤ A stub is included in the program inmemory image for each lib reference
 - ➤ Stub call → check if the referred lib is in memory → if not, load the lib
 - execute the lib
 - > DLL (Dynamic link library) on Windows





Review Slides (1)

- 3 types of address binding?
 - > compile-time
 - > load-time
 - > execution-time
- logical address? physical address?
 - ➤ virtual → physical mapping?
- dynamic loading? static loading?
- dynamic linking? static linking?



Outline

- How to refer memory in a program?
 - > address binding
- How to load a program into memory ?
 - > static/dynamic loading and linking
- How to move a program between mem. & disk?
 - > swap
- How to allocate memory?
 - > paging, segment






Swapping

- A process can be swapped out of memory to a backing store, and later brought back into memory for continuous execution
 - Also used by midterm scheduling, different from context switch
- Backing store a chunk of disk, separated from file system, to provide direct access to these memory images
- Why Swap a process:
 - Free up memory
 - Roll out, roll in: swap lower-priority process with a higher one




- Swap back memory location
 - If binding is done at compile/load time
 - swap back memory address must be the same
 - If binding is done at execution time
 - swap back memory address can be different
- A process to be swapped == must be idle
 - Imagine a process that is waiting for I/O is swapped



Process Swapping to Backing Store

Major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped







Memory Allocation


- Fixed-partition allocation:
 - > Each process loads into one partition of fixed-size
 - Degree of multi-programming is bounded by the number of partitions

- Variable-size partition
 - ➤ Hole: block of contiguous free memory
 - Holes of various size are scattered in memory



Multiple Partition (Variable-Size) Method

- When a process arrives, it is allocated a hole large enough to accommodate it
- The OS maintains info. on each in-use and free hole
- A freed hole can be merged with another hole to form a larger hole





Dynamic Storage Allocation Problem


- How to satisfy a request of size n from a list of free holes
- First-fit allocate the 1st hole that fits
- Best-fit allocate the smallest hole that fits
 - Must search through the whole list
- Worst-fit allocate the largest hole
 - Must also search through the whole list
- First-fit and best-fit better than worst-fit in terms of speed and storage utilization



Buddy Cell Allocation Algorithm

- An efficient heuristic algorithm for implementing best-fit policy
- It makes use of splitting memory into halves to try to give a best fit.
 - ➤ The buddy system (binary) allows a single allocation block to be split, to form two blocks half the size of the parent block. Those two blocks are known as "buddies".
 - ➤ The buddy of blocks must have the same size and adjacent to in memory, so that they can be merged later.

Buddy Cell Allocation Algorithm





- Alloc(8), Alloc(8), Alloc(4), Free(8), Free(8)
- Advantages:
 - Less external fragmentation
 - ➤ Efficient: O(logN) search time, O(1) memory merge and split



Fragmentation

- External fragmentation
 - ➤ Total free memory space is big enough to satisfy a request, but is not contiguous
 - Occur in variable-size allocation
- Internal fragmentation
 - Memory that is internal to a partition but is not being used
 - Occur in fixed-partition allocation
- Solution: *compaction*
 - Shuffle the memory contents to place all free memory together in one large block at execution time
 - Only if binding is done at execution time







Review Slides (2)

- Swapping?
- Contiguous memory allocation?
 - fixed-size memory allocation?
 - variable-size memory allocation?
 - first-fit, best-fit, worst-fit?
- External & internal fragmentation?
 - >compaction?

Non-Contiguous Memory Allocation — Paging



Paging Concept

Method:


- Divide physical memory into fixed-sized blocks called frames
- Divide logical address space into blocks of the same size called pages
- ➤ To run a program of *n* pages, need to find *n* free frames and load the program
- keep track of free frames
- > Set up a page table to translate logical to physical addresses

■ Benefit:

- Allow the physical-address space of a process to be noncontiguous
- Avoid external fragmentation
- Limited internal fragmentation
- Provide shared memory/pages



- Page table:
 - ➤ Each entry maps to the base address of a page in physical memory
 - > A structure maintained by OS for each process
 - Page table includes only pages owned by a process
 - A process cannot access memory outside its space




Address Translation Scheme

- Logical address is divided into two parts:
 - Page number (p)
 - used as an index into a page table which contains base address of each page in physical memory
 - N bits means a process can allocate at most 2^N pages
 2^N x page size memory size
 - Page offset (d)
 - combined with base address to define the physical memory address that is sent to the memory unit
 - ♦ N bits means the page size is 2^N
- Physical addr = page base addr + page offset



Address Translation Architecture

- If Page size is 1KB(2^10) & Page 2 maps to frame 5
- Given 13 bits logical address: p=2,d=20 (in decimal) Hot to translate it to physical addr.?
 - > 5*(1KB)+20 =1,010,000,000,000+0,000,010,100 =1,010,000,010,100




.

Address Translation Examples

- Total number of pages does not need to be the same as the total number of frames
 - > Total # pages determines the logical memory size of a process
 - Total # frames depending on the size of physical memory
- E.g.: Given 32 bits logical address, 36 bits physical address and 4KB page size, what does it mean?
 - ightharpoonup Page table size: $2^{32} / 2^{12} = 2^{20}$ entries
 - ➤ Max program memory: 2³² = 4GB
 - ➤ Total physical memory size: 2³⁶ = 64GB
 - ➤ Number of bits for page number: 2²⁰ pages → 20bits
 - \rightarrow Number of bits for frame number: 2^{24} frames \rightarrow 24bits
 - \triangleright Number of bits for page offset: 4KB page size = 2^{12} bytes \rightarrow 12



Free Frames





Page / Frame Size

- The page (frame) size is defined by hardware
 - > Typically a power of 2
 - Ranging from 512 bytes to 16MB / page
 - > 4KB / 8KB page is commonly used
- Internal fragmentation?
 - ➤ Larger page size → More space waste
- But page sizes have grown over time, because...
 - > Memory, process, data sets have become larger
 - > Fewer page faults and better I/O(paging) performance
 - Page table can be smaller



Paging Summary

- Paging helps separate user's view of memory and the actual physical memory
- User view's memory: one single contiguous space
 - > Actually, user's memory is scatter out in physical memory
- OS maintains a copy of the page table for each process
- OS maintains a frame table for managing physical memory
 - One entry for each physical frame
 - Indicate whether a frame is free or allocated
 - > If allocated, to which page of which process or processes



Implementation of Page Table

- Page table is kept in memory
- Page-table base register (PTBR)
 - > The physical memory address of the page table
 - > The PTBR value is stored in PCB (Process Control Block)
 - Changing the value of PTBR during Context-switch
- With PTBR, each memory reference results in 2 memory reads
 - One for the page table and one for the real address
- The 2-access problem can be solved by
 - Translation Look-aside Buffers (TLB) (HW) which is implemented by Associative memory (HW)



- All memory entries can be accessed at the same time
 - > Each entry corresponds to an associative register
- But number of entries are limited
 - > Typical number of entries: 64 ~ 1024
 - Associative memory parallel search

Page #	Frame #	


Address translation (A´, A´´)

- If A´ is in associative register, get frame # out.
- Otherwise get frame # from page table in memory



Translation Look-aside Buffer (TLB)

- A cache for page table shared by all processes
- TLB must be flushed after a context switch
 - Otherwise, TLB entry must has a PID field (address-space identifiers (ASIDs))





Effective Memory-Access Time

- 20 ns for TLB search
- 100 ns for memory access
- Effective Memory-Access Time (EMAT)
 - > 70% TLB hit-ratio:

```
EMAT = 0.70 \times (20 + 100) + (1-0.70) * (20+100+100) = 150 \text{ ns}
```

➤ 98% TLB hit-ratio

$$EMAT = 0.98 \times 120 + 0.02 \times 220 = 122 \text{ ns}$$



Review Slides (3)

- memory frame? page? typical page size?
- page table? virtual > physical translation?
- What is PTBR register? When to update it?
- Memory reads # for each reference?
- HW support for paging speed?
 - associative memory
 - > TLB



Memory Protection


- Each page is associated with a set of protection bit in the page table
 - > E.g., a bit to define read/write/execution permission
- Common use: valid-invalid bit
 - Valid: the page/frame is in the process' logical address space, and is thus a legal page
 - Invalid: the page/frame is not in the process' logical address space



Valid-Invalid Bit Example

■ Potential issues:

- ➤ Un-used page entry cause memory waste → use page table length register (PTLR)
- ▶ Process memory may NOT be on the boundary of a page → memory limit register is still needed






Shared Pages

- Paging allows processes share common code, which must be reentrant
- Reentrant code (pure code)
 - > It never change during execution
 - > text editors, compilers, web servers, etc
- Only one copy of the shared code needs to be kept in physical memory
- Two (several) virtual addresses are mapped to one physical address
- Process keeps a copy of its own private data and code



Shared Pages by Page Table

Shared code can appear at different locations in the logical address space of all processes






Page Table Memory Structure

- Page table could be huge and difficult to be loaded
 - > 4GB (2³²) logical address space with 4KB (2¹²) page
 - →1 million (2²⁰) page table entry
 - Assume each entry need 4 bytes (32bits)
 - → Total size=4MB
 - ➤ Need to break it into several smaller page tables, better within a single page size (i.e. 4KB)
 - Or reduce the total size of page table
- Solutions:
 - Hierarchical Paging
 - Hash Page Tables
 - Inverted Page Table




Hierarchical Paging


- Break up the logical address space into multiple page tables
 - Paged the page table
 - ➤ i.e. *n*-level page table
- Two-level paging (32-bit address with 4KB (2¹²) page size)
 - \rightarrow 12-bit offset (d) \rightarrow 4KB (2¹²) page size
 - \rightarrow 10-bit outer page number \rightarrow 1K (2¹⁰) page table entries
 - \gt 10-bit inner page number \rightarrow 1K (2¹⁰) page table entries
 - > 3 memory accesses



Two-Level Page Table Example




2¹⁰




м

Two-Level Address Translation



Two-Level Page Table Translation Example





64-bit Address

- How about 64-bit address? (assume each entry needs 4Bytes)
 - > 42 (p1) + 10 (p2) + 12 (offset)
 - \rightarrow outer table requires 2^{42} x 4B = 16TB contiguous memory!!!
 - > 12 (p1)+10 (p2)+10 (p3)+10 (p4)+10 (p5)+12 (offset)
 - \rightarrow outer table requires $2^{12} \times 4B = 16KB$ contiguous memory
 - → 6 memory accesses!!!
- Examples:
 - > SPARC (32-bit) and Linux use 3-level paging
 - ➤ Motorola 68030 (32-bit) use 4-level paging




Hashed Page Table

- Commonly-used for address > 32 bits
- Virtual page number is hashed into a hash table
- The size of the hash table varies
 - ➤ Larger hash table → smaller chains in each entry
- Each entry in the hashed table contains
 - > (Virtual Page Number, Frame Number, Next Pointer)
 - Pointers waste memory
 - Traverse linked list waste time & cause additional memory references


Hash function f(p) = p%5

Buckets:




м.

Hashed Page Table Address Translation



Improved Hashed Page Table Implementation



Source: M. Talluri, M. D. Hill, and Y. A. Khalidi. 1995. A new page table for 64-bit address spaces. *SIGOPS Oper. Syst. Rev.* 29, 5 (December 1995), 184-200. http://pages.cs.wisc.edu/~markhill/papers/sosp95_pagetables.pdf




Inverted Page Table

- Maintains NO page table for each process
- Maintains a frame table for the whole memory
 - One entry for each real frame of memory
- Each entry in the frame table has
 - (PID, Page Number)
- Eliminate the memory needed for page tables but increase memory access time
 - > Each access needs to search the whole frame table
 - > Solution: use hashing for the frame table
- Hard to support shared page/memory

M

Inverted Page Table Addr Translation





Review Slides (4)


- memory protection by page table?
 - ➤ valid, invalid bits?
- page table memory structure?
 - ➤ hierarchical → 2-level, 3-level, etc
 - hash table linked list
 - > inverted page table
- How are pages shared by different processes?

Non-Contiguous Memory Allocation — Segmentation




Segmentation

- Memory-management scheme that supports user view of memory
- A program is a collection of segments. A segment is a logical unit such as:
 - > main program
 - function, object
 - local/global variables,
 - stack, symbol table,
 - > arrays, etc...



Logical View of Segmentation






Segmentation Table

- Logical address: (seg#, offset)
 - Offset has the SAME length as physical addr.
- Segmentation table maps two-dimensional physical addresses; each table entry has:
 - ➤ Base (4 bytes): the start physical addr
 - > Limit (4 bytes): the length of the segment
- Segment-table base register (STBR):
 - > the physical addr of the segmentation table
- Segment-table length register (STLR):
 - > the # of segments



Segmentation Hardware

- Limit register is used to check offset length
- MMU allocate memory by assigning an appropriate base address for each segment
 - Physical address cannot overlap between segments






Address Translation Comparison

- Segment
 - > Table entry: (segment base addr. , limit)
 - > Segment base addr. can be arbitrary
 - > The length of "offset" is the same as the physical memory size


■ Page:

- Table entry: (frame base addr.)
- Frame base addr. = frame number * page size
- > The length of "offset" is the same as page size






Example of Segmentation



Sharing of Segments






Protection & Sharing

- Protection bits associated with segments
 - Read-only segment (code)
 - Read-write segments (data, heap, stack)
- Code sharing occurs at segment level
 - Shared memory communication
 - Shared library
- Share segment by having same base in two segment tables



Basic Concept


- Apply segmentation in logical address space
- Apply paging in physical address space





Address Translation


- CPU generates logical address
 - Given to segmentation unit
 - produces linear addresses
 - > Linear address given to paging unit
 - generates physical address in main memory
- Segmentation and paging units form equivalent of MMU





Example: The Intel Pentium


- Logical-address space is divided into 2 partitions:
 - > 1st: 8K(2¹³) segments (private), local descriptor table (LDT)
 - > 2nd: 8K(2¹³) segments (shared), global descriptor table (GDT)
- Logical address:
 - \triangleright max # of segments per process = $2^{14} = 16K$
 - \triangleright size of a segment $\leq 2^{32} = 4GB$





Intel Pentium Segmentation


- Segment descriptor
 - Segment base address and length
 - Access right and privileged level





Intel Pentium Paging (Two-Level)


- Page size can be either 4KB or 4MB
 - > Each page directory entry has a flag for indication





Example Question

- Let the physical mem size is 512B, the page size is 32B and the logical address of a program can have 8 segments. Given a 12 bits **hexadecimal** logical address "448", translate the addr. With blow page and segment tables.
- linear addr:0101111110, phy addr:0010111110





Review Slides (5)

Segmentation vs. Paging?

	Paging	segmentation
Length	Fixed	Varied
Fragmentation	Internal	External
Table entry	Fable entry Page number → frame number	
View	Physical memory	User program

Paged segmentation?



Problem Set

- 8.1: Explain the difference between internal and external fragmentation
- 8.3: Why are segmentation and paging sometimes combined into one scheme?
- 8.4: Most system allow a program to allocate more memory to its address space during execution. Allocation of data in the heap segments of programs is an example of such allocated memory. What is required to support dynamic memory allocation in the following schemes?
 - > A. Contiguous memory allocation
 - B. Pure segmentation
 - Pure paging



Problem Set

- 8.7: Explain why sharing a reentrant module is easier when segmentation is used than when pure paging is used.
- 8.14: Consider a logical address space of 64 pages of 1024 words each, mapped onto a physical memory of 32 frames.
 - How many bits are there in the logical address?
 - How many bits are there in the physical address?
- 8.16: Given five memory partitions of 100 KB, 500 KB, 200 KB, 300 KB, and 600 KB (in order), how would the first-fit, best-fit, and worst-fit algorithms place processes of 212 KB, 417 KB, 112 KB, and 426 KB (in order)? Which algorithm makes the most efficient use of memory?

Problem Set

- 8.18: Consider a computer system with 1 32-bit logical address and 4-KB page size. The system supports up to 512 MB of physical memory. How many entries are there in each of the following?
 - A conventional single-level page table
 - > An inverted page table
- 8.21: Consider the following segment table, what are the physical address for the following logical addresses?
 - (a) 0,430 (b) 1,10 (c) 2,500 (d) 3,400 (e) 4,112

	Segment	Base	Length
	0	219	600
	1	2300	14
	2		
	90	100	
	3	1327	580
Chapter8 Me	4	1952	96



Interesting Reading

- M. Talluri, M. D. Hill, and Y. A. Khalidi. 1995. A new page table for 64-bit address spaces. SIGOPS Oper. Syst. Rev. 29, 5 (December 1995), 184-200.
- http://pages.cs.wisc.edu/~markhill/papers/sosp95_p agetables.pdf