Tallyard platform workflows

Every workflow in the platform, drawn as a simple diagram with the steps, the rules and who is told what. As built on 16 October 2026, after the round 2 changes from the partner review of 14 October and the follow-up to the recording audit of 16 October.

SECTIONS	WORKFLOWS	LIVE APP	SAMPLE PASSWORD
7	**77**	**tallyard-platform.vercel.app**	**sandbox**

Everything here describes the sandbox: data stays in each visitor's browser, the world is sample data, and carbon, price and timeline figures are indicative.


How to read this

Each workflow has its own page: a diagram first, then the same flow written out as numbered steps, then the rules (who may do it, what is refused, what stays hidden) and the notifications it sends. Some workflows also show a lifecycle: the states a record moves through.

Colours: who does each step

- Architect
- Client (developer)
- Donor building owner
- Site surveyor
- Deconstruction contractor
- Sustainability consultant
- The platform, automatically

Shapes



Rectangles are actions, diamonds are decisions or checks, rounded ends are outcomes. Dashed grey boxes are things the platform does by itself, such as checking access or sending a notification.

Contents

How it fits together

1. Take a material from site survey to a listing
2. Take a material from shortlist to reservation
3. Understand who sees what
4. How notifications and activity reach people
5. Start a new organisation

Accounts and the sandbox

1. Sign in and return to the page you asked for
2. Create an account and an organisation
3. First visit to a new workspace
4. Reset a forgotten password in the sandbox
5. Invite a teammate
6. Accept an invite and join the team
7. Switch between sample accounts
8. Reset the sandbox
9. Come back after the 16 October update
10. Pages you may not open, and pages that do not exist
11. Search with Ctrl K or Cmd K
12. Undo a change

Architect

1. Create a project
2. Wait for the client to accept, or ask again
3. Edit the programme
4. Choose planning and sustainability requirements
5. Follow the setup checklist on a new project
6. Find materials in the Marketplace
7. See lots shared with your project
8. Look at a material, save it and download its geometry
9. Work through the shortlist
10. Send materials for approval
11. Prepare and export the specification

Client (developer)

1. Accept or decline a project request
2. Join a new client organisation from an invite
3. Approve or decline a material
4. Request a reservation
5. Withdraw a reservation request
6. When the seller accepts or declines
7. Follow a reservation from request to reserved
8. Work through the to do list
9. Review the circular economy statement
10. Track requirements and evidence
11. Read the dashboard figures
12. Follow the programme and certification across projects

Donor building owner

1. Add a donor building
2. Add a new project and appoint an architect
3. Browse the Marketplace as an owner
4. Appoint a surveyor to a building
5. Confirm or decline a building a surveyor added
6. Read the recovery plan
7. List a lot: private, shared or published
8. Set disclosure and read the disclosure score
9. Grant or revoke sharing with projects
10. Create, copy and revoke a share link
11. What a person who opens a share link sees
12. Accept or decline a reservation request
13. Request testing of items
14. Appoint a contractor and apply their dates
15. Track requirements before demolition
16. The guard on reserving your own lots

Surveyor and deconstruction contractor

1. Capture an item from the Capture page
2. Capture from a building's Capture tab
3. Add a building before any appointment and ask the owner to confirm it
4. Owner confirms or declines a surveyed building
5. Move early captures into an appointment
6. Submit the survey to the owner
7. Request testing and record the booking and results
8. Deconstruction contractor sets availability dates
9. Owner applies the contractor's dates

Sustainability consultant


1. Answer a request to join a project
2. Set, override or reset a project target
3. Follow projects from the Overview and the Projects list
4. Enter a result with its date and source
5. Track a requirement's status and evidence
6. Target certification credits and set their status
7. Map reclaimed materials to credits
8. Draft and export the circular economy statement
9. Send the statement for the client's review
10. Read the Sustainability tab
11. Check compliance and export the workbook
12. Import and review a demolition bill

Things worth a look

SECTION

How it fits together

Tallyard connects five kinds of organisation around one reclaimed material: the surveyor records it in a building coming down, the donor building owner decides who may see it, the architect shortlists it, the client approves and reserves it, and the sustainability consultant reports its carbon. Each organisation works in its own workspace and sees only what its role allows. This section shows the whole journey first, then who sees what, how people are told, and how a new organisation starts.


Surveyor captures items on site
Surveyor submits the survey
Owner decides who may see each lot
Not yet
Publish
Share
Stays private
Published to the Marketplace
Shared in confidence with chosen projects
Architect finds and shortlists
Architect sends for approval
No, architect may reopen
Client approves?
Yes
Client requests a reservation
No, client may ask again
Owner accepts the request?
Yes
Contacts shown to client and owner
Consultant reads carbon and prepares reports


HOW IT FITS TOGETHER

Take a material from site survey to a listing

Surveyor | Donor building owner | Platform

Where Building, Capture (/app/buildings/:id/capture or /app/capture), Inventory (/app/buildings/:id/inventory), Recovery plan (/app/buildings/:id/priorities), Listings (/app/buildings/:id/listings) and Sharing (/app/buildings/:id/sharing)

This is the supply half of the journey. The surveyor records what a building holds, the owner reviews it and then chooses, lot by lot, whether it stays private, is shared in confidence with chosen projects, or is published to the Marketplace.


Surveyor captures an item
Item saved as a private lot
Owner told, when a surveyor captured it
Surveyor submits the survey
Owner told the survey is in
Owner reviews inventory and recovery plan
Who should see this lot?
Nobody yet
Buyers
Stays private
Owner sets an ask and a reserve
Publish or share?
Publish
Share
Disclosure score would be high?
Shared in confidence with allowed projects
Yes
No
Refused until less is disclosed
Live on the Marketplace

STEPS

1. Surveyor Captures an item on the building's Capture tab or the standalone Capture page, with its material, size, quantity, condition, photos and expected date.
2. Platform Saves the item with its own lot, private by default, and starts the survey if it had not started.
3. Platform Tells the owner that new items were captured, but only when the surveyor captured them; repeat captures by the same surveyor at the same building on the same day fold into one notification.
4. Surveyor Presses Submit survey when the walk round is done.
5. Platform Records who surveyed the building and tells the owner the survey is in, linking to the Recovery plan.
6. Donor building owner Reviews the Inventory and the Recovery plan to decide what to recover.
7. Donor building owner On Listings, sets each lot to Private, Shared or Published, entering an ask and a reserve per unit for Shared or Published.
8. Platform Checks the building's disclosure score before publishing and refuses if it would be high.
9. Donor building owner On Sharing, switches on the projects allowed to see shared lots; each project shows only as a blind line, and the choice covers every shared lot the owner has, in all its buildings.

RULES

- Only the owner and the appointed surveyor can capture or edit items. A deconstruction contractor on its own sees only the Overview and Availability tabs and sets expected dates.
- A building that a surveying firm added itself stays private to that firm until its owner confirms it on Requests, or until the firm, once appointed to the owner's own record of it, moves its captures there. Until then nothing in it can be shared or published and the survey cannot be submitted.
- Only the surveyor can submit a survey. It is refused until the building is linked to its owner and at least one item is captured, and it cannot be submitted twice. Items captured after submitting still reach the owner; Reopen survey only marks it as in progress again.
- Sharing or publishing needs an ask and a reserve, both above zero, in whole price steps, and the reserve cannot be above the ask.
- Publishing is refused when the disclosure score would be high: Publishing at this disclosure level lets an outsider narrow down the building. Reduce what is disclosed first.
- Material, size and quantity are fixed when the item is captured. Once a lot is shared or published its condition and expected date are locked too, and the availability date can be changed only while the lot is private.
- A lot held by an accepted reservation cannot change visibility: This lot is reserved. Its visibility cannot change.
- The owner chooses how much a listing discloses: location as region or local authority, timing as a three-month window or a month, and which photos are public.
- The owner and the surveyor also track the requirements that apply before demolition on the building's Requirements tab; nothing there reaches a buyer.


NOTIFICATIONS

- Owner: each capture by a surveyor, folded per day (New items captured).

- Owner: items a surveyor captured before the appointment and moved into the building, "Captured before your appointment. Private until you decide."
- Owner: the survey was submitted, with the item count (Surveys submitted).
- Architects: when a lot is published, any architecture practice with a project the lot is available in time for hears of it, without the owner or building being named (New materials for your projects).
- Architect and accepted client of each project the owner allows: New lot shared with the project when a lot is shared, or N lots shared when the owner allows a project and already has shared lots; if the project has not accepted the confidentiality terms, it is told to accept them first (Lots shared with a project).

LIFECYCLE

Every captured lot starts private. The owner moves it between private, shared and published until a reservation is accepted, which holds it for one project and fixes its visibility.




HOW IT FITS TOGETHER

Take a material from shortlist to reservation

Architect | Client or developer | Donor building owner | Sustainability consultant | Platform

Where Marketplace (/app/marketplace and /app/marketplace/:publicId), project Shortlist (/app/projects/:id/shortlist), Approvals (/app/projects/:id/approvals), Reservations (/app/projects/:id/reservations), the owner's Requests (/app/requests), and the consultant's Sustainability tab (/app/projects/:id/sustainability)

This is the demand half of the journey. The architect shortlists a material for a project and sends it to the client, the client approves it and asks the owner to reserve it, and the owner accepts or declines a request that does not say who the buyer is.


Architect finds a material in the Marketplace
Architect saves it to a project shortlist
Client has accepted the project?
No
Yes
Cannot send for approval yet
Architect sends it for approval
Client approves?
No
Yes
Architect may reopen it with a new note
Client requests a reservation
Owner sees a blind request
Owner accepts?
No
Yes
Declined, client may ask again
Other waiting requests for the lot declined
Contacts shown to client and owner
Consultant reads carbon from reserved materials

STEPS

1. Architect Finds a material in the Marketplace, or under Shared with you for lots shared in confidence, and presses Save to project.
2. Architect On the project's Shortlist, presses Send for approval, or Send to client for the chosen items, with an optional message.
3. Client or developer On Approvals, opens each material and presses Approve or Decline, with an optional note.
4. Architect Presses Reopen on a declined material, with a new note, so it can be sent again.
5. Client or developer On Reservations, presses Request reservation on an approved material and then Send request; the screen says the seller does not see who you are until they accept.
6. Donor building owner On Requests, reads the request as a blind buyer line and presses Accept, then Accept and reserve, or Decline.
7. Platform On acceptance, holds the lot for that project, declines any other waiting requests for it with the note Reserved for another buyer, and takes it off the Marketplace.
8. Client or developer Sees the seller's organisation, contact name and email on Reservations, with Contact the seller to agree terms.
9. Donor building owner Sees the buyer's organisation, contact name, email and message, with Agree the terms directly with the buyer.
10. Sustainability consultant Reads the carbon saved by reserved materials on the Sustainability tab, writes the statement on Circular economy and presses Send to the client for review, which freezes the text the client reads, and presses Export workbook on Compliance.

RULES

- Only the project's architect can save, move, note, send or reopen shortlist items. A lot shared in confidence can be saved only to a project it is shared with, never to Saved, and cannot be moved.
- Nothing can be sent for approval until the client has accepted the project: The client has not accepted this project yet, so nothing can be sent for approval.
- Only the client can approve or decline, and only items that were sent. A decision is refused if the lot is no longer shared with the project or no longer available. An approved item cannot be removed from the shortlist.
- Only the client can request a reservation, and only for an approved material that is still shared with the project and available. One waiting request per material per project.
- A donor building owner acting as client of its own New project cannot reserve its own lot: This lot is yours. Allocate it directly; reserving is for other sellers.
- The client can withdraw a request while the owner has not decided it, and can ask again after a decline or withdrawal.
- Only the owner of the building can decide a request, only once, and cannot accept when the lot is already held for another project. Straight after deciding, the owner can press Undo on the confirmation message, as long as nothing else has changed since.
- The architect and the consultant never see the seller's name: their activity says The seller.
- The sustainability consultancy reaches the project, and hears of its decisions and reservations, only once the client has accepted the project and the consultancy has accepted the architect's request too.


NOTIFICATIONS

- Client: N materials to approve on the project, with the architect's message (Materials sent for approval).
- Architect, and the consultancy once it has joined: the client approved or declined a material (Client decisions).

- Owner: Reservation request for the item, with the blind buyer line, and Request withdrawn if the client withdraws (Reservation requests).
- Client: the seller's organisation accepted the reservation, with the contact name and email, or Reservation declined with the seller's note (Reservation decisions).
- Architect: the material is reserved, without naming the seller (Reservation decisions). The architect gets no notification for a decline; it shows in project activity.
- Consultant: no notification about reservations; requests and decisions show only in project activity.
- Clients of other projects with a waiting request for the same lot: Reservation declined, Reserved for another buyer.

LIFECYCLE

A reservation request waits until the owner accepts or declines it, the client withdraws it, or the owner accepts another buyer's request for the same lot.




HOW IT FITS TOGETHER

Understand who sees what

Donor building owner | Architect | Client or developer | Sustainability consultant | Surveyor | Platform

Where Marketplace (/app/marketplace), Shared with you and Review terms in the Marketplace, the owner's Sharing tab (/app/buildings/:id/sharing), share links (/app/links/:linkId), Requests (/app/requests) and project Reservations (/app/projects/:id/reservations)

Buyers and sellers stay anonymous to each other until a reservation is accepted. Buyers read a lot only as a public listing, and the owner reads each project only as a blind buyer line.


Owner sets the lot to?
Private
Shared or published
Private, building team only
Public listing made from the lot
Shared
Published
Project allowed and terms accepted, or link?
Yes
No
Architects see it in the Marketplace
Shown under Shared with you
Hidden from that project
Architect shortlists, client approves
Client requests a reservation
Owner sees only the blind buyer line
Owner accepts?
Yes
Yes
No
Client and owner see names and emails
Architect and consultant still read The seller
Both sides stay anonymous

STEPS

1. Platform Keeps a private lot visible only to the building's owner and its surveyor; a deconstruction contractor sees the items only to set expected dates.
2. Platform Turns a shared or published lot into a public listing, the only form any buyer reads.
3. Donor building owner Allows chosen projects on the Sharing tab, each shown as organisation type, project type, region and the three-month window it is needed. One choice covers every shared lot the owner has.
4. Architect Presses Review terms and accepts the confidentiality terms for the project, once, so shared lots appear under Shared with you; the client can accept them too.
5. Donor building owner Can instead send a share link to chosen shared lots; anyone signed in who opens it and accepts the terms sees those lots.
6. Client or developer Requests a reservation of an approved material; the owner sees only the blind buyer line, and the buyer's organisation, contact and message stay hidden until the owner accepts.
7. Platform When the owner accepts, gives the client the seller's organisation, contact and email, and the owner the buyer's organisation, contact, email and message.

RULES

- A public listing shows the title, specification, quantity, condition, test status, grade, source type, seller type, era band, location as region or local authority, availability as a window, a guide price range, avoided carbon and only photos the owner made public.
- A public listing never shows the building name, street, postcode, the owner or its people, tenants, the surveyor, the contractor, the item tag, exact dates, or the owner's ask and reserve.
- The owner never sees a project's name, client or architect before accepting a reservation: only the blind line, such as Design team, commercial project, region, needed April to June 2028.
- Shared lots reach a project only when the owner has allowed it and the architect or the client has accepted the confidentiality terms for that project, or through an active share link.
- If the owner declines, or the client withdraws, neither side learns who the other is.
- The owner learns only the type of organisation that opened a share link, never who. Revoking a link removes its lots from every opener at once.
- After acceptance the client and the owner see each other. The architect and the consultant never see the seller; their activity reads The seller.
- The consultant has no Shortlist, Approvals or Reservations tab, and the Sustainability tab shows no money figures to anyone.
- A donor building owner reads the Marketplace as a client would, but never its own lots; it manages those in its buildings.
- No third party learns of a project before its client accepts: the consultancy is asked only then, and sees the project only once it accepts too.
- A deconstruction contractor sees only the Overview and Availability of a building: no lots, prices, buyers, inventory, testing or requirements, and no requirement activity.
- Inviting a contractor by email, or a client contact, reveals nothing about who is on Tallyard; the sign-up page names no organisation or project behind an invite.

- A surveyor never learns which organisation declined a building, nor which buildings an owner already has.
- A page for a record you are not part of reads You do not have access to this.

NOTIFICATIONS

- Owner: Your share link was opened, naming only the type of organisation, folded per day into a count (Share links).
- Openers of a revoked link: A shared link was withdrawn.
- Architect and accepted client: lots shared with their project, asking them to accept the terms first when they have not.


HOW IT FITS TOGETHER

How notifications and activity reach people

Every role | Platform

Where The bell in the top bar, Notifications (/app/notifications), Recent activity on each Home (/app/home), the project Activity tab (/app/projects/:id/activity), the building Activity page (/app/buildings/:id/activity) and Settings, Notifications (/app/settings/notifications)

Every action writes an activity line and may send notifications. Both are addressed to organisations and written in words each reader may see, and each reader is taken to the right page in their own workspace. The diagram follows one example: the architect sends materials and the client is told.


Architect sends materials for approval
Activity line written for each audience
Notification addressed to each organisation told
Reader has this kind switched on?
No
Yes
Left out of that reader's inbox
Shows in the bell and Notifications
Client opens the line
Can the reader open that page?
Marked read for that reader only
Yes
No
Opens the same thing in their workspace
Goes home, or shows no link

STEPS

1. Platform Writes an activity line for each audience, so the client may read the seller's name while the architect reads The seller and the owner reads A buyer.
2. Platform Sends a notification to each organisation that should be told; everyone in that organisation receives it.
3. Platform Leaves out of a person's inbox any kind they have switched off in Settings, Notifications.
4. Platform Shows the rest in the bell, with an unread count, and on the Notifications page, grouped by day with All, Unread and per kind filters.
5. Any reader Opens a line and is taken to the same thing in their own workspace.
6. Any reader Opening a line marks it read; a reader can also mark one line read, or press Mark all as read.

RULES

- Notifications stay in the app; nothing is emailed.
- Read state is per person. The person who acted has their own organisation's copy already marked read.
- Each person chooses which kinds reach them. Only kinds that fit their role are offered, and all start switched on.
- Only two kinds of event fold into one line with a count: captures by one surveyor at one building on the same day, and opens of one share link on the same day.
- Per reader links: a line that points at another side's page leads to the matching page in the reader's workspace. The architect goes to Shortlist instead of Approvals or Reservations, the client goes to Approvals instead of Shortlist, the architect and client go to the Sustainability tab instead of the consultant's own pages, and anything else leads to the project or building overview.
- When the reader cannot open the page, an activity line shows no link and a notification leads to Home.
- Sidebar badges count what waits: the owner's Requests counts reservation requests and buildings to confirm, a client's project counts materials waiting for approval, a building's Requirements tab counts requirements at risk for the owner and the surveyor, and Project requests appears for a client or a consultancy while an architect waits for an answer.
- Each building has an Activity page, linked from its Overview as projects have, open to every side on the building and filtered to what that organisation may read.
- A notice that invites an action that has gone is taken away: when a request to confirm a building is withdrawn, merged or deleted its notice leaves the owner's bell, and answering marks it read for the person who answered.
- Activity and notifications about a project reach a consultancy only once it has joined the project.

NOTIFICATIONS

- Kinds each role can switch on or off. Architect: lots shared with a project, client decisions, reservation decisions, new materials for your projects, team and projects.
- Client or developer: lots shared with a project, materials sent for approval, reservation decisions, team and projects, sustainability and compliance.
- Donor building owner: materials sent for approval on its New projects, reservation requests and decisions, surveys submitted, new items captured, team and projects, building confirmations, testing, availability dates, share links, sustainability and compliance.
- Surveyor: appointments, team and projects, building confirmations, testing.
- Sustainability consultant: client decisions, team and projects, sustainability and compliance.


HOW IT FITS TOGETHER

Start a new organisation

New person | Architect | Client or developer | Donor building owner | Surveyor | Sustainability consultant | Platform

Where Create your account (/signup), then Home (/app/home); colleagues join through Settings, Team (/app/settings/team) and an invite link (/invite/:token)

A person creates an account in two steps and chooses the organisation type, which sets up the workspace. A new organisation starts empty, and its home page leads with the first steps for its type. Someone invited to a client organisation, or to be a building's contractor, joins straight into that role.



STEPS

1. New person On Create your account, enters full name, work email and a password, then presses Continue.
2. New person Enters the organisation name, picks one of five organisation types and presses Create account. An email invited to answer a project request skips this: it joins the client organisation that invited it.
3. Platform Creates the organisation and the person, signs them in and opens Home with a welcome message.
4. Architect Sees Welcome to your workspace and the Create your first project dialog, with In the Marketplace now below; the sidebar has Home, Marketplace, Saved, Projects and New project.
5. Client or developer Sees a welcome with three next steps; a project appears once an architect asks to add the organisation as client and a member presses Accept under Project requests.
6. Donor building owner Sees Add your first building with three steps and Add building; the sidebar has Home, Marketplace, Donor buildings and Requests, and New projects once it adds one.
7. Surveyor Sees a first run with three steps and Add building, to start capturing before any owner appoints the firm; the sidebar has Home, Capture and Clients. A firm invited by email to be a building's contractor becomes it on joining.
8. Sustainability consultant Sees No projects yet with three steps until an architect asks the consultancy to join a project whose client has accepted, and it accepts; waste engagements come only with the sample data and cannot be started in the platform. The sidebar has Home, Projects and Engagements, with Project requests while one waits.
9. Any member Invites colleagues from Settings, Team with Invite a colleague and Copy link; the invitee opens the link, enters a name and password and joins.

RULES

- The five types are Architecture practice, Developer or client, Donor building owner, Surveying or deconstruction firm, and Sustainability consultancy.
- The type is fixed once chosen: members can rename the organisation and set its address, but not change its type.
- Sign up is refused for an email already in use: An account with this email already exists. Sign in instead. Passwords need at least 8 characters.
- A deconstruction contractor signs up as a Surveying or deconstruction firm and acts as contractor only when a building's owner or surveyor invites it, from the list or by email, to set dates on that building. A firm that only dates buildings reads Deconstruction contractor and has no Capture page.
- A client reaches a project only after accepting the architect's request; the architect finds a new client organisation by typing its exact name and may invite a contact there by email. Every donor building owner has the Marketplace.
- An invite is refused for someone already in the organisation, for an email another account uses, or when a pending invite exists. A used or revoked invite link no longer works.
- In the sandbox no email is sent: the invite is a link the member copies and passes on. Five sample accounts use the password sandbox.


NOTIFICATIONS

- Organisation: someone joined, after an invite is accepted (Team and projects).
- Client: an architect asks to add them to a project (Team and projects); the architect hears whether the client accepted or declined, and when an invited contact joins.
- Consultant: an architect asks to add the consultancy to a project, once its client has accepted (Team and projects); the architect hears its answer, and the client hears when it joins.
- Architect: appointed by a donor building owner to a New project (Team and projects).

- Surveyor: a donor building owner appointed the firm to survey a building, or the firm was invited to set dates (Appointments).
- Owner: a surveying firm that added a building asks the owner, by email, to confirm it is theirs (Building confirmations).

LIFECYCLE

An invite waits until the invitee joins through the link or a member revokes it.



SECTION

Accounts and the sandbox

This section is about everyone who uses the platform, whatever their organisation. It covers getting in (sign in, sign up, password reset, invites), coming back after the 16 October update, moving between the sample accounts, resetting the sandbox, and the tools that work on every page: search, undo, and the pages shown when something cannot be opened. Everything runs in the person's own browser as a sandbox, no email is ever sent, and steps anyone can take are drawn in plain white boxes.


ACCOUNTS AND THE SANDBOX

Sign in and return to the page you asked for

Any person | Platform

Where Sign in page (/signin), reached from the landing page or by opening any /app address while signed out

A person signs in with their email and password, or with one click on a sample account card. If they were sent to sign in from a page inside the app, they land back on that page; otherwise they land on their home page.



STEPS

1. Any person Opens an address inside the app, such as a project page, while signed out, or opens Sign in from the landing page.
2. Platform Sends a signed-out person to Sign in and remembers the address they asked for.
3. Any person Enters Email and Password and presses Sign in, or clicks one of the five cards under Or continue with a sample account.
4. Platform Checks that the email and password match an account in this browser and signs the person in.
5. Platform Opens the page they asked for, or their home page (/app/home) if there was none.
6. Platform In a browser whose sandbox was replaced by the 16 October update, a failed sign-in for an email with no account adds "The sandbox was updated on 16 October. Accounts made before then need to be created again." with Create your account again, which opens sign-up with the typed email filled in.

RULES

- An empty field, or an email that does not look like an email address, is flagged under the field before anything is checked.
- A wrong email or a wrong password shows the same message, That email and password do not match, so the page never reveals which accounts exist.
- The update line is left out for a known email with a wrong password, for a likely typo (an address one edit from a sample organisation's domain, or within two edits of an account in the sandbox), in a browser that was never updated, and 30 days after the browser found the update.
- A person still remembered from before the update, whose account is gone, sees the same line in a callout before any attempt, and the dead sign-in is forgotten.
- Remember me on this device is ticked by default. Unticked, closing the browser signs the person out. The sample account cards always remember.
- The five cards are Priya Nair (Architect, Studio Oriel), Isla Brennan (Client (developer), Lantern Quay Developments), Tom Ashby (Donor building owner, Ostlea Estates), Dana Kowalski (Site surveyor, Tarnbrook Deconstruction) and Marcus Lindqvist (Sustainability consultant, Halewick Sustainability). Every sample account uses the password sandbox.
- A sample card signs in with the password sandbox. If someone has changed that account's password on Reset your password, the card fails with the mismatch message until the sandbox is reset.
- The remembered address is only ever a page inside the app on this site; anything else is ignored and the person goes to their home page. Opening /app or /app/home while signed out leads to a plain Sign in.
- A person who opens Sign in, Create your account or Reset your password while already signed in goes straight on to the app.
- Sign out is in the avatar menu. It shows You are signed out and opens a plain Sign in page, without offering the page they left.

- Signing in only opens the door: each page still checks what this person may see (see Pages you may not open).

NOTIFICATIONS

- None


ACCOUNTS AND THE SANDBOX

Create an account and an organisation

Any person | Platform

Where Create your account (/signup), from the Create an account link on Sign in

A new person creates their own account and a new organisation in two steps. The organisation type they choose decides which workspace they get: architect, client, donor building owner, surveyor or sustainability consultant. An email that an architect invited to answer a project request joins that client organisation instead.



STEPS

1. Any person On Step 1 of 2 enters Full name, Work email and Password, then presses Continue. Coming from the sign-in line Create your account again, the email is already filled in.
2. Platform Checks the three fields and, if they are fine, moves to Step 2 of 2, Your organisation.
3. Any person Enters Organisation name, picks one Organisation type card, then presses Create account.
4. Platform Checks every field again, including whether the email already has an account, then creates the organisation and the person and signs them in.
5. Platform If a building waits for a deconstruction contractor at that email and the new organisation is a surveying or deconstruction firm, makes it the contractor and tells both sides.
6. Platform Opens home and shows the message Welcome to (organisation name), Your workspace is ready.
7. Any person If the email has an invite to answer a project request, step 2 instead reads "Join the organisation that invited you" with no organisation fields; pressing Join makes the person the first member of that client organisation, where the request waits on Home.

RULES

- The five organisation types are Architecture practice, Developer or client, Donor building owner, Surveying or deconstruction firm, and Sustainability consultancy. Architecture practice is selected until the person picks another.
- The password needs at least 8 characters. The email must look like an email address, for example name@company.example. The organisation name cannot be left empty.
- Whether the email is already in use is only checked on Create account. If it is, step 2 shows An account with this email already exists. Sign in instead.
- The organisation type cannot be changed later: Settings, Organisation says it sets the workspace and cannot be changed.
- A new organisation starts empty; the new person is its only member until they invite colleagues.
- Back on step 2 returns to step 1 without losing what was typed.
- The new person stays signed in on this device after closing the browser.
- The open sign-up page never names the organisation, project or practice behind an invite; those show only through the invite link.

NOTIFICATIONS

- None. The welcome is an on-screen message only.


ACCOUNTS AND THE SANDBOX

First visit to a new workspace

Architect | Client (developer) | Donor building owner | Site surveyor | Sustainability consultant

Where Home (/app/home), straight after Create account

A new organisation has no records, so each home page opens on a first run suited to its type, with its next steps instead of zero tiles. The architect is walked into creating a first project; the others see what to do or what to wait for.



STEPS

1. Platform Opens home for the new organisation's workspace.
2. Architect Sees the Create your first project dialog open at once. Creating the project opens its page; closing the dialog leaves the Welcome to your workspace card.
3. Architect On the Welcome card can press Create a project or Browse the Marketplace, beside three steps: Create your first project, Find materials in the Marketplace, Send your shortlist for approval. Under it, In the Marketplace now shows the categories with stock and links into them.
4. Donor building owner Sees one card, Add your first building, with three steps (add a building coming down, appoint a surveyor, decide what to recover and who may see it) and Add building. Marketplace is already in the sidebar.
5. Site surveyor Sees a first-run card with three steps (add a building or wait for an appointment, capture each item on site, submit the survey to the owner) and Add building.
6. Client (developer) Sees a welcome with three next steps: your architect adds you as the client, accept the project, approve and reserve materials; and recent activity.
7. Sustainability consultant Sees No projects yet with three steps: an architect adds your consultancy and you accept, set the goals and targets, write the circular economy statement. Any waiting project requests sit above it.

RULES

- The dialog opens by itself only for an architect, and only on the visit straight after Create account. A person who joins through an invite does not get it.
- The architect's Welcome card stays until the organisation has a project; then the normal dashboard takes its place. The other first runs give way once the organisation has buildings, projects or requests.
- No first run shows empty tiles, an empty programme or an empty tracking table.
- Client and consultant workspaces cannot start a project themselves; they are brought in by an architect, and the consultancy only once the client has accepted.

NOTIFICATIONS

- None. The on-screen message reads Welcome to (organisation name), Your workspace is ready.


ACCOUNTS AND THE SANDBOX

Reset a forgotten password in the sandbox

Any person | Platform

Where Reset your password (/forgot-password), from Forgot password? on Sign in

In the sandbox no email is sent, so the person sets a new password on the page itself and is signed in straight away. The page says plainly that a live service would email a link instead.



STEPS

1. Any person Clicks Forgot password? beside the Password field on Sign in.
2. Any person Enters Email, New password and Confirm new password, then presses Reset password.
3. Platform Checks the fields, checks an account exists for that email, and saves the new password.
4. Platform Signs the person in, opens home and shows Password updated, You are signed in with your new password.

RULES

- The page shows: In the sandbox you reset your password on this page. A live service would email you a link instead.
- Anyone who types an account's email can set its password here; nothing checks that the email is theirs. This is a sandbox shortcut.
- An unknown email is refused with We could not find an account with that email.
- The new password needs at least 8 characters and both entries must match (The two passwords do not match).
- After a reset the sign-in is not remembered: closing the browser signs the person out.
- Any account can be reset this way, including the sample accounts. A sample account with a changed password can no longer use its one-click card on Sign in; Reset the sandbox puts the password back to sandbox.
- Back to sign in returns to Sign in without changing anything.

NOTIFICATIONS

- None


ACCOUNTS AND THE SANDBOX

Invite a teammate

Any member of an organisation | Platform

Where Settings, Team (/app/settings/team), from Settings in the sidebar or the avatar menu

Any member invites a colleague into their own organisation by email address. The sandbox sends no email: it makes an invite link and copies it, ready to pass on.



STEPS

1. Any member Opens Settings, then Team, and types the colleague's address under Invite a colleague.
2. Any member Presses Create invite.
3. Platform Makes an invite link, copies it and shows Invite created. Link copied.
4. Any member Passes the link on; Copy link beside the invite under Pending invites copies it again.
5. Any member May press Revoke on a pending invite; the message Invite revoked offers Undo.

RULES


- Anyone in the organisation can invite and revoke; there is no separate admin.
- The invite is always into the inviter's own organisation, so the colleague gets the same workspace type.
- Refused with a reason under the field: Enter a valid email address; This person is already a member; Another account already uses this email (someone in another organisation); This person already has a pending invite.
- No email is sent. If the browser blocks copying, the link is shown in a message to copy by hand.
- Because all sandbox data stays in one browser, the link only works when it is opened in this same browser. Opened anywhere else it shows This invite link is not valid.
- Pending invites shows each email, its link, how long ago it was sent and by whom. Accepted and revoked invites drop off the list.
- Members lists everyone in the organisation with the date they joined.

NOTIFICATIONS

- None when the invite is made or revoked. When it is accepted, see Accept an invite.

LIFECYCLE

Only a pending invite link works. Undo after Revoke works only while nothing else has changed since.




Accept an invite and join the team

Invited person | Platform | Members of the organisation

Where Join your team (/invite/:token), opened from the invite link

The invited person opens the link, sees who invited them and to which organisation, and creates their account with a name and password. They join that organisation and land in its workspace.



STEPS

1. Invited person Opens the link and sees Join (organisation name), who invited them, and the organisation type. An invite to answer a project request instead names the practice, the client and the project, for example "Studio Oriel asked Harrowgate Homes to accept Pellow Row, and invited this email to answer."
2. Invited person Keeps the email shown (it cannot be changed), enters Full name and Password, and presses the Join (organisation name) button.
3. Platform Creates the person in the inviting organisation, marks the invite accepted and signs them in on this device.
4. Platform If a building waits for a deconstruction contractor at that email and the organisation is a surveying or deconstruction firm, makes the firm its contractor and tells both sides.
5. Platform Notifies the organisation that the person joined, opens home and shows Welcome to (organisation name), You have joined the team. For a project invite, the request to accept the project waits on their Home.

RULES

- The email is fixed to the address the invite was sent to.
- A link that was never issued in this browser, already used or revoked shows This invite link is not valid, which adds that sandbox invites open only in the browser where they were made, with Go to sign in.
- If an account with that email was created meanwhile, joining is refused with An account with this email already exists. Sign in instead.
- The name cannot be empty and the password needs at least 8 characters.
- Someone already signed in who opens the link is warned that joining creates a new account for the invited email and signs them in with it.
- The new member gets the organisation's workspace and sees what the organisation sees; there are no separate permissions for each person inside an organisation.
- Already have an account? Sign in leads to Sign in instead.

NOTIFICATIONS

- The organisation gets one notification for its members: (name) joined (organisation name), They accepted the invite sent to (email). It links to Settings, Team. The person who joined sees it already read. A member who has turned off Team and projects in Settings, Notifications does not see it.
- For a project invite, the architect's practice: '[name] joined [client]. They can now accept [project].'


ACCOUNTS AND THE SANDBOX

Switch between sample accounts

Any signed-in person | Platform

Where Avatar menu, Switch account (top bar); or Settings, Sandbox (/app/settings/sandbox)

To follow a material from one side of the platform to the other, a person jumps straight into another sample account without typing a password. This exists only in the sandbox.



STEPS

1. Any signed-in person Opens the avatar menu in the top bar and points at Switch account, or opens Settings, Sandbox.
2. Any signed-in person Picks one of the accounts under Sample accounts in this sandbox, or presses Switch beside it in Settings.
3. Platform Signs in as that person without a password, opens their home and shows Signed in as (name).

RULES

- Only the five sample accounts are listed. Accounts people created themselves never appear, so they cannot be switched to.
- The current account shows a tick in the menu, or a Signed in badge in Settings, and cannot be picked.
- Anyone signed in can switch, including someone using an account they created. To get back to that account they sign in with its email and password.
- Switching keeps the same Remember me choice as the sign-in it replaces.

NOTIFICATIONS


- None

Reset the sandbox

Any signed-in person | Platform

Where Settings, Sandbox (/app/settings/sandbox), also reached from the Sandbox badge in the top bar

Puts every sample record and photo back as it was at the start, wiping all changes made in this browser. It is used to rehearse a demo again from a clean start.



STEPS

1. Any signed-in person Opens Settings, Sandbox, and presses Reset under Reset the sandbox.
2. Any signed-in person Confirms with Reset sandbox in the dialog Reset the sandbox?, or presses Cancel.
3. Platform Clears stored photos and puts all sample data back, including the sample accounts and their notifications.
4. Platform Shows Sandbox reset, Every sample record is back as it started, and opens home. A person whose own account no longer exists is signed out and sees Sign in.

RULES

- Anyone signed in can reset. The dialog warns that all changes made in this browser are lost: captures, listings, decisions, reservations and new accounts.
- Accounts people created, their organisations and their invites are removed. Someone signed in with one is signed out.
- Sample account passwords go back to sandbox.
- The sample story is dated again from the day of the reset, so its dates move with it.
- It affects only this browser; there is no server and nothing is sent anywhere.
- There is no undo for a reset.
- Reset also forgets that this browser was updated on 16 October, so the update notice and the sign-in line no longer show.

NOTIFICATIONS

- Notifications go back to the sample set; nobody is told of the reset.


ACCOUNTS AND THE SANDBOX

Come back after the 16 October update

Any person | Platform

Where Every Home (/app/home), the notice at the top; Help, Updated on 16 October (/app/help/updated); Sign in (/signin); a bar at the foot of any open tab

The sandbox lives in each visitor's browser, so the 16 October update had to replace or carry over what an earlier build stored. A returning visitor is told what happened and what changed, an earlier account that is gone is explained at sign-in, and an open tab offers to reload when a newer build is deployed.


Opens the app after the update
What did this browser hold?
A version 1 sandbox
A round 2 sandbox, old key
Nothing
Replaced, recorded as updated
Carried over as it was
Fresh sample data, no notice
Home notice: earlier work is back to the sample
Home notice: updated with the review changes
See what changed?
Yes
Close
Help, Updated on 16 October
Notice stays closed in this browser

STEPS

1. Platform Before anything reads the data, finds what an earlier build stored. A version 1 sandbox is removed and the update recorded; a version 2 sandbox from the earlier round 2 build is carried over to the new key with nothing lost; leftovers beside data this build already has are cleared without a notice.
2. Platform Shows a closable notice on every Home: "The sandbox was updated on 16 October with the changes from the 14 October review.", adding "Anything you changed before then is back to the sample data." when the sandbox was replaced.
3. Any person Presses See what changed to open Help, Updated on 16 October, which lists the round 2 changes: the person's own first, each with a link to a page they can open, such as their first project or the Marketplace checking against it, then the other workspaces' changes without links. Or closes the notice.
4. Any person If they try to sign in with an account made in the old sandbox, reads the update line with Create your account again (see Sign in).
5. Platform In a tab left open, checks the served page when the person comes back to the tab and every ten minutes while it is in view; when a newer build is deployed, shows "A new version of Tallyard is available." with Reload and Not now.

RULES

- The data is stored under a key named after its version, so a tab of an older build never reseeds the new one, and the new build never writes the old key.
- The notice shows for sample accounts and accounts made before the update; an account made after it sees none. Closing it is remembered in this browser.
- The sign-in line stops 30 days after this browser found the update.
- Every link in Help, Updated on 16 October is checked against what the person may open.
- The check for a newer build runs in production builds only, and at most every 30 seconds.
- Reset the sandbox forgets the update and its notice.

NOTIFICATIONS

- None. The notice, the Help topic and the reload bar are on screen only.


ACCOUNTS AND THE SANDBOX

Pages you may not open, and pages that do not exist

Any person | Platform

Where Any address; inside the app the page shows within the sidebar and top bar

Every address inside the app is checked against the person's workspace and records before the page appears. A page they may not open shows a calm no-access page, and an address that does not exist shows Page not found; neither reveals anything about the record behind it.



STEPS

1. Any person Opens an address, for example from a link, a notification or a bookmark.
2. Platform If the address is inside the app and the person is signed out, sends them to Sign in first and brings them back afterwards.
3. Platform Checks that the page exists and that this person's workspace, organisation and records allow it; a query such as ?project= or a section such as #statement does not change the page checked.
4. Platform Shows the page, or You do not have access to this, or Page not found, each with Go to home.
5. Platform For a project the person's organisation has been asked to join, as client or as consultancy, and has not yet answered, shows "Accept [project] to open it" with a button to Project requests instead.

RULES

- Home, Notifications, Settings and Help open for everyone signed in.
- Workspace pages are tied to the organisation type: Saved and New project are for architects; Buildings and Capture for owners and surveyors; Requests for owners; Project requests for clients and consultancies; Engagements for consultants.
- The Projects list opens for architects, clients and consultants, and for a donor building owner who is the client of a New project. The Marketplace opens for architects, clients, consultants and every donor building owner. A single material opens only if that person may see its listing; an owner never opens its own.
- A project opens only for organisations on it, and for a client or consultancy only once it has accepted. A building opens only for its owner, its surveyor or its deconstruction contractor. Inside a building, Inventory, Capture, Testing and Requirements are for the owner and the surveyor; Recovery plan, Listings and Sharing for the owner; Availability for the contractor; Activity for every side, showing what its organisation may read.
- An address for a project or building that does not exist shows the no-access page, the same as one the person may not open, so nobody can tell which records exist.
- The no-access page says the page belongs to another workspace or organisation and to ask the person who sent the link. It never shows the record's name or any figure, except the project's name to an organisation asked to accept it.
- Old addresses still work: /app/discover goes to the Marketplace and a project's carbon tab goes to Sustainability.
- If a page fails to load, the app shows Something went wrong inside the sidebar and top bar, suggesting a sandbox reset if it keeps happening.
- Outside the app, an unknown address shows Error 404 with Go to home, back to the landing page.

NOTIFICATIONS

- None


ACCOUNTS AND THE SANDBOX

Search with Ctrl K or Cmd K

Any signed-in person | Platform

Where Anywhere inside the app: Search in the top bar, or Ctrl K (Cmd K on a Mac)

A search box over everything the person may open: pages, projects, buildings, inventory items and materials. Choosing a result goes straight to it.



STEPS

1. Any signed-in person Presses Ctrl K, or Cmd K on a Mac, or clicks Search in the top bar.
2. Platform Opens the box Search materials, projects and pages; before typing it lists the person's pages, projects and buildings. A search also finds the tabs inside project and building folders, named with their folder, for example Recovery plan, Wexcombe House.
3. Any signed-in person Types words; results are grouped as Pages, Projects, Buildings, Materials and Inventory.
4. Any signed-in person Picks a result to open it, or presses the shortcut again or Escape to close.

RULES

- Results come only from what the person may open: their workspace's pages and Notifications, the projects their organisation is on, and the buildings their organisation owns, surveys or dates as contractor, with those buildings' inventory items.
- A deconstruction contractor's inventory results open the no-access page, because a contractor alone may not open a building's inventory.
- Materials are searched only by architects, clients, consultants and donor building owners; an owner never finds its own lots. They come from public listings, listings shared with them, and materials already reserved for their projects.
- A material result shows its picture, family and location; nothing private about the seller is searchable.
- Every word typed must match. Results whose name starts with what was typed come first. At most 24 results show.
- The shortcut works even while typing in a field, but only inside the app, not on the sign-in pages.

NOTIFICATIONS


- None

Undo a change

Any signed-in person | Platform

Where The message that appears at the bottom of the screen after a change, across the app

Many changes, such as saving a material, revoking an invite or changing a notification setting, show a short message with an Undo button. Pressing it puts everything back as it was just before that change.



STEPS

1. Any signed-in person Makes a change, for example Revoke on an invite.
2. Platform Shows a message with Undo for about eight seconds.
3. Any signed-in person Presses Undo.
4. Platform Puts the data back exactly as it was before that change, including removing any notification the change sent.

RULES

- Undo works only while nothing else has changed since, so it never throws away later work by anyone in this browser. If something has changed, pressing Undo does nothing and no message explains why.
- Undo is offered only in the message after the change; it is lost once the message goes or the page reloads.
- Not everything has Undo: for example signing in, creating an account, creating an invite, switching account and resetting the sandbox do not.
- There is no keyboard shortcut for undo.

NOTIFICATIONS

- A notification created by the change is removed again by the undo.

SECTION

Architect

This section follows the architect, who creates projects, sets their programme and requirements, and finds reclaimed materials for them in the Marketplace. The architect shortlists materials against a project's dates, sends them to the client for approval, and turns what is approved into a specification. Every workflow here is what the platform does today.


ARCHITECT

Create a project

Architect | Client or developer | Sustainability consultant | Platform

Where New project in the sidebar under Projects (/app/projects/new), the New project button on Projects (/app/projects), and Create your first project on Home for a practice with no projects

The architect sets up a project in one form: name and type, the client with a note and, for a client new to Tallyard, a contact email, the programme, the location with its planning and sustainability requirements, and the team. The platform suggests RIBA stage dates, creates an empty shortlist and asks the client organisation to accept the project. A consultancy named here is asked only once the client accepts.


Open New project
Name the project and choose a type
Type is Other?
Yes
No
Describe the type, optional
Choose the client and add a message
A new client?
Yes
No
Add a client contact email, optional
Set stage, site start and completion
Choose region and local authority
Tick requirements, or leave suggested
Every field valid?
No
Yes
Errors show beside each field
Project made with suggested stage dates
Client asked to accept, contact invited
Project overview opens

STEPS

1. Architect Opens New project and types a Project name, which must be new within the practice.
2. Architect Chooses a Project type from twelve kinds of building or Other (the form starts on Office); with Other, Describe the type is offered and is optional.
3. Architect Chooses the Client from the practice's clients, or A new client and types its name (a practice with no clients yet just types the name), and may write a Message to the client.
4. Architect For a new client, may add a Client contact email: if nobody from that organisation uses Tallyard yet, that person is invited to join it and accept the project.
5. Architect Under Programme sets the Current RIBA stage and Site start, and optionally Practical completion and Materials needed on site from.
6. Architect Under Location and requirements chooses the Region and, optionally, the Local authority from one list of every authority grouped by region; choosing an authority sets the region.
7. Architect Optionally opens Planning and sustainability requirements, where the suggested ones for that place are already ticked, and changes the ticks. Left closed, the suggested ones are tracked until the architect chooses.
8. Architect Optionally chooses a Sustainability consultant and writes a Description, then selects Create project.
9. Platform Checks every field and shows each problem beside its field; nothing is saved until all pass.
10. Platform Creates the project with an empty shortlist, suggested stage dates marked Suggested dates, the client link set to waiting and, when a consultancy was chosen, a request to it that waits for the client.
11. Platform Asks the client organisation to accept, issues the invite when a contact email was given, and opens the project overview with its programme card and setup checklist.

RULES

- Only an architect can use this form. Clients, consultants and surveyors cannot create projects; a donor building owner has its own New project, on which it is the client (see the owner section).
- The project name is required and must not repeat another project name in the same practice: 'A project with this name already exists.'
- The type list is Office, Residential, Hotel, Mixed use, Retail, Education, Healthcare, Laboratory, Industrial and logistics, Cultural and civic, Sport and leisure, Student housing and Other. The Other description is up to 60 characters and is seen by the project team only; a seller only ever reads the plain type, for example 'other project'.
- The client list holds the practice's existing client organisations that have not declined. A typed name that matches a developer, or one of the practice's clients, reuses that organisation; any other name creates a new client organisation, so the form never reveals who sells materials. The practice cannot name itself as the client.
- The client contact email must look like an email address. It is refused when someone from the client organisation already uses Tallyard ('Someone from this organisation already uses Tallyard and can accept the request on Project requests.') or when the email belongs to another organisation ('This email belongs to someone in another organisation. Choose that organisation as the client instead.').
- Current RIBA stage runs from 0 to 7 and starts at stage 2. Site start is needed; if it is left blank, the Materials needed on site from date is used as site start. The date materials are needed must be today or later and must fall between site start and practical completion; left blank, it is the site start. Practical completion, left blank, is 18 months (540 days) after site start.

- Stage dates are suggested: for a project at stage 0 to 4, the current stage starts today and the remaining design stages share the time up to site start in proportion to their typical lengths (4, 8, 12, 16 and 20 weeks); earlier stages are placed before today. For a project at stage 5 or later, the design stages are placed back from site start at their typical lengths. If site start is too close the form says 'Site start is too soon for the remaining design stages.'
- Region is required and starts on Central London. The region list is grouped London (inner and outer regions as the ONS defines them), England outside London, then Wales and Scotland. A listed local authority is valid only in its own region; outside London Another local authority accepts a typed name. Changing the region clears the local authority.
- Requirements are optional. The closed panel reads, for example, '12 apply to Camden, Central London, 10 suggested. Choose now or later.' Left closed, the suggested requirements are tracked on the project, and every screen says so, until the architect reviews them; the checklist step stays open. A choice made in the panel, even an empty one, counts as reviewed.
- The consultancy is never told about the project at creation; it is asked once the client accepts.
- The first-run version of the form (Create your first project on Home) asks only for name, client, type, site start and region; everything else takes its default.

NOTIFICATIONS

- The client organisation is told 'Practice asked to add you as client on Project', with the architect's message if there is one (otherwise 'Accept to see the project and approve materials for it.'), linking to Project requests. It also appears in their activity.
- With a contact email, no email is sent: the overview offers Copy invite link for the architect to pass on, and the practice activity records that the email was invited to join the client and answer the request.
- The architect sees a confirmation, for example 'Riverside Works created. Waiting for Client to accept. Set up the programme while you wait.'

- The project activity records 'created the project', for the practice only.


ARCHITECT

Wait for the client to accept, or ask again

Architect | Client or developer | Platform

Where Project Overview (/app/projects/:id) and Shortlist (/app/projects/:id/shortlist) for the architect; Project requests (/app/projects/requests) and the top of Home for the client

A new project is not visible to its client until the client organisation accepts it. While the architect waits they can keep working, change the client, or invite a contact at a client nobody uses Tallyard from yet. If the client declines, the architect can ask the same client again or choose another one. Acceptance also asks the consultancy the architect named.


Client is asked to accept
Anyone at the client on Tallyard?
No
Yes
Invite a contact by email, copy the link
Contact joins the client organisation
Client answers?
Accept
Not yet
Decline
Architect told, consultancy asked
Waiting line on overview and shortlist
Architect is told they declined
Client sees the project
Change client?
Ask again or another?
Yes
No
Ask again
Choose another client
Keep working, sending stays off
Choose another client and send request
Send request to the same client

STEPS

1. Platform Shows the architect 'Waiting for Client to accept.' as one sentence in the setup checklist with Change client beside it, as a banner on the shortlist with the date it was asked, and a neutral Client to accept pill with an envelope in the project header and on the Projects list.
2. Platform If nobody from the client organisation uses Tallyard yet, says so instead and offers a field for a contact at the client; shortlisting can carry on.
3. Architect Enters the contact's email and sends the invite; the banner then names the email with Copy invite link, Resend and Use another email.
4. Client or developer The contact opens the link, or signs up with that email, and joins the client organisation; the request then waits on their Home (see the client section).
5. Client or developer Opens Project requests, or sees the waiting request at the top of Home, reads the project's name, practice, who asked, type, place, stage, site start, practical completion, the consultancy the architect proposes and the message, then selects Accept or Decline.
6. Client or developer When declining, may write a note under 'Tell Practice why' and confirms Decline.
7. Architect While waiting, may select Change client, pick one of the practice's other clients or A new client, add a Client contact email for a new one and a Message to the client, and select Send request.
8. Architect After a decline, sees 'Client declined this project' with the date and their note, and selects Ask again or Choose another client.
9. Platform On acceptance, the project appears in the client's workspace, sending materials for approval opens, and the named consultancy is asked to join.

RULES


- Until the client accepts, the client organisation cannot open the project or see it in its lists, and nothing can be sent for approval: 'The client has not accepted this project yet, so nothing can be sent for approval.' The architect can still edit the programme, choose requirements and shortlist.
- Until the client accepts, no consultancy sees the project or hears of it.
- The architect only ever sees the client organisation's name, never its people. A decline reaches the architect under the organisation's name.
- The project header and the Projects list show a Client to accept or Client declined pill, and Details shows the client as 'waiting to accept' or 'declined'.
- Only a waiting request can be answered: 'This request has already been answered.' Only the client organisation named on the project can answer it.
- Asking the same client again while its request is still waiting is refused: 'A request is already waiting for this client.' After a decline the same client can be asked again.
- Once the client has accepted, the client cannot be changed: 'The client has already accepted this project.'
- Only the newest invite link for a project works; Resend or Use another email replaces it. An invite is refused once someone from the client uses Tallyard, or for an email that belongs to another organisation.
- Before accepting, the client sees no shortlist, no listing and no figure from the project.
- A request sent from Change client or Ask again, and an invite, can be undone from its confirmation.
- Change client offers the practice's other clients and A new client; the client already waiting is not offered again. Ask again opens on the client that declined.

NOTIFICATIONS

- Every request: the client organisation is told 'Practice asked to add you as client on Project', with the message, linking to Project requests. The project activity records 'asked Client to join as client'.
- When an invited contact joins: the practice is told '[name] joined [client]. They can now accept [project].'
- Accept: the architect's practice is told 'Client accepted Project. They can now see the project and approve materials you send.' The project activity records 'accepted the project as client'. The named consultancy is asked to join (see Answer a request to join a project in the consultant section).
- Decline: the architect's practice is told 'Client declined Project', with 'Their note: ...' or else 'Ask again or choose another client from the project overview.' The decline is recorded in the architect's activity only, under the organisation's name.

LIFECYCLE

The client link starts waiting; only acceptance lets the client see the project and receive materials, and an accepted client can no longer be changed.




ARCHITECT

Edit the programme

Architect | Donor building owner (as client, no architect yet) | Platform

Where Project Overview (/app/projects/:id), Programme card at the top, with Edit programme and, while the dates are not yet kept, Keep these dates

The programme sets the RIBA stage dates, site start, practical completion and when materials are needed on site. It leads every project overview. Every timeline check on the project uses the materials date, so the architect keeps or corrects the suggested dates early.


Open Edit programme on the programme card
Set the current RIBA stage
Use suggested stage dates?
Yes
No
Suggest stage dates fills stages 0 to 4
Set site start, completion and materials date
Dates in order?
No
Yes
Errors show beside each date
Type each stage start
Select Save programme
Keep these dates on the card
Programme saved as set
Chart and timeline checks update

STEPS

1. Architect On the Programme card, which leads the overview, selects Edit programme.
2. Architect Chooses the Current RIBA stage, the stage the project is at now.
3. Architect Types the start of stages 0 to 4, or selects Suggest stage dates to fill them from typical stage lengths; each row shows its length.
4. Architect Sets Site start (stage 5 starts here), Practical completion (stage 6 starts here) and Materials needed on site from.
5. Architect Selects Save programme.
6. Platform Checks the dates, saves the programme as set, and removes the Suggested dates or Client's dates pill.
7. Platform Redraws the chart and the programme check pill, and rechecks every shortlisted material against the materials date.
8. Architect Alternatively selects Keep these dates on the card to keep the suggested dates, or the client's dates, as they are; the confirmation offers Undo.

RULES

- Only the project's architect can edit the programme. The client and the consultant see the same Programme card without its buttons.
- On a donor building owner's New project with no architect yet, the owner may keep or edit the dates. Once an architect is appointed, those dates read "Client's dates" until the architect keeps or edits them, and the owner reads "Your dates until the architect confirms them."
- Each stage must start after the one before; site start must be after the start of stage 4; practical completion must be after site start; materials must be needed between site start and practical completion. Each failure shows beside its date.
- Only stages 0 to 4 are typed. Stage 5 starts at site start and stage 6 (Handover) at practical completion; stage 7 follows a year after practical completion. The whole programme chart ends 120 days after practical completion, so Handover runs off the right edge.
- Suggest stage dates refuses when site start is too close: 'Site start is too soon for the remaining design stages.'
- The programme check pill compares the stage planned for today with the stage declared: On programme, Behind programme, Ahead of programme or Not started. It carries an Indicative marker.
- The chart can show the Whole programme or From today, with each shortlisted material's availability coloured by its fit, and Stage dates opens a table of every stage. Stages come from the RIBA Plan of Work 2020.
- Each stage band names itself when it fits, and today's stage always does; a key under the stage lane names every stage drawn. Each band is a button that shows its name and dates on hover, keyboard focus or a tap. The axis labels months, never quarters, and always names the year.
- Saving without any change does nothing. A saved programme can be undone from its confirmation.
- Edit (in the project header) changes name, type, region, local authority and description only; the stage and every date live in Edit programme.

NOTIFICATIONS

- None. The project activity records 'updated the programme'.


ARCHITECT

Choose planning and sustainability requirements

Architect | Platform

Where Project Overview (/app/projects/:id), Planning and sustainability card, Review requirements, Choose requirements or Edit; the same on the Requirements tab (/app/projects/:id/requirements); also the setup checklist and the New project form

The architect picks which planning policies and sustainability standards the project tracks, from those that apply to its region and local authority. Until the architect reviews them, the requirements suggested for the place are tracked. The chosen ones are then tracked by the team on the Requirements tab.


Edit moves the project elsewhere
Project made, suggestions tracked
Ones that still apply kept, new suggestions added
Select Review requirements
Review opens on saving
List of what applies at this place
Tick or untick requirements
Select Save
Any ticked?
Yes
No
Card lists the chosen requirements
Empty choice kept, step done
Tracked on the Requirements tab

STEPS

1. Platform While the architect has not chosen, tracks the requirements suggested for the place: the overview card reads, for example, '10 suggested for Camden, Central London', explains that they are tracked until the architect chooses, and offers Review requirements.
2. Architect Selects Review requirements, Choose requirements or Edit requirements on the Planning and sustainability card, on the Requirements tab or in the setup checklist.
3. Platform Opens 'Planning and sustainability requirements', starting from the tracked set, grouped as National, London Plan 2021 and GLA guidance (London regions only) and the local authority's own plan when one is set.
4. Architect Ticks the requirements to track; each shows its code, source, summary, trigger and what it asks for. An entry not yet summarised carries a Not yet summarised pill.
5. Architect Selects Save.
6. Platform Saves the choice; the card lists the first four with 'N more' and a link, View requirements for the architect and Track requirements for the client and consultant.
7. Architect If they later change the region or local authority through Edit, the dialog says how many chosen requirements no longer apply, how many new ones are suggested and that they are added on saving.
8. Platform On save keeps what still applies, adds the suggestions new to the place and opens the review at once, so it only confirms the set.

RULES

- Only the project's architect can choose requirements. The client and consultant see the card; with nothing chosen and nothing suggested it tells them the architect has not chosen any yet.
- Only requirements that apply to the project's region and local authority can be chosen: 'Choose requirements that apply to this location.'
- A project nobody has reviewed keeps tracking the suggestions for its place, and the checklist step stays open with Review requirements. Saving, even with nothing ticked, counts as reviewed; an empty choice is kept as chosen.
- Every entry is an indicative summary as at October 2026, with the note 'Check the current published documents before you rely on them.' and an Indicative marker. Entries for authorities without a written summary, and the national entries for Wales and Scotland, are labelled placeholders.
- In the New project form the suggested requirements for the chosen place are ticked as soon as the panel is opened, and a change of place re-ticks the new suggestions.
- Cancelling the review after a move leaves what the dialog described.
- Saving the same choice again does nothing. A save from the dialog can be undone from its confirmation.

NOTIFICATIONS

- None. The project activity records 'chose N planning and sustainability requirements' or 'cleared the planning and sustainability requirements'.


ARCHITECT

Follow the setup checklist on a new project

Architect | Client or developer | Platform

Where Project Overview (/app/projects/:id), directly under the programme card; progress also shows on Projects (/app/projects) and on the architect Home

A new project shows a compact strip of six setup steps under its programme card: check the programme, the client accepts, choose requirements, add a consultant, shortlist and send. It leads with the next required step and its button, and hides once the essentials are done.


New project overview opens
Programme card leads, Keep these dates
Checklist strip: progress and Next step
Client accepts the project
Optional requirements and consultant
Shortlist materials
Send materials for approval
No
Programme, client and shortlist done?
Yes
Checklist hides

STEPS

1. Platform Shows 'Set up Project' with progress ('N of 6 done'), then 'Next:' with the step's title and its button, then the waiting client in one sentence with Change client beside it.
2. Architect Check the programme: selects Keep these dates or Edit programme on the programme card above, the only place those buttons sit.
3. Client or developer Client accepts the project: the step waits for the client; the architect can select Change client, or Ask again after a decline, which gets its own banner.
4. Architect Choose planning and sustainability requirements (optional): selects Review requirements while the suggestions are tracked, Choose requirements, or Edit requirements once some are chosen.
5. Architect Add a sustainability consultant (optional): selects Add consultant, which opens the Team tab (Open team once one is named). The step reads 'asked once the client accepts', 'Waiting for [consultancy] to accept', 'declined to join' or 'on the team'.
6. Architect Shortlist materials: selects Find materials, which opens the Marketplace checking against this project.
7. Architect Send materials for approval: selects Open shortlist; this step waits until the client has accepted.
8. Architect May select Show all steps to see every step as a tile, or Show fewer to return to the strip.

RULES

- Only the project's architect sees the checklist.
- Each step is Done, Next, To do, Waiting or Needs you. A declined client or consultancy marks its step Needs you.
- The next step shown is a required one before an optional one, so a new project leads with Shortlist materials, Find materials rather than the optional requirements.
- The checklist hides once the programme is confirmed (Keep these dates or Save programme), the client has accepted and at least one material is shortlisted, even if the optional steps are not done.
- The send step is done as soon as any material has gone to the client. The consultant step is done only once the consultancy has accepted.
- Show all steps is remembered in this browser. Until it is opened the six steps are listed for screen readers only.
- The Projects list shows the same progress as a pill, for example 'Setting up, 2 of 6', with the next step. On the architect Home, projects still setting up lead, with their pills and next step.

NOTIFICATIONS

- None from the checklist itself; each step's own action notifies as described in its workflow.


ARCHITECT

Find materials in the Marketplace

Architect | Platform

Where Marketplace in the sidebar (/app/marketplace), All listings tab; Find materials on a project opens it checking that project (?project=)

The architect browses reclaimed structure, envelope and finishes, usually checking every card against one project's materials date. Category folders, search, filters and the availability slider narrow the list; New for your projects picks out recent materials that arrive in time.


Open the Marketplace
Check against a project?
Yes
No
Choose a project in the checking strip
Cards show fit and counts
See New for your projects
Open a category folder
Narrow with search, family and Filters
Set Available by on the slider
Anything matches?
No
Yes
Clear search and filters
Open a material

STEPS

1. Architect Opens Marketplace, or selects Find materials on a project, or follows a project card's "N new materials fit" link on Home, each of which names the project to check against in the address.
2. Architect In the checking strip selects Choose a project (or Change project); the strip reads 'Checking against Project' with the date materials are needed. The cross beside it stops checking.
3. Platform Marks each card with its fit and counts them, for example '10 available now, 1 in time', with a chip 'N new for Project' (or 'N new for your projects' with no project checked) that jumps to the New for row.
4. Architect Optionally turns on Only show what arrives in time.
5. Platform On the landing view shows Browse by category (Structure, Envelope, Finishes) and New for your projects, then All materials. A link from Home lands on the New for Project row, even when the address is pasted or reloaded.
6. Architect Opens a folder, then narrows by family chips, the search box, or the typology tabs All, Structure, Envelope and Finishes.
7. Architect Opens Filters and sets Available by on the month slider, Family, Condition, Location and Sustainability band, then selects Done.
8. Architect Removes a filter from its chip or selects Clear all; with no results, selects Clear search and filters.
9. Architect Sorts by Newest listed or Most carbon avoided, and opens a material; Back returns to the same place on the page.

RULES

- All listings holds only openly listed materials that are available and not reserved for any buyer. Lots shared privately are under Shared with you.
- Fit words are Available now, In time, Tight and Too late, worked out against the project's Materials needed on site from date; the strip carries an Indicative marker.
- Only a project chosen in the checking strip or on a material page is remembered for the person. A project named in a link applies to that visit only, so the sidebar Marketplace opens on no project afterwards. Search, folder, filters and sort live in the address, so Back and shared links restore them.
- With no projects the strip says 'Create a project to check materials against its start on site.' and offers New project instead of Choose a project.
- A category folder with no materials cannot be opened. With a project checked, each folder shows its own fit counts. A folder opened because the page was inside it closes again when the person moves on.
- New for your projects is for architects only: materials listed in the last 30 days, not already on any of the practice's lists, and not too late for at least one of the architect's projects (Tight still counts). With a project checked it reads 'New for Project' and shows only what is in time for that project. It shows four, with Show all for the rest, and hides when there is nothing new.
- The Available by slider runs from Available now through the end of each month to Any time, over a bar chart of when materials arrive, with a dashed line marked 'Materials needed for Project'.
- Lowest guide price sorting is offered to clients and donor building owners only; architects get Newest listed and Most carbon avoided.
- Cards give availability in short form, for example Expected Jan to Mar 2027; the material page gives it in full.
- Pressing / jumps to the search box.

NOTIFICATIONS

- When a donor building owner publishes a material that is not too late for one of the practice's projects, the architect's practice is told 'New material for Project', for example 'Material is available in time for Project.', linking to the material. The owner and the building are never named.


ARCHITECT

See lots shared with your project

Donor building owner | Architect | Client or developer | Platform

Where Marketplace, Shared with you tab (/app/marketplace?tab=shared)

A donor building owner can share lots privately with a project instead of listing them openly. The architect or client accepts confidentiality terms once for that project; the lots then appear under the project and can be shortlisted for it alone.


Owner shares lots with a project
Architect and client are told
Shared with you shows a count
Terms accepted for this project?
No
Yes
Select Review terms
Tick to accept the terms
Select Accept and show lots
Lots appear under the project
Save a lot to that project
Lot stays with this project only

STEPS

1. Donor building owner Marks lots as shared with selected projects and approves the project on their Sharing tab (described in the owner section). The owner sees the project only as a blind description.
2. Platform Shows the Shared with you tab with a dot when lots wait behind the terms, and a group per project reading 'N lots are shared privately with Project'.
3. Architect Selects Review terms, reads the confidentiality terms and ticks 'I accept these terms for Project'.
4. Architect Selects Accept and show lots.
5. Platform Lists the lots under the project with Terms accepted, and records it in the project activity.
6. Architect Opens a lot or saves it to that project's shortlist.

RULES

- Before the terms are accepted only the number of shared lots shows, never their details.
- Terms are accepted once per project, by its architect or its client; then both see the lots. The terms are labelled as simulated.
- The sustainability consultant never sees lots shared in confidence; Shared with you tells them so.
- A shared lot can only be saved to the project it is shared with. It cannot go to Saved ('Shared in confidence with a project. It can be saved only to a project it is shared with.') and cannot be moved to another project ('Shared in confidence with this project. It cannot be moved.').
- Shared lots stay out of the open marketplace. The material page tags them Shared in confidence.
- If the owner stops sharing, the shortlist row reads 'No longer shared with this project' and it can no longer be sent or decided.
- Lots reached through an owner's share link, whose own terms were accepted when the link was opened, show under the project before the project's terms.

NOTIFICATIONS

- When an owner approves a project with lots to share, the architect's practice and the client (once it has accepted the project) are told 'N lots shared with Project', with 'Accept the confidentiality terms to see them.' before the terms, linking to Shared with you.
- When an owner shares one more lot with an approved project, the same people are told 'New lot shared with Project'.
- Accepting the terms sends no message; the project activity records 'accepted the confidentiality terms for shared lots'.


ARCHITECT

Look at a material, save it and download its geometry

Architect | Platform

Where Material page (/app/marketplace/:publicId), opened from any card; Saved in the sidebar (/app/saved)

The material page shows a listing in the order an architect decides: pictures and a 3D view, availability against their projects, sustainability, key facts and the full specification. From here the architect saves it to a project or to Saved, and downloads its drawing, 3D model or BIM model.



STEPS

1. Architect Opens a material from a card, the programme chart or search.
2. Architect Steps through the pictures: public photos, the 3D view (drag or use the arrow keys to turn it; on a phone, drag sideways), the illustration and the dimensioned drawing on plain white. A steel column stands upright, as in the BIM model.
3. Platform Under Availability shows the fit against the project being checked, with a marker 'Materials needed from [date]', or 'Against your projects' for up to five projects.
4. Architect Selects Save to project and ticks a project or Saved in the menu; selecting a ticked place removes it again.
5. Platform Saves it as Shortlisted on that project, or into Saved, and confirms with Undo.
6. Architect Selects Download and chooses 2D drawing (DXF), 3D model (OBJ) or BIM model (IFC), or uses the Geometry files section lower down.
7. Platform Builds the file from the recorded dimensions and downloads it, or says why it cannot.
8. Architect Once the client has approved the material on a project, selects Specification to open that project's specification.
9. Architect Returns with the Marketplace crumb or Browse the Marketplace, which keep the project the visit was checking against.
10. Architect Later, on Saved, selects Move to project when a project comes along, or removes the material.

RULES

- The page is built only from the public listing. The architect never sees who sells it; a client sees only the seller's type, and the seller and the exact site are shared with the client once a reservation is accepted. The guide price section is for clients and donor building owners only.
- The 3D view and every download are generated from the recorded dimensions and labelled so. Long members open in close-up with a full length toggle; the download is the full length.
- Save to project lists every project the architect works on, then Saved, then New project. A place that cannot take it explains why: 'Not shared with this project.', 'No longer available.', 'Reserved by another buyer.', or for a shared lot going to Saved 'Shared in confidence with a project. It can be saved only to a project it is shared with.'
- Saving the same material to the same place twice does nothing. An item the client has approved cannot be removed: 'Approved by the client. It cannot be removed.'
- Only architects get Save to project. Clients and consultants who can open the page can still download.
- DXF is the 2D profile in millimetres, OBJ the 3D model extruded to the recorded length, IFC4 a BIM model that opens in Revit and other BIM tools. BIM family is shown locked as Coming in version 2. Where the section is not recorded the download is greyed out with the reason.
- Saved takes only openly listed materials. Moving from Saved follows the same rules as moving a shortlist item.

NOTIFICATIONS

- None. Saving to a project records 'shortlisted Material' in the project activity.


ARCHITECT

Work through the shortlist

Architect | Client or developer | Platform

Where Project, Shortlist tab (/app/projects/:id/shortlist)

The shortlist is the project's working list of materials, shown as a board with four columns or as a list. The architect adds notes, moves or removes items, sends them to the client and reopens any the client declines.



STEPS

1. Architect Opens the Shortlist tab and sees totals (materials, mass, avoided carbon) and the columns Shortlisted, Waiting for approval, Approved and Declined.
2. Architect Switches between Board and List; Add materials opens the Marketplace for this project.
3. Architect From a card's actions menu chooses Open material, Add a note or Edit note, Move to, or Remove from shortlist.
4. Architect Selects shortlisted cards and sends them to the client (see Send materials for approval).
5. Client or developer Approves or declines each sent item on their Approvals tab.
6. Architect On a declined card reads the client's note, then from its actions menu selects Reopen, writes a new note under Your note and selects Reopen to put it back on the shortlist.

RULES


- Only the practice's own architects on the project get controls; a client never sees the architect's shortlist board.
- A note, up to 1,000 characters, can be added or edited while the item is Shortlisted or Declined; the client sees it with the material. Otherwise: 'The note can be edited while the item is shortlisted or declined.'
- Move to takes a Shortlisted or Declined item to another of the architect's projects or to Saved, where it arrives as Shortlisted: the client's earlier decision and the sent date do not travel. An item waiting for approval stays 'until the client decides'; an approved item 'stays on this project'; a shared lot cannot be moved; a place that already holds the material says 'Already on this list.'
- Any item except an approved one can be removed. An approved card is locked and shows its approval date and any reservation.
- Only a declined item can be reopened: 'Only a declined item can be reopened.'
- A row whose lot is no longer shared or available reads 'No longer shared with this project' or 'No longer available' and cannot be selected to send.
- Every note, move, removal and reopen can be undone from its confirmation. Board or List is remembered.

NOTIFICATIONS

- Moves, removals and reopens add a line to the project activity, for example 'reopened Material'. Notifications go out only when items are sent or decided (see Send materials for approval).

LIFECYCLE

Sent items wait for the client; approved items are locked on the project; declined items can be reopened, moved or removed.




ARCHITECT

Send materials for approval

Architect | Client or developer | Sustainability consultant | Platform

Where Project, Shortlist tab (/app/projects/:id/shortlist), Send to client; the client decides on Approvals (/app/projects/:id/approvals)

The architect sends chosen shortlisted materials to the client with a message. The client approves or declines each one; the architect hears back and can reopen a declined material with a new note.



STEPS

1. Architect Ticks the shortlisted cards to send; a bar shows 'N selected' with Select all and Send to client.
2. Architect Selects Send to client; with nothing ticked, every material that can be sent is included.
3. Platform Opens 'Send to Client', listing each material with its fit, and warns that they cannot be changed while the client decides.
4. Architect Adds an optional Message and selects Send for approval.
5. Platform Moves the items to Waiting for approval with the sent date, and notifies the client.
6. Client or developer On the Approvals tab selects Approve or Decline for each material, with an optional note.
7. Platform Moves each item to Approved or Declined and notifies the architect's practice and the consultancy, once it has joined the project.
8. Architect Reopens a declined material with a new note to send it again, or leaves it.

RULES

- Only the project's architect can send, and only once the client has accepted the project; until then the Send to client button is off and the banner explains why.
- Only Shortlisted items still shared with the project and still available can go. If none qualify: 'Nothing selected can go to the client.'
- The message is up to 1,000 characters and is shown to the client with the materials.
- Only the project's client decides, and only on items sent to them: 'Only an item sent to the client can be decided.' A decision is refused if the lot is no longer shared ('No longer shared with this project.') or no longer available ('No longer available.').
- Approved materials are locked on the project, feed the Approved specification, and can then be reserved by the client.
- A send can be undone from its confirmation.

NOTIFICATIONS

- On send: the client organisation is told 'N materials to approve on Project', with the architect's message or 'Sent by Name, Practice.', linking to Approvals. The project activity records 'sent Material to the client for approval'.
- On each decision: the architect's practice and the project's consultancy (once it has joined) are told 'Client approved Material' or 'Client declined Material', with the client's note or 'On Project.', linking to the shortlist.
- Each decision also adds a line to the project activity.


ARCHITECT

Prepare and export the specification

Architect | Client or developer | Platform

Where Project, Specification tab (/app/projects/:id/specification), with ?mode=approved or ?mode=draft

The specification is a schedule with one clause per material, every public field grouped by section, and the architect's notes. It has an Approved mode for what the client approved and a Draft mode that adds what is still shortlisted or waiting, and it exports as a spreadsheet or prints on A4.


Open the Specification tab
Which materials?
Approved
Draft
Clauses for approved materials
Clauses for all not declined
Write notes for this schedule
Write a note on each clause
Notes save when you leave the field
How to share it?
Spreadsheet
Paper
Export spreadsheet downloads a file
Print an A4 schedule

STEPS

1. Architect Opens the Specification tab and chooses Approved or Draft under Which materials, each with its count.
2. Platform Shows 'Specification schedule' or 'Draft specification schedule', one clause per material with its status, every public field by section, and the caveats. The architect's schedule leaves out the Price section (guide price and market signal) and its caveat; the client's keeps them.
3. Architect Writes Notes for this schedule at the top.
4. Architect Writes an Architect's note on any clause, for example fixing, testing, finish or tolerances.
5. Platform Saves each note when the field loses focus, or on Cmd or Ctrl Enter.
6. Architect Selects Export spreadsheet to download the schedule, or Print for an A4 copy.

RULES

- The architect and the client can open the specification; only the architect can write notes, and the client reads them. A donor building owner that is the client of its own New project reads it as the client does. The consultant has no Specification tab.
- Approved shows approved materials only. Draft shows Shortlisted, Waiting for approval and Approved; declined materials are left out. Materials no longer shared or available are left out of both.
- The tab opens on Approved, unless nothing is approved yet and the draft has materials, when it opens on Draft.
- The schedule note is up to 4,000 characters and each clause note up to 2,000; clearing a clause note removes it.
- The spreadsheet has the schedule title, project line, schedule note and caveats, then one row per clause with every public field and the note. It carries only public listing fields and the practice's own words; the architect's screen, print and spreadsheet all leave out the guide price and market signal. The file is named after the project and today's date.
- Print and Export spreadsheet are off while the schedule is empty. An empty Approved schedule offers See the draft when the draft has materials; an empty draft offers the architect Open the shortlist.
- A clause for a material reserved for this project is marked reserved.

NOTIFICATIONS

- None.

SECTION

Client (developer)

This section is about the client: the developer organisation a project is built for. The client accepts the architect's request to join a project, joining Tallyard from an invite if nobody there uses it yet, approves or declines the materials the architect proposes, asks sellers to reserve approved materials and, with the sustainability consultant, keeps requirements and the circular economy statement on track. Its Home is a dashboard of indicative figures and a to do list across all its projects; a client with no projects yet sees its first steps instead.


CLIENT (DEVELOPER)

Accept or decline a project request

Client (developer) Architect

Where Home, request cards at the top (/app/home), and Projects, Project requests in the sidebar (/app/projects/requests)

An architect must ask before adding a client organisation to a project. The client reads the request and accepts it to see the project and approve materials, or declines it with an optional note.



STEPS

1. Architect Creates a project naming your organisation as client, or asks you again later, with an optional message.
2. Platform Sends your organisation a notification and shows the request as a card at the top of Home and under Project requests in the sidebar, with a count badge.
3. Client (developer) Reads the card: project name, architect practice, who asked and when, type, location, stage, site start, practical completion, the sustainability consultancy the architect proposes ('asked once you accept') and the message.
4. Client (developer) Chooses Accept, or chooses Decline and writes an optional note in the dialog titled 'Decline [project]?', then confirms with Decline.
5. Platform On accept, links the project: a message 'You joined [project]' offers Open project, the project appears under Projects in the sidebar with its tabs, the architect can now send materials for approval, and the proposed consultancy is asked to join.
6. Platform On decline, records the decision under the organisation's name and tells the architect, with the note if one was given. The project stays out of the client's workspace.
7. Architect After a decline, can ask the same client again or choose another client from the project overview.

RULES

- Only a person in a developer (client) organisation can answer, and only for a project that names their organisation as client.
- Only a request still waiting can be answered. A second answer is refused with 'This request has already been answered.'
- Before accepting, the client never sees the shortlist, any listing or any figure; only the project facts and the message.
- Until the client accepts, the project is not in the client's workspace and the architect cannot send anything for approval. Opening the project's address shows 'Accept [project] to open it' with a button to Project requests.
- Until the client accepts, no consultancy sees the project or is asked about it.
- A decline reaches the architect under the organisation's name, never the name of the person who declined.
- Project requests appears in the sidebar, with a count, only while at least one request is waiting. The page itself (/app/projects/requests) also lists answered requests as Accepted or Declined with the date.
- A donor building owner never receives project requests: it becomes a client only of its own New projects.
- There is no undo for accepting or declining a project request.

NOTIFICATIONS

- Client organisation: '[practice] asked to add you as client on [project]', with the architect's message, or 'Accept to see the project and approve materials for it.' when there is none.
- Architect on accept: '[client] accepted [project]. They can now see the project and approve materials you send.' The project activity records that the client accepted.
- Consultancy, on accept, when the architect named one: '[practice] asked to add you as sustainability consultant on [project]', '[client] has accepted the project. Accept to see it and set its targets.'

- Architect on decline: '[client] declined [project]', with the client's note, or 'Ask again or choose another client from the project overview.' when there is none. Only the architect is told.


CLIENT (DEVELOPER)

Join a new client organisation from an invite

Client (developer) | Architect | Platform

Where The invite link (/invite/:token), or Create your account (/signup) with the invited email; then Home (/app/home) and Project requests (/app/projects/requests)

When an architect names a client nobody uses Tallyard from yet, nobody can accept the project. The architect invites a contact by email; that person joins the client organisation, from the link or by signing up with the same email, and the request to accept the project waits on their Home.


Architect adds a client contact email
Invite tied to the project
How does the contact arrive?
Link
Sign up
Opens the invite link
Signs up with the invited email
Reads who asked, for which project
Step 2: Join the organisation that invited you
Enters name and password, presses Join
Joins the client organisation
Practice told they can now accept
Request waits on Home, Accept or Decline

STEPS

1. Architect Gives a Client contact email on New project or Change client, or later in the field on the waiting banner, and passes on the link with Copy invite link; no email is sent from the sandbox.
2. Client (developer) Opens the link and reads, for example, 'Studio Oriel asked Harrowgate Homes to accept Pellow Row, and invited this email to answer', then enters a full name and password and presses Join.
3. Client (developer) Or opens Create your account and types the invited email: step 2 becomes 'Join the organisation that invited you', with no organisation fields and a Join button.
4. Platform Creates the person as the first member of the client organisation, signs them in and shows the request at the top of their Home and under Project requests.
5. Client (developer) Accepts or declines the project as any client does.

RULES

- The open sign-up page names no organisation, project or practice: it says only 'This email has an invite to answer a project request. Open the link you were sent to see who invited you, or join now.' The names show only through the invite link.
- Only the newest invite for a project works; Resend or Use another email replaces it. Accepting the project unlocks sending for approval.
- An invite is refused once someone from the client organisation uses Tallyard, for an email another organisation uses, or once the client has accepted.
- Sandbox invites open only in the browser where they were made.

NOTIFICATIONS

- The architect's practice, when the contact joins: '[name] joined [client]. They can now accept [project].'
- The client organisation: the usual '[practice] asked to add you as client on [project]' request, already waiting.


CLIENT (DEVELOPER)

Approve or decline a material

Client (developer) | Architect | Sustainability consultant

Where Project, Approvals tab (/app/projects/:id/approvals); also the To do list on Home

The architect sends shortlisted materials to the client for a decision. The client reads the facts and the indicative cost against buying new, then approves or declines each one with an optional note. Approving buys nothing; it makes the material ready to reserve.


Architect sends materials for approval
Client notified, badge on Approvals
Open the Approvals tab
Read facts, cost and carbon
Approve this material?
Yes
No
Choose Approve, optional note
Choose Decline, optional reason
Still shared and available?
No
Yes
Refused with a reason
Decision saved, team notified
Approved
Declined
Approved, ready to reserve
Declined, architect may propose again

STEPS

1. Architect Sends one or more shortlisted materials to the client with a message; this is possible only once the client has accepted the project.
2. Platform Notifies the client, adds a badge to the project folder and the Approvals tab, and adds an 'Approve or decline' item to the To do list on Home.
3. Client (developer) Opens Approvals and reads each card under 'Waiting for your decision': the material facts, the indicative package cost against the same new, and the architect's message.
4. Client (developer) Chooses Approve or Decline, adds an optional note in the dialog, and confirms.
5. Platform Checks the material is still shared with the project and still available, then saves the decision and logs it in the project activity.
6. Platform Tells the architect and the consultant; the card moves to the Decided list with its decision and note.
7. Client (developer) For an approved material, follows Reserve on the Decided list to the Reservations tab.

RULES


- Only the project's client can decide, and only on an item the architect has sent. Anything else is refused with 'Only an item sent to the client can be decided.'
- A material that stops being shared with the project, or is reserved for another buyer, drops off the Approvals tab and the To do list. If that happens while the dialog is open, the decision is refused with 'No longer shared with this project.' or 'No longer available.'
- Approving does not buy or reserve anything. The dialog says: 'Approving tells the architect they can specify it. Nothing is bought: you can then ask the seller to reserve it.'
- While a material waits for the client, the architect can still remove it from the shortlist; it then leaves the Approvals tab.
- A declined material goes back to the architect, who can reopen it with a new note and send it again. An approved material cannot be removed or moved by the architect.
- The three figures at the top (Waiting for your decision, Approved, Avoided carbon if you approve) and every cost are labelled Indicative. Costs are the indicative package: guide price plus testing, storage and delivery, against the same new.
- A message after each decision offers Undo.
- The client never sees the seller's name or the donor building at this stage.
- An approval is due 7 days after it was sent; after that it reads as overdue on the To do list.

NOTIFICATIONS

- Client when sent: '[n] materials to approve on [project]', with the architect's message, or 'Sent by [name], [practice].'
- Architect and consultancy (once it has joined the project) on a decision: '[client] approved [material]' or '[client] declined [material]', with the note.
- Project activity for the whole team: '[person] approved [material]' or '[person] declined [material]'.

LIFECYCLE

A material is shortlisted, sent, then approved or declined by the client. Only the architect can reopen a declined one or remove one that is waiting; an approved one stays on the project.




CLIENT (DEVELOPER)

Request a reservation

Client (developer) | Donor building owner (seller)

Where Project, Reservations tab (/app/projects/:id/reservations), button Request reservation

For each approved material the client sees an indicative package and asks the seller to hold the material for the project. The seller receives a blind request that says only what kind of buyer it is, never who.



STEPS

1. Client (developer) Opens Reservations, which lists every approved material. Pills at the top count To request, With the seller and Reserved, above a Cost card and a Carbon card for the project.
2. Platform Works out an indicative package for each material: material at the guide price, testing, storage for the months until materials are needed, handling out and delivery to site, against the same quantity new.
3. Platform Picks the hub for the package itself: the listing's collection hub if it has one, otherwise the cheapest suitable hub. The client does not choose a hub.
4. Client (developer) Chooses Request reservation (Request again after a decline or withdrawal), reads the panel 'The seller sees your request as', and writes an optional message to the seller.
5. Client (developer) Chooses Send request.
6. Platform Checks the request is allowed, saves it with the package fixed as at today, and logs it for the project team.
7. Platform Sends the seller a notification that carries only the blind line, in the form '[buyer type], [project type], [region], needed [three month window]', for example 'Design team, commercial project, London, needed April to June 2027'.

RULES

- Only the project's client can request, and only for a material it has approved: 'Only an approved material can be reserved.'
- Refused when the material is no longer shared with the project ('No longer shared with this project.'), no longer available ('No longer available.'), already with the seller ('A request for this material is already with the seller.') or already reserved for this project ('Already reserved for this project.').
- A donor building owner working as client on its own New project cannot reserve its own lot: 'This lot is yours. Allocate it directly; reserving is for other sellers.'
- The seller sees only the blind line: buyer type, project type, region and the three month window when materials are needed. Never the client's name, the project name or any figure.
- The message hint asks for quantity, timing or testing only, with no names or contact details; these are shared only if the seller accepts.
- Testing is costed only for steel sections that are not already tested or certified. Covered only materials are never stored at an open yard.
- While a request is open or accepted the package stays as it was on the day of the request ('As at your request'); otherwise it is 'Worked out today'.
- All prices and package costs are labelled Indicative until terms are agreed with the seller. A message after sending offers Undo.

NOTIFICATIONS

- Seller (donor building owner): 'Reservation request for [item tag]', with the listing title and the blind line.
- Project activity for the client, architect and consultant: '[person] requested a reservation of [material]'.


CLIENT (DEVELOPER)

Withdraw a reservation request

Client (developer) | Donor building owner (seller)

Where Project, Reservations tab (/app/projects/:id/reservations), button Withdraw on a request awaiting the seller

While the seller has not answered, the client can take a reservation request back. The material stays approved and can be requested again later.



STEPS

1. Client (developer) Finds a card that reads 'Requested ... Waiting for the seller.' and chooses Withdraw.
2. Platform Checks the seller has not decided, then marks the request withdrawn and logs it for the project team.
3. Platform Tells the seller the buyer withdrew, still without naming the buyer.
4. Platform Shows 'You withdrew this request' on the card with a Request again button, and the To do list shows 'Choose again for [material]' until the client requests again.

RULES

- Only the project's client can withdraw, and only a request still awaiting the seller: 'This request has already been decided.'
- An accepted reservation cannot be withdrawn here; the parties agree any change directly once contacts are exchanged.
- The seller is told only that 'the buyer' withdrew.
- A message after withdrawing offers Undo.

NOTIFICATIONS

- Seller: 'Request withdrawn for [item tag]. The buyer withdrew their request for [material].'
- Project activity for the client, architect and consultant: '[person] withdrew the reservation request for [material]'.


CLIENT (DEVELOPER)

When the seller accepts or declines

Donor building owner (seller) | Client (developer) | Architect | Sustainability consultant

Where Seller: Requests (/app/requests). Client: Project, Reservations tab (/app/projects/:id/reservations)

The seller answers a blind request. Accepting holds the lot for that project, declines every other waiting request for the same lot, and exchanges contacts between the client and the seller only. Declining returns the material to the client to request again.


Seller opens the blind request
Accept the request?
Yes
No
Lot already held for someone?
Decline with optional note
Yes
No
Refused, reserved for another buyer
Lot held for this project
Client told the seller declined
Other waiting requests declined
Client can request again
Client and seller contacts exchanged
Client told, architect told it is reserved
Reserved, contact the seller

STEPS

1. Donor building owner (seller) Opens Requests and reads the blind line and the message, then chooses Accept or Decline and confirms ('Accept and reserve' or 'Decline').
2. Platform On accept, checks no other request already holds the lot, then marks this request reserved.
3. Platform Declines every other request still waiting for the same lot, from any project, with the note 'Reserved for another buyer.'
4. Platform Exchanges contacts: the seller sees the client organisation, the person who asked and their email; the client sees the seller organisation, contact and email.
5. Client (developer) Sees 'Reserved on [date]. Contact the seller to agree terms.' with the seller, contact and an email link.
6. Platform On decline, marks the request declined with the seller's note and tells the client; the card shows 'The seller declined this request' and Request again.
7. Client (developer) After a decline, follows the 'Choose again' item on the To do list or Request again on the card. A request turned down because another buyer reserved the lot cannot be retried: the material leaves the client's Reservations and Approvals tabs.

RULES

- Only the owner of the donor building the lot comes from can decide, and only a request still waiting: 'This request has already been decided.'
- A lot can be reserved for one project only. Accepting a second request is refused with 'Reserved for another buyer.'
- Contacts are exchanged between the client and the seller only. The architect and the consultant never see the seller: their activity reads 'The seller accepted the reservation of [material]'.
- Before acceptance neither side learns who the other is.
- Once reserved, the lot leaves the open marketplace and cannot be approved or requested by any other project.
- An accepted reservation counts as secured avoided carbon on the project and the client dashboard.
- Prices stay indicative: the client and the seller agree terms directly, outside the platform.
- The seller gets a message offering Undo straight after accepting or declining.

NOTIFICATIONS

- Client on accept: '[seller] accepted your reservation. [material] is reserved for [project]. Contact [name], [email].'
- Architect on accept: '[material] is reserved. The seller accepted the client's reservation on [project].' No seller name.
- Client on decline: 'Reservation declined: [material]', with the seller's note, or 'The seller declined this request.'
- Clients of competing requests: 'Reservation declined: [material]. Reserved for another buyer.' Their project activity reads 'The seller reserved [material] for another buyer'.
- Architect on decline, and the consultant in every case: no notification; the project activity shows a line from 'The seller' without a name.


CLIENT (DEVELOPER)

Follow a reservation from request to reserved

Client (developer) | Donor building owner (seller)

Where Project, Reservations tab (/app/projects/:id/reservations); Home, Reservations panel (/app/home)

Each reservation request is one record that moves through a few states. This shows every state a request can reach and what the client can do next from each one.



STEPS

1. Client (developer) Sends a request for an approved material; the card and the Home panel show Awaiting the seller.
2. Client (developer) While it waits, can choose Withdraw; the card then shows 'You withdrew this request' and Request again.
3. Donor building owner (seller) Declines it; the card shows 'The seller declined this request' with the note, and Request again.
4. Donor building owner (seller) Accepts another buyer's request for the same lot first; this request is declined with 'Reserved for another buyer.' and the material leaves the client's Reservations and Approvals tabs.
5. Donor building owner (seller) Accepts it; the card shows 'Reserved on [date]. Contact the seller to agree terms.' with the seller's organisation, contact and email.
6. Client (developer) After a withdrawal or a decline, chooses Request again, which starts a new request with a fresh package.

RULES


- Only one request per material can be open at a time for a project.
- Reserved is final in the platform, apart from the seller's Undo straight after accepting. There is no cancel or withdraw after acceptance; the client and the seller agree any change directly.
- The Home Reservations panel lists only requests awaiting the seller or reserved, and counts To request, With the seller and Reserved.
- The status words are the same everywhere: Awaiting the seller, Reserved, Declined, Withdrawn.

NOTIFICATIONS

- See 'Request a reservation', 'Withdraw a reservation request' and 'When the seller accepts or declines' for who is told at each step.

LIFECYCLE

Each request is one record. Reserved is final; after Declined or Withdrawn the client can choose Request again, which starts a new record.




CLIENT (DEVELOPER)

Work through the to do list

Client (developer) | Platform

Where Home, To do panel (/app/home)

The To do list on the client's Home is built from the records each time it is shown, so an item disappears by itself once the underlying task is done. It gathers approvals, reservations to request, statement reviews and requirements at risk across all the client's projects.



STEPS

1. Platform Adds 'Approve or decline [material]' for each material sent and waiting, due 7 days after it was sent; it clears when the client decides.
2. Platform Adds 'Request a reservation for [material]' for each approved material with no open request; it clears when a request is sent.
3. Platform Adds 'Choose again for [material]' when the seller declined or the client withdrew; it clears when the client requests again.
4. Platform Adds 'Review the circular economy statement' when the consultant sends it, due 14 days later; it clears when the client marks it reviewed, and stays if the consultant edits the statement meanwhile.
5. Platform Adds 'Check [requirement]: at risk' for each requirement marked at risk; it clears when the status changes.
6. Client (developer) Chooses an item to open the Approvals, Reservations, Sustainability or Requirements tab of that project and does the task there.

RULES

- Nothing on the list can be ticked off by hand: an item clears only when the record behind it changes.
- Order: items with a due date first, earliest due first (so overdue items lead), then undated items oldest first, then by title.
- Only approvals (7 days) and statement reviews (14 days) have due dates. Overdue items show 'Overdue by n days' and the panel shows how many are overdue.
- Requirements at risk always show in the warning colour, whoever marked them.
- A material reserved for another buyer, or no longer shared, leaves the list without an item to choose again.
- The Reservations panel beside it counts To request, With the seller and Reserved, and links to the approved materials still to request.
- When the list is empty it reads 'Nothing to do. Approvals and reviews appear here.'

NOTIFICATIONS

- None. The list is derived from the records; the notifications for each underlying event are sent by those workflows.


CLIENT (DEVELOPER)

Review the circular economy statement

Client (developer) Sustainability consultant

Where Project, Sustainability tab, Circular economy statement card (/app/projects/:id/sustainability#statement)

The consultant drafts the circular economy statement and sends it to the client. Sending freezes the text: the client reads and reviews the version sent, dated when it was sent, while the records move on. The client marks it reviewed, with optional comments the consultant then sees.


Consultant sends the statement for review
Consultant sends the updated statement
Text frozen as sent
Client notified, item on To do
Open the Sustainability tab
Choose Read and review
Read the version sent and the caveat
Add optional comments
Choose Mark as reviewed
Statement marked reviewed
Consultant told, with the comments
Reviewed by the client

STEPS

1. Sustainability consultant Edits the statement drafted from the project records and sends it to the client; this needs the client and the consultancy to have accepted the project.
2. Platform Freezes the text as sent, notifies the client, puts a badge on the Sustainability tab and adds a review item due in 14 days to the To do list.
3. Client (developer) Opens the Circular economy statement card, which reads 'Ready for your review', and chooses Read and review.
4. Client (developer) Reads every section of the version sent, with its bulleted lists, under the warning caveat; writes optional comments for the consultant and chooses Mark as reviewed.
5. Platform Records the review with the date and comments, logs it for the project team and tells the consultant.
6. Sustainability consultant If the statement changes after sending, presses Send the updated statement, which replaces the frozen version and asks for review again.

RULES


- Only the project's client can mark the statement reviewed, and only while it is with the client for review: 'The statement has not been sent for review.'
- Only the consultant can edit or send the statement. The client reads it; the architect does not see the statement card.
- A statement never sent reads 'Not sent yet' to the client and the architect, on the Sustainability card, the scheme card and the tracking table, or 'Being drafted' once the consultant has started editing it; the client cannot open it until it is sent. After review the client can still open it with Read the statement.
- An edit after sending does not pull the statement back: the client keeps reading, and can still review, the version sent, and sees 'This is the version sent on [date]. [Consultancy] has updated the statement since, so ask them for the latest if you need it.'
- The statement is indicative and carries the caveat in the dialog. A toast offers Undo after marking it reviewed.

NOTIFICATIONS

- Client when sent: 'Circular economy statement ready for review. [project]. Sent by [name], [consultancy].'
- Client when the updated statement is sent: 'Updated circular economy statement ready for review'.
- Consultant when reviewed: '[client] reviewed the circular economy statement', with the comments or 'No comments.'

LIFECYCLE

Only the consultant sends, and each send freezes the text the client reads. Editing never moves the statement back; only the client moves it from ready to reviewed.




CLIENT (DEVELOPER)

Track requirements and evidence

Client (developer) | Sustainability consultant | Architect

Where Project, Requirements tab (/app/projects/:id/requirements)

The planning and sustainability requirements that apply to the project are tracked with a status and an evidence log. The client and the consultant keep them current; the architect chooses which apply and can read them.



STEPS

1. Architect Chooses which requirements apply from the project's local authority and region, on the project overview or the Requirements tab. Until then the requirements suggested for the place are tracked, and the tab says so.
2. Client (developer) Opens Requirements, from the tab or Track requirements on the overview card, sees the bar of requirements by status and 'n of m ready', and filters with All, At risk, Open, Evidence ready or Not applicable.
3. Client (developer) Sets a status from the list: Not started, In progress, At risk, Evidence ready or Not applicable.
4. Client (developer) Chooses Add evidence and writes a note, optionally linking an output held in the platform, such as the compliance workbook or the circular economy statement.
5. Platform Saves the change with who made it and when, logs it for the project team, and moves a not started requirement to in progress when its first evidence is added.
6. Platform When the status becomes At risk or Evidence ready, notifies the other of the two (the consultancy when the client changed it, once it has joined).

RULES


- Only the client and the consultant can change a status or add evidence. The architect reads the tab.
- Only requirements that apply to the project can be changed: 'That requirement does not apply to this project.'
- Evidence needs a note or a linked output: 'Add a note or choose an output.' Only the person who added evidence can remove it. Each change offers Undo.
- Not applicable requirements are left out of the total and the ready share.
- Each card also shows figures the platform already holds for that requirement, such as carbon or content against target.
- An at risk requirement adds a badge to the Requirements tab and an item to the client's To do list.
- Requirements are indicative planning aids, not certification or planning advice.

NOTIFICATIONS

- Consultancy (once it has joined the project), when the client marks a requirement at risk or evidence ready: '[requirement] is [status] on [project]. Marked by [name], [organisation].'
- Client, when the consultant does the same, once the client has accepted the project.
- Other status changes and evidence are logged in the project activity only.

LIFECYCLE

Any status can be chosen from the list at any time; the arrows show the usual moves. The only automatic move is from not started to in progress when the first evidence is added.




CLIENT (DEVELOPER)

Read the dashboard figures

Client (developer) | Platform

Where Home (/app/home), the four figures under the greeting

The client's Home opens with four indicative figures across all its projects: cost, saving against new, avoided carbon secured and reuse by value. The platform works each one out from the records; the screen only shows them.



STEPS

1. Platform Indicative cost: adds up the package totals of every reclaimed material in four stages: Confirmed (earlier deals at the agreed material price), Reserved, With the seller and Approved; shown as a donut by stage.
2. Platform Saving against new: what the same quantities would cost bought new, minus the indicative cost; shown as an amount marked 'Cheaper than new' or 'Costs more than new', with the share less than buying new.
3. Platform Avoided carbon, secured: carbon avoided against buying new for earlier deals and accepted reservations only, against the sum of the projects' carbon targets, with a line for how much more the approved materials would add.
4. Platform Reuse by value: the reused share of the projects' bills of materials by value; below it, reused and recycled content by value against the projects' own aim, weighted by each bill's value.
5. Client (developer) Reads the figures and follows a project card or tab for the detail.

RULES

- Every figure is labelled Indicative and comes from guide prices and the package engine, not agreed prices.
- With nothing approved the cost tile reads 'Nothing approved yet' and the saving tile 'Shown once materials are approved'.
- With no carbon target set the carbon tile reads 'No carbon target set'. With no bill of materials the reuse tile reads 'No bill yet'.
- Only secured materials (earlier deals and reservations the seller accepted) count as secured carbon and reuse; approved materials are shown separately as what more they would add.
- Only projects the client organisation has accepted are counted.
- A client with no projects sees no figures: Home opens on a welcome with three next steps (your architect adds you as the client, accept the project, approve and reserve materials) and recent activity. A donor building owner that is the client of a New project sees the same four figures on its own Home, under Your new projects as developer.

NOTIFICATIONS

- None.


CLIENT (DEVELOPER)

Follow the programme and certification across projects

Client (developer) Platform

Where Home (/app/home): Programme across your projects, Sustainability tracking, Your projects and recent activity

Below the figures, the client's Home lays every project on one timeline, then shows a tracking table for certification, circular economy and requirements, then a card per project. It answers where each project is and what is at risk, without opening each one.


Open Home
Programme across your projects
Stages, site start, completion, materials needed
Sustainability tracking table
BREEAM, LEED and WELL targets and credits
Content by value and statement status
Requirements ready and at risk
Your projects cards
Something at risk or waiting?
Yes
No
Open that project
Nothing to act on

STEPS

1. Platform Programme across your projects: one time axis with a row per project showing its RIBA stages, site start, practical completion, when materials are needed on site, and a line for today. A project without a programme reads 'Programme not set'.
2. Platform Sustainability tracking: per project, the BREEAM, LEED and WELL cells, each with the target rating, credits ready and at risk, and a pill with an icon and a word for its state against target (On target, Near target, Off target); content by value against target with the statement status; and requirements ready, in progress and at risk, with the place they are for, for example 'For Newham, Inner London East'.
3. Platform Your projects: a card per project with its drawing and swatches, stage, materials needed date, counts To decide, Approved and Reserved, and the indicative cost so far. A project still setting up reads 'Being set up', then 'Nothing shortlisted yet' or 'Shortlisting under way'.
4. Client (developer) Follows a project name, a card or an at risk pill into the project to act.

RULES

- Certification tracking is read from the consultant's records. It is indicative and not certification advice; the table carries that caveat.
- A project with no consultancy reads 'No consultant appointed yet' under its name and still shows its three scheme cells, with the defaults from its requirements where they apply and 'Not targeted' otherwise. A consultancy that has not joined is named as waiting to accept or declined, never as setting targets.
- The programme dates come from the project programme; the client cannot edit them here. Every rating state comes from one rule shared with the Sustainability tab and the consultant's Home.
- Recent activity lists decisions and reservations on the client's projects; seller names appear only for the client's own accepted reservations.
- Each project row links into that project; nothing on this part of Home can be changed here.

NOTIFICATIONS

- None.

SECTION

Donor building owner

The donor building owner holds buildings that are coming down or being stripped out, and decides what in them is recovered, who may see it and who may reserve it. They appoint the surveyor and the deconstruction contractor, ask testing companies for tests, track the requirements that apply before demolition, list lots privately, in confidence or publicly, and answer reservation requests. Every owner can also read the Marketplace, and can be the client of its own New project, sourcing reclaimed materials with an architect.


DONOR BUILDING OWNER

Add a donor building

Donor building owner | Surveyor (told if appointed)

Where Buildings (/app/buildings), button Add building, or Add building in the sidebar under Donor buildings (/app/buildings?new=1)

The owner records a building that is coming down or being stripped out, so it can be surveyed and what it holds offered for reuse. The record is private to the owner organisation; nothing is listed until the owner decides.



STEPS

1. Donor building owner Presses Add building and, under What kind of building?, picks Donor building.
2. Donor building owner Enters the building name and address and chooses the Region (required), and optionally the postcode district and the Local authority. The local authority list holds every listed authority grouped by region, so choosing one also sets the region; outside London, Another local authority takes a typed name.
3. Donor building owner Optionally adds the year built, storeys, floor area, the structure element by element, and the programme dates: Strip-out starts, Dismantling starts, Site clear by.
4. Donor building owner Optionally picks a firm under Surveyor, then presses Add donor building.
5. Platform Checks the details, saves the building as private with location shown by region and timing by three-month window, starts tracking the requirements that apply before demolition at that place, and opens its Overview.
6. Platform If a surveyor was chosen, tells that firm it is appointed and links it to Capture.
7. Donor building owner Can later change the name, address, postcode district, region, local authority and programme with Edit details on the building, and the structure on the Overview. A move says how many requirements before demolition stop applying and how many more are tracked.

RULES

- Only a donor building owner can add a donor building this way.
- Name, address and region are required. The year built must be between 1800 and this year.
- A listed local authority is accepted only under its own region: "Choose a local authority in this region." A typed name that is in fact listed says where it is listed. A typed name is accepted only outside London. Names are stored in their listed spelling, so "westminster" or "Westminster City Council" both read Westminster.
- The programme dates must run in order: strip-out, then dismantling, then clear by. Otherwise the save is refused.
- The surveyor, if chosen, must be a surveying or deconstruction firm.
- The building and everything captured in it stay private to the owner and the firms working on it until the owner lists something.

NOTIFICATIONS

- The chosen surveying firm: "[owner] appointed you to survey [building]", linking to Capture.
- The building activity log records that the owner added it.


DONOR BUILDING OWNER

Add a new project and appoint an architect

Donor building owner (as client) | Architect

Where Add new project on Buildings (/app/buildings?new=project), in the New projects section of the owner Home, or on the Marketplace strip Building something too?; or Add building, then New project. The project opens at /app/projects/:id

A New project is a building the owner is putting up or refurbishing. The owner organisation becomes its client and developer, and appoints an architecture practice who shortlists reclaimed materials; the owner then approves and reserves them, as any client would.


Press Add new project
Dialog opens on New project
Enter name, type, region, RIBA stage
Set date materials needed on site
Details valid?
No
Yes
Error shown, fix and retry
Project created, owner is client
Architect chosen?
No
Owner may keep or edit the dates
Yes
Appoint an architect later
Architect told, shortlist ready
Architect shortlists materials
Owner approves and reserves

STEPS

1. Donor building owner Presses Add new project on Buildings or on the owner Home, which opens the dialog on New project with Project name; or presses Add building and picks New project.
2. Donor building owner Enters the project name, region, project type and RIBA stage, and optionally the local authority from the grouped list. If the type is Other, a short description for the team only.
3. Donor building owner Sets Materials needed on site from; the stage dates are suggested from it.
4. Donor building owner Optionally picks an Architect, then presses Add new project.
5. Platform Creates the project with the owner organisation as client, already linked, adds a New projects section to the owner sidebar and shows a quiet New project pill in the project header for the owner.
6. Platform If an architect was chosen, adds them to the team, opens their shortlist for the project and tells them.
7. Donor building owner While no architect is appointed, may press Keep these dates or Edit programme on the project's programme card to set the dates itself.
8. Donor building owner If no architect was chosen, uses the card Appoint an architect to start sourcing on the project Overview or Team tab, or Appoint on the Buildings list, and presses Appoint.
9. Platform On appointment, dates the owner set read "Client's dates" for the architect, who keeps or edits them; the owner then reads "Your dates until the architect confirms them."
10. Architect Shortlists reclaimed materials and sends them for approval.
11. Donor building owner Approves materials and requests reservations from the project Approvals and Reservations tabs, and follows them under Your new projects as developer on its Home.

RULES

- Only a donor building owner can add a New project from Buildings; it is a project, not a building. Add building on its own still opens on Donor building.
- The project name must be unique among the owner organisation's projects.
- The materials date must be today or later, and site start must leave room for the remaining design stages.
- The architect must be an architecture practice. A project has one architect: appointing a second is refused with "This project already has an architect."
- The owner may set the programme only while no architect is appointed; after that only the architect can, and keeping or editing makes the dates the architect's plan.
- No sustainability consultant is set when the owner creates the project.
- On its own projects the owner gets the client workspace: approvals and reservations, not the architect's shortlist tools.
- With a New project, the owner Home adds Your new projects as developer: the client dashboard's indicative cost, saving, carbon and reuse tiles, the to do list and the programme, worked out by the same rules.
- The owner cannot reserve lots from its own buildings for its own project (see the guard on reserving your own lots).

NOTIFICATIONS

- The appointed architect: "[owner] added you as architect on [project]. Your client is [owner]."
- The project activity log records that the project was created and, later, that the architect was appointed.


DONOR BUILDING OWNER

Browse the Marketplace as an owner

Donor building owner | Platform

Where Marketplace in the owner sidebar (/app/marketplace) and material pages (/app/marketplace/:publicId); also search with Ctrl K or Cmd K

Every donor building owner may build too, so every owner reads the Marketplace, as a client would: guide prices and the price sort, but nothing to save to. Its own lots never appear there; it manages them in its buildings. A New project is how it checks materials against a start on site.



STEPS

1. Donor building owner Opens Marketplace, which sits under Home in every owner's sidebar.
2. Platform Shows the Marketplace in the client view: guide price ranges and the Lowest guide price sort, with no Save to project.
3. Platform Leaves the owner's own lots out of the grid, the folders, search and material pages.
4. Donor building owner Without a New project, reads the strip "Building something too? Add a new project to save materials to it and check them against its start on site." and presses Add new project, which opens Buildings on New project.
5. Donor building owner With a New project, chooses it in the checking strip, so each card shows its fit against that project's materials date.
6. Donor building owner Opens a material page and reads its facts, availability and guide price, and downloads its drawing, 3D model or BIM model.

RULES

- Only other sellers' lots show: openly listed ones, lots reserved for the owner's own New projects, and lots shared with them or reached through a share link the owner opened.
- An owner never sees its own lots as listings. Opening one of its own material pages shows the no-access page; it manages those lots in its buildings.
- Nothing names another seller or building: every card and page is built from the public listing.
- Only architects save materials. The architect of the owner's New project shortlists for it; the owner approves and reserves.
- New for your projects is for architects only.
- Search (Ctrl K or Cmd K) finds other sellers' materials for every owner, never its own.

NOTIFICATIONS

- None.


DONOR BUILDING OWNER

Appoint a surveyor to a building

Donor building owner | Surveyor

Where Building, Overview (/app/buildings/:id), Survey card, Surveying firm

The owner appoints a surveying firm to capture what the building holds, changes the firm, or removes the appointment. The surveyor then captures items and submits the survey.



STEPS

1. Donor building owner Opens the building Overview and, in the Survey card, picks a firm under Surveying firm.
2. Donor building owner Presses Save. Choosing None and saving removes the appointment.
3. Platform Records the appointment and tells the firm, which gets the building with Overview, Capture, Inventory, Testing and Requirements tabs.
4. Platform If the firm had already added the same building itself and captured in it, offers the firm to move those items into this appointment (see Move early captures into an appointment in the surveyor section).
5. Surveyor Captures items; each new item is private to the owner and the surveyor.
6. Surveyor Submits the survey, and the owner is pointed to the Recovery plan.

RULES

- Only the building's owner can appoint or remove its surveyor.
- The firm must be a surveying or deconstruction firm; anything else is refused with "Choose a surveying firm."
- Saving the same firm again changes nothing. A toast offers Undo.
- Removing the surveyor takes the building away from that firm; the survey status is kept.

NOTIFICATIONS

- The surveying firm: "[owner] appointed you to survey [building]", linking to Capture.
- The owner: captures are folded into one note, "[person] captured N items at [building]".
- The owner, if the firm moves items it captured earlier: "[firm] added N items to [building]", "Captured before your appointment. Private until you decide."
- The owner: "[firm] submitted the survey of [building]", linking to the Recovery plan.
- Removing the surveyor tells nobody; the building activity log records it.


DONOR BUILDING OWNER

Confirm or decline a building a surveyor added

Surveyor | Donor building owner

Where Requests, Buildings tab (/app/requests?tab=buildings)

A surveying firm can add a building before any appointment and ask its owner, by email, to confirm it. The owner either confirms it, which brings the building and everything captured into the owner portfolio, confirms it into a building the owner already has with the same surveyor, or says it is not theirs.



STEPS

1. Surveyor Adds a building to survey and, under Ask the owner to confirm, enters the owner's name, email and a message.
2. Platform Keeps the request waiting for that email. If an owner account already uses it, that owner is told at once; otherwise it appears once someone signs up with that email as an owner.
3. Donor building owner Opens Requests, Buildings and sees the building name, address, region, local authority, the firm that added it, how much is captured and the message.
4. Platform If the owner already has a building that looks like the same place (the same name or address, or the same postcode district with a similar name) with the same surveying firm, warns "You already have [building] with [firm] as surveyor. Confirming adds the surveyor's N items to it, so you keep one record."
5. Donor building owner Presses Confirm it is ours; or, on a match, Confirm as your [building] or Add as a separate building; or presses Not ours and, in Not your building?, adds an optional Note for the surveyor and confirms with Not ours.
6. Platform On confirm, makes the owner organisation the building owner and keeps the firm appointed as its surveyor. On Confirm as your [building], moves every item, lot, photo and testing request into the owner's record, fills its gaps (structure, programme and facts), removes the surveyor's copy and lists the request under Answered. On decline, leaves the building with the firm, unlinked.

RULES

- Only a donor building owner organisation with a member using the email named can answer; others are refused with "This request is addressed to someone else."
- A request can be answered once. A building already linked to an owner cannot be claimed again.
- Until confirmed, the building is private to the firm, nothing in it can be shared or published, and the survey cannot be submitted.
- Confirming adds the building with what was captured; nothing is shared or listed until the owner decides.
- Confirm as your [building] is offered only when the owner's matching record has the same surveyor and its survey is not submitted. With a submitted survey the card says the items cannot join it and offers Add as a separate building or Not ours.
- Moved items keep their tags unless the owner's building already has items or uses another prefix; then they continue its numbering.
- The match is worked out on the owner's side only; the surveyor never learns which buildings the owner has.
- On decline the surveyor never learns which organisation answered; the owner's note, if any, is passed on.
- Only one request can wait per building. The firm can withdraw it, or ask again after a decline.
- Answering marks the owner's notice read for the person who answered. A request that is withdrawn, merged away or deleted takes its notice off the owner's bell.


NOTIFICATIONS

- Owners using the email, when the request is made: "[firm] surveyed a building for you".
- The surveyor on confirm: "[owner] confirmed [building]. You stay appointed as its surveyor."
- The surveyor on Confirm as your [building]: "[owner] confirmed [building]. They already had it as [name], so your N items moved there. You stay appointed as its surveyor."

- The surveyor on decline: "[building] was not confirmed", with the owner's note or a prompt to check the email, never the owner name.
- The Requests item in the owner sidebar shows a count of waiting buildings and reservation requests.

LIFECYCLE

A claim waits for the owner, then ends confirmed, declined or withdrawn. After a decline or withdrawal the surveyor can ask again with a new request.




DONOR BUILDING OWNER

Read the recovery plan

Donor building owner | Platform

Where Building, Recovery plan tab (/app/buildings/:id/priorities)

Once items are captured, the platform ranks them so the owner can see which are worth taking out carefully and which should go to recycling. The plan is read only; it informs what the owner later lists.



STEPS

1. Platform Scores every item out of 100 from four parts: net value 40, avoided carbon 30, market demand 20 and ease of removal 10. These weights are placeholders.
2. Platform Works out net value as the guide price less the cost of careful removal, for the whole quantity.
3. Platform Marks an item worth recovering (reuse) unless removal would cost more than it fetches or it is unlikely to come out intact; those go to recycle (steel and curtain wall) or downcycle (everything else).
4. Platform Shows Recoverable net value (indicative), the share Held by the top three, and how many are Worth recovering.
5. Donor building owner Reads the ranking, highest score first, selects a row to see how its score is made, and checks the UK decision tree legend.
6. Donor building owner Goes to Listings to decide what to share or publish.

RULES

- Only the building owner sees the Recovery plan tab; the surveyor and contractor do not.
- The UK decision tree has five steps: reuse, upcycle, downcycle, recycle, scrap. This version assigns only reuse, downcycle and recycle.
- Figures are indicative and rule based. Nothing on this page changes a lot or what buyers see.
- With nothing captured the page shows "Nothing to rank yet".

NOTIFICATIONS

- None


DONOR BUILDING OWNER

List a lot: private, shared or published

Donor building owner | Platform

Where Building, Listings tab (/app/buildings/:id/listings), List on a private row or Edit on a shared or published one; the same editor appears in the item panel from Inventory

Each captured item is a lot that starts private. The owner decides whether to keep it private, share it in confidence with selected projects, or publish it to the marketplace, and sets an ask, a reserve and an available-from date.


Open Listings, press List or Edit
Lot reserved?
Yes
No
Locked while reserved
Private, Shared or Published?
Private
Shared or Published
Saved as private
Enter ask and reserve per unit
Prices valid?
No
Yes
Fix the prices
Publishing at a High score?
Yes
No
Blocked, share or disclose less
Press Share, Publish or Save
Matching teams told, owner unnamed

STEPS

1. Donor building owner Opens Listings, filters by All, Private, Shared or Published, and presses List on a private lot or Edit on a shared or published one. The button is greyed out on a reserved lot.
2. Donor building owner Picks Private, Shared with selected projects, or Published to the marketplace.
3. Donor building owner For shared or published, enters an Ask and a Reserve per unit, or presses Use suggested.
4. Donor building owner While the lot is still private, can set Available from; buyers see it as a month or a three-month window.
5. Platform Shows the disclosure score with this lot and a live preview of the public listing card.
6. Donor building owner Presses Publish, Share or Save. A toast offers Undo.
7. Platform Records the change and tells the teams that should know, without naming the owner or the building.

RULES


- Only the building owner can change a lot. A lot with an accepted reservation is locked: "This lot is reserved. Its visibility cannot change."
- Sharing and publishing need an ask and a reserve, both above zero, in whole price steps for the material, with the reserve not above the ask.
- Buyers never see the ask or the reserve, only the guide price range.
- The available-from date can change only while the lot is private.
- Publishing a lot that is not yet published is refused when the disclosure score with it would be High (see the disclosure workflow). Sharing is never blocked by the score.
- Private lots are seen only by the owner organisation and its surveyor. Shared lots are seen in confidence by projects the owner allows in Sharing, and by people who open a share link. Published lots are on the marketplace with the building never named.
- If the owner makes a lot private while a reservation request is waiting, the request stays open and the owner can still accept it.

NOTIFICATIONS

- Published: architects whose projects it would reach in time hear "New material for [project]", with no owner or building name.
- Shared: the architect and client of each project the owner already allows hear "New lot shared with [project]"; if they have not accepted the confidentiality terms, they are asked to first.
- Going private, or changing only the prices, tells nobody; the owner activity log records it.

LIFECYCLE

A lot moves freely between private, shared and published until the owner accepts a reservation; then it is held for that project and cannot change. A request made while the lot was shared or published can still be accepted after the lot goes private.




DONOR BUILDING OWNER

Set disclosure and read the disclosure score

Donor building owner | Platform

Where Building, Listings tab (/app/buildings/:id/listings), Disclosure settings card; photo switches in the item panel

The disclosure score estimates how easily an outsider could work out which building the published lots come from. The owner controls how precisely location and timing are shown, and the platform blocks new publishing when the score is High.


Open Listings, Disclosure settings
Choose location: region or local authority
Choose timing: three-month window or month
Platform adds up the score
Score band?
Low or Medium
High
Publishing allowed
New publishing blocked
Disclose less, or share instead

STEPS

1. Donor building owner Sets Location shown to Region or Local authority, and Timing shown to Three-month window or Month. Each change saves at once, with Undo.
2. Donor building owner Chooses, per photo in the item panel, whether it is shown on the listing.
3. Platform Adds up the score: location 5 for region or 20 for local authority; timing 5 for a window or 15 for a month; published lots 0 for one, 10 for two or three, 20 for four or more; 15 if the published steel includes both beams and columns, or three or more different section sizes; 10 if any public photo.
4. Platform Bands it Low below 25, Medium from 25, High from 40, and lists in words what an outsider could infer.
5. Donor building owner Presses Reset to go back to region, three-month window and private photos.

RULES

- Only the building owner can change disclosure settings or photo visibility.
- The score covers the building's published lots only; shared lots do not count.
- At High, publishing another lot is refused: "Publishing at this disclosure level lets an outsider narrow down the building. Reduce what is disclosed first." Lots already published stay published.
- The score weights and bands are placeholders.
- Changing the location or timing setting is never refused, even when it lifts the score to High; only publishing another lot is blocked.

NOTIFICATIONS

- None


DONOR BUILDING OWNER

Grant or revoke sharing with projects

Donor building owner | Architect | Client

Where Building, Sharing tab (/app/buildings/:id/sharing), Shared with projects list

The owner chooses which projects on the platform may see the lots it shares in confidence. Each project appears only as a blind line, and the choice applies to every building the owner has.



STEPS

1. Donor building owner Opens Sharing and reads each project as kind of team, project type, region and when materials are needed, never its name.
2. Donor building owner Turns the switch on or off for a project. A toast offers Undo.
3. Platform Records the choice for all the owner's buildings and shows Lots shared and Projects allowed.
4. Architect or client Accepts the confidentiality terms once for the project, then sees the shared lots in the Marketplace under Shared with you.

RULES

- Only a donor building owner can grant or revoke. Its own New projects, and any project where it is client or architect, are not listed and are refused.
- Which lots are shared is set per lot in Listings; this list decides only which projects may see them.
- A project sees shared lots only after its architect or client accepts the confidentiality terms.
- Both sides stay anonymous: names are exchanged only when the owner accepts a reservation.
- Revoking takes effect at once.

NOTIFICATIONS

- On granting, when the owner has lots shared: the project's architect and client hear "N lots shared with [project]", shared in confidence by a donor building owner.
- Revoking tells nobody; the owner activity log records it as a blind line.


DONOR BUILDING OWNER

Create, copy and revoke a share link

Donor building owner

Where Building, Sharing tab (/app/buildings/:id/sharing), Share by link card

The owner can send a link to chosen shared lots of one building to anyone on Tallyard, for example someone outside the projects it already shares with. The owner sees how many organisations opened it, by type only, and can revoke it at any time.



STEPS

1. Donor building owner Presses Create link, ticks the shared lots to include (or Select all) and optionally gives it a Name for their own reference.
2. Platform Creates the link and copies its address; it is listed with its lots, who created it and when.
3. Donor building owner Uses Copy link to copy it again and Preview to see it as openers do.
4. Platform Shows "Not opened yet" or, for example, "Opened by 3 organisations (2 architecture practices, 1 developer or client)".
5. Donor building owner Presses Revoke and confirms Revoke link to withdraw it.

RULES


- Only the building owner can create or revoke a link.
- A link can hold only lots that are shared with selected projects at the time; private, published or reserved lots cannot be added.
- If a lot in the link is later made private, it drops out of the link and the row reads, for example, "2 of 3 lots still shared". A lot later published stays in the link. A reserved lot is hidden from people who open the link.
- The owner never learns who opened a link, only the type of each organisation. Each organisation counts once.
- The name is never shown to people who open the link.
- Create link shows only while the building has a shared lot that is not reserved; otherwise the card says Share lots first. Creating a link offers Undo; revoking does not.
- Links work only in this browser while the sandbox lasts.

NOTIFICATIONS

- The owner, on each organisation's first open: "Your share link was opened. An architecture practice opened [name]", folded into a count per link.
- Everyone who opened the link, on revoke: "A shared link was withdrawn. Any you saved show as no longer shared."

LIFECYCLE

A link is active from creation until the owner revokes it; a revoked link reads as no longer active for everyone.




DONOR BUILDING OWNER

What a person who opens a share link sees

Anyone signed in (architect, client, consultant, surveyor or another owner) | Donor building owner

Where Link page (/app/links/:linkId)

Whoever receives a share link opens it while signed in, accepts the confidentiality terms, and then sees the lots as anonymous listings. Their projects can then shortlist and reserve those lots like any other.



STEPS

1. Opener Opens the link while signed in and reads "A donor building owner shared N lots with you".
2. Opener Presses Accept and view, agreeing not to pass the details on, or Not now.
3. Platform Records the open for the organisation and tells the owner its type only.
4. Opener Sees each lot as a card: title, kind of material, quantity, availability window, region or local authority, collection, avoided carbon and sustainability band.
5. Opener Architects, clients, consultants and owners with a New project open the full material page; architects can save lots to a shortlist. Others open a facts panel.

RULES

- Openers never see the building name, address, owner, item tag, private photos, ask or reserve.
- Terms are accepted once per organisation. The owner organisation itself sees a preview and is never counted as an opener.
- Lots made private, and lots reserved by any project, drop out; lots later published stay. With none left the page says "No lots to show".
- A revoked link reads "This link is no longer active", and anything saved from it shows as no longer shared. A link this browser has never seen reads "This link is not in this sandbox" and explains that sandbox links open only in the browser where they were made.
- Projects where the opener's organisation is architect or client can see the linked lots, without the owner allowing them in Sharing and without the project's own confidentiality terms.

NOTIFICATIONS

- The owner: "Your share link was opened", with the type of organisation, folded into a count.
- The opener, if the owner later revokes: "A shared link was withdrawn".


DONOR BUILDING OWNER

Accept or decline a reservation request

Client | Donor building owner (as seller) | Architect (told)

Where Requests, Reservations tab (/app/requests), Awaiting you and Decided

When a client asks to reserve one of the owner's shared or published lots, the owner sees a blind request and accepts or declines it. Accepting holds the lot for that project, declines any competing requests and exchanges names and contacts.


Client asks to reserve a lot
Owner told, buyer shown as a blind line
Owner reviews it in Requests
Accept?
No
Yes
Press Decline, optional reason
Client told, seller stays unnamed
Press Accept, then Accept and reserve
Lot held for this project
Competing requests declined
Names and contacts exchanged
Agree terms directly with the buyer

STEPS

1. Client Requests a reservation of an approved material, with a message.
2. Platform Tells the owner, describing the buyer only as kind of team, project type, region and when it is needed.
3. Donor building owner Reviews the request with its own indicative figures at the guide price, and a badge if other requests wait for the same lot.
4. Donor building owner Presses Decline and confirms, with an optional Reason, or presses Accept and confirms Accept and reserve, with an optional Note for the buyer. A toast offers Undo.
5. Platform On accept, holds the lot for the project, stops offering it, declines other waiting requests with "Reserved for another buyer", and shows each side the other's organisation, contact and email.
6. Donor building owner Agrees the terms directly with the buyer, outside the platform.

RULES


- Only the owner of the lot's building can decide. A request can be decided once.
- Only one request per lot can be accepted; accepting when another is already accepted is refused with "Reserved for another buyer."
- Before acceptance neither side learns who the other is. After it, the owner sees the buyer's organisation, contact, email and message, and the client sees the seller's.
- The architect and the consultant never see who the seller is.
- A reserved lot is locked: its visibility, prices and date cannot change and it cannot go in a share link.
- The client can withdraw a request while it waits; it then leaves the owner's list. Decided keeps accepted and declined requests only.
- Before acceptance the owner does not see the buyer's message; the screen says it is shared when the owner accepts.

NOTIFICATIONS

- The owner, on a new request: "Reservation request for [tag]" with the blind buyer line; on withdrawal: "Request withdrawn for [tag]".
- The client, on accept: "[seller] accepted your reservation" with the seller contact and email. Any note for the buyer shows on the client's Reservations tab as the seller's note.
- The architect, on accept: "[material] is reserved", without the seller name.
- The client, on decline: "Reservation declined: [material]", with "The seller's note: [reason]" or "The seller declined this request."
- Clients of competing requests: "Reservation declined: [material]", with "Reserved for another buyer."
- On a decline the architect and consultant are not notified; their project activity shows that the seller declined.

LIFECYCLE

A request waits for the owner, then ends reserved, declined (by the owner or because another buyer was accepted) or withdrawn by the client.




DONOR BUILDING OWNER

Request testing of items

Donor building owner | Surveyor

Where Building, Testing tab (/app/buildings/:id/testing), button Request testing

The owner, or the surveyor, asks one of the listed testing companies to inspect or test chosen items, with a preferred date and a message, then records the visit and the results. Either side can view, copy or download the request sheet the company would receive. Results update each item's test status, and steel grade, which buyers see on listings.


Open Testing, press Request testing
Choose the items
Choose tests that suit them
Choose a company, date and message
Press Send request
Recorded, other side told
View request: copy or download
Visit going ahead?
No
Yes
Press Cancel
Record booking with visit date
Record results, one per item
Test status shows on listings

STEPS

1. Donor building owner Presses Request testing, ticks the items, then the tests offered for those kinds of item.
2. Donor building owner Picks a Company that offers every chosen test in the building's region, optionally a Preferred from date and a Message, and presses Send request.
3. Platform Records the request as Sent and tells the surveyor. The card shows Preferred from [date] and the message. Nothing is sent to the company in the sandbox; the confirmation names who was told, points to View request and offers Undo.
4. Owner or surveyor Presses View request to open "Request to [company]": the sheet the company would receive, with who it is to and from, the building, each item with its size, quantity and location, the tests, the preferred date and the message; presses Copy text or Download .txt.
5. Owner or surveyor Presses Record booking and saves the visit date the company confirmed; Change booking moves it.
6. Owner or surveyor Presses Record results and saves one result per item, with a steel grade where a grade test was done.
7. Owner or surveyor Can instead press Cancel and confirm Cancel request, with an optional reason, until results are recorded.
8. Platform Updates each item's test status and grade, which show on any listing.

RULES


- Only the owner or the appointed surveyor can request, book, record or cancel; a contractor alone cannot.
- At least one item and one test are needed; the company must offer every chosen test in the region.
- The preferred date and the visit date must be today or later. With no preferred date the sheet reads "Preferred from: no preference".
- The request sheet is marked Simulated: "A sample request. No testing company receives it." Both sides can view it on every request, whatever its status.
- Results need one line per item. Items whose lots are reserved cannot change.
- Only the owner records results for items that are shared or published, as only the owner changes what a listing says.
- A request can be cancelled only before results are recorded.

NOTIFICATIONS

- The surveyor, when the owner acts (or the owner, when the surveyor acts): "[person] asked [company] to test N items", "Testing visit booked", "Test results recorded".
- Cancelling tells nobody; the building activity log records it.

LIFECYCLE

A testing request is sent, then booked, then has results; it can be cancelled until results are in.




DONOR BUILDING OWNER

Appoint a contractor and apply their dates

Donor building owner | Surveyor | Deconstruction contractor | Platform

Where Building, Overview (/app/buildings/:id), Deconstruction contractor card; then Inventory (/app/buildings/:id/inventory)

The owner invites a deconstruction contractor to say when each item is expected to come out, choosing a firm already on Tallyard or inviting one by email. A new contractor never inherits the previous one's dates. The contractor's dates stay apart from what buyers see until the owner applies them to private lots.


Open Overview, contractor card
Firm in the list?
No
Invite by email, Send invite
Yes
Firm on Tallyard with that email?
No
Yes
Invite waits on the building
Choose the firm, press Save
Firm appointed at once
Firm joins with that email
Previous contractor's dates cleared
Contractor told to set dates
Contractor sets a month per item
Owner compares, Use contractor dates
Lot private and not reserved?
Yes
No
Lot date updated
Skipped, make private to change

STEPS

1. Donor building owner In the Deconstruction contractor card, picks a firm under Invite a contractor (or Change contractor) and presses Save. Choosing None removes it.
2. Donor building owner For a firm not in the list, presses Invite by email, enters the Contractor's email and presses Send invite.
3. Platform If a surveying or deconstruction firm on Tallyard uses that email, appoints it at once and names it. Otherwise the card shows Invited, Waiting for [email], with Withdraw, and the firm becomes the contractor when it signs up as a surveying or deconstruction firm, or joins one by invite, with that email.
4. Platform When the contractor changes or is removed, clears every date the previous contractor set and says so, for example "Fennick Dismantling's 5 dates were cleared."; Undo restores them. A waiting invite says the dates are cleared when the new firm joins.
5. Platform Tells the firm, which gets the building with only Overview and Availability tabs.
6. Deconstruction contractor On Availability, sets or clears the month each item is expected to come out.
7. Platform Stores each date as the dismantling start if it falls in that month, otherwise the first of the month, and tells the owner.
8. Donor building owner Sees the contractor date beside each lot in Inventory, and presses Use contractor dates (N) for all, or Use contractor date in one item panel.
9. Platform Updates private, unreserved lots and reports how many were skipped because they are shared, published or reserved.

RULES

- The owner or the surveyor can invite, change or remove a contractor. A firm chosen from the list must be a surveying or deconstruction firm.
- An invite by email never reveals who is on Tallyard: an email at an organisation of another kind is treated like an unknown one and simply waits. Only a surveying or deconstruction firm joining with that email takes it up.
- One invite waits per building. Choosing a firm from the list replaces it, and Withdraw cancels it. Nothing is emailed from the sandbox.
- A new contractor never inherits the previous contractor's dates.
- Only the appointed contractor can set these dates. A contractor never sees lots, prices or buyers, and cannot capture, test or open the building's requirements.
- Contractor dates never reach buyers directly; only the owner changes a lot's date, and only while the lot is private.
- A firm that is also the surveyor gets the Availability tab beside its other tabs.

NOTIFICATIONS

- The contractor: "[owner] invited you to set availability dates at [building]", also when it joins from an email invite.
- When a firm joins from an email invite, the side that invited it and the owner: "[firm] joined and can set dates at [building]", with "They accepted your invitation." and any dates that were cleared.
- The owner: "[contractor] set dates for N items at [building]. Review them in the inventory and apply the ones you agree with", folded per day.
- The owner, if the surveyor invited the contractor: "[surveyor] invited [contractor] to [building]".
- Removing the contractor, or recording or withdrawing an invite by email, tells nobody; the building activity log records it.


DONOR BUILDING OWNER

Track requirements before demolition

Donor building owner | Surveyor | Platform

Where Building, Requirements tab (/app/buildings/:id/requirements); the Requirements line on the owner Home building card and on the surveyor Home building row

Each donor building tracks the planning requirements that apply before it comes down at its location: a national demolition notice, in London the pre-demolition audit and diversion target, and the local authority's own policy. The owner and the surveyor keep each one's status and evidence current.


Open the building's Requirements tab
What applies at this place listed
What needs updating?
Status
Choose a status
Surveyor marked at risk or ready?
Yes
No
Owner is notified
Evidence
Add a note of evidence
Not started becomes In progress
Saved and logged
At risk counted on homes and the tab

STEPS

1. Platform Picks the requirements from the building's region and local authority: National (England, Wales or Scotland, before demolition), the London Plan 2021 and GLA guidance for a London region, and the local authority's plan when one is set. An authority with no written summary gets a placeholder marked Not yet summarised.
2. Owner or surveyor Opens the Requirements tab from the building or the sidebar, or follows the line on the owner's building card or the surveyor's building row, for example "Requirements 1 of 4 ready, 1 at risk".
3. Owner or surveyor Sets a status: Not started, In progress, At risk, Evidence ready or Not applicable.
4. Owner or surveyor Adds evidence as a note; the first evidence moves a Not started requirement to In progress.
5. Platform Logs each change in the building activity for the owner and the surveyor, and counts the requirements at risk as a badge on the tab and its sidebar item.
6. Donor building owner When moving the building to another region or local authority in Edit details, reads how many requirements stop applying and how many more are tracked; statuses and evidence stay with the ones that still apply.

RULES

- Only the owner and the surveyor of the building can open the tab and change it. A firm that is only the deconstruction contractor cannot open it, nor can any buyer.
- Requirement activity reaches the owner and the surveyor only, never the contractor. A firm that both surveys and dismantles hears as the surveyor.
- Only the person who added a piece of evidence can remove it. Each change offers Undo.
- Not applicable requirements are left out of the total and the ready share.
- Every entry is an indicative summary to check against the published documents; a placeholder summarises nothing yet.
- Nothing on this tab reaches a listing or a buyer.

NOTIFICATIONS

- The owner, when the surveyor marks a requirement At risk or Evidence ready: "[requirement] is [status] on [building]", "Marked by [name], [firm]."
- Every other change, and every change the owner makes: no notification, an entry in the building activity only.


DONOR BUILDING OWNER

The guard on reserving your own lots

Architect | Donor building owner (as client of a New project)

Where Project, Reservations tab (/app/projects/:id/reservations), Request reservation

An owner that is also the client of a New project may come across its own lots, for example published ones its architect shortlists. The platform refuses a reservation of a lot from the owner's own building, because reserving is for buying from other sellers.


Architect shortlists a lot
Owner approves it
Owner presses Request reservation
Owner presses Send request
Lot from the owner's own building?
Yes
No
Refused: this lot is yours
Request sent to the seller
Seller accepts or declines

STEPS

1. Architect Shortlists a material for the New project and sends it for approval.
2. Donor building owner Approves it on the Approvals tab, then on Reservations presses Request reservation and Send request.
3. Platform Checks who owns the lot's building. If it is the project's own client, refuses with "This lot is yours. Allocate it directly; reserving is for other sellers."
4. Platform Otherwise sends a blind request to the seller, as for any client.

RULES

- A New project cannot reserve a lot from a building its own client owns.
- Nothing stops the architect shortlisting, or the owner approving, its own lots; the refusal comes only at Send request.
- The owner never sees its own lots in the Marketplace, search or as material pages, but its architect can. The owner cannot allow its own projects in Sharing, and opening its own share link does not count. Its shared lots still reach its New project if that project's architect opens one of the owner's share links; published lots always do.
- Allocating your own materials directly is not in this version.

NOTIFICATIONS

- None; the refusal is shown on screen.

SECTION

Surveyor and deconstruction contractor

Surveyors and deconstruction contractors sign up with the same kind of workspace, a surveying or deconstruction firm. As surveyor, the firm walks a donor building and records what it holds, item by item, then hands the survey to the owner; it can start before any appointment, ask the owner to confirm the building, and move what it captured early into the building once the owner appoints it. It or the owner can ask a testing company to test items, and both keep the requirements that apply before demolition. As deconstruction contractor, invited per building from a list or by email, the firm says when each item is expected to come out, and the owner decides whether to use those dates.


SURVEYOR AND DECONSTRUCTION CONTRACTOR

Capture an item from the Capture page

Surveyor | Donor building owner | Platform

Where Capture in the surveyor's sidebar or the Capture button on the surveyor's Home (/app/capture); the chosen building is kept in the address as ?building=

The quickest way to record what a building holds while walking round it on a phone. The person picks the building at the top, describes the item in their own words, and the capture assist fills the fields; they grade it, say when it should come out, add photos and save.


Open Capture and choose the building
Describe what you see
Capture assist fills the fields
Check family, size and quantity
Grade condition and recoverability
Set expected month and add photos
All required fields filled?
No
Yes
Missing fields are highlighted
Item saved as private
Owner told when a surveyor captures
Which button?
Save and capture another
Save
Form clears for the next item
Item opens in the inventory

STEPS

1. Surveyor Opens Capture from the sidebar or the Capture button on Home; the page opens on the building last chosen, or else the one with the latest capture.
2. Surveyor Chooses the building in the Building list, which groups buildings by client with the firm's Not yet linked buildings last.
3. Surveyor Types or dictates the item in Describe what you see, for example 48 no. UB 457x191x67, 7.5 m long, bolted.
4. Platform The capture assist reads the words and fills the family, size, quantity and a suggested recoverability, marks each such field Filled and lists what is still to fill.
5. Surveyor Corrects any field; a field the person has changed keeps their value even if the description changes.
6. Surveyor Chooses Condition (A Good, B Fair, C Poor) and Recoverability (A Comes out intact, B With care, C Unlikely intact).
7. Surveyor Sets Expected to come out, which starts at the dismantling month in the programme (or this month if there is none), and optionally the location and notes.
8. Surveyor Adds photos with Take photo or Add another.
9. Surveyor Presses Save and capture another, or Save.
10. Platform Records the item with its tag and a private lot, marks the survey In progress if it had not started, and shows the item under Recently captured. Save opens the item in the building's Inventory instead.

RULES

- Only people on the owner or surveyor side of a building can capture in it. A firm that is only the deconstruction contractor cannot, and those buildings are not offered in the list. A firm that works only as a contractor has no Capture item in its sidebar and reads Deconstruction contractor in its organisation menu.
- Architects, clients and consultants cannot open the Capture page.
- An owner may also use this page, but only the surveyor has a link to it in the sidebar. For an owner, Add building on this page adds one of its own donor buildings.
- Family, size, quantity, condition, recoverability and the expected month are required. A steel section must be in the section table, and every size and quantity must be a number above zero.
- The capture assist is rule-based reading of the words typed. It suggests; the person can change every field.
- Every new item starts private, with a private lot. Photos are kept private and the owner decides what is shown.
- The expected month is the surveyor's estimate and is labelled 'Expected by the surveyor. The owner sets the date when listing.'
- Save and capture another keeps the location and the expected month for the next item. Switching building keeps what was typed.
- Once saved, an item's family, size and quantity cannot be changed and there is no delete, so a mistake is put right with Undo on the confirmation message straight after saving.
- If the person has no building yet, the page says 'Add the building you are in' and offers Add building (see Add a building before any appointment).

NOTIFICATIONS

- When a surveyor captures in a building linked to its owner, the owner is told '[person] captured [tag] at [building]'. Further captures by the same person at the same building on the same day are added to that one notice as a running count.

- When the owner captures, nobody is notified. In a building not yet linked to an owner, nobody is notified.


SURVEYOR AND DECONSTRUCTION CONTRACTOR

Capture from a building's Capture tab

Surveyor | Donor building owner | Platform

Where Building, Capture tab (/app/buildings/:id/capture); also the Capture item button in the building header and Capture items on the Overview's Survey card

The same capture form as the Capture page, opened from inside one building with no building list. It sits next to the recently captured items and the survey bar, so the surveyor can capture, check progress and submit from one place.


Open the building from the sidebar
Open the Capture tab
Fill in the capture form
Item saved as private
Recently captured list updates
More items to record?
Yes
No
Review items in the Inventory tab
Submit the survey from the survey bar

STEPS

1. Surveyor Opens the building under its client (or under Not yet linked) in the sidebar and chooses the Capture tab.
2. Surveyor Fills in the form exactly as on the Capture page: describe, check the filled fields, grade, set the month, add photos.
3. Platform Saves the item as private and adds it to Recently captured, which shows the last five items with a link to the Inventory.
4. Surveyor Opens an item in the Inventory to correct its condition, recoverability, expected month, location, notes or photos.
5. Surveyor Uses the survey bar beside the form to submit the survey when the walk-round is done.

RULES

- A surveyor's building has the tabs Overview, Capture, Inventory, Testing and Requirements, plus Availability when the same firm is also its deconstruction contractor. Every side on the building can open its Activity page from the Overview.
- The Capture, Inventory, Testing and Requirements tabs are refused to a firm that is only the deconstruction contractor.
- The owner has no Capture tab, but can capture in its own building from Capture the first item on an empty Inventory, or Capture on the Overview while nothing is captured.
- Condition, recoverability and the expected month can be corrected only while the item's lot is private. Once it is shared or published they are fixed.
- Location, notes and photos can be corrected at any time by the owner or the surveyor. The family, size and quantity cannot be changed after saving.

NOTIFICATIONS

- The same as the Capture page: the owner is told of each surveyor capture, grouped per person, building and day. Corrections to an item notify nobody; they are recorded in the activity log.


SURVEYOR AND DECONSTRUCTION CONTRACTOR

Add a building before any appointment and ask the owner to confirm it

Surveyor | Donor building owner | Platform

Where Add building in the surveyor's sidebar or on Home (/app/buildings?new=1), or on the Capture page; then the building's Overview, Owner card (/app/buildings/:id)

A surveying firm can start a survey before any owner has appointed it. It adds the building, captures freely, and asks the owner, by email address, to confirm the building is theirs. Until the owner confirms, the building is private to the firm and some steps are blocked.


Press Add building
Enter building details and programme
Owner email given now?
No
Yes
Building saved as Not linked yet
Press Ask the owner
Surveyor withdraws
Request waits for the owner
Capture items while waiting
Owner answers?
Ask again
Confirms
Not ours
Linked, survey can be submitted
Shown as Not confirmed
Ask again or delete?
Delete building
Building and its items removed

STEPS

1. Surveyor Presses Add building in the sidebar, on Home or on the Capture page, and fills in Add a building to survey: name, address and region are required; the local authority (from one list grouped by region, which sets the region), the building facts, structure and programme dates are optional.
2. Surveyor Optionally fills in Ask the owner to confirm in the same dialog: the owner's name, email and a message.
3. Platform Creates the building, private to the firm, lists it in the sidebar under Not yet linked and on Home with the steps Added, Owner confirms, Capturing and Submitted.
4. Surveyor If no email was given, presses Ask the owner (on the Owner card in Overview, in the building header or on the Buildings list), enters the owner's email and presses Send request.
5. Platform Records the request as Waiting for the owner and notifies any donor building owner organisation with a member using that email.
6. Surveyor Captures items as normal while the request waits, and can correct the building's details with Edit details; a waiting request can be withdrawn with Withdraw.
7. Surveyor If the owner says Not ours, sees Not confirmed with the owner's note, and can press Ask again or Delete building.
8. Surveyor If the owner instead appoints the firm to its own record of the same building, moves the items there (see Move early captures into an appointment).

RULES


- Only a surveying or deconstruction firm can add a building this way, and only the firm that added it can ask its owner, withdraw the request, edit its details or delete the building.
- Only one request can wait at a time; withdraw it before asking a different email.
- Until the owner confirms, the building is private to the firm: nothing in it can be shared or published, because only an owner has the Recovery plan, Listings and Sharing tabs.
- Until the owner confirms, the survey cannot be submitted. The Submit survey button is disabled with 'Link the building to its owner first.'
- Capture, testing requests, requirement tracking and inviting a deconstruction contractor still work while the building waits.
- If no owner account uses the email yet, the request waits and appears once someone signs up with that email as a donor building owner.
- Delete building is on the Owner card whenever the building is not linked. It removes the building with its items, photos, lots and testing requests, withdraws any waiting request, and cannot be undone. A building linked to its owner cannot be deleted.
- The breadcrumb reads Appointments, then Not yet linked, then the building.
- Nothing is emailed in the sandbox; the owner sees the request when they sign in.

NOTIFICATIONS

- The owner organisation is told '[firm] surveyed a building for you', which opens Requests, Buildings tab. Each Ask again sends a new notice.
- Withdrawing a request, deleting the building or moving it into an appointment notifies nobody about the request, and takes the owner's notice of it off their bell; it is recorded in the firm's activity log.

LIFECYCLE

Where a surveyor's own building stands with its owner, as the Owner card's label shows it. Once linked or moved into an appointment it cannot go back, and it can no longer be deleted.




SURVEYOR AND DECONSTRUCTION CONTRACTOR

Owner confirms or declines a surveyed building

Donor building owner | Surveyor | Platform

Where Requests, Buildings tab (/app/requests?tab=buildings)

The owner's side of the building request. The owner sees which firm surveyed which building and how many items were captured, and either confirms it is theirs, confirms it into a building they already have with the same surveyor, or says it is not.



STEPS

1. Donor building owner Opens Requests, which shows a badge for waiting requests, and the Buildings tab.
2. Donor building owner Reads the building, its address, the firm that added it, the message, and how many items were captured so far.
3. Platform If the owner already has a building that looks like the same place with the same surveying firm, warns "You may already have [building]" and shows the owner's record.
4. Donor building owner Presses Confirm it is ours; on a match, Confirm as your [building] or Add as a separate building; or Not ours, adding an optional note for the surveyor before pressing Not ours again.
5. Platform On confirm, links the building to the owner, adds it to their donor buildings with everything captured, keeps the firm appointed as surveyor, and opens the building. On Confirm as your [building], moves the surveyor's items, lots, photos and testing requests into the owner's record and removes the surveyor's copy.
6. Platform On decline, tells the surveyor the building was not confirmed, without naming the organisation that answered, and moves the request to Answered.

RULES

- Only a donor building owner organisation with a member using the email named in the request can answer it.
- A request that was withdrawn or already answered cannot be answered again.
- Confirming shares or lists nothing; every item stays private until the owner decides.
- Confirm as your [building] needs the owner's record to have the same surveyor and a survey not yet submitted.
- The surveyor never learns which organisation declined, nor which buildings the owner already has.

NOTIFICATIONS

- On confirm the surveyor is told '[owner] confirmed [building]. It is in their portfolio now. You stay appointed as its surveyor.'
- On Confirm as your [building] the surveyor is told '[owner] confirmed [building]. They already had it as [name], so your N items moved there. You stay appointed as its surveyor.'
- On decline the surveyor is told '[building] was not confirmed', with the owner's note, or else a prompt to check the email address and ask again.


SURVEYOR AND DECONSTRUCTION CONTRACTOR

Move early captures into an appointment

Surveyor | Donor building owner | Platform

Where Surveyor Home and Appointments (/app/buildings), under the appointed building; the top of the unlinked building's Overview (/app/buildings/:id); Move into an appointment on its Owner card

A surveyor who added a building herself and captured in it may later be appointed by its owner to the owner's own record of the same building. Rather than keep two records, she moves what she captured into the appointment. The owner is told, and the items stay private until the owner decides.


Owner appoints the firm to a building
Firm added the same building itself?
Yes
Not matched
Prompt: this building is here twice
Move the items?
Move into an appointment, choose a building
Keep separate
Move items here
Prompt hidden for this person
Appointment survey submitted?
Yes
No
Refused, nothing more can join
Items, lots, photos and tests move
Firm's own record removed
Owner told, items stay private

STEPS

1. Donor building owner Appoints the surveying firm to one of its buildings.
2. Platform Pairs each building the firm added itself, not yet linked to an owner, with an appointed building that looks like the same place: the same name or address once spaces and punctuation are ignored, or the same postcode district with a similar name.
3. Surveyor Sees "[building] is here twice" under the appointment on Home and on Appointments, with "You added [building] yourself before [owner] appointed you. Move its N captured items here?", and on the unlinked building's Overview "Merge into [building] for [owner]".
4. Surveyor Presses Move items here (Move into their [building] on the unlinked Overview), or Keep separate to hide the prompt.
5. Surveyor Where nothing was matched, presses Move into an appointment on the unlinked building's Owner card, picks the Appointed building and presses Move items.
6. Platform Moves every item with its lot, photos and testing requests into the appointed building, fills the appointed record's gaps (structure, programme dates, year built, storeys, floor area), keeps the further survey status, withdraws any waiting request to confirm the building, moves activity and notification links, removes the firm's own record and opens the appointed building.

RULES

- Only the firm that added the unlinked building can move it, and only into a building an owner appointed that firm to survey.
- An appointment whose survey is already submitted is never offered and is refused: "The survey of that building is already submitted, so nothing more can be added to it."
- Items keep their tags unless the appointed building already has items or uses another prefix; then they continue its numbering, so no tag repeats.
- The matching is done for the surveyor only; nothing about it reaches the owner until items are moved.
- Keep separate is remembered for that person in this browser. The confirmation offers Undo.
- Moved items stay private, with private lots, until the owner decides.

NOTIFICATIONS

- The owner, when items move: "[firm] added N items to [building]", "Captured before your appointment. Private until you decide." It links to the Inventory.
- A waiting request to confirm the moved building is withdrawn and its notice is taken off the owner's bell.
- Both organisations' activity records that the firm moved N items captured earlier into the building.


SURVEYOR AND DECONSTRUCTION CONTRACTOR

Submit the survey to the owner

Surveyor | Donor building owner | Platform

Where The survey bar on the building's Capture tab and Inventory, and on the Capture page (/app/buildings/:id/capture, /app/buildings/:id/inventory, /app/capture)

When the walk-round is done the surveyor hands the survey to the building's owner, who is told at once and can start deciding what to recover. The survey can be reopened later to mark it in progress again.


Capture at least one item
Survey bar appears
Building linked to its owner?
No
Yes
Submit survey stays disabled
Press Submit survey and confirm
Survey marked Submitted
Owner told to review the inventory
Surveyor may press Reopen survey
Owner plans recovery
Survey back to In progress

STEPS

1. Surveyor Once at least one item is captured, sees the survey bar with the number of items captured and presses Submit survey.
2. Surveyor Confirms in the dialog 'Submit the survey to [owner]?'.
3. Platform Marks the survey Submitted with the date, records who surveyed the building, and tells the owner.
4. Donor building owner Opens the notice, which leads to the building's Recovery plan, and reviews what was captured.
5. Surveyor Can keep capturing without reopening; new items still reach the owner. Presses Reopen survey to mark it in progress again, then submits again later.

RULES


- Only the building's surveyor can submit or reopen the survey; the owner and a firm that is only the contractor cannot.
- Refused when the building is not yet linked to its owner, when nothing has been captured, or when the survey is already submitted.
- The survey bar appears only to the surveyor and only once at least one item is captured.

NOTIFICATIONS

- The owner is told '[firm] submitted the survey of [building]' with the item count and who captured them, linking to the Recovery plan.
- Reopening notifies nobody; it is recorded in the activity log.

LIFECYCLE

The survey status shown on the building, the Capture page and the surveyor's Home.




SURVEYOR AND DECONSTRUCTION CONTRACTOR

Request testing and record the booking and results

Surveyor | Donor building owner | Platform

Where Building, Testing tab (/app/buildings/:id/testing); also Request testing on the Overview's Testing card and on an item in the Inventory

The surveyor or the owner asks one of the listed testing companies to inspect or test chosen items, with a preferred date and a message, then records the visit date and the results the company reports. Either side can view, copy or download the request sheet the company would receive. Results update each item's test status, and its steel grade where tested, which buyers see on listings.


Surveyor or owner presses Request testing
Choose items, then tests
One company offers every test?
No
Yes
Send two separate requests
Recorded as Sent, other side told
View request, copy or download
Cancel
Record booking with the visit date
Cancel
Record results, one per item
Request cancelled
Any item's lot reserved?
Yes
No
Refused: a reserved lot cannot change
Surveyor, and a lot shared or published?
Yes
No
Only the owner can record these
Test status and grade updated
Results recorded, other side told

STEPS

1. Surveyor Opens the Testing tab and presses Request testing, or presses Request testing on an item, which starts with that item chosen. The owner can do the same.
2. Surveyor Chooses the items, then the tests that suit those items, then a company that offers all of them in the building's region; adds an optional preferred date and message; presses Send request.
3. Platform Records the request as Sent and tells the other side of the building. The card shows Preferred from [date] and the message. Nothing is sent to the company in the sandbox: the dialog footnote and the confirmation say who is told, or that the request is recorded here only, and the confirmation offers Undo.
4. Surveyor Presses View request to open "Request to [company]", the sheet the company would receive: to and from, the building, each item with its size, quantity and location, the tests, the preferred date and the message; presses Copy text or Download .txt to send it by email herself.
5. Surveyor When the company confirms a visit, presses Record booking, enters the visit date and a note, and presses Save booking. Change booking moves the date.
6. Surveyor After the visit, presses Record results and gives one result per item: Inspected or Tested, a steel grade (S275, S355 or Unknown) where a grade test was chosen, and a note; presses Save results.
7. Platform Writes each item's test status and any grade given, marks the request Results recorded, and tells the other side.
8. Surveyor Can press Cancel, then Cancel request, on a request that has no results yet.

RULES

- Only the owner or the surveyor of the building can request, book, record or cancel. A firm that is only the deconstruction contractor cannot open Testing.
- At least one item and one test are required. Tests offered follow the families of the chosen items, and the company must offer every chosen test in the building's region. If no one company does, the dialog says 'No one company offers all of these tests. Send two requests.'
- The preferred date and the visit date must be today or later.
- The request sheet is marked Simulated: 'A sample request. No testing company receives it.' The preferred date reads the same on screen and in the text, or 'Preferred from: no preference'.
- Results can be recorded only once a visit is booked, and every item in the request needs a result. A visual and dimensional survey alone gives Inspected only; a grade can be given only for steel sections with a coupon or hardness test.
- Results cannot be recorded when any item's lot is reserved by a buyer.
- If any item's lot is shared or published, only the owner can record the results, because only the owner changes what a listing says. The surveyor sees 'The owner records this one.' and Save results is disabled.
- A request with results, or one already cancelled, cannot change.


NOTIFICATIONS

- On a new request, the other side is told '[person] asked [company] to test N items at [building]'. A surveyor's request tells the owner; an owner's request tells the surveyor. If there is no one on the other side, such as a building not yet linked to its owner, nobody is told.
- On a booking, the other side is told 'Testing visit booked at [building]' with the company and date.
- On results, the other side is told 'Test results recorded at [building]'.

- Cancelling notifies nobody; it is recorded in the activity log.

LIFECYCLE

A testing request moves from Sent to Visit booked to Results recorded; it can be cancelled until results are in.




SURVEYOR AND DECONSTRUCTION CONTRACTOR

Deconstruction contractor sets availability dates

Donor building owner | Surveyor | Deconstruction contractor | Platform

Where Owner or surveyor: building Overview, Deconstruction contractor card (/app/buildings/:id). Contractor: Availability tab (/app/buildings/:id/availability), also Set dates in the building header, on the surveyor Home row and on Appointments

The owner or the surveyor invites a deconstruction contractor to a building, from the list or by email. The contractor then says, item by item, the month it expects each item to come out. These dates stay apart from the surveyor's estimate and go to the owner, never to buyers. A new contractor starts with no dates.


Owner or surveyor invites a contractor
Chosen from the list?
By email
Invite waits until the firm joins
Yes
Contractor is told
Contractor opens the Availability tab
Reads surveyor estimate per item
Sets months, or fills blanks from programme
Presses Save dates
Owner told dates were set
Owner reviews them in the inventory

STEPS

1. Donor building owner On the building's Overview, in the Deconstruction contractor card, chooses a firm under Invite a contractor and presses Save, or presses Invite by email for a firm not in the list. The surveyor can do the same, and either can change or remove the contractor there.
2. Platform Appoints the contractor and tells them; the building appears in their sidebar under its owner with the Overview and Availability tabs. An email that no surveying or deconstruction firm uses yet waits on the building until such a firm joins with it.
3. Platform When the contractor changes or is removed, clears the previous contractor's dates and says how many, for example "Fennick Dismantling's 5 dates were cleared."
4. Deconstruction contractor Opens Availability, from the notice, the Set dates button in the building header, on Home or on Appointments, or the Overview's Your dates card, and sees the owner's programme and each item with its quantity, location and what the surveyor expects.
5. Deconstruction contractor Presses Set month on an item and picks the month, clears a month with Clear the month, or presses Fill blanks from the programme to start every blank at the dismantling month.
6. Deconstruction contractor Presses Save dates; the page shows Dates set for N of M items.
7. Platform Stores the contractor's month beside the surveyor's estimate and tells the owner.

RULES

- Only the owner or the surveyor of the building can invite, change or remove the contractor, and only a surveying or deconstruction firm can be chosen. The building's own surveying firm can be chosen too; it then gets the Availability tab beside its other tabs, and its Home row reads Surveyor and contractor with Dates set for N of M and Set dates.
- An invite by email reveals nothing about who is on Tallyard: an email at an organisation of another kind simply waits.
- Only the appointed contractor can set dates, and a new contractor never inherits another's dates.
- A firm that is only the contractor sees just Overview and Availability. Capture, Inventory, Testing and Requirements are refused, and it never sees lots, prices, visibility or buyers. Its Home shows Clients, Buildings to date, Dates set and Still to date, and it has no Capture item.
- The contractor's dates never reach buyers directly; only the owner changes a lot's date.
- A month that holds the dismantling start is saved as that exact start date; any other month is saved as its first day.
- In the sample data, Tarnbrook Deconstruction is both surveyor and contractor at Harrowden Court, with no dates set yet.

NOTIFICATIONS

- The contractor is told '[firm] invited you to set availability dates at [building]', also when it joins from an invite by email.
- When the surveyor invites the contractor, the owner is also told '[firm] invited [contractor] to [building]'. When the owner invites, the surveyor is not told.
- When a firm joins from an invite by email, the side that invited it and the owner are told '[firm] joined and can set dates at [building]', with any dates cleared.
- When dates are saved, the owner is told '[contractor] set dates for N items at [building]', kept to one notice per building, contractor and day.

- Removing the contractor, or recording or withdrawing an invite by email, notifies nobody; it is recorded in the activity log.


SURVEYOR AND DECONSTRUCTION CONTRACTOR

Owner applies the contractor's dates

Donor building owner | Platform

Where Building, Inventory tab (/app/buildings/:id/inventory), button Use contractor dates

The owner compares the contractor's month with each lot's date in the inventory and, with one button, copies the contractor's dates onto the lots that can still change. This is how the contractor's dates can reach what buyers later see.



STEPS

1. Donor building owner Follows Review their dates in the inventory from the contractor card, or opens the Inventory tab.
2. Donor building owner Reads the Contractor column; where the contractor's month differs from the lot, the row also shows what the lot reads now.
3. Donor building owner Presses Use contractor dates (N), where N is how many lots would change.
4. Platform Sets each private, unreserved lot's date to the contractor's month and reports how many were applied and how many were skipped.

RULES

- Only the owner can apply the contractor's dates. The Contractor column shows only when a contractor is invited, and the button only when at least one lot would change.
- Lots that are shared, published or reserved are skipped; the owner is told to make them private to change their dates.
- Buyers see the new dates only when the owner shares or publishes the lot.
- The change can be undone from the confirmation message.

NOTIFICATIONS

- None. It is recorded in the owner's activity log.

SECTION

Sustainability consultant

This section covers the sustainability consultant. An architect asks the consultancy to join a project once its client has accepted it, and the consultancy sees the project only after it accepts too. The consultant then sets each project's targets, tracks its planning requirements and certification credits, and writes the circular economy statement for the client to review. The consultant also checks compliance figures, exports the workbook, and reviews demolition bills on waste engagements.


SUSTAINABILITY CONSULTANT

Answer a request to join a project

Sustainability consultant | Architect | Client or developer | Platform

Where Consultant: Home, request cards at the top (/app/home), and Projects, Project requests (/app/projects/requests). Architect: project Team tab (/app/projects/:id/team)

An architect who names a sustainability consultancy on a project asks it to join, as it asks the client. The consultancy is asked only once the client has accepted the project, and reaches the project only once it accepts too. If it declines, the architect can ask again or choose another consultancy.


Architect names the consultancy
Client has accepted the project?
Not yet
Request waits for the client
Client accepts
Yes
Choose another
Consultancy asked to join
Accept the project?
Accept
Decline, optional note
Ask again
Architect and client told
Architect told, under the consultancy name
Project opens for the consultant
Ask again or another?

STEPS

1. Architect Chooses a Sustainability consultant on New project or on the Team tab; the confirmation reads Consultancy asked to join, "They see the project once they accept, and once the client has."
2. Platform Holds the request until the client accepts the project, then asks the consultancy: a notification and a card on its Home and under Project requests, with a badge in its sidebar.
3. Sustainability consultant Reads the card: project name, architect practice, client, who asked and when, type, location, stage, site start and practical completion, then chooses Accept, or Decline with an optional note.
4. Platform On accept, adds the project to the consultant's Projects and Home, and tells the architect and the client.
5. Platform On decline, tells the architect only, under the consultancy's name; the Team tab reads "[consultancy] declined to join this project on [date]. Their note: ..." with Ask again.
6. Architect Presses Ask again on the Team tab, or chooses another consultancy.

RULES

- Until the client has accepted, the consultancy is not told about the project and cannot open it; the setup checklist and the Team tab say it is asked once the client accepts.
- Until the consultancy accepts, it cannot open the project. Opening the project's address shows "Accept [project] to open it" with a button to Project requests.
- Until it joins, the consultancy is named as waiting to accept or declined, never as setting targets: the Sustainability tab reads, for example, "[consultancy] has not accepted the project yet. Defaults from the requirements are shown."
- Activity and notifications about reservations, client decisions and sustainability reach only a consultancy that has joined.
- Only a waiting request can be answered: "This request has already been answered." A decline reaches the architect under the consultancy's name, never a person's.
- Projects and sample records made before this change count as accepted.

NOTIFICATIONS

- The consultancy, once the client has accepted: "[practice] asked to add you as sustainability consultant on [project]", "[client] has accepted the project. Accept to see it and set its targets."
- The architect and the client on accept: "[consultancy] joined [project] as sustainability consultant", "They can now set targets and follow carbon and compliance on the project."
- The architect on decline: "[consultancy] declined [project]", with "Their note: ..." or "Ask again or choose another consultancy on the Team tab."


SUSTAINABILITY CONSULTANT

Set, override or reset a project target

Sustainability consultant | Client (told)

Where Project, Goals and targets (/app/projects/:id/targets)

Each goal starts with a default target taken from the planning and sustainability requirements that apply to the project. The consultant keeps the default, overrides it with a project value, marks the goal not targeted, or later resets it to the default. The result is the project's effective target, which every dashboard and page reads.



STEPS

1. Sustainability consultant Opens the project and the Goals and targets tab, which lists eight goals: reused and recycled content by value, reused content by value, upfront carbon avoided by reuse, upfront carbon (modules A1 to A5), demolition waste diverted from landfill, BREEAM rating, LEED certification and WELL certification.
2. Platform Shows each goal's default, the requirement it comes from and its basis, with the requirements that apply listed at the top.
3. Sustainability consultant Chooses Edit target on a goal, enters a number or picks a rating level, and may add a reason that the project team sees.
4. Sustainability consultant Or ticks Not targeted on this project to switch the goal off, then chooses Save target.
5. Platform Refuses a value that does not fit the goal's unit with a message; otherwise marks the row Overridden, shows who set it and when, keeps the default on record and logs the change in the project activity.
6. Platform Notifies the client organisation, once it has accepted the project, of the new target.
7. Sustainability consultant Chooses Reset to default on an overridden goal to go back to the requirement's default.
8. Platform Uses the effective target (the override, else the default) on the Sustainability tab, Certification, Requirements, Compliance, the statement, the workbook and the consultant, client and architect home dashboards; the consultant's Home builds its meters from the same rows.

RULES

- Only the project's consultant can edit targets. The Goals and targets tab is not shown to the architect or the client; they see targets, read only, on the Sustainability tab.
- A value that does not fit the goal's unit is refused with a message and nothing is saved.
- Marking a rating goal (BREEAM, LEED or WELL) not targeted also turns that scheme off, so its credits that nobody has changed yet start as not targeted.
- Saving the same value and reason again changes nothing and sends nothing.
- Reset to default appears only on an overridden goal and sends no notification.
- A goal with no default and no override shows No target set. A goal is marked indicative when Tallyard works out its figure or when its default is not from a published source.
- Each save and reset offers Undo in the confirmation message.

NOTIFICATIONS

- Client organisation (once it has accepted the project): New target on the project, with the goal and value, linking to the Sustainability tab. Sent on each save, including Not targeted.
- Reset to default: none, only an activity entry.


SUSTAINABILITY CONSULTANT

Follow projects from the Overview and the Projects list

Sustainability consultant | Platform

Where Home (/app/home), Projects (/app/projects) and each project's Overview (/app/projects/:id)

The consultant reads every project against its targets without opening each tab: the Home meters, the Projects list and an Overview section of his own all read the same goal rows as Goals and targets, so an override shows the same status everywhere.


Open Home or Projects
Meters from the Goals and targets rows
Content, avoided carbon secured, state
Statement status, requirements at risk
Something off target or at risk?
Yes
No
Open the project Overview
Nothing to act on
Figures, statement, targets, schemes, risks
Follow a link to edit

STEPS

1. Platform On Home, shows tiles including Avoided carbon, secured (with "N tCO2e more with approved materials") and Targets met, then a card per project with its meters, the borough and region, a Requirements line ("0 of 10 ready" with an at risk pill) and links to each at risk requirement.
2. Platform On Projects, lists each project as a card or a table row with reused and recycled content by value and upfront carbon avoided by reuse, secured, against their targets with their state, the statement status, and requirements ready and at risk.
3. Sustainability consultant Opens a project, whose Overview leads with the programme card, then his own section: the four Sustainability figures against target, the statement card, the target meters, each scheme's certification snapshot and the requirements at risk.
4. Sustainability consultant Follows Edit targets, Open certification, Open the statement or a requirement to act.

RULES

- Carbon is measured on secured materials (earlier deals and accepted reservations); approved materials are shown as what more they would add.
- Targets met counts every goal with a target, as Goals and targets lists them, judged by the same rule as the Sustainability tab and the client's tracking.
- The shortlist and approval counts on the Overview are left out for the consultant.
- Only projects the consultancy has accepted appear. A consultancy with no projects and no engagements sees its first steps instead of zero tiles, below any waiting requests.
- Every figure is indicative and comes from public listings and the project's own records.

NOTIFICATIONS

- None.


SUSTAINABILITY CONSULTANT

Enter a result with its date and source

Sustainability consultant

Where Project, Goals and targets (/app/projects/:id/targets), Enter result

Some goals cannot be worked out by Tallyard, such as upfront carbon, waste diverted and the rating levels. The consultant records the latest result with the date it applies to and where it comes from, so the status against the target can be shown.



STEPS

1. Platform Works out reused and recycled content by value, reused content by value and upfront carbon avoided by reuse from the bill of materials and the secured materials; these rows have no Enter result button.
2. Sustainability consultant Chooses Enter result on upfront carbon, demolition waste diverted, BREEAM, LEED or WELL.
3. Sustainability consultant Enters the result or picks the level, sets the As at date (today unless changed) and writes the Source, for example a stage 2 life cycle assessment, then chooses Save result.
4. Platform Shows the result under Now with its date and source, updates the status meter and logs it in the project activity.
5. Platform Shows a BREEAM, LEED or WELL result as the latest predicted rating for that scheme on Certification, the Sustainability tab and Compliance.

RULES

- Only the consultant can enter results, and only for goals Tallyard does not measure; an attempt on a measured goal is refused.
- The result must fit the goal's unit, the As at date must be on or before today and the source must not be empty; otherwise the save is refused with a message.
- Entering the same value, date and source again changes nothing. A new result replaces the earlier one; there is no button to remove a result.
- Measured results need the project's bill of materials for content by value; without it the row reads Needs the bill of materials.
- Saving offers Undo in the confirmation message.

NOTIFICATIONS

- None. The result is recorded in the project activity only.


SUSTAINABILITY CONSULTANT

Track a requirement's status and evidence

Sustainability consultant | Client or developer | Architect (reads)

Where Project, Requirements (/app/projects/:id/requirements)

Every planning and sustainability requirement that applies to the project is tracked with a status and a list of evidence. The consultant and the client keep it current together, and each is told when the other marks a requirement at risk or evidence ready.


Open the Requirements tab
Platform lists requirements that apply
What needs updating?
Evidence
Status
Add a note or link an output
Choose a status
Note or output given?
At risk or Evidence ready?
No
Yes
Yes
No
Refused, nothing added
Not started becomes In progress
Client is notified
Saved and logged
Client can do the same, consultant told

STEPS

1. Platform Lists the requirements the architect chose for the project, or the ones suggested for its region and local authority until the architect has chosen, each with its scope, source and summary.
2. Platform Shows what Tallyard already holds for each requirement under Held in Tallyard, such as the goal figures it sets and the circular economy statement status.
3. Sustainability consultant Filters by All, At risk, Open, Evidence ready or Not applicable.
4. Sustainability consultant Sets the status: Not started, In progress, At risk, Evidence ready or Not applicable.
5. Sustainability consultant Chooses Add evidence, writes what was done and where it is held, and may link an output: Compliance workbook, Circular economy statement, Sustainability summary or Certification tracking.
6. Platform Moves a Not started requirement to In progress when its first evidence is added, and logs status changes and new evidence in the project activity.
7. Client or developer Can change status and add evidence the same way; the client may link the Circular economy statement, Specification, Sustainability summary or Certification tracking.

RULES

- The consultant and the client (once it has accepted the project) may edit; the architect reads the tab only.
- Evidence needs a note or an output; an empty entry is refused with Add a note or choose an output.
- Only the person who added a piece of evidence can remove it.
- A requirement that does not apply to the project is refused.
- The Requirements tab shows a badge with the number of requirements at risk for the consultant and the client.
- While the architect has not reviewed the requirements, the suggested ones for the place are tracked and the page says so. If none apply, the page points to the project overview. On a building owner's own project with no architect, the owner is prompted to appoint one.
- Status changes, new evidence and removals offer Undo in the confirmation message.

NOTIFICATIONS

- When the consultant marks At risk or Evidence ready: the client organisation (once linked) is told the requirement's new status.
- When the client marks At risk or Evidence ready: the consultant organisation is told, once it has joined the project.
- Other statuses and evidence: no notification, activity entry only.


SUSTAINABILITY CONSULTANT

Target certification credits and set their status

Sustainability consultant | Client (told)

Where Project, Certification (/app/projects/:id/certification?scheme=breeam)

For BREEAM, LEED, WELL and the circular economy measures, the consultant chooses which credits the project is seeking and keeps each one's status current. Tallyard suggests a status from its own records with the reason, which the consultant can accept or ignore.



STEPS

1. Sustainability consultant Opens Certification and picks a scheme tab: BREEAM, LEED, WELL or Circular economy; each tab shows how many credits are targeted.
2. Platform Shows the scheme summary: the target (for BREEAM, LEED and WELL with a link, Change in Goals and targets), the latest predicted rating and a bar of the targeted credits by status.
3. Sustainability consultant Turns a credit's switch on or off; credits start targeted when the scheme is targeted and the credit is usually sought.
4. Platform For a targeted credit, shows Suggested: and a status with the reason from Tallyard's records, for example content by value against the aim or how many items need screening.
5. Sustainability consultant Chooses Use suggestion or picks a status: Not started, In progress, At risk or Evidence ready.
6. Sustainability consultant Writes a note, for example where the assessor holds the evidence, and chooses Save note.
7. Platform Records who updated the credit and when, and logs targeting and status changes in the project activity.

RULES

- Only the project's consultant can open Certification; the client and the architect see the scheme summaries on the Sustainability tab.
- A credit must be targeted before its status can be set: the status menu is greyed out, and the platform refuses with Target this credit before you set its status. Not applicable is not offered for credits.
- The suggestion appears only on a targeted credit, only when Tallyard's records say something about it, and only when it differs from the current status.
- Saving a note does not add an activity entry; it records who updated the credit and when.
- Everything on the page is labelled indicative, not certification advice.

NOTIFICATIONS

- When a credit is marked At risk: the client organisation (once linked) is told the credit is at risk.
- Other changes: none, activity entry only.


SUSTAINABILITY CONSULTANT

Map reclaimed materials to credits

Sustainability consultant

Where Project, Certification (/app/projects/:id/certification), By credit and By material views

The project's reclaimed materials (earlier deals, accepted reservations and approved shortlist items) are mapped to the credits that rely on them. A rule ticks the right materials by default, and the consultant adds or leaves out individual materials, either per credit or in a grid.



STEPS

1. Platform Lists the project's materials from their public listings, each tagged Confirmed (earlier deal), Reserved (accepted reservation) or Approved (approved on the shortlist).
2. Platform Ticks each material by the credit's rule, for example every reused item, steel sections only, or items built before 1970 or untested.
3. Sustainability consultant Ticks or unticks a material; the hint reads Included by the rule, Added by you, Left out by you or Not covered by the rule.
4. Sustainability consultant Switches to By material to see a grid of materials against every targeted credit that maps materials, and ticks there.
5. Platform Uses the mapped materials in the credit's suggestion and in the Certification mapping sheet of the compliance workbook.

RULES

- Only the consultant can change the mapping, and only for materials that are on the project.
- Credits that do not map individual materials say so and refuse a mapping.
- Material checkboxes are greyed out while a credit is not targeted; the By material grid shows only targeted credits that map materials.
- Ticking a material back to what the rule says drops the override.
- No prices or seller details appear; only public listing data is used.
- With no reclaimed materials yet, the page says credits fill in as the client approves and reserves materials, and the By material grid is not shown.

NOTIFICATIONS

- None.


SUSTAINABILITY CONSULTANT

Draft and export the circular economy statement

Sustainability consultant

Where Project, Circular economy tab (/app/projects/:id/statement)

Tallyard writes a circular economy statement in eight sections from the project's records. The consultant edits any section, is warned when the figures behind an edited section change, and can copy, print or download the statement for Word at any time.



STEPS

1. Platform Writes the sections: project and policy context, strategic approach, reclaimed materials, reused and recycled content by value, upfront carbon avoided, targets and commitments, certification, and next steps, using the effective targets and the targeted credits.
2. Platform Groups the reclaimed materials by status and family with no listing codes, gives one line per certification scheme with credits at risk and with evidence ready, and derives the next steps from the records: request reservations for approved materials, follow up requests with the seller, close each gap below target, record missing results, resolve credits at risk, set a target for a rating scheme recorded as a requirement, then the step for the RIBA stage. List lines show as bullets.
3. Sustainability consultant Chooses Edit on a section, changes the text and chooses Save; Reset to generated text returns it to Tallyard's text.
4. Platform Keeps the generated text the edit replaced, and when the project's figures later change shows a warning on that section.
5. Sustainability consultant Chooses Use updated text to take the new generated text, or Keep my text to keep the edit against the new figures.
6. Sustainability consultant Chooses Copy text, Print (laid out on A4) or Download for Word, which saves a .docx with real bullet lists, named after the project and today's date.

RULES

- Only the project's consultant can open this page and edit. The client reads the statement on its Sustainability tab once it has been sent; the architect never sees it.
- Save is unavailable while a section's text is empty; Reset to generated text brings back Tallyard's text.
- Editing a statement already sent keeps its status: the client goes on reading the version sent, and the consultant is offered Send the updated statement (see Send the statement for the client's review).
- Saving and resetting a section offer Undo in the confirmation message.
- The Word file is built in the browser; nothing is sent anywhere.
- A Check before you submit warning shows on screen; the indicative footer appears on screen, in print, in the Word file and in the copied text.
- Figures read one decimal place throughout, and "No avoided carbon is on record yet" when there is none.

NOTIFICATIONS

- None while drafting.


SUSTAINABILITY CONSULTANT

Send the statement for the client's review

Sustainability consultant | Client or developer

Where Consultant: Circular economy tab (/app/projects/:id/statement). Client: Sustainability tab, statement card (/app/projects/:id/sustainability#statement)

When the draft is ready, the consultant sends it to the client. Sending freezes the text: the client reads, comments on and marks reviewed the version sent. If the statement changes afterwards, the consultant sends the updated statement, which replaces the frozen copy and asks for review again.


Send to the client for review
Client accepted the project?
No
Yes
Send button stays unavailable
Text frozen as sent
Client notified, to-do on home
Client chooses Read and review
Client adds optional comments
Client chooses Mark as reviewed
Consultant notified with comments
Reviewed by the client
Statement changed since sending?
Yes
No
Send the updated statement
Stays reviewed

STEPS

1. Sustainability consultant Chooses Send to (client name) for review; the button then reads Sent for review and is unavailable until the statement changes.
2. Platform Freezes the sections as sent, sets the status to With the client for review, clears any earlier review, notifies the client organisation and adds a to-do, Review the circular economy statement, due 14 days after sending, to a developer client's home.
3. Platform Shows the client a badge on its Sustainability tab and a highlighted statement card reading Ready for your review.
4. Client or developer Chooses Read and review, reads the version sent, dated when it was sent, may write comments for the consultant, and chooses Mark as reviewed.
5. Platform Sets the status to Reviewed by the client, notifies the consultant organisation with the comments, and shows the comments on the statement page.
6. Sustainability consultant After an edit, or when the figures move on, sees "Changed since you sent it", "Sent on [date]. Send the updated statement so [client] reviews the latest version.", and chooses Send the updated statement, which replaces the frozen copy. A reviewed statement can also be sent again without changes.

RULES


- Only the consultant sends; only the client (or a building owner on its own project, who acts as the client) marks it reviewed.
- Sending is not possible until the client has accepted the project: the button is unavailable and the platform refuses.
- Marking reviewed is refused unless the statement has been sent: The statement has not been sent for review.
- An edit never pulls the statement back from the client: a statement with the client stays With the client for review, and a reviewed one stays Reviewed, until the consultant sends the updated statement. The client keeps the review to-do and can still mark the version sent as reviewed.
- While the statement waits for review, sending again is possible only once its text differs from the version sent.
- The client cannot decline or return the statement; it can only add comments and mark it reviewed.
- A statement never sent reads Draft to the consultant and Not sent yet to the client and the architect; once the consultant has started editing it, the client's card reads Being drafted. After review the client can still choose Read the statement.
- The architect never sees the statement itself.
- Send and review both offer Undo in the confirmation message.

NOTIFICATIONS

- On send: the client organisation gets Circular economy statement ready for review, linking to the Sustainability tab.
- On sending the updated statement: the client organisation gets Updated circular economy statement ready for review.
- On review: the consultant organisation gets the client reviewed the circular economy statement, with the comments or No comments.

LIFECYCLE

The client sees these as Not sent yet or Being drafted, Ready for your review and Reviewed. Each send freezes the text the client reads; editing never moves the status back.




SUSTAINABILITY CONSULTANT

Read the Sustainability tab

Sustainability consultant | Client or developer | Architect

Where Project, Sustainability (/app/projects/:id/sustainability; the old /carbon address redirects here)

The Sustainability tab is the shared summary every side of the project sees: figures, targets, avoided carbon, certification schemes and the requirements roll up. It is read only; the consultant follows its links to the pages where things are edited.



STEPS

1. Platform Shows four headline figures: Avoided carbon, secured; Avoided carbon, live list; Content by value; and Reclaimed mass, secured. The carbon and content figures have progress rings against the effective targets.
2. Platform Shows the circular economy statement card to the consultant (Open the statement) and the client (Read and review, or Read the statement); the scheme card and the architect read only its status, Not sent yet until it is sent.
3. Platform Shows the targets that are set or have results, the avoided carbon section, a card per certification scheme and the requirements roll up with the titles of those at risk.
4. Sustainability consultant Uses Edit targets, Open certification, Open the statement and Open requirements to go to the editing pages.

RULES

- Everyone on the project can open it: architect, client once linked, and consultant. Nothing on it is edited in place.
- The targets note reads "Targets are set by [consultancy]." only once the consultancy has joined; otherwise "[consultancy] has not accepted the project yet.", "[consultancy] declined to join." or "[consultancy] is asked to join once the client accepts.", each followed by "Defaults from the requirements are shown."
- Figures come from public listings and the project's own records; no prices are shown. Carbon and content figures are labelled indicative.

NOTIFICATIONS

- None.


SUSTAINABILITY CONSULTANT

Check compliance and export the workbook

Sustainability consultant

Where Project, Compliance (/app/projects/:id/compliance)

The consultant's compliance page gathers content by value, avoided carbon, reclaimed mass, the statement status, certification and the reused items in one place. It prints to A4 and exports a spreadsheet workbook for the planning submission or the assessor.



STEPS

1. Platform Labels the page Forecast, design stage and states the policy basis, London Plan 2021 and the 2022 guidance.
2. Platform Shows content by value secured against the project's effective target, or against the policy aim when the project has no target, with the figures with approved materials and without reuse beside it, and how much each bill line adds through reuse.
3. Platform Shows upfront carbon avoided and reclaimed mass, the statement status (Open the statement), the certification summary per scheme (Open certification), the reused items and the bill of materials.
4. Sustainability consultant Chooses Print for a report laid out on A4, or Export workbook.
5. Platform Builds the workbook in the browser with sheets for Summary, Bill of materials, Reused items, Targets, Requirements, Certification mapping and Assumptions, and names the file after the project and today's date.

RULES

- Only the project's consultant can open Compliance and export the workbook.
- Without a bill of materials, content by value is not shown; avoided carbon and reused items are still counted.
- Untargeted credits are listed as Not targeted in the mapping sheet; credits without a note carry the standard assessor caveat.
- Every figure is indicative and labelled as such; nothing leaves the browser.

NOTIFICATIONS

- None.


SUSTAINABILITY CONSULTANT

Import and review a demolition bill

Sustainability consultant

Where Sidebar, Engagements, then the engagement (/app/engagements/:id/waste)

For a demolition engagement, the consultant brings in the contractor's bill of arisings, checks how each row was coded to a waste stream and destination, fixes the unclear ones and exports a waste and reuse workbook. The figures are actuals from the contractor's bill.



STEPS

1. Sustainability consultant Opens an engagement from the Engagements section of the sidebar and, while no bill is loaded, sees Import the demolition bill.
2. Sustainability consultant Chooses Use the sample bill or Upload a workbook (.xlsx).
3. Platform Reads each row, codes it to a waste stream and destination with high, medium or low confidence, skips title and total rows, and checks the stated total against the rows.
4. Platform Shows Rows to review: a row without a stream, a destination or a tonnage is not counted until it is reviewed.
5. Sustainability consultant Turns on Only rows to review (the low confidence rows) and sets the Stream and Destination for each, beside the text as written on the bill; an edited row leaves that filter and is counted as edited.
6. Platform Updates diversion from landfill against the aim, reuse rate, counted demolition waste and the potential carbon benefit, with hazardous and excavation rows reported separately.
7. Sustainability consultant Chooses Export workbook, or Replace to load a different bill, or Clear bill to start again.
8. Platform Builds the workbook in the browser with sheets for Summary, Arisings, Recycling and waste reporting, Reuse carbon, Certification mapping and Assumptions.

RULES

- Only the engagement's consultant can open it; the building owner on the engagement cannot.
- A file with no recognisable header row, or with no rows, is refused with a message to use the sample bill or a bill with the same columns.
- Rows can be edited only after a bill is loaded.
- The page is labelled Actual, from contractor's bill; the carbon benefit is indicative and reported separately as module D.
- Load, Replace and Clear bill offer Undo; row edits do not. The workbook never leaves the browser.

NOTIFICATIONS

- None. Loading a bill adds an entry to the consultant organisation's activity; clearing it or editing rows adds none.

APPENDIX

Things worth a look

While checking each workflow against the code, these gaps came up. None of them breaks a journey, but each is a product decision you may want to make. The section and workflow where each appears is given in brackets.

1. A lot made private keeps its waiting reservation requests, and the owner can still accept one.
   Donor building owner, List a lot
2. When the owner declines a reservation, the architect is not notified; it only shows in project activity. The consultant gets no reservation notifications at all.
   Client, Seller decision; Donor building owner, Decide reservation requests
3. When another buyer reserves a lot, the approved material drops out of the client's Approvals and Reservations with no prompt to choose again.
   Client, Seller decision
4. Once saved, a captured item's material, size and quantity cannot be changed and the item cannot be deleted. Undo straight after saving is the only fix.
   Surveyor, Capture an item
5. A result the consultant enters for a goal cannot be removed from the screen, only replaced.
   Sustainability consultant, Enter a result
6. The client cannot send a circular economy statement back to the consultant, only comment and mark it reviewed.
   Sustainability consultant, Statement review
7. An owner cannot claim a building a surveyor added from its own side. The two records join only when the surveyor asks the owner to confirm it, or moves her captures into the owner's record once appointed.
   Surveyor, Move early captures into an appointment
8. Waste engagements exist only in the sample data. Nothing in the platform starts a new one.
   How it fits together, Getting a new organisation started
9. Removing a surveyor or a deconstruction contractor tells nobody; only the building's activity records it.
   Donor building owner, Appoint a surveyor; Contractor dates
10. A share link page hides every reserved lot, including one reserved for the opener's own project.
    Donor building owner, Open a share link
11. Search shows inventory results to a deconstruction contractor that then open a no-access page.
    Accounts and the sandbox, Search
12. Sandbox limits, expected for now: Reset your password lets anyone who knows an account's email set its password; invite links only work in the same browser; changing a sample account's password stops its one-click card working until the sandbox is reset.
    Accounts and the sandbox