

The layout is unchanged: embedded PGP blob, env-only remotes, `RCLONE_CONFIG=/dev/null , crypt remote S3CRYPT over :s3:glacier-deep-archive-backup-ab/encrypted-standard-storage , mount on /media/AWSCRYPT , secrets wiped on exit. Syntax-checked.`



RcloneMount.sh
Shell Script · 7.44 KB

 Download

What was broken

- `rc=$?2` appends a literal 2 to the exit code (0 becomes 02). It is now `rc=$?` .
- `RCLONE_S3_LOG_FILE` , `RCLONE_S3_LOG_LEVEL` , `RCLONE_S3_BWLIMIT` , `RCLONE_S3_TRANSFERS` , `RCLONE_S3_MAX_TRANSFER` , and `RCLONE_S3_CUTOFF_MODE` are not rclone names. Globals are `RCLONE_<FLAG>` . Backend options stay `RCLONE_S3_<OPT>` (`region` , `provider` , `acl` , `keys` , `chunk_size` , `upload_concurrency`). Same values.
- The `dtach` socket was built and never used, and the fallback text said foreground while the command always passed `--daemon` . `dtach` now owns the mount when present (`dtach -a "$sock"` to reattach). `--daemon` is only the fallback, with `--daemon-wait 45s` . Both at once double-forks and hides the error.
- The wipe list had `CLONE_CONFIG_SECRET_PASSWORD` (typo) and never cleared the obscured crypt secrets. It now matches the variables that are actually exported.
- Crypt passwords are required, because the mount is `S3CRYPT: . Plaintext` `RCLONE_PASSWORD` and `RCLONE_SALT` are unset after `rclone obscure --` , so the daemon does not keep them. S3 keys still have to stay in the daemon environment.

What was added, same design

- Loopback pinentry first, then the XFCE pinentry if loopback is disabled in `gpg-agent.conf` .
- Mountpoint create/already-mounted check. On Gentoo, `/media` often needs root to create.
- `--vfs-cache-mode writes` , cache under `${XDG_CACHE_HOME:-$HOME/.cache}/rclone-s3crypt` . Without a write cache, an S3 FUSE mount fails for most programs.
- Log file `${XDG_STATE_HOME:-$HOME/.local/state}/rclone/mount-YYYY-MM-DD-HHMMSS.log` (no colons).
- `--s3-no-check-bucket` so a missing `ListBucket` does not abort the mount.

- 15s poll after detach, then a clear failure if the mountpoint is not mounted.

Left alone on purpose

- Blob, bucket, prefix, us-east-1, private ACL, transfers 1, bwlimit 250M, max-transfer 1000G. That cap stops the mount after 1000G; it was already set.
- No --allow-other (needs user_allow_other in /etc/fuse.conf).
- No --rc by default. It fights a second mount on port 5572. Unmount with fusemount3 -u /media/AWSCRIPT.
- Objects in DEEP_ARCHIVE still will not read until restored. This prefix is encrypted-standard-storage.