Web Progress — Software Bug Tracker

Application: Web-Progress | Version:V2.0.2 | Reported By: Abdelrahman Ali | date:09/06/2026

Bug ID	Mode	Feature / Module	Bug Summary	Steps to Reproduce	Expected Behaviour	Priority	Severity	Scope	Status	Fix Version	Notes
bug_1	Both	Web Progress Installer	Progress bar appears with installing complete but no confirmation message shown; closing only happens after OK on a missing/absent dialog.	1- Open WP Installer 2- Choose Both 3- Fill required data 4- Press Install	Show confirmation dialog 'Installation Finished'. On OK, installer closes.	High	Medium	Pipeline & Structure	Done	V2.0.2	
bug_2	Both	Web Progress Installer	After install finishes, switching to Web Server or Data Uploader option hides the confirmation message—user has no feedback on completion.	1- Open WP Installer 2- Choose Both 3- Fill data 4- Press Install 5- Switch to Web Server or Data Uploader	Confirmation message should persist regardless of option change.	High	Low	Pipeline & Structure	Done	V2.0.2	
bug_3	Both	Web Progress Installer	Browsed URL from IIS does not work with 'localhost'; user must manually replace it with machine IP.	1- Open WP Installer 2- Choose Both 3- Fill data 4- Press Install 5- Open IIS & browse URL 6- Replace localhost with IP	URL should work with both localhost and machine IP automatically.	High	High	Pipeline & Structure	Done	V2.0.2	
bug_4	Both	Web Progress Installer	Web page shows both Structure and Pipeline tabs even when only Pipeline scope was selected during install.	1- Open WP Installer 2- Choose Both 3- Select Pipeline scope only 4- Install 5- Browse web page	Only selected scopes should appear as tabs on the web page.	Medium	Low	Pipeline	Open		
bug_5	Both	Web Progress Installer	Clicking 'Database Settings' shows error 'Can't get server list' before opening the connection window.	1- Open WP Installer 2- Choose Both 3- Press Database Settings	Connection window should open directly without prior error.	High	Medium	Pipeline & Structure	Done	V2.0.2	
bug_6	Both	Web Progress Installer	No field to connect source DB during install, so web page shows no data before running Data Migration Tool.	1- Open WP Installer 2- Choose Both	Add source DB connection field in installer to pre-populate web page data.	High	Medium	Pipeline & Structure	Blocked	V2.0.2	Cant connect database from installer.
bug_7	Both	Data Migration Tool	User must manually copy IIS URL and modify it to connect Data Migration Tool to the web page.	1- Install WP 2- Open IIS & copy URL 3- Open Data Migration 4- Paste & modify URL	Auto-link installer, migration tool, and web page without manual URL editing.	High	Medium	Pipeline & Structure	Done	V2.0.2	
bug_8	Both	Data Migration Tool	Upload interval field is disabled in SC mode, preventing the user from starting the uploader.	1- Install WP 2- Open Data Migration 3- Choose SC Mode 4- Fill required data	Upload interval should be editable in SC mode.	High	High	Structure (SC)	Done	V2.0.2	
bug_9	Both	Data Migration Tool – Save Profile	After saving a profile, closing and reopening the tool auto-loads last data without prompting to load the profile.	1- Install WP 2- Open Data Migration 3- Fill data 4- Save profile & close 5- Reopen tool	Tool should open blank or prompt the user to load a saved profile.	High	High	Pipeline & Structure	Done	V2.0.2	
bug_10	Both	Data Migration Tool	Opening a second migration instance for a second vessel requires closing the first instance first.	1- Install WP 2- Open Data Migration for Vessel 1 3- Open another Data Migration for Vessel 2	Multiple Data Migration instances should run simultaneously.	High	High	Pipeline & Structure	Done	V2.0.2	
bug_11	Both	Data Migration Tool – Save Profile	After deleting a saved profile externally and reopening the tool, the deleted profile name still appears in the window title.	1- Install WP 2- Save profile & close 3- Delete profile file 4- Reopen Data Migration	Deleted profiles should not appear; tool should open with no profile name.	High	High	Pipeline & Structure	Blocked		The software use last saved without any profiles
bug_12	Both	Web Progress Page	Home page icon missing when only one vessel is created.	1- Install WP 2- Open Data Migration 3- Create 1 vessel (Pipeline) 4- Start uploader 5- Check web page	Home page icon should display regardless of vessel count.	Low	Low	Pipeline	Done	V2.0.2	
bug_13	Both	Web Progress Page	Vessel icon and vessel name missing on web page when only one vessel exists.	1- Install WP 2- Open Data Migration 3- Create 1 vessel (Pipeline) 4- Start uploader 5- Check web page	Vessel icon and name should display for any number of vessels.	High	Low	Pipeline	Done	V2.0.2	
bug_14	Both	Data Migration Tool	Any unhandled error causes the logs table to disappear; it only returns after restarting the tool.	1- Install WP 2- Open Data Migration 3- Trigger any error during Pipeline upload	Logs table should persist and record all events/errors without restarting.	High	Medium	Pipeline	Done	V2.0.2	
bug_15	Both	Data Migration Tool	Log table contents are lost after closing and reopening the tool, even with a loaded profile.	1- Install WP 2- Open Data Migration 3- Start upload 4- Save profile & close 5- Reopen & load profile	Logs should be persisted and restored when re-loading a profile.	Medium	Medium	Pipeline	Done	V2.0.2	

bug_16	Both	Data Migration Tool	Editing the pipes table in Project DB while migration is running throws an unhandled error and crashes the tool.	1- Install WP 2- Open Data Migration (Pipeline) 3- Start upload 4- Edit start KP of a pipe	Error should be handled gracefully; DB edits should be allowed during migration.	High	Medium	Pipeline	**Done**	V2.0.2	
bug_17	Both	Data Migration Tool	SC scope appears on both vessels when Vessel 1 has Pipeline+SC and Vessel 2 has Pipeline only.	1- Install WP with Pipeline+SC 2- Create Vessel 1 (Pipeline+SC) 3- Create Vessel 2 (Pipeline only)	SC scope should only appear on Vessel 1.	High	High	Pipeline & Structure	**Blocked**		should every vessel created at different machine and showed with it's data
bug_18	Both	Prerequisites / Setup	No automation script to handle prerequisites (offline install, IIS features, URL Rewrite), increasing setup time significantly.	N/A	Create a deployer or automation script for prerequisites.	High	High	Pipeline & Structure	**Open**		R&D work on decrease installation steps by create deployer
bug_19	Both	Data Migration Tool	When 'Pipeline divided into blocks' is enabled with 5-min interval, divided pipes appear only after 2 cycles (10 min) instead of 1.	1- Install WP 2- Open Data Migration 3- Enable pipeline divided 4- Set 00:05 interval 5- Start uploader	Data should appear after the first cycle (5 min).	High	Medium	Pipeline	**Done**	V2.0.2	
bug_20	Both	Data Migration Tool	With pipeline divided into blocks, the first segment of every pipe is duplicated on the web page.	1- Install WP 2- Open Data Migration 3- Enable pipeline divided 4- Start uploader 5- Review web page	No duplicate segments; each pipe part should appear exactly once.	High	Medium	Pipeline	**Done**	V2.0.2	
bug_21	Both	Data Migration Tool	Loading spinner freezes after starting the timer, preventing stop, edit, or close actions.	1- Install WP 2- Open Data Migration (Pipeline+SC) 3- Start uploader	All controls (stop, edit, close) must remain responsive during upload.	High	Medium	Pipeline & Structure	**Done**	V2.0.2	
bug_22	Both	Data Migration Tool	When two vessels share overlapping pk_pipeid values, the first 3 pipes of Vessel 1 disappear from the web page.	1- Install WP 2- Create Vessel 1 (pipes pk=1–5) 3- Create Vessel 2 (pipes pk=1–3) 4- Start both uploaders	All pipes from all vessels should display correctly regardless of pk_pipeid overlap.	High	Medium	Pipeline	**Done**	V2.0.2	
bug_23	Both	Data Migration Tool	The installer and Data Migration Tool are not connected; user must complete two separate workflows.	N/A	Integrate installer and Data Migration Tool into one unified module/workflow.	High	High	Pipeline & Structure	**Done**	V2.0.2	
bug_24	Both	Data Migration Tool	'Export to CSV' for the logs table does not prompt the user to choose a save path.	1- Install WP 2- Open Data Migration 3- Press Export to CSV	A file-browser dialog should allow the user to choose the export path.	Low	Low	Pipeline & Structure	**Done**	V2.0.2	
bug_25	Both	Data Migration Tool	Home page shows empty (no vessels) when 2+ vessels exist; back-navigation link also expires.	1- Install WP 2- Create 2+ vessels 3- Start uploaders 4- Press Home Page on web	Home page should always show all vessels and provide stable navigation links.	High	High	Pipeline & Structure	**Done**	V2.0.2	
bug_26	Remotely	Data Migration Tool	When create Remotely pipeline web progress with 2 machines (Data Uploader machine - Web Sever machine) will find no logs for Offshore logging at Data Migration tool and no progress appear at web progress page for pipeline progress	1-Create Data Uploader by web progress Installer (Data Uploader machine) 2-Create Web server by web progress installer (Web server machine-Real IP) 3-enter name of vessel at data migration tool 4-connect Project DB and start uploader. 5-Check progress of pipeline at web progress web page.	should log of Data Offshore logging migrated successfully and also progress of pipeline appeared at web progress page.	High	High	Pipeline	**Done**	V2.0.3	
bug_27	Both	Web Progress Page	When open Tasks Tab From SC mode and open 3D Model Window then Restore down the opened page then maximize the page will find the aspect ratios of the 3D Model within the viewer do not return to their original state upon restoring the 3D Model	1-Open WP Installer 2-Choose Both 3-Fill data at SC scope only 4-Press Install 5-open Data migration and choose SC scope 6-fill data and start uploader 7-open tasks tab and open 3d model 8-Restore down and maximize the opened page	should when restore down the main page and maximize it the 3D model and details page saved the size of ratios	low	low	Structure (SC)	**New**		
bug_28	Both	Web Progress Page	The required folder hierarchy for the 3D Model is not automatically created during application installation. The user must create it manually.	-	need to created the folder automatically with installing process, the user should not create it.	low	low	Structure (SC)	**New**		
bug_29	Both	Web Progress Page	Scrolling the events table to the right in SC Findings tab corrupts the table header alignment.	1- Install WP (Structure) 2- Open Data Migration (Structure) 3- Open Findings tab 4- Scroll Right	Column headers must stay aligned with data columns at all scroll positions.	Low	Low	Structure (SC)	**New**		
bug_30	Both	Web Progress Page	In SC Findings tab, the user cannot scroll down to see the last event when the list spans more than one page.	1- Install WP (Structure) 2- Open Data Migration (Structure) 3- Open Findings tab 4- Scroll down	All events must be accessible via pagination or infinite scroll.	Low	Low	Structure (SC)	**New**		
bug_31	Both	Web Progress Page	In SC Findings tab, the user cannot scroll down to see the last anomaly when the list spans more than one page.	1- Install WP (Structure) 2- Open Data Migration (Structure) 3- Open Findings tab – Anomalies 4- Scroll down	All anomalies must be accessible via pagination or infinite scroll.	Low	Low	Structure (SC)	**New**		

bug_32	Both	Data Migration Tool	Switching 'Display Events & Anomalies' from Logging DB to Processing DB after initial upload shows no events from Processing DB.	1- Install WP (Pipeline) 2- Open Data Migration 3- Upload with Logging DB source 4- Stop upload 5- Switch to Processing DB 6- Start upload	Events/anomalies from Processing DB should load correctly on source switch.	Medium	Low	Pipeline	**New**		Blocked need to negotiations business
bug_33	Both	Data Migration Tool	Changing Start/End KP Unit to Kilometre after initial upload causes no updates; pipes with KM KP remain invisible.	1- Install WP (Pipeline) 2- Open Data Migration 3- Upload with Logging DB 4- Stop upload 5- Change KP Unit to Kilometre 6- Start upload	Pipes with Kilometre KP values should display correctly after unit change.	Medium	Low	Pipeline	**New**		
bug_34	Both	Web Progress Page	The Last Update pill in the header shows no value.	1-Open WP Installer 2-Choose Both 3-Fill data at Pipeline scope 4-Press Install 5-open Data migration and choose pipeline scope 6-fill data and start uploader 7-open pipeline page	• Shows date/time of the last data sync from the vessel, e.g. 20 Oct 2026, 13:42 (office time) • Updates automatically after each sync	High	low	Pipeline	**New**		
bug_35	Both	Web Progress Page	All accounts show the same Last Login (7/14/2020 4:59 PM) — seeded value.	1-Open WP Installer 2-Choose Both 3-Fill data at Pipeline scope 4-Press Install 5-open Data migration and choose pipeline scope 6-fill data and start uploader 7-open users page	• Last Login updated on every successful sign-in • Accounts never used show 'Never'	Medium	low	Pipeline	**New**		
bug_36	Both	Web Progress Page	Admin and migration accounts share admin@admin.com.	1-Open WP Installer 2-Choose Both 3-Fill data at Pipeline scope 4-Press Install 5-open Data migration and choose pipeline scope 6-fill data and start uploader 7-open users page	• Email must be unique across accounts • Save blocked with message 'This email is already used by another account'	High	low	Pipeline	**New**		
bug_37	Both	Web Progress Page	Reports uploaded on the vessel machine appear in the list, but the PDF stays on the vessel, so office users cannot view or download it.	1-Open WP Installer 2-Choose Both 3-Fill data at Pipeline scope 4-Press Install 5-open Data migration and choose pipeline scope 6-fill data and start uploader 7-open Reports page 8-add new pdr report	• PDF uploaded to the office server together with the report record • Any user can view/download once status is 'Available'	High	Medium	Pipeline	**New**		
bug_38	Both	Data Migration Tool	When create pipeline web progress with 1 machines (Both) and add pipe in Data migration tool with logging data 2 KM but the pipe legnth is 5 km and also the start and end kilo is logged and poslog was 200 so the pipe sholuld appear not complated because there are 3 km not logged with the center of the pipe.	1-Open WP Installer 2-Choose Both 3-Fill data at Pipeline scope 4-Press Install 5-open Data migration and choose pipeline scope 6-fill data and start uploader 7-open web progress page	Sholuld appear not complated because there are 3 km not logged with the center of the pipe.	High	High	Pipeline	**New**		

Web Progress – Requirements & Enhancements

ID	Module / Page	Type	Title	Description	Acceptance Criteria	Priority	UI Mockup Ref	Status	Target Version	Notes
WP-01	General UI	Enhancement	**Add favicon to browser tab**	Browser tab shows Chrome's default globe because no favicon is set. Use the company logo as the site icon.		Medium	All pages	Open	2.0.3	
WP-02	Pipeline Progress	**New Requirement**	**In-progress pipes bar fits section without scrollbar**	Current In-Progress Pipes section uses a horizontal navigation/scroll bar. Pipe parts must scale to fit the section width whether the pipeline is short or long.	• No horizontal scrollbar at any screen • Each part's width proportional to its length • Very short parts keep a minimum visible width	High	1 · Pipeline Progress	Open	2.0.3	
WP-03	Pipeline Progress	Enhancement	**Consistent pipeline / part terminology**	KPI says 'Completed Pipelines 4/5' while KP bar shows Part1–Part5 of one pipeline.	• Same term (pipeline or part) used in KPI cards, charts and All Pipes page	Low	1 · Pipeline Progress	Open	2.0.3	
WP-04	Findings – Events Table	**New Requirement**	**Save column layout for all users (shared schema)**	User can hide any column, drag columns to change order, and resize width so need to Saved layout must be stored on the server and appear the same for every user on every computer.	• 'Save layout' stores visible columns, order, widths, sorting, filters and grouping on the server per project + grid (Events / Anomalies) • All users load the saved layout on next open • Unsaved changes prompt before leaving the page	High	11 · Findings – Events table	Open	2.0.3	
WP-05	Findings – Events Table	**New Requirement**	**Keyboard navigation in Events table**	Navigate and use the Events table with the keyboard.	• Arrow keys move between cells / rows; focused cell highlighted • Shift+ ←/→ (or horizontal arrows at row edge) scroll columns • PageUp / PageDown change page; Home / End first / last column, Ctrl+Home / Ctrl+End first / last row • Enter opens the selected event details (and media); Esc closes • Ctrl+F focuses search; Tab moves through filter row • Shortcut list shown in a '?' tooltip	low	11 · Findings – Events table	Open	2.0.3	
WP-06	Findings – Events Table	**New Requirement**	**Export uses the saved layout**	Excel / PDF export buttons should export what the user sees.	• Export includes only visible columns, in the same order, with current filters	Medium	11 · Findings – Events table	Open	2.0.3	