ATP EDUCATION GUIDE

Automatic trading bots: how to create one, how to deploy it, and how it works

A step-by-step manual for a brand-new user. Every screen name, field and message in this guide is taken from the ATP screens as they are built. Practice (PAPER) money only.

Sign in · Connect broker · Your own settings · Strategy · Test · Start on paper · Watch · Pause / stop / exit

Information and education only, not investment advice. This guide explains how the software works. It does not say what to trade, when, or how much. Results on past prices or on paper say nothing about the future.

Contents

1. What a "bot" is in ATP 3
2. Before you start: what you need 4
3. Step 1 - Sign in 5
4. Step 2 - Connect your broker (or practise without one) 6
5. Step 3 - Save your own Trade settings and Risk limits 7
6. Step 4 - Pick or build a strategy (every way that exists) 9
7. Step 5 - Test first: the backtest 11
8. Step 6 - Deploy on PAPER: "Start a trading bot" 12
9. Step 7 - Watch the bot card, approvals and notifications 14
10. Step 8 - Pause, stop and exit 16
11. How a bot works after you start it (one cycle) 17
12. PAPER first, and how LIVE is switched 18
13. Safety boxes 19
14. Worked example: from template to paper bot (made-up numbers) 20
15. FAQ and troubleshooting 22
16. Glossary 24

Appendix - For the administrator 25

How to read this guide

- **Blue bold words** are the exact names you see on the screen (pages, buttons, fields).
- `Grey boxed words` are the exact messages ATP shows.
- A path such as **Settings › Trade settings › Position size** means: open Settings, then Trade settings, then the Position size section.
- Each big step ends with a green **Check** line. If you do not see what it says, read the FAQ (section 15).
- Some parts appear only when your platform has switched them on. They are marked **may be off**.

1. What a "bot" is in ATP

A **trading bot** is your own strategy, switched on for one symbol, that ATP checks again and again on its own. When the strategy's conditions are met on a closed candle, the bot sends one entry through the same order path that a manual order uses. Your own settings decide the size, the exits and whether it asks you first.

On the screen the menu entry is **AI Trading Bot** (in the BUILD section). The page itself is titled **Trading bot**. The bot does not think for you. It only follows the rules you picked.

The pieces

Piece	What it is, in plain words	Where you see it
Strategy (the rules)	The conditions that must be true on the chart for an entry, for example "a level breaks and the price comes back to it". It produces a **signal**, not advice.	**Strategies › Library / Build**
Backtest (the test)	The same rules run over past candles, to see how often they fired and what those trades did. It is a test of the rules, not a promise.	**Strategies › Test**, or the **Result** step of Build
Deployment (the running bot)	One strategy + one symbol + your choices (size, how entries are sent, Ask me first or not). Each one is a card under **Your bots**.	**AI Trading Bot** page
Trading worker (the engine)	A program on the ATP server that checks every running bot on a fixed rhythm, even when your browser or phone is closed.	You see its result on the bot card: `Checked just now`
PAPER vs LIVE	PAPER = practice money at real market prices; nothing reaches your broker. LIVE = real orders at your broker. Today the platform is PAPER only.	Badge on each bot card and approval
Your own settings	Position size, Risk limits, exits, holding, order type, paper capital. ATP pre-chooses none of them. Each starts as `Not set`.	**Settings › Trade settings**, **Settings › Risk limits**




Figure 1. The pieces of a bot, left to right.

> **One idea to keep:** the strategy gives a **signal**. Everything about the trade itself - lots or quantity, exits, how the order is sent, whether you approve first - comes only from **your own** settings. If one of them is `Not set`, the bot places nothing and tells you which setting it needs.

2. Before you start: what you need

You need	Why	Where
An ATP account	Every bot, setting and trade belongs to your account.	The sign-in screen
A connected broker	Even a **paper** bot reads live prices through your broker. Without one, Start on paper is refused.	**Settings › Account & broker › Broker accounts**
Your own Trade settings	Holding, order type, position size, paper starting capital, New entries. Each starts `Not set`.	**Settings › Trade settings**
Your own Risk limits (optional)	Each check is a switch, **off by default**. Turn on only what you want.	**Settings › Risk limits**
A strategy	From the Library, a template, the builder or the Copilot.	**Strategies**

The order of the steps




Figure 2. The eight steps of this manual.

Where things are in the menu

Menu section	Entries
TRADE	Today, Terminal (or Charts and Option chain), My trades (Positions · Orders · Money · Results)
FIND	Find setups, Signals, Sectors & indices
BUILD	Strategies (Library · Build · Test), AI Trading Bot
LEARN & AI	AI Copilot, Learn
ACCOUNT	Settings (Broker accounts are inside Settings)

On a phone, the bottom bar shows the first four entries and a **More** button. Every page can also be found with the search in the top bar.

Tip: **Settings › Set up your account** has a short "Get started" list: **Connect your broker**, **Start your trading bot**, **Get alerts on your phone (Telegram)**.

3. Step 1 - Sign in

1.1 Open the ATP website. You see the sign-in screen with the heading **Sign in**.

1.2 New user: press **Create an account** (under "New here?"). Type your **Email** and a **Password** (at least 10 characters, not a common password). If you were given a beta code, press **Have a beta invite code?** and type it. Accept the terms if the screen asks, then press **Create account**.
If the screen says "New here? Ask your team owner for an invite link.", sign-up is by invitation: ask the person who runs your team.

1.3 Existing user: type **Email** and **Password**, then press **Sign in**. Other sign-in ways may be listed above the email box (for example **Continue with your broker**).

1.4 If two-step sign-in is on for your account, the screen **Two-factor check** asks for the 6-digit **Authenticator code**; press **Verify**.

1.5 Forgot the password? Press **Forgot password?**, then **Send reset link**, and follow the email.

Check: you should now see the **Today** page and the menu (TRADE, FIND, BUILD, LEARN & AI, ACCOUNT).

4. Step 2 - Connect your broker (or practise without one)

Connect

2.1 Open **Settings › Account & broker › Broker accounts** (search "broker" also finds it). The page is about one thing: **Connect your broker**, with a tile for each broker. A tile marked **Coming soon** cannot be connected yet.

2.2 Press your broker's tile. A connect panel opens with the fields that broker needs, each with a short hint ("From step N"). Fill them in and confirm.

2.3 When it works, the panel says `Connected ✓` and the broker appears under your brokers with its status.

The daily login for orders

Some brokers end their login every morning. For Upstox the screen explains two kinds of connection:

Connection	What it does (words from the screen)
Analytics Token	"charts and market data, saved once a year. It cannot place orders."
Upstox login	"needed for orders. Upstox ends it every morning." The dialog title is **Upstox login for orders**: "Once each trading day, before orders."

A data-only Upstox row shows the button **Log in for orders**. Other rows may show **Connect again** or **Remove**. When a login has ended, the top bar's price dot says `Broker login needed`.

> **For a PAPER bot:** ATP needs a stored broker connection to read prices. The start check refuses a paper bot only when **no** broker is stored. The daily "login for orders" matters for orders at the broker (LIVE). If the worker cannot read prices, the bot card shows a waiting line such as `Waiting: broker login needed`.

Practise without a broker

Without a broker you can still: sign in, read **Learn**, browse **Strategies › Library**, save your **Trade settings** and **Risk limits**, and set up a strategy in **Strategies › Build**.

You cannot start a trading bot. The page shows `A trading bot reads live prices from your broker. Connect your broker first.` and the server says `Connect your broker on the Broker page first: even a paper bot reads live prices through your broker.`

Tests on past prices also ask for the broker: `Connect your broker on the Broker page to run this on real prices.` (Made-up "sample" prices are kept for the platform administrator only.)

Check: you should now see your broker listed on **Broker accounts**, and the Settings row in the menu without a red or amber dot.

5. Step 3 - Save your own Trade settings and Risk limits

Open **Settings › Trade settings**. The page opens with: `ATP sets no trading value for you. Every choice starts as Not set until you save your own.` Each section is a card with its own Save button (for example **Save position size**). After a save you see `Saved.` (or `Nothing changed.`). Under each field it says **Saved: …** or that it is Not set. Facts set by the exchange or your broker sit under **Set by the exchange or your broker**; you cannot change those.

The sections and the fields a bot reads

Section	Field (screen name)	What it decides for a bot
Order defaults	**Holding**: Intraday / Carry forward	Close the same day or carry forward. A bot with no holding of its own and this Not set places nothing.
	Order type (incl. **Limit with price protection**), **Price protection** %	How the bot sends its entries. If Not set, the bot form asks.
	Product (MIS / NRML)	The broker product for a futures or options order.
Position size	**Size by**: Fixed lots / Fixed quantity / % of capital / Risk-based (Risk limits)	How the size of a new entry is worked out.
	Lots, **Quantity**, **Share of capital**	The number for the way chosen. If none, the bot form asks "Lots for this bot" or "Shares for each entry".
Exits	**Square-off time** and the multi-leg answers	"Intraday positions are closed at this time. Not set: ATP closes nothing by itself." The fact **Exits always work** is listed here.
Options	**Expiry**, **Strike**, **Strikes away from ATM**, **Option side**, **Spread width**	Which contract an option or futures bot trades. If Not set, the bot form asks.
Risk limits	A few switches (India VIX check, overnight written straddles / strangles)	The main checks are on their own page (below).
Automation	**New entries**: Placed automatically / Ask me first	Whether your bots place an entry by themselves or ask you first. Not set and not chosen on the bot = the bot places nothing.
	An entry request waits (minutes), **New entries from** / **New entries until**	How long an "Ask me first" request stays open; a time window for new entries. "Exits always work."
Paper account	**Starting capital** (₹), **Charges**, **Brokerage per order**, **Slippage**	The practice money. If Starting capital is Not set, an automatic paper entry places nothing. Charges Not set = statutory charges only, no brokerage, no slippage.

Stop-loss and target values for a bot are not typed here. They come from the strategy (the builder's **Exits: your own values**, a template's **Exits for this bot**, or the full form under **More ways to trade**). See sections 6 and 8.

Settings › My trading defaults is different: it holds starting values that pre-fill a new bot form. On the bot form you can untick **Use my defaults for this bot**.

Risk limits

Open **Settings › Risk limits**. It says: "Turn on only the checks you want. Off: your order is the lots you type. Exits are never checked." Every switch is **off by default**.

Check (screen name)	What it does when on
Max lots per order	An order above this size is not placed; you are offered this size instead.
Max open positions	No new entry while you hold this many. A spread counts as one.
Daily loss limit (% or ₹)	Once today's loss reaches it, no new entry today. Exits always work.
Max new entries per day	No new entry after this many today.
Cool-down after losses in a row	After this many losses in a row, new entries pause for these minutes.
Minimum reward:risk	A trade whose target pays less than this for each rupee at risk is not placed. (Only if you turn it on.)
Margin safety	Plan to use at most this share of your available margin.
Risk-based sizing	The size is your risk per trade divided by the stop distance, in whole lots.
More checks: Risk across open positions · Cool-down after a stop-out · Drawdown steps · Market event days · Two bots on opposite sides of one symbol · Account basis for the % limits (₹)	

Press Save risk limits. A block message later links straight to the check that held an entry back.

The minimum before a first paper bot

Set this	Where	Or
Starting capital	**Trade settings › Paper account**	-
Holding	**Trade settings › Order defaults**	Some bots carry their own (a daily strategy holds for days)
Order type	**Trade settings › Order defaults**	Pick it on the bot form
Size	**Trade settings › Position size**	Type it on the bot form
New entries	**Trade settings › Automation**	Pick it on the bot form

> **Nothing is pre-chosen.** ATP never fills a trading value for you. Next to a field on a form you can tick Save as my default to store it in your Trade settings.

Check: you should now see **Saved: …** under Starting capital, Holding, Order type, your size and New entries, and the count of checks that are on at the top of Risk limits.

6. Step 4 - Pick or build a strategy (every way that exists)

Way	Where	What you get	Switch
A. Library (ready-made)	**Strategies › Library**	Built-in strategies with their settings; Try it on a symbol	always
B. Templates	**Strategies › Library**, section Templates	Signal recipes; Use on the trading bot / Test it first. Paper only.	may be off
C. The builder	**Strategies › Build**	Your own rules in five steps, then a test	always
D. Copilot chat card	AI Copilot › Ask	A draft from your words; you fill every value	may be off
E. Strategy interview	AI Copilot › Advanced › Idea builder › Advanced: the strategy interview	Questions first, then a plan you can start on paper	may be off
F. Pine Script	Find setups › Advanced › Pine Script	Translates a TradingView Pine condition into a **screen**. It is not a bot.	may be off

"May be off" means your platform switches that part on. If you do not see it, it is not on for your account yet (a template card then says `Not switched on for your account yet`).

A. Library

A1 Open **Strategies › Library** ("Ready-made strategies to try on paper."). Filter by category or search.

A2 Open a card: Main settings, More settings, How it reads the chart. A built-in's stop and targets are shown apart with `Suggested — change in settings`.

A3 Try it on a symbol opens a drawer: type a Symbol and see how the strategy reads it now (with Open chart). Nothing starts.

B. Templates may be off

B1 Under Templates, each card shows the idea and "A signal reads: ...", and Settings and rules.

B2 Press Test it first (opens Strategies › Test with the template picked) or Use on the trading bot (opens the bot form with it picked). Nothing starts from the Library.

C. The builder (Strategies › Build)

"Five short steps: start, market, entry, exits, result. Then start it on paper."

Step	What you do
Start	Pick a starting point: Bull put spread · Bear call spread · Iron condor · Pullback to a demand / supply area · Breakout and retest · My own rules. Or Or describe it in your own words → type Your idea → Read my words. It lists **Understood**, **Not in the builder yet (left out)** and **Not understood**. (A card marked Coming soon cannot be picked yet.)
Market	Symbol (or Other → Symbol name), Timeframe (1m ... 1D), side: Long / Short / Both.

Entry	Blocks: an indicator compared with a number or another indicator. A block with a missing value says `Needs your value`. A template brings its own entry.
Exit & risk	Exits: your own values: Stop (x ATR), Target 1 (R), Target 2 (R), Minimum R:R. `A blank box is off: no stop-loss, no target, no minimum R:R.` Then What to trade (option structure, strikes, width, Lots).
Result	Save and test on past prices → Result on past prices → Start on paper ("Opens the Trading bot with this strategy picked. Nothing starts until you press Start on paper there.")

The older full builder is still under **Advanced** on the Build page.

D. The Copilot chat strategy card may be off

D1 In AI Copilot, describe your rules in your own words.

D2 The answer's button opens the Trading bot page with the card Your draft from the Copilot: the rules per side, Values you decide (empty until you fill them - the Copilot never suggests a number), and Left out of this draft.

D3 Press Save as my strategy (or Save and go to Start after a test), or Discard the draft. The saved strategy is then picked in the start form. Only a complete draft tested on past data shows the button Start this strategy in the chat.

E. The strategy interview may be off

It asks before it answers: capital, how much loss you can carry, how you want to trade, what and how much time you have. Then it reads the market candles, builds a plan and can start it on **PAPER**. Values it proposes are shown for you to accept; nothing is placed by it.

F. Pine Script may be off

"Paste a TradingView Pine script: see what translates, read each condition in plain words and run it as a screen. The script is never run." It makes a **screen** (a list of matching symbols), not a bot.

Check: you should now see your strategy in the Pick a strategy list of the Trading bot page - under **Ready-made**, **My strategies**, **More from the Library** or **Strategy templates**.

7. Step 5 - Test first: the backtest

A backtest runs the same rules over past candles: one entry per signal bar, your exits, and Indian charges. Two places:

- **Strategies › Build**, step **Result**: **Save and test on past prices** (or **Test on past prices** for a template).
- **Strategies › Test** (page **Backtesting**): pick **Strategy**, **Symbol**, optional **Advanced settings** and **Trade as** (underlying or options), then **Run Backtest**.

What the numbers mean

Number	Meaning
Trades / Total Trades	How many entries the rules made on those candles.
Win rate	Share of trades that closed with a profit.
Net P&L	Total profit or loss after the charges counted, in rupees.
Max drawdown	The deepest fall from a high point of the equity line.
Average R	Average result as a multiple of the risk per trade. Shows `Needs your stop` when you set no stop.
Profit factor	Gross profit divided by gross loss.
Avg win / Avg loss	The average winning and losing trade.
Expectancy (per trade)	The average result of one trade.
Equity	A small line of the account value trade by trade.

Behind tabs you see the trades list, a chart with entries and exits, and more analytics (for example most wins / losses in a row). `No trades: the entry did not fire on these prices.` means the rules never met.

> **No performance claims.** The page footnote says: "Backtests use past prices; past results do not promise future ones. Paper money only." A good or bad test does not tell you what will happen. Use it to check that the rules do what you meant.

Check: you should now see **Result on past prices** with Net P&L, Win rate, Max drawdown, Trades, Average R and Equity, and the button **Start on paper**.

8. Step 6 - Deploy on PAPER: "Start a trading bot"

Open **AI Trading Bot**. The page **Trading bot** says: "Your strategy trades with paper money here, so you can watch how it does. No real money is used." Press **Start a trading bot** (it jumps to the form). There is **no LIVE switch** on this page.

6.1 **Pick a strategy** (field 1). Groups: Ready-made, My strategies, More from the Library, Strategy templates. One line under it says what it waits for. For a template, also choose **Chart timeframe**; **About this template** says it starts with the template's usual settings.

6.2 **Pick a symbol** (field 2). Pick from the list or type it as the exchange writes it. If empty: `Pick or type a symbol.` An index is traded through its options or futures, not as shares.

6.3 **Exits for this bot** (templates only): **Stop** (for example "Where the idea is wrong") and **Take profit** ("No fixed target", "At a multiple of my risk" → **Times my risk**, "When the template says the idea has ended", "Where the wave projection points"). Notes under it say what still applies, e.g. "Trailing, break-even and time exits work as before."

6.4 **Option choices** (option symbols only), shown only if your Trade settings do not have them: **How this bot trades the option**, **Expiry**, **Strike**, **Strikes away from ATM**, width. "The strategy only gives the side. Nothing is chosen for you."

6.5 **Size**, shown if your Position size is Not set: **Lots for this bot** (options / futures) or **Shares for each entry** (shares), 1 to 500.

6.6 **New entries**, shown if Automation › New entries is Not set: **Placed automatically** or **Ask me first**.

6.7 **How this bot sends its entries**, shown if your Order type is Not set: **Market** or **Limit with price protection** (then **Price protection (%)**, 0.05 to 5).

6.8 Read the summary line, for example "Trades ... shares, 2 per entry." Under **Details**: how long it holds and "Paper money only; your risk limits apply." If your defaults apply, a box says so with **Use my defaults for this bot**. For a derived contract a preview shows what each side would trade now.

6.9 Press **Start on paper**. It stays off, with one line saying why, until every needed field is set.

If the form shows a "needs" line

Message under the button	What to do
`Pick or type a symbol.`	Fill field 2.
`Enter how many lots this bot trades (1 to 500).` / `Enter how many shares this bot trades on each entry (1 to 500).`	Type the size, or save it once in **Settings › Trade settings › Position size**.
`Choose whether this bot places entries by itself or asks you first.`	Pick New entries, or save it in **Trade settings › Automation**.
`Choose how this bot sends its entries.`	Pick Market or Limit with price protection.
`Enter the price protection % (0.05 to 5).`	Type the band.

`Needs your setting: Expiry.` / `Strike.` / `Strikes away from ATM.`	Pick it in the option box, or save it in **Trade settings › Options**.

Tick **Save as my default** beside a field to store it for next time.

After you press Start on paper

Success: `Started on paper: SYMBOL. It shows under Your bots and starts checking the market on its next round.`

Refusal	Meaning
`Connect your broker on the Broker page first: even a paper bot reads live prices through your broker.`	Go back to Step 2.
`This strategy already runs for this symbol in your organisation. Stop that bot first, or pick another strategy or symbol.`	One running bot per strategy + symbol.
"The … options are not loaded yet, so the bot cannot pick a contract. Ask your admin to sync the instrument list, or check the symbol."	The contract list is missing on the platform.
"The … plan allows N active deployment(s); you have N."	Your plan's bot count is reached.
`Your role cannot start a bot. Ask your organisation's owner.`	Your team role has no permission.

More ways to trade (options, futures, exits, filters) on the same page opens the full form (option structures, exits such as trailing stop, break-even and time exit, filters). It is paper only here.

Check: you should now see your bot under **Your bots** with `Running`, `Not checked yet` or `Checked just now`, and `No signal yet`.

9. Step 7 - Watch the bot card, approvals and notifications

What the bot card shows

Part of the card	Example words
Name and mode	The strategy name; a LIVE badge only on a live bot
What it trades	Chips: "SYMBOL options" / "SYMBOL futures" / the symbol, and "During the day" or "Held for days"
State	`Running`, `Paused` (with a reason, e.g. `Paused by you`), `Stopped`
Last check	`Checked just now`, `Checked 3 min ago`, `Not checked yet`
Last signal	`Last signal 12 min ago` or `No signal yet`
Waiting line	`Waiting: market closed`, `Waiting: more candles needed`, `Waiting: market data is behind`, `Waiting: broker login needed`, `Waiting: practice (PAPER) only for now`
Problem chip	`Last check failed · retrying`
New entries	"Asks you first" / "Places entries by itself" / "New entries not set - places nothing", with "(from your Trade settings)" or "(this bot's own choice)"
Open trades	The bot's own open positions with P&L and an exit button
Why no trade? Last bars **may be off**	The last closed bars, newest first, each with its reason (table below)

If the engine itself is silent, the list shows `Bots are not being checked right now`.

"Why no trade?" reasons

Reason on the card	Reason on the card
A trade was placed	Sent to you for approval
No setup on this bar	Same setup as before - already handled
A position from this bot is already open	Another of your bots holds the other direction on this symbol
Needs your setting in Trade settings - nothing was placed	Your risk settings held the entry back
Past your last time for new entries	Prices were late - the bar was skipped
Not enough bars yet to read the chart	No contract matched your option / future settings
The broker account was not ready	The market was closed
A short cannot be carried overnight in cash shares	Your OI checks held the entry back

The detail line under a "Needs your setting" row names the field and where to set it, for example `Needs your setting: Holding (Settings › Trade settings › Order defaults)`, `Needs your setting: New entries (Settings › Trade settings › Automation)`, `Needs your setting: Lots (Settings › Trade`

`settings › Position size) - nothing was placed`, `Needs your setting: Starting capital (Settings › Trade settings › Paper account)`.

"Ask me first": approving an entry

7.1 When the bot's rules meet, it sends you a request instead of placing (card reason: `Sent to you for approval`).

7.2 Open **Signals** ("Trades your trading bots, scans and Copilot suggest."). The item shows a **PAPER** chip.

7.3 Press **Approve paper trade** or **Skip**. A request you do not answer expires after your **An entry request waits** minutes. The page footnote: "You approve every order."

Notifications

- **Inbox**: **Settings › Trading › Inbox**. Entries, exits, refusals, risk blocks, a daily loss limit, a bot paused after repeated failures, approvals waiting, and an end-of-day summary.
- **Telegram** may be off: **Settings › Alerts** → **Connect Telegram**. Use **Send test** to check.

Check: you should now see the card's last check time moving (for example `Checked just now`) while the market is open, and new items in Signals or the Inbox when the rules meet.

10. Step 8 - Pause, stop and exit

Action	Where	What happens
Pause	Bot card › Pause	No new entries while paused. State shows `Paused by you`. Resume starts it again.
Stop	Bot card › Stop → Yes, stop it (or Keep it running)	"It takes no new trades. An open paper trade is still watched until it closes." A stopped bot cannot be resumed; start a new one.
Remove	Stopped bot › Remove (shown only when it has no open trade)	"It leaves your list of bots. Its closed trades stay in your trade history..." Show stopped bots (N) lists them.
Exit a trade	The bot card's open trade, or **My trades › Positions** › Exit now	Closes that paper position at the current price. Never blocked.
Exit all	**My trades › Positions** › Exit all (two or more positions)	It asks first, with the open P&L: "Exit all N open positions at the current price? Sold legs close first, then the legs that protect them." It closes PAPER positions; a LIVE one closes in your broker's app, as its row says.

> **Order of safe stopping:** (1) Pause or Stop the bot so it takes no new entries; (2) close any open trade with Exit now or Exit all if you want it closed now. Stopping alone does not close an open trade.

ATP also pauses a bot by itself after several failed checks in a row (the card says why), and new entries wait when a kill switch is on (section 11).

Check: you should now see the bot as `Paused` or `Stopped`, and no open position for it in **My trades › Positions** if you exited.

11. How a bot works after you start it (one cycle)

The trading worker runs on the server, apart from the website. Closing your browser or phone does not stop it. About once every minute (one base candle; the platform sets the exact rhythm) it does one **cycle**:




Figure 3. Timeline of one worker cycle. Exits are handled before any new entry.

The main rules of the cycle

Rule	In plain words
Closed candles only	The decision uses closed candles. The candle still forming is dropped, the same as in the backtest.
Exits before entries	Open positions are checked against live prices (stops, targets, your square-off time if you set one) before any new entry.
One entry per signal bar	The same bar is never entered twice. If the strategy is still "in signal" on later bars, the card says "Same setup as before - already handled".
One position per bot	While its trade is open, the bot takes no new entry.
Late prices are skipped	If the candle feed is behind the clock, no signal is taken on it.
Same order path	A bot entry goes through the same checks and order record as an order you place yourself.
Your settings decide	Missing Holding, New entries, size or Starting capital = nothing placed, with "Needs your setting".
Kill switch	While a kill switch is on (whole platform, your account, or one strategy), no new entries go out. Exits still work. A risk-limit block on PAPER never turns a kill switch on.
Auto-pause	A bot that fails several checks in a row is paused, with an alert. A data problem resumes by itself when data returns.

12. PAPER first, and how LIVE is switched

Said plainly

- Today the platform is in **Phase 0: PAPER only**. Every new LIVE entry is refused.
- The LIVE switches belong to the **platform owner / administrator only**. A user cannot turn LIVE on from his own screens.
- The Trading bot page has no LIVE switch at all. Strategy templates run on paper only.

Why PAPER first

- Paper uses real market prices but practice money. Nothing reaches your broker.
- You see how your rules, your size and your limits behave, with no money at risk.
- You learn the screens: approvals, "Needs your setting", exits, pause and stop.

What LIVE needs (when the owner allows it later)

#	Condition (from the code)	Who
1	The platform's PAPER-only lock is off and LIVE trading is switched on	Owner / admin
2	Your role has live permission and your plan includes live trading	Admin
3	Your email is verified; two-step sign-in; a fresh authenticator check when creating a LIVE bot	You
4	A usable broker login (the daily login for orders)	You
5	The go-live checklist (**Settings › Advanced**, shown only once the PAPER-only lock is off)	You + admin

Even with "Ask me first" on a live bot, Phase 0 places an approved entry as a paper order ("Approve (paper order)").

13. Safety boxes

The AI never places orders

The AI Copilot can draft a strategy, explain a chart or propose an alert. It never places, blocks or changes an order. An order happens only when **you press Place / Approve**, or when **your own saved bot rules** do it inside the order path. A Copilot draft must be saved by you and started by you.

Exits are never blocked

No setting, limit, window or kill switch holds back a stop, a target or **Exit now**. Trade settings lists it as a fact: "No setting holds back a stop, a target or Exit now." Risk limits: "Exits are never checked."

Your own limits

Every Risk limit is your own switch, off by default. Turn on what you want: daily loss, max open positions, max lots, cool-downs and more. A team admin may set a ceiling above yours; then a message says `Ask your admin`.

Nothing is pre-chosen

ATP never fills in lots, quantity, capital, exits, order type or holding for you. Templates and the Copilot may *suggest*; nothing applies until you save it.

Signals, not advice

A bot's signal says that **your** rules were met on the chart. It is not a recommendation. Past results and paper results do not promise anything.

14. Worked example: from template to paper bot (made-up numbers)

> **Everything here is synthetic.** "DEMO" is not a real symbol. The numbers only show how to read the screens. They are not a result of any real strategy and say nothing about the future.

A. The trader's own settings (his choices, not ATP's)

Setting	Where	His value
Starting capital	Trade settings › Paper account	₹2,00,000 (practice)
Charges	Trade settings › Paper account	Statutory charges only
Holding	Trade settings › Order defaults	Intraday
Order type	Trade settings › Order defaults	Market
Size by / Quantity	Trade settings › Position size	Fixed quantity / 10
New entries	Trade settings › Automation	Ask me first
Daily loss limit	Settings › Risk limits	On, ₹2,000
Max open positions	Settings › Risk limits	On, 2

B. Pick and test

1. **Strategies › Library › Templates** → a breakout-and-retest template → **Test it first**.
2. On **Backtesting**: Symbol "DEMO", the template's timeframe → **Run Backtest**.
3. He reads the (made-up) result:

Total Trades	Win Rate	Net P&L	Max Drawdown	Profit Factor	Expectancy
24	41.7%	−1,180.00	3,450.00	0.93	−49.17

How to read it: 24 entries; 10 closed with a profit (41.7%); after charges the total was a loss of ₹1,180; the deepest fall was ₹3,450; gross profit was a little less than gross loss (0.93). He decides himself whether the rules did what he meant. ATP gives no verdict.

C. Start on paper

1. **Use on the trading bot** → the form opens with the template picked.
2. Pick a symbol: "DEMO". **Exits for this bot**: Stop "Where the idea is wrong", Take profit "At a multiple of my risk", Times my risk "2".
3. No size, entry style or New entries box appears: his Trade settings already hold them.
4. Summary: "Trades DEMO shares." → **Start on paper** → `Started on paper: DEMO. …`

D. One cycle, with made-up prices

Moment	What happens	What he sees
Candle closes	The rules are met on the closed candle; the area is ₹101.20 - ₹101.60 (synthetic).	-
Checks	New bar, Intraday set, no open position, inside the window.	-

Ask me first	A request is sent instead of an order.	Card: "Sent to you for approval". Signals: **Approve paper trade** / **Skip**
He approves	Order path: limits pass (no loss today, 0 of 2 positions), 10 shares, paper fill at ₹101.50, stop stored at ₹100.40.	Inbox: an entry notice. Card: open trade with P&L
Later cycles	Exits first: the stop and target (2 × risk = ₹103.70) are checked on live prices.	P&L moves on the card
Exit	Either level is reached, or he presses **Exit now**.	Inbox: an exit notice; the trade moves to history

Risk per share = 101.50 − 100.40 = ₹1.10. Risk for 10 shares = ₹11. The target at 2 × risk = 101.50 + 2.20 = ₹103.70. All synthetic.

15. FAQ and troubleshooting

Common "Needs your setting" messages

Message	Fix
`Needs your setting: Holding (Settings › Trade settings › Order defaults)`	Save Holding, or start the bot with its own holding.
... "your Carry forward setting does not fit this bot (it reads ... candles) - set this bot's own holding"	Carry forward fits a daily-candle bot or a spread held for days. Give this bot its own holding.
`Needs your setting: New entries (Settings › Trade settings › Automation)`	Choose Placed automatically or Ask me first.
`Needs your setting: Lots (Settings › Trade settings › Position size) - nothing was placed`	Save a size, or type it on the bot form.
`Needs your setting: Starting capital (Settings › Trade settings › Paper account)`	Save your paper starting capital.
`Needs your setting: Expiry.` / Strike / Strikes away from ATM	Pick them on the form or save them in Trade settings › Options.
Card: "New entries not set - places nothing"	Same as New entries above.

"Why did my bot not trade?"

What you see	Meaning / what to do
No setup on this bar	The rules were not met. Normal.
Waiting: market closed	The bot checks only while the exchange session is open.
Waiting: more candles needed / Not enough bars yet	The strategy needs more history first. It goes on by itself.
Prices were late / Waiting: market data is behind	The feed fell behind; the bar was skipped.
Waiting: broker login needed	Log in to your broker again on Broker accounts.
Past your last time for new entries	Your New entries until time has passed. Exits still work.
A position from this bot is already open	One position per bot.
Your risk settings held the entry back	A Risk limit you turned on said no. The message links to the check.
Sent to you for approval	"Ask me first" is on. Approve it in Signals.
No contract matched your option / future settings	Check Expiry / Strike rules and the symbol.
Last check failed · retrying / Paused after failures	Read the reason on the card; resume when fixed.
Bots are not being checked right now	The engine is silent. Tell your platform admin.
Waiting: practice (PAPER) only for now	A LIVE bot during Phase 0. Use PAPER.

Short answers

- **Does the bot stop when I close the app?** No. It runs on the server.
- **Can I start two bots on the same strategy and symbol?** Not while one is running or paused; stop it first.
- **Does Stop close my trade?** No. Close it with Exit now / Exit all.
- **Can a limit block my exit?** No. Exits are never blocked.
- **Can I switch a bot to LIVE?** No. LIVE is the owner's / admin's switch, and Phase 0 is PAPER only.

16. Glossary

Word	Meaning
Bot / deployment	A strategy switched on for one symbol, checked by the worker.
Strategy	Your set of chart conditions that produce a signal.
Signal	The moment your conditions are met on a closed candle. Not advice.
Template	A ready signal recipe with settings you can change.
Backtest	Running the rules over past candles.
Worker	The server program that checks bots on a fixed rhythm.
Cycle	One round of the worker over all running bots.
Closed candle	A candle whose time is over; its open, high, low and close are final.
PAPER	Practice money at real prices. Nothing goes to the broker.
LIVE	Real orders at your broker. Locked in Phase 0.
Phase 0	The current stage: PAPER only.
Not set	A setting you have not saved. ATP does not fill it.
Ask me first	The bot sends you a request; nothing is placed until you approve.
Holding	Intraday (close the same day) or Carry forward.
Lot	The exchange's unit for futures and options; a size is a whole number of lots.
R / R-multiple	Result measured in units of the risk taken (entry to stop).
ATR	Average true range: a measure of how much price usually moves per candle.
Drawdown	A fall from a high point of the account value.
Price protection	A market entry sent as a limit a set % past the price.
Square-off	Closing intraday positions at a time you set. Not set: ATP closes nothing by itself.
Kill switch	A stop for new entries (platform, account or one strategy). Exits still work.
Analytics Token	A broker connection for data only; it cannot place orders.

Appendix - For the administrator

Platform switches (feature flags) that change what a user sees in this guide. Users never see these names.

Flag	Effect on this guide
`ui_v2`	The screens described here (Trading bot page, Build in five steps, Settings index, Trade settings).
`strategy_templates`	Templates in Library, Build start cards, Test and the bot list.
`ai_copilot`	The Copilot, its draft card, the strategy interview, the strategist.
`strategy_lab_pine`	Pine Script panel on Find setups (screen only).
`why_no_trade`	"Why no trade? Last bars" on the bot card.
`telegram_inbound`	Two-way Telegram (commands and PAPER approvals).
`phase0_paper_only`	ON: every new LIVE entry refused. Owner only.
`live_trading`	New LIVE deployments. Owner only. Also needs the user scope `trading:live`, a live-capable plan, verified email and step-up.
`multi_account`	"Practice accounts" (extra paper accounts) on the Broker page.
`market_store_reads`	Store-first candles for the worker and backtests.

Operator settings: worker cycle length (default 60 s), auto-pause after consecutive failures (default 5). Sample data is visible to the platform admin only under the new UI.

Points the code did not make fully clear (to confirm before the video)

1. **Python Strategy Lab:** no Python strategy lab was found in the code. The only "code" path is the Pine Script translator, which makes a screen, not a bot.
2. **User kill switch button:** the server has account and strategy kill switches; no button to press one was found in the user screens (the Terminal status bar shows "New orders stopped / allowed"; the admin console has the global switch).
3. **Library stop / targets:** a built-in's stop and targets are labelled "Suggested — change in settings", but the three-step bot form has no field to change them; the start request carries no strategy settings. Where a user edits them for a Library bot is not clear.
4. **Paper bot and the daily login:** a paper start needs only a stored broker connection; whether an Analytics-token-only connection keeps a paper bot's candles flowing all day for every broker was not proven from the code.
5. **Build test without a broker:** the builder's test asks for stored history first; whether it runs with no broker for a new user was not proven.
6. **Ready-made strategy lines** say "Closes before the market does", while Square-off time Not set means "ATP closes nothing by itself". Which applies to a ready-made intraday bot with no square-off saved needs confirming.
7. **Telegram:** "Connect Telegram" depends on the platform's own Telegram bot token, which is an owner item.