
# **CSC 6580 Spring 2020**

Instructor: Stacy Prowell

## **Assembly Language**

### Resources

- ODA <a href="https://onlinedisassembler.com/odaweb">https://onlinedisassembler.com/odaweb</a>
- X86 Opcode and Instruction Reference <a href="https://ref.x86asm.net">https://ref.x86asm.net</a>
- Intel Documentation (search Intel 64 and IA-32 Architectures Software Developer's Manual)
- The incomplete reference <a href="https://felixcloutier.com/x86">https://felixcloutier.com/x86</a>
- The Compiler Explorer <a href="https://godbolt.org/">https://godbolt.org/</a>



Assembly instructions **read** and/or **modify** processor state and memory (through the processor's interface, the cache controller)

## **Assembly Instructions**

There are a lot. How many? The number varies, depending on how you count.

https://bit.ly/2GmdT7h

Measure	Count	Comment
AT&T mnemonic (e.g., add1)	1,279	Counts the number of unique mnemonics in AT&T syntax.
Intel mnemonic (e.g., add)	981	This is a rough estimate of the number of different kinds of operations the x86 instruction set can perform, ignoring the operand type and size. There are various caveats as described earlier, such as some operations having multiple different mnemonics.
Mnemonic and operand types (e.g., add_r32_imm32)	3,683	Distinguishes instructions in every way possible and is thus a sort of upper bound on the number of instructions. If you are looking for a very fine-grained notion of instruction, this is a good measure.
Mnemonic and operand width (e.g., add_32_32)	2,034	This is an estimate of the number of different kinds of instructions, if an operation on 8 bits is considered to be different from the same operation on 16 bits (because sometimes, these actually have different semantics, as shown with the zeroing of the upper 32 bits for the add1 instruction). Does not distinguish instructions that operate on registers vs. constants vs. memory locations.
Every valid bit sequence (e.g., 0x83, 0xC0, 0x01)	?	Counts every bit sequence that makes a valid x86 instruction. Unfortunately there are too many to count.

## Assembly Instructions

It is arguable that the official documentation is not complete, either.

See the "Sandsifter" project:

https://github.com/xoreaxeax/sandsifter

So even assemblers don't understand the complete x86 ISA.

## Breaking the x86 ISA

Christopher Domas xoreaxeaxeax@gmail.com

July 27, 2017

Abstract— A processor is not a trusted black box for running code; on the contrary, modern x86 chips are packed full of secret instructions and hardware bugs. In this paper, we demonstrate how page fault analysis and some creative processor fuzzing can be used to exhaustively search the x86 instruction set and uncover the secrets buried in a chipset. The approach has revealed critical x86 hardware glitches, previously unknown machine instructions, ubiquitous software bugs, and flaws in enterprise hypervisors.

## **Assembly Instructions**

The Sandsifter project "fuzzed" the Intel chip and discovered lots of undocumented instructions... and also bugs.

Both vary based on the *specific processor* tested.

```
sbb byte ptr [edi], ah
 mov dword ptr [0x141a1726], eax
 xor eax. 0xdlaa9221
 adc dword ptr [esi + 0x46], 0x2084b8d1
 jmp 0x15
 jmp 0x15
push ebp
stosb byte ptr es:[edi], al
scasd eax, dword ptr es:[edi]
stood dword ptr es:[edi], eax
imul esp, dword ptr [edx + ecx*4 - 0x17], -0x75
insd dword ptr es:[edi], dx
                                                   3ed729c7ade1730add527d4c85b0f9c6
```

## **Assembly Instructions**

You are *not expected* to become an expert on assembly language on any platform; there are *very few* of those, and even their knowledge is incomplete and sometimes wrong. You just need to know the basics.

New features are added all the time, for a variety of reasons and sometimes for specific, special cases. Compiler writers struggle to keep up.

(Curious about how compilers work? LLVM has good documentation. <a href="https://llvm.org/pubs/2002-08-09-LLVMCompilationStrategy.pdf">https://llvm.org/pubs/2002-08-09-LLVMCompilationStrategy.pdf</a>)




#### Intel® AVX-512 architecture evolution and support in Clang/LLVM

2014 LLVM Developers' Meeting, Oct 28-29

Robert.Khasanov Zinovv.Y.Nis

@intel.com



#### AVX-512 Features

- 512h-wide vectors(%ZMM0-31)
- · Masked instructions. 64b-mask registers (%KO-7)
- · Gathers/Scatters
- Permutations
- Embedded broadcast



- Compressed displacement
- Embedded suppression of all exceptions

Intel® Architecture Instruction Set Programming Reference

#### AVX-512 in Clang/LLVM


- · Total: 651 instructions, 4000+ intrinsics
- 30% of these instructions implemented
- · Encodings, lowering and intrinsics covered with tests
- 100+ patches, 9000+ LOCs
- Work in progress!

Available in trunk since July 2014! clang -march=knl...

clang-march=skx ...

#### New features AVX-512VL: Vector Length Orthogonality Apply AVX-512F instructions to 128b (%XMM) and 256b (%YMM) registers · AVX-512F (starting with Xeon Phi) VADDPD (%rcx), %zmm2, %zmm3 AVX-512{F,VL} (starting with Skylake Xeon) VADDPD (%rcx), %ymm2, %ymm3 VADDPD (%rcx), %xmm2, %xmm3 AVX-512BW: Byte & word support AVX-512F packed instructions work on double- and quadwords AVX-512BW packed instructions work on byte and words b63 b62 b61 b60 b59 AVX-512BW also introduced 32b and 64b mask instructions Perfect for handling graphics R G B A AVX-512DQ: New HPC instructions Extended Tuple INT64 arithmetic support:







NECESSATION IN THE COLUMENT IS DECIMEN TO DECIMEN TO DECIMEN TO DECIMEN TO DECIMEN THE PROPERTY OF INTERPRETATION FOR THE

ormance only on Intel microprocessors. Performance tests, such as SYSmark and MobileMark, are measured using specific computer systems, or vary. You should consult other information and performance tests to assist you in fully evaluating your contemplated purchases, including the performance of that product when combined with other products. Copyright © 2014, Intel Corporation. All rights reserved. Intel, Pentium, Xeon, Xeon Phi, Core, VTune, Cilk, and the Intel logo are \*Other names and brands trademarks of Intel Corporation in the U.S. and other countries. Intel's compilers may or may not optimize to the same degree for non-intel microprocessors for optimizations that are not unique to Intel microprocessors. These optimizations include SSE3, SSE3, and SSSE3 instruction sets and other optimizations. Intel does not guarantee the may be claimed as the availability, functionality, or effectiveness of any optimization on microprocessors not manufactured by Intel. Microprocessors. Please refer to the applicable product User and Reference Guides for more information regarding the specific instruction sets covered by this notice property of others

Let's answer some questions about this program.

How many times does it loop?

How long does it take? We'll compile it, and then disassemble it using objdump\*\*:

```
$ gcc -c delay.c
$ objdump -d delay.o
```

```
void delay() {
  unsigned char i, j;
  j = 0;
  while(--j) {
    i = 0;
    while(--i);
  }
}
```

<sup>\*\*</sup> We're going to talk more about objdump later

```
void delay() {
  unsigned char i, j;
  j = 0;
  while(--j) {
    i = 0;
    while(--i);
  }
}
```

		-				
00000000000000000	<d< td=""><td>ela</td><td>y&gt;:</td><td></td><td></td><td></td></d<>	ela	y>:			
0:	55				push	rbp
1:	48	89	e5		mov	rbp,rsp
4:	с6	45	ff	00	mov	BYTE PTR
[rbp-0x1],0x0						
8:	eb	0e			jmp	18
<delay+0x18></delay+0x18>						
a:	с6	45	fe	00	mov	BYTE PTR
[rbp-0x2],0x0						
e:	80	6d	fe	01	sub	BYTE PTR
[rbp-0x2],0x1						
12:	80	7d	fe	00	cmp	BYTE PTR
[rbp-0x2],0x0						
16:	75	f6			jne	e
<delay+0xe></delay+0xe>						
18:	80	6d	ff	01	sub	BYTE PTR
[rbp-0x1],0x1						
1c:	80	7d	ff	00	cmp	BYTE PTR
[rbp-0x1],0x0						
20:	75	e8			jne	a
<delay+0xa></delay+0xa>						
22:	90				nop	
23:	5d				pop	rbp
24:	с3				ret	

```
void delay() {
                                                            0000000000000000 <delay>:
  unsigned char i, j;
                                                                           ba ff ff ff ff
                                                                                                       mov
                                                            edx,0xffffffff
  j = 0;
                                                               5:
                                                                           b8 00 00 00 00
                                                                                                             eax,0x0
                                gcc -c -O delay.c
  while(--j) {
                                                                           2c 01
                                                                                                       sub
                                                                                                             al,0x1
                                                               a:
                                                                           75 fc
                                                                                                       jne
                                                               c:
     i = 0;
                                                             <delay+0xa>
                                                               e:
                                                                           80 ea 01
                                                                                                       sub
                                                                                                             dl,0x1
     while(--i);
                                                                           75 f2
                                                              11:
                                                                                                       jne
                                                             <delay+0x5>
                                                              13:
                                                                           с3
                                                                                                       ret
```

```
void delay() {
  unsigned char i, j;
  j = 0;
  while(--j) {
    i = 0;
    while(--i);
  }
}
gcc -c -02 delay.c
  0: c3
ret
ret
ret
```

If you analyze source code, you are analyzing (at best) an approximation of the real behavior.

Compilers can, *and do*, omit code you wrote, insert code you didn't write, and change your code for a variety of purposes. If you want to know (more completely) what a program is going to do, you have to analyze the machine code. Even the output of a disassembler might not be true (which we will see later).

# A Bit on the X86 Instruction Set Architecture (ISA)

## Some X86 Architecture: 16-bit registers

SP

SI

DI

#### 16-bit registers

Accumulator

Base

BX

Counter

CX

Data

DX

Stack Pointer

(Stack) Base PointerBP

Source Index

Destination Index

The AX, BX, CX, and DX registers are high / low byte-addressable.

 $\bullet$  AX = AH.AL

BX = BH.BL

CX = CH.CL

DX = DH.DL

8 bits: A byte

16 bits: A word

## Some X86 Architecture: 32-bit registers

#### Extended registers:

- EAX, EBX, ECX, EDX
- ESP, EBP
- ESI, EDI
- EIP

#### Register aliasing:

#### EAX

= (16 bits).**AX** 

= (16 bits).AH.AL

8 bits: A byte 16 bits: A word

32 bits: A dword (double word)

### Some X86\_64 Architecture: 64-bit registers

"R" is for register.

- RAX, RBX, RCX, RDX
- RSP, RBP
- RSI, RDI
- RIP

But also...

• R8, R9, R10, R11, R12, R13, R14, R15

(RAX through RDI count as R0-R7.)

Aliasing:

RAX

= (32-bits).**EAX** 

= (32-bits).(16-bits).**AX** 

= (32-bits).(16-bits).AH.AL


8 bits: A byte

16 bits: A word

32 bits: A dword (double word)

64 bits: A qword (quadword)

Some X86\_64
Architecture:
64-bit registers &
80-bit registers &
128-bit registers



## Some X86 Architecture: Segment Registers

• (	Code segment	CS	286: CS, DS, SS, ES
-----	--------------	----	---------------------

Data segment DS

Stack segment SS

Extra segment registers ES, FS, GS

The extra segment registers are typically used by the operating system.

386: Added FS, GS

You can read about protected mode and the LDT and GDT. Head to Wikipedia and search Global Descriptor Table.

## Some X86 Architecture: Flags (FLAGS)

```
Carry
                               CF
                                                Direction flag? See the MOVS family of
                                               instructions.
Parity
                               PF (even =
1, odd = 0)
Adjust / Auxiliary AF (4-bit carry)
Zero
                                ZF
                                SF
Sign
                                TF (single-
Trap
step)
Interrupt Enable IF (allowed = 1)
Direction
                               DF
(increment = 0)
Overflow
                               OF
```

IOPL (2

Privilege

## Some X86 Architecture: More flags (EFLAGS)

•	Carry	CF	•	Resume	RF
•	Parity	PF (even =	•	Virtual 8086	VM
	1, odd = 0)			(compatibility = 1)	
•	Adjust / Auxiliary	AF (4-bit carry)	•	Alignment Check	AC (enabled = 1)
•	Zero	ZF	•	Virtual Interrupt	VIF
•	Sign	SF	•	Virtual Interrupt Po	ending
•	Trap	TF (single-			VIP
	step)		•	CPU ID	ID
•	Interrupt Enable	IF (allowed = 1)	•	Virtual Address De	scriptor
•	Direction	DF			VAD
	(increment = 0)			(allowed = 1)	
•	Overflow	OF			

IOPL (2

Privilege

	Intel x86 FLAGS register <sup>[1]</sup>					
Bit#	Mask	Abbreviation	Description	Category	=1	=0
	FLAGS					
0	0x0001	CF	Carry flag	Status	CY(Carry)	NC(No Carry)
1	0x0002		Reserved, always 1 in <b>EFLAGS</b> <sup>[2][3]</sup>			
2	0x0004	PF	Parity flag	Status	PE(Parity Even)	PO(Parity Odd)
3	0x0008		Reserved <sup>[3]</sup>			
4	0x0010	AF	Adjust flag	Status	AC(Auxiliary Carry)	NA(No Auxiliary Carry
5	0x0020		Reserved <sup>[3]</sup>			
6	0x0040	ZF	Zero flag	Status	ZR(Zero)	NZ(Not Zero)
7	0x0080	SF	Sign flag	Status	NG(Negative)	PL(Positive)
8	0x0100	TF	Trap flag (single step)	Control		
9	0x0200	IF	Interrupt enable flag	Control	EI(Enable Interrupt)	DI(Disable Interrupt)
10	0x0400	DF	Direction flag	Control	DN(Down)	UP(Up)
11	0x0800	OF	Overflow flag	Status	OV(Overflow)	NV(Not Overflow)
12-13	0x3000	IOPL	I/O privilege level (286+ only), always 1 <sup>[clarification needed]</sup> on 8086 and 186	System		
14	0x4000	NT	Nested task flag (286+ only), always 1 on 8086 and 186	System		
15	0x8000		Reserved, always 1 on 8086 and 186, always 0 on later models			
			EFLAGS			
16	0x0001 0000	RF	Resume flag (386+ only)	System		
17	0x0002 0000	VM	Virtual 8086 mode flag (386+ only)	System		
18	0x0004 0000	AC	Alignment check (486SX+ only)	System		
19	0x0008 0000	VIF	Virtual interrupt flag (Pentium+)	System		
20	0x0010 0000	VIP	Virtual interrupt pending (Pentium+)	System		
21	0x0020 0000	ID	Able to use CPUID instruction (Pentium+)	System		
22-31	0xFFC0 0000		Reserved	System		
			RFLAGS			
32-63	0xFFFF FFFF 0000 0000		Reserved			

All the flag bits live in the FLAGS register (and EFLAGS and RFLAGS).

You cannot access this register directly... but you can manipulate it using special instructions:

- PUSHF pushes the FLAGS register content on the top of the stack
- POPF loads the FLAGS register from the top of the stack

Similar instructions extend to EFLAGS and RFLAGS.

- LAHF moves FLAGS bits 0-7 into AH
- SAHF moves AH into bits 0-7 of FLAGS

source: https://en.wikipedia.org/wiki/FLAGS register

## **Creating an Assembly Routine**

Given a list of unsigned ints, find the largest. Doing this in C is fairly obvious.

```
unsigned int max(unsigned int count, unsigned int vals[]) {
  unsigned int max = 0;
  for (int index = 0; index < count; ++index) {
    if (vals[index] > max) max = vals[index];
  } // end of for loop
  return max;
}
```

On my 64-bit Ubuntu system, an **unsigned** int is 4 bytes long (32 bits).

Basic function boilerplate first.

- Save the stack pointer: RSP
- Use RBP to access the stack

How do we get the arguments? How do we return the answer?

```
push rbp
mov rbp, rsp
;
; body
;
mov rsp, rbp ; Not always done.
pop rbp
ret
```

## Aside: Calling Convention

Linux, MacOS X, Solaris, and most operating systems use the AMD64 calling convention.

#### https://bit.ly/2TU24Nw

There is actually a lot of information in a calling convention.

Microsoft (and UEFI!) has their own (not shown): <a href="https://bit.ly/2TWA6kd">https://bit.ly/2TWA6kd</a>

		Preserved across
Register	Usage	function calls
%rax	temporary register; with variable arguments	No
	passes information about the number of vector	
	registers used; 1st return register	
%rbx	callee-saved register	Yes
%rcx	used to pass 4th integer argument to functions	No
%rdx	used to pass 3 <sup>rd</sup> argument to functions; 2 <sup>nd</sup> return	No
	register	
%rsp	stack pointer	Yes
%rbp	callee-saved register; optionally used as frame	Yes
	pointer	
%rsi	used to pass 2 <sup>nd</sup> argument to functions	No
%rdi	used to pass 1st argument to functions	No
%r8	used to pass 5th argument to functions	No
%r9	used to pass 6th argument to functions	No
%r10	temporary register, used for passing a function's	No
	static chain pointer	
%r11	temporary register	No
%r12-r14	callee-saved registers	Yes
%r15	callee-saved register; optionally used as GOT	Yes
	base pointer	
%xmm0-%xmm1	used to pass and return floating point arguments	No
%xmm2-%xmm7	used to pass floating point arguments	No
%xmm8-%xmm15	temporary registers	No
%mm0-%mm7	temporary registers	No
%k0-%k7	temporary registers	No
%st0,%st1	temporary registers; used to return long	No
	double arguments	
%st2-%st7	temporary registers	No
%fs	Reserved for system (as thread specific data reg-	No
	ister)	
mxcsr	SSE2 control and status word	partial
x87 SW	x87 status word	No
x87 CW	x87 control word	Yes

## Aside: Calling Convention: TL;DR?

The registers RDI, RSI, RDX, RCX, R8, and R9 (in order) should be used for *integer and memory address* arguments and XMM0, XMM1, XMM2, XMM3, XMM4, XMM5, XMM6, and XMM7 (in order) should be used for *floating* point arguments.

For system calls, R10 is used instead of RCX.

Additional arguments are passed on the stack and the return value is stored in RAX if it is an integer or pointer, and in XMM0 if it is a floating point result. (Sometimes a second register might be used, too.)

You must make sure you *do not modify*, or you *save and restore*, the value in RBP, RBX, R12, R13, R14, and R15.

#### Function boilerplate:

- Save base pointer (because it is probably being used by the calling function) on the stack.
- Move the stack pointer into the base pointer.
- Do stuff...
- Reset the stack pointer to the (unmodified) base pointer.
- Restore the base pointer from the stack.
- Return.

```
push rbp
mov rbp, rsp
  ; Array length is in EDI
  ; Array pointer is in RSI
  ; Return value should be in RAX
mov rsp, rbp
pop rbp
ret
```

Need a scratch register to hold the maximum value (the max variable in the original program); might as well be RAX. Be sure to use a register whose value is not guaranteed to be preserved across a function call.

Need a pointer into the array (the index variable in the original program). Let's use ECX (unsigned int is 32 bits), since it is a scratch register not expected to be preserved.

```
push rbp
mov rbp, rsp
mov rax, 0
mov ecx, 0
    ; Loop goes here
mov rsp, rbp
pop rbp
ret
```

We need the loop index to run from zero up to the value in **EDI**.

Loops in assembly are almost always do-while loops. That is, the body is always executed at least once.

To get a proper while loop we need to test if **EDI** is zero before we start, or we'll have a bug!

We need the loop index to run from zero up to the value in **EDI**.

Loops in assembly are almost always do-while loops. That is, the body is always executed at least once.

To get a proper while loop we need to test if **EDI** is zero before we start, or we'll have a bug!

```
push rbp
      mov rbp, rsp
      mov rax, 0
      cmp edi, 0
      je out
      mov ecx, 0
loop:
          ; Compare goes here
           inc ecx
           cmp ecx, edi
           il loop
out:
           mov rsp, rbp
      pop rbp
      ret
```

Next we need to see if we have found a better maximum value and, if so, replace the current maximum.

To do this, we can use a computed (relative) address.

```
push rbp
      mov rbp, rsp
      mov rax, 0
      cmp edi, 0
      je out
      mov ecx, 0
loop:
          ; Compare goes here
           inc ecx
           cmp ecx, edi
           jl loop
out:
           mov rsp, rbp
      pop rbp
      ret
```

## **Aside: Addressing**

$$\begin{cases} & \text{FS:} \\ & \text{GS:} \end{cases} \begin{bmatrix} \vdots \\ & \text{GPR} \\ \vdots \end{bmatrix} + \left( \begin{bmatrix} \vdots \\ & \text{GPR} \\ \vdots \end{bmatrix} * \begin{bmatrix} 1 \\ 2 \\ 4 \\ 8 \end{bmatrix} \right) \\ & &$$

The X86 ISA computes addresses in a way that is helpful for pointers.

The address is:

+ displacement

[base + index\*scale + displacement]

The base and index are registers, and the displacement is an integer. The scale may be 1, 2, 4, or 8. The register sizes must be the same.

## **Aside: Address Examples**

These are all in Intel syntax. We'll cover AT&T syntax later.

Assume EAX contains 512 and EBX contains 5.

mov BYTE [60], al	Copy the byte at address 60 (in the data segment DS) into AL
mov WORD [rax], ax	Copy the word (16 bits, LE) at address 512 into AL
cmp DWORD [rax+60], ebx	Compare the double word (32 bits, LE) at address 512 + 60 = 572 with the value in EBX
mov rsi, QWORD [rax+rbx*8]	Copy the quad word (64 bits, LE) stored in RSI to address 512 + 5*8 = 552
lea esi, [rax+rbx*4+60]	Copy the address 512 + 5*4 + 60 = 592 into ESI

### **Aside: Math**

Load effective address (LEA) is great for simple math.

Need to compute 756+EAX\*4?

lea eax, [756+eax\*4]

Compare **EAX** to the array value and, if **EAX** is greater, skip replacing it's value.

This kind of "jump over" logic is common.

```
push rbp
      mov rbp, rsp
      mov rax, 0
      cmp edi, 0
      je out
      mov ecx, 0
loop:
      cmp eax, DWORD [rsi+rcx*4]
           jg over
           mov eax, DWORD [rsi+rcx*4]
over:
           inc ecx
           cmp ecx, edi
           jl loop
out:
           mov rsp, rbp
      pop rbp
      ret
```

We don't ever modify the stack, so *technically* we can dispense with the stack stuff.

```
-push rbp
     mov rbp, rsp
      mov rax, 0
      cmp edi, 0
      je out
      mov ecx, 0
loop:
      cmp eax, DWORD [rsi+rcx*4]
           jg over
           mov eax, DWORD [rsi+rcx*4]
over:
           inc ecx
           cmp ecx, edi
           jl loop
out:
          mov rsp, rbp
      ret
```

We don't ever modify the stack, so *technically* we can dispense with the stack stuff.

It's usual to replace:

- cmp rdi, 0 with test rdi, rdi
- mov rax, 0 with xor rax, rax

```
mov rax, 0
      cmp edi, 0
      je out
      mov ecx, 0
loop:
      cmp eax, DWORD [rsi+rcx*4]
           jg over
           mov eax, DWORD [rsi+rcx*4]
over:
           inc ecx
           cmp ecx, edi
           jl loop
out:
      ret
```

We don't ever modify the stack, so *technically* we can dispense with the stack stuff.

It's usual to replace:

- cmp rdi, 0 with test rdi, rdi
- mov rax, 0 with xor rax, rax

```
xor rax, rax
      test edi, edi
      je out
      xor ecx, ecx
loop:
      cmp eax, DWORD [rsi+rcx*4]
           jg over
           mov eax, DWORD [rsi+rcx*4]
over:
           inc ecx
           cmp ecx, edi
           jl loop
out:
      ret
```

Let's assemble it! Put the code in a file called max.asm.

We can call the function if we export it (then we can import it in C). Use global for that.

We can assemble it with NASM\*\*:

```
nasm -f elf64 max.asm
```

```
; nasm -f elf64 max.asm
; gcc -static -o max max.o
global max
max:
      xor rax, rax
      test edi, edi
      je out
      xor ecx, ecx
loop:
      cmp eax, DWORD [rsi+rcx*4]
           jg over
           mov eax, DWORD [rsi+rcx*4]
over:
           inc ecx
           cmp ecx, edi
           jl loop
out:
      ret
```

<sup>\*\*</sup> The Netwide Assembler: <a href="https://nasm.us/">https://nasm.us/</a>

### Aside: Linking Assembly and C

- Create .c files and compile them (gcc -c).
- Create .asm files and assemble them (nasm -felf64).
- Link everything (ld/gcc).
- From assembly use **extern** to declare C functions you need. Then set up the arguments and **call** the function, according to the calling convention.
- From C use **extern** to declare assembly functions you need. Then make sure the assembly handles the arguments according to the calling convention.

### Aside: Linking Assembly and C

• Linking is hard. If you can, you should let gcc do it. You can do it with 1d, but it can be hard.

• Really curious? Run the gcc link with -v at the end.

Here max could be provided by the C function shown earlier, or by the assembly function. It can be provided by anything that satisfies the *calling* convention.

```
$ nasm -f elf64 max.asm
$ gcc -o test test.c max.o
$ ./test
103
$ gcc -c -02 max.c
$ gcc -o test test.c max.o
$ ./test
103
```

Let's look at our program's machine code. We used 0x18, or 24 bytes.

```
0000000000000000 <max>:
   0:
             48 31 c0
                                          rax, rax
                                  xor
             85 ff
                                  test
                                          edi,edi
   5:
             74 10
                                  je
                                          17 <out>
   7:
             31 c9
                                          ecx,ecx
                                  xor
0000000000000009 <loop>:
   9:
             3b 04 8e
                                          eax, DWORD PTR
                                  cmp
[rsi+rcx*4]
             7f 03
                                  jg
                                          11 <over>
   c:
             8b 04 8e
   e:
                                  mov
                                          eax, DWORD PTR
[rsi+rcx*4]
0000000000000011 <over>:
             ff c1
  11:
                                  inc
                                          ecx
  13:
             39 f9
                                  cmp
                                          ecx,edi
  15:
             7c f2
                                  jl
                                          9 <loop>
0000000000000017 <out>:
  17:
             с3
                                  ret
```

C source shown earlier compiled by GCC with -O2 and disassembled with objdump.

Recall: **EDI** is length, **RSI** is array pointer.

```
0000000000000000 <max>:
   0:
             85 ff
                                                 edi,edi
                                         test
   2:
             74 24
                                         je
                                                 28
<max+0x28>
   4:
             8d 47 ff
                                         lea
                                                 eax,[rdi-
0x1]
                                         lea
             48 8d 4c 86 04
rcx,[rsi+rax*4+0x4]
              31 c0
                                         xor
                                                 eax,eax
   e:
             66 90
                                         xchg
                                                 ax,ax
  10:
             8b 16
                                                 edx, DWORD
                                         mov
PTR [rsi]
  12:
              39 d0
                                                 eax,edx
                                         cmp
             0f 42 c2
  14:
                                                eax,edx
                                         cmovb
  17:
             48 83 c6 04
                                         add
                                                 rsi,0x4
  1b:
             48 39 ce
                                                 rsi,rcx
                                         cmp
             75 f0
                                                 10
  1e:
                                         jne
< max + 0x10 >
             с3
  20:
                                         ret
  21:
             0f 1f 80 00 00 00 00
                                                 DWORD PTR
                                         nop
[rax+0x0]
              31 c0
  28:
                                         xor
                                                 eax,eax
             с3
  2a:
                                         ret
```

What's going on here?

Now rcx is the address just past the end of the array. No idea why this is done.

```
0000000000000000 <max>:
             85 ff
                                                 edi,edi
   0:
                                         test
   2:
             74 24
                                                 28
                                         ie
< max + 0x28 >
   4:
             8d 47 ff
                                          lea
                                                 eax,[rdi-
0x1]
             48 8d 4c 86 04
                                         lea
rcx,[rsi+rax*4+0x4]
   c:
             31 c0
                                         xor
                                                 eax, eax
   e:
             66 90
                                         xchg
                                                 ax,ax
  10:
             8b 16
                                                 edx, DWORD
                                         mov
PTR [rsi]
              39 d0
                                                 eax,edx
  12:
                                         cmp
  14:
             0f 42 c2
                                                eax,edx
                                         cmovb
  17:
             48 83 c6 04
                                         add
                                                 rsi,0x4
             48 39 ce
  1b:
                                                 rsi,rcx
                                         cmp
             75 f0
  1e:
                                         ine
                                                 10
<max+0x10>
  20:
             c3
                                         ret
  21:
             0f 1f 80 00 00 00 00
                                                 DWORD PTR
                                         nop
[rax+0x0]
              31 c0
  28:
                                         xor
                                                 eax,eax
  2a:
              c3
                                         ret
```

Why?

It's a no-op. It changes no registers, and no flags, and just consumes two bytes to align the start of the loop on a 8-byte boundary.

This happens a lot.

```
0000000000000000 <max>:
   0:
              85 ff
                                          test
                                                 edi,edi
   2:
              74 24
                                                  28
                                          jе
< max + 0x28 >
   4:
              8d 47 ff
                                          lea
                                                 eax,[rdi-
0x1]
                                          lea
             48 8d 4c 86 04
rcx,[rsi+rax*4+0x4]
   c:
              31 c0
                                          xor
                                                 eax,eax
   e:
              66 90
                                          xchg
                                                 ax,ax
  10:
              8b 16
                                                 edx, DWORD
                                          mov
PTR [rsi]
  12:
              39 d0
                                                 eax,edx
                                          cmp
  14:
             0f 42 c2
                                                 eax,edx
                                          cmovb
  17:
             48 83 c6 04
                                          add
                                                 rsi,0x4
  1b:
             48 39 ce
                                                 rsi,rcx
                                          cmp
              75 f0
                                                 10
  1e:
                                          jne
< max + 0x10 >
              с3
  20:
                                          ret
  21:
             0f 1f 80 00 00 00 00
                                                 DWORD PTR
                                          nop
[rax+0x0]
              31 c0
  28:
                                          xor
                                                 eax,eax
              с3
  2a:
                                          ret
```

Get the next element of the array (pointed to by RSI) and compare it to EAX. Note how few bytes are used.

```
0000000000000000 <max>:
   0:
             85 ff
                                                edi,edi
                                         test
   2:
             74 24
                                         je
                                                 28
<max+0x28>
   4:
             8d 47 ff
                                         lea
                                                eax,[rdi-
0x1]
                                         lea
             48 8d 4c 86 04
rcx,[rsi+rax*4+0x4]
   c:
             31 c0
                                         xor
                                                eax,eax
   e:
             66 90
                                         xchg
                                                ax,ax
  10:
             8b 16
                                                edx, DWORD
                                         mov
PTR [rsi]
  12:
             39 d0
                                                eax,edx
                                         cmp
             0f 42 c2
  14:
                                                eax,edx
                                         cmovb
  17:
             48 83 c6 04
                                         add
                                                rsi,0x4
  1b:
             48 39 ce
                                                rsi,rcx
                                         cmp
             75 f0
                                                10
  1e:
                                         jne
< max + 0x10 >
             с3
  20:
                                         ret
  21:
             0f 1f 80 00 00 00 00
                                                DWORD PTR
                                         nop
[rax+0x0]
             31 c0
  28:
                                         xor
                                                eax,eax
             с3
  2a:
                                         ret
```

The CMOVx family of instructions are conditional moves.

CMOVB is conditional move *below*. That is, if the prior compare showed that EAX was below (less than) EDX, then do the move.

There are a lot of these.

This eliminates our "if" branching logic.

```
0000000000000000 <max>:
   0:
              85 ff
                                                   edi,edi
                                           test
   2:
              74 24
                                                   28
                                           ie
< max + 0x28 >
   4:
              8d 47 ff
                                           lea
                                                   eax,[rdi-
0x1]
              48 8d 4c 86 04
                                           lea
rcx,[rsi+rax*4+0x4]
              31 c0
   c:
                                           xor
                                                   eax,eax
   e:
              66 90
                                           xchg
                                                   ax,ax
  10:
              8b 16
                                                   edx, DWORD
                                           mov
PTR [rsi]
  12:
              39 d0
                                                   eax,edx
                                           cmp
  14:
              0f 42 c2
                                           cmovb
                                                  eax,edx
  17:
              48 83 c6 04
                                           add
                                                   rsi,0x4
  1b:
              48 39 ce
                                                   rsi,rcx
                                           cmp
              75 f0
  1e:
                                           jne
                                                   10
\langle max+0x10 \rangle
  20:
              c3
                                           ret
  21:
              0f 1f 80 00 00 00 00
                                                   DWORD PTR
                                           nop
[rax+0x0]
              31 c0
  28:
                                           xor
                                                   eax,eax
  2a:
              c3
                                           ret
```

If we switch our program to using CMOVB, we save only one byte (because the instruction is longer) but we eliminate a branch inside a loop, which can significantly improve performance.

```
0000000000000000 <max>:
   0:
              85 ff
                                                  edi,edi
                                           test
   2:
              74 24
                                           je
                                                   28
< max + 0x28 >
   4:
              8d 47 ff
                                           lea
                                                  eax,[rdi-
0x1]
                                           lea
              48 8d 4c 86 04
rcx,[rsi+rax*4+0x4]
   c:
              31 c0
                                           xor
                                                  eax,eax
   e:
              66 90
                                           xchg
                                                  ax,ax
  10:
              8b 16
                                                  edx, DWORD
                                           mov
PTR [rsi]
  12:
              39 d0
                                                  eax,edx
                                           cmp
  14:
              0f 42 c2
                                           cmovb
                                                  eax,edx
  17:
              48 83 c6 04
                                           add
                                                  rsi,0x4
  1b:
              48 39 ce
                                                  rsi,rcx
                                           cmp
              75 f0
                                                  10
  1e:
                                           jne
\langle max+0x10 \rangle
              с3
  20:
                                           ret
  21:
              0f 1f 80 00 00 00 00
                                                  DWORD PTR
                                           nop
[rax+0x0]
              31 c0
  28:
                                           xor
                                                  eax,eax
              с3
  2a:
                                           ret
```

Now advance RSI to point to the next value in the array, and compare it to RCX to see if we are done. If not, branch backward.

Check out the bytes for jne 10. Note that 0xf0 is -0x10 in 8-bit two's complement, and the first address after the branch instruction is hex 0x20, and 0x20-0x10 = 0x10.

0x2b is 32+11 = 43 bytes (but 9 are nops)

```
0000000000000000 <max>:
              85 ff
                                                  edi,edi
   0:
                                          test
   2:
              74 24
                                                  28
                                          ie
< max + 0x28 >
   4:
              8d 47 ff
                                          lea
                                                  eax,[rdi-
0x1]
              48 8d 4c 86 04
                                          lea
rcx,[rsi+rax*4+0x4]
   c:
              31 c0
                                          xor
                                                  eax,eax
   e:
              66 90
                                          xchg
                                                 ax,ax
 10:
              8b 16
                                                  edx, DWORD
                                          mov
PTR [rsi]
              39 d0
                                                  eax,edx
 12:
                                          cmp
 14:
              0f 42 c2
                                          cmovb
                                                 eax,edx
 17:
             48 83 c6 04
                                          add
                                                  rsi,0x4
             48 39 ce
 1b:
                                                  rsi,rcx
                                          cmp
              75 f0
 1e:
                                                  10
                                          jne
< max + 0x10 >
  20:
              c3
                                          ret
  21:
             0f 1f 80 00 00 00 00
                                                  DWORD PTR
                                          nop
[rax+0x0]
  28:
              31 c0
                                          xor
                                                  eax,eax
  2a:
              c3
                                          ret
```

### **A Better Solution**

We can actually do better. There is a special instruction family: LOOP. These instructions decrement ECX, check for zero, and may check other flags. They were created to do looping.

All we have to do is run the loop backward, and modify the input arguments (which, after all, are not guaranteed to be preserved).

This reduces our program size to just 21 bytes. Does it matter? Sometimes it does. But this is also *faster*.

```
; nasm -f elf64 max.asm
; gcc -static -o max max.o
global max
max:
          xor rax, rax
          test edi, edi
          ie out
          mov ecx, edi
loop:
          mov edx, DWORD [rsi+rcx*4-4]
          cmp eax, edx
          cmovb eax, edx
          loop loop
out:
```

ret

#### A Better Solution

NASM has a nice macro facility. We can add a macro to reference an element of the array. This can make the code less error-prone.

We could also rename the registers... but this might be a bad idea because it could lead to confusion.

```
; nasm -f elf64 max.asm
; gcc -static -o max max.o
global max
%define value(b) DWORD [rsi+(b)*4-4]
max:
          xor rax, rax
          test edi, edi
          je out
          mov ecx, edi
loop:
          mov edx, value(rcx)
          cmp eax, edx
          cmovb eax, edx
          loop loop
out:
          ret
```

### What's the Point?

There are a *lot* of instructions, some added for specific cases.

An ordinary algorithm can start out pretty obvious... and rapidly become difficult to understand.

It is very easy to make hard-to-find errors in assembly.

Writing assembly will still often beat the compiler because you, the programmer, have information (the loop can run backwards) that the compiler doesn't.

Writing assembly can be tough.

If you really want to obfuscate a program, use convoluted assembly.

# Calling Library Routines from Assembly

Let's write a stand-alone program to compute the square root of a number. We'll use the C libraries. We will also use the C runtime, so we need a main function.

- strtod convert char \* to double
- sqrt compute the square root of a double
- **printf** print the results
- puts print a string without formatting

To start a stand-alone program we should define the main symbol as the entry point of our code.

To access the C functions, we use extern.

Command line arguments are just like those of main.

int argc	RDI
char * argv[]	RSI Entries are quad word pointers, so 8 bytes each with a terminating NULL pointer
char * envp[]	RDX

The program name is in [RSI]. The first argument (if any) is in [RSI+8], etc.

Remember that **RDI** is one plus the number of arguments (since it counts the program name as the first).

Let's get started.

First let's write code to check the number of arguments and to make sure everything works like we would expect.

```
Compile with:
```

```
nasm -felf64 sqrt1.asm
gcc -static -o sqrt1 sqrt1.o

(Instead of -static, try -no-pie.)
```

```
; nasm -f elf64 sqrt1.asm
; gcc -static -o sqrt1 sqrt1.o
             global main
             extern puts
             section .text
main:
             cmp rdi, 2
             je okay1
             mov rdi, eargs
             call puts
             mov eax, 1
             ret
okay1:
             mov rdi, [rsi+8]
             call puts
             mov rdi, endl
             call puts
             mov eax, 0
             ret
             section .data
eargs:
             db "ERROR: Expected exactly one argument.",
10, 0
endl:
             db 10,0
```

### **Aside: Sections and Segments**

The assembly file we created had sections. Specifically, it mentioned two.

- .text contains unmodifiable executable instructions; accumulated into the code segment CS
- .data contains unmodifiable fixed data; accumulated into the data segment DS

If we wanted to have *modifiable* data, we could have included a .bss section, too. This is (historically) the *block started by symbol* area of fixed-size, uninitialized, modifiable variables. This is adjacent to the data segment, and is also referenced via the DS segment register.

The page table can be set up to control read / write access to the pages where these reside, but you seldom need to worry about that.

Declare main and identify external functions.

```
global main
extern printf
extern strtod
extern sqrt
extern puts
```

Add a .data section at the end with some defined strings.

```
global main
    extern printf
    extern strtod
    extern sqrt
    extern puts

;...

section .data
eargs:db "ERROR: Expected exactly one argument.",10,0
endl:    db 10,0
fmt:    db "sqrt(%f) = %f",10,0
```

Add the .text section with the usual function boilerplate.

This is a good idea whether or not the stack is actually used. You can optimize it later; but don't prematurely optimize!

The leave instruction is exactly the same as: mov rsp, rbp pop rbp

section .text

push rbp
mov rbp, rsp

**;** ...

done: leave ret

main:

### **Aside: Local Variables and the Stack**

Since we will be calling other functions, we need to worry about RDI and RSI. We can save these on the stack. We also need a local variable to hold the floating point value of the argument.

The stack grows "backward" in memory; as you push items, the stack pointer decreases. We can reserve memory on the stack by subtracting the amount we need from the current stack pointer.

We want to store EDI (4 bytes) and RSI (8 bytes). We also want to store another quad word (8 bytes). Thus we need 20 bytes: sub rsp, 20

- EDI will be stored at [RBP-4], so the four bytes go in [RBP-4], [RBP-3], [RBP-2], and [RBP-1].
- RSI will be stored at [RBP-12]
- The local variable will be at [RBP-20]

### **Aside: Local Variables and the Stack**

The stack should always be aligned on a 16-byte boundary before a function call. If you do not do this, and the function uses XMM registers, you will get a segfault. (You can get away with not aligning if you don't... maybe.)

It is the caller's job to make sure the stack is aligned. The stack is aligned on a 16-byte boundary before a call.

- The function is called. The return address (8 bytes) is pushed onto the stack. The stack is no longer aligned.
- The first thing most functions do is **push rbp** (8 bytes). The stack is, again, aligned.

If we want to reserve space, we have to make sure the stack is aligned. For 20 bytes we can do this two ways.

Round up to the next multiple of 16: sub rsp, 32

Clear the bottom four bits of the pointer:

sub rsp, 20 and rsp, -16

Reserve space on the stack and store EDI and RSI.

Let's make sure we got one command line argument (well, actually two: the program name and the first argument).

If we did not, we print an error message and set **EAX** (the return value) to a non-zero value to indicate an error.

```
section .text
main:
            push rbp
            mov rbp, rsp
      sub rsp, 32
      mov DWORD [rbp-4], edi
      mov DWORD [rbp-12], rsi
      cmp edi, 2
      je okay1
      mov rdi, eargs
      call puts
      mov eax, 1
      jmp done
okay1:
      ; ...
done:
            leave
            ret
```

We use **strtod** to convert a text string into a **double** value. This takes two arguments:

- The string to convert
- A pointer-pointer, or NULL

We need the pointer to the string to be in RDI, we need RSI to be 0, and we will get the (floating point) result in XMMO, which we store in the reserved space on the stack.

The movsd instruction moves a double value.

```
; ...
okay1:
      mov rdi, QWORD [rbp-12]
                                    ; argv
      mov rdi, QWORD [rdi+8]
                                    ; argv[1]
      mov rsi, 0
      call strtod
      movsd QWORD [rbp-20], xmm0
      ; ...
done: leave
            ret
            ; ...
```

Next we need to take the square root.

We need the first (floating point) argument to be in XMM0, and the return value will be in XMM0, which is why we had to save on the stack earlier.

We can just call **sqrt**.

```
; ...
okay1:
     mov rdi, QWORD [rbp-12]
                                  ; argv
     mov rdi, QWORD [rdi+8]
                                  ; argv[1]
     mov rsi, 0
     call strtod
     movsd QWORD [rbp-20], xmm0
     call sqrt
     ; ...
done: leave
           ret
           ; ...
```

Now we need to print the result.

We need the original value to be in XMM0, and the square root to be in XMM1.

We put the format string into RDI. EAX holds the number of floating point arguments being provided (two in this case).

We put zero in EAX (the return value) and fall-through to done.

```
; ...
okay1:
     mov rdi, QWORD [rbp-12]
                                   ; argv
     mov rdi, QWORD [rdi+8]
                                  ; argv[1]
     mov rsi, 0
     call strtod
     movsd QWORD [rbp-20], xmm0
     call sqrt
     movsd xmm1, xmm0
     movsd xmm0, QWORD [rbp-20]
     mov rdi, fmt
     mov eax, 2
     call printf
     mov eax, 0
done: leave
           ret
           ; ...
```

Homework Due: Tuesday, 4 February

### Homework: Several Square Roots

Modify the square root program to compute and print the square root of all arguments to the program. There may be zero arguments. You can use argc, or you can watch for the NULL pointer in argv to iterate through the list, but watch out for registers being clobbered by the functions you call! Call your program sqrt\_list.

```
$ sqrt_list
$ sqrt_list 16 9 65536 2
sqrt(16.000000) = 4.000000
sqrt(9.000000) = 3.000000
sqrt(65536.000000) = 256.000000
sqrt(2.000000) = 1.414214
```

### Next time: Inline assembly