#### **HPSC Lecture 17**

#### Outline:

- Fine grain vs. coarse grain parallelism
- Manually splitting loops between threads
- Examples with bugs

### Reading:

- /codes/openmp
- https://computing.llnl.gov/tutorials/openMP/

## Fine vs. coarse grain parallelism

Fine grain: Parallelize at the level of individual loops, splitting work for each loop between threads.

Coarse grain: Split problem up into large pieces and have each thread deal with one piece.

May need to synchronize or share information at some points.

## Fine vs. coarse grain parallelism

Fine grain: Parallelize at the level of individual loops, splitting work for each loop between threads.

Coarse grain: Split problem up into large pieces and have each thread deal with one piece.

May need to synchronize or share information at some points.

More similar to what must be done in MPI.

## Fine vs. coarse grain parallelism

Fine grain: Parallelize at the level of individual loops, splitting work for each loop between threads.

Coarse grain: Split problem up into large pieces and have each thread deal with one piece.

May need to synchronize or share information at some points.

More similar to what must be done in MPI.

Domain Decomposition: Splitting up a problem on a large domain (e.g. three-dimensional grid) into pieces that are handled separated (with suitable coupling).

Solve 
$$u'_i(t) = c_i u_i(t)$$
 for  $t \ge 0$   
with initial condition  $u_i(0) = \eta_i$ . Decoupled system of ODEs  
for  $i = 1, 2, ..., n$ 

```
Solve u'_i(t) = c_i u_i(t) for t \ge 0
with initial condition u_i(0) = \eta_i. Decoupled system of ODEs
for i = 1, 2, ..., n
```

Exact solution:  $u_i(t) = e^{c_i t} \eta_i$ .

Solve 
$$u'_i(t) = c_i u_i(t)$$
 for  $t \ge 0$   
with initial condition  $u_i(0) = \eta_i$ . Decoupled system of ODEs  
for  $i = 1, 2, ..., n$ 

Exact solution:  $u_i(t) = e^{c_i t} \eta_i$ .

Euler method:  $ui(t + \Delta t) \approx ui(t) + \Delta t ciui(t) = (1 + ci\Delta t)ui(t)$ .

Implement this for large number of time steps for large n.

Solve 
$$u'_i(t) = c_i u_i(t)$$
 for  $t \ge 0$   
with initial condition  $u_i(0) = \eta_i$ . Decoupled system of ODEs  
for  $i = 1, 2, ..., n$ 

Exact solution:  $u_i(t) = e^{c_i t} \eta_i$ .

Euler method:  $ui(t + \Delta t) \approx ui(t) + \Delta t ciui(t) = (1 + ci\Delta t)ui(t)$ .

Implement this for large number of time steps for large n.

For each *i* time stepping can't be easily made parallel.

But for large n, this problem is embarassingly parallel:

Problem for each i is completely decoupled from problem for any other i. Could solve them all simultaneously with no communication needed.

```
!$omp parallel do
do i=1,n
    u(i) = eta(i)
    enddo
do m=1, nsteps
    !$omp parallel do
    do i=1,n
        u(i) = (1.d0 + dt*c(i))*u(i)
        enddo
    enddo
```

Note that threads are forked nsteps+1 times.

Requires shared memory:

don't know which thread will handle each i.

## Might try to fork threads only once via: Wrong!

```
!$omp parallel private(m)
!$omp do
do i=1,n
    u(i) = eta(i)
    enddo
do m=1, nsteps
    !$omp do
    do i=1,n
        u(i) = (1.d0 + dt*c(i))*u(i)
        enddo
    enddo
!$omp end parallel
```

Might try to fork threads only once via: Wrong!

```
!$omp parallel private(m)
!$omp do
do i=1,n
    u(i) = eta(i)
    enddo
do m=1, nsteps
    !$omp do
    do i=1,n
        u(i) = (1.d0 + dt*c(i))*u(i)
        enddo
    enddo
!$omp end parallel
```

Error: the loop on m will be done independently by each thread. (Actually works in this case but not good coding.)

### Can rearrange loops:

```
!$omp parallel private(m)
!$omp do
do i=1,n
    u(i) = eta(i)
    enddo
!$omp do
do i=1,n
    do m=1, nsteps
        u(i) = (1.d0 + dt*c(i))*u(i)
        enddo
    enddo
!$omp end parallel
```

#### Can rearrange loops:

```
!$omp parallel private(m)
!$omp do
do i=1,n
    u(i) = eta(i)
    enddo
!$omp do
do i=1,n
    do m=1, nsteps
        u(i) = (1.d0 + dt*c(i))*u(i)
        enddo
    enddo
!$omp end parallel
```

Only works because ODEs are decoupled — can take all time steps on  $u_1(t)$  without interacting with  $u_2(t)$ , for example.

# Coarse grain solution of ODEs

Split up  $i=1,2,\ldots,n$  into nthreads disjoint sets. A set goes from i=istart to i=iend These private values are different for each thread.

Each thread handles 1 set for the entire problem.

```
!$omp parallel private(istart,iend,i,m)
istart = ??
iend = ??
do i=istart,iend
    u(i) = eta(i)
    enddo

do i=istart,iend
    do m=1,nsteps
        u(i) = (1.d0 + dt*c(i))*u(i)
        enddo
    enddo
    enddo
!$omp end parallel
```

Threads are forked only once, Each thread only needs subset of data.

# Setting istart and iend

```
Example: If n=100 and nthreads = 2, we would want:
  Thread 0: istart= 1 and iend= 50,
  Thread 1: istart=51 and iend=100.
If nthreads divides n evenly...
  points per thread = n / nthreads
  !$omp parallel private(thread num, istart, iend, i)
      thread num = 0 ! needed in serial mode
       !$ thread num = omp get thread num()
      istart = thread num * points per thread + 1
iend = (thread_num+1) * points_per_thread
      do i=istart, iend
           ! work on thread's part of array
           enddo
  !$omp end parallel
```

# Setting istart and iend more generally

```
Example: If n=101 and nthreads = 2, we would want:
  Thread 0: istart= 1 and iend= 51,
  Thread 1: istart=52 and iend=101.
If nthreads might not divide n evenly...
  points per thread = (n + nthreads - 1) / nthreads
  !$omp parallel private(thread num, istart, iend, i)
      thread num = 0! needed in serial mode
       !$ thread num = omp get thread num()
      istart = thread num * points per thread + 1
iend = min((thread_num+1) * points_per_thread, n)
      do i=istart, iend
           ! work on thread's part of array
           enddo
  !$omp end parallel
```

Given a vector (1-dimensional array) x, Compute the normalized vector  $x/||x||_1$ , with  $||x||_1 = \text{sum}(|x|)$ 

Fine-grain: Using parallel do loops.

```
norm = 0.d0
!$omp parallel do reduction(+ : norm)
do i=1,n
    norm = norm + abs(x(i))
    enddo

!$omp parallel do
do i=1,n
    x(i) = x(i) / norm
    enddo
```

Note: Must finish computing norm before using for any x(i), so we are using the implicit barrier after the first loop.

Another fine-grain approach, forking threads only once:

```
! from /codes/openmp/normalize1.f90
norm = 0.d0
    !$omp parallel private(i)
    !$omp do reduction(+ : norm)
    do i=1.n
        norm = norm + abs(x(i))
        enddo
    !$omp barrier ! not needed (implicit)
    !$omp do
    do i=1.n
        x(i) = x(i) / norm
        enddo
    !$omp end parallel
```

Compute the normalized vector  $x/||x||_1$ 

Coarse grain version:

Assign blocks of *i* values to each thread. Threads must:

• Compute thread's contribution to  $||x||_1$ ,

$$norm\_thread = \sum_{i \text{ start}}^{i \text{ end}} |x_i|,$$

Collaborate to compute total value IxI1:

$$||x||_1$$
 norm\_thread

• Loop over i = istart, iend to divide xi by ||x||1.

```
! from /codes/openmp/normalize2.f90
      norm = 0.d0
     !$omp parallel private(i,norm thread, &
    !Somp istart,iend,thread_num)
!S thread num = omp_get_thread num()
istart = Thread num * points per_thread + 1
iend = min((thread_num+1) * points_per_thread, n)
    norm thread = 0.d0
    do i≡istart,iend
          norm thread = norm thread + abs(x(i))
          enddo
     ! update global norm with value from each thread:
     !$omp critical
       norm = norm + norm thread
     !$omp end critical
     !$omp barrier !! needed here
    do i=istart, iend
          y(i) = x(i) / norm
          enddo
     !$omp end parallel
```

# Example: Normalizing a vector — parallel block

enddo

```
norm thread = 0.d0
do i=istart, iend
    norm thread = norm thread + abs(x(i))
    enddo
! update global norm with value from each threa
!$omp critical
  norm = norm + norm thread
!$omp end critical
!$omp barrier !! needed here
do i=istart, iend
    v(i) = x(i) / norm
```

1. Not declaring proper variables private

- 1. Not declaring proper variables private
- 2. Setting norm = 0.d0 inside parallel block.

Ok if it's in a omp single block. Otherwise second thread might set to zero after first thread has updated by norm\_thread.

- 1.Not declaring proper variables private
- 2.Setting norm = 0.d0 inside parallel block.

Ok if it's in a omp single block. Otherwise second thread might set to zero after first thread has updated by norm\_thread.

3.Not using omp critical block to update global norm.

Data race.

- 1.Not declaring proper variables private
- 2.Setting norm = 0.d0 inside parallel block.

Ok if it's in a omp single block. Otherwise second thread might set to zero after first thread has updated by norm\_thread.

3. Not using omp critical block to update global norm.

Data race.

4. Not having a barrier between updating norm and using it.

First thread may use norm before other threads have added their contributions.

- 1.Not declaring proper variables private
- 2.Setting norm = 0.d0 inside parallel block.

Ok if it's in a omp single block. Otherwise second thread might set to zero after first thread has updated by norm\_thread.

3. Not using omp critical block to update global norm.

Data race.

4. Not having a barrier between updating norm and using it.

First thread may use norm before other threads have added their contributions.

None of these bugs would give compile or run-time errors! Just wrong results (sometimes).

```
Solve u'_i(t) = c_i u_i(t) for t \ge 0 with initial condition u_i(0) = \eta_i.
```

Exact solution:  $u_i(t) = e^{c_i t} \eta_i$ .

Euler method:  $ui(t + \Delta t) \approx ui(t) + \Delta t c i u i(t) = (1 + c i \Delta t) u i(t)$ .

New condition: Stop time stepping when any of the ui(t) values exceeds 100.

(Will certainly happen as long as  $c_j > 0$  for some j.)

Stop time stepping when any of the ui(t) values exceeds 100.

#### Idea:

Each time step, compute umax = maximum value of ui over all i and exit the time-stepping if <math>umax > 100.

Stop time stepping when any of the  $u_i(t)$  values exceeds 100.

#### Idea:

Each time step, compute umax = maximum value of ui over all i and exit the time-stepping if <math>umax > 100.

Each thread has a private variable  $max\_thread$  for the maximum value of ui for its values of i. Updated for each i.

Stop time stepping when any of the ui(t) values exceeds 100.

#### Idea:

Each time step, compute umax = maximum value of ui over all i and exit the time-stepping if <math>umax > 100.

Each thread has a private variable  $max\_thread$  for the maximum value of ui for its values of i. Updated for each i.

Each thread updates shared umax based on its umax\_thread. This needs to be done in critical section.

Stop time stepping when any of the ui(t) values exceeds 100.

#### Idea:

Each time step, compute umax = maximum value of ui over all i and exit the time-stepping if <math>umax > 100.

Each thread has a private variable  $max\_thread$  for the maximum value of ui for its values of i. Updated for each i.

Each thread updates shared umax based on its umax\_thread. This needs to be done in critical section.

Also need two barriers to make sure all threads are in sync at certain points.

Stop time stepping when any of the ui(t) values exceeds 100.

#### Idea:

Each time step, compute umax = maximum value of ui over all i and exit the time-stepping if <math>umax > 100.

Each thread has a private variable  $max\_thread$  for the maximum value of ui for its values of i. Updated for each i.

Each thread updates shared umax based on its umax\_thread. This needs to be done in critical section.

Also need two barriers to make sure all threads are in sync at certain points.

Study code in /codes/openmp/umax1.f90.

```
!$omp parallel private(i,m,umax thread, &
!$omp
                               istart, iend, thread num)
!$ thread num = omp get thread num()
istart = Thread num * points per thread + 1
iend = min((thread num+1) * points per thread, n)
do m=1, nsteps
     umax thread = 0.d0
     !$omp single
        umax = 0.d0
     !Somp end single
do i=istart,iend
u(i) = (1.d0 + c(i)*dt) * u(i)
          umax thread = max(umax thread, u(i))
          enddō
     !$omp critical
        umax = max(umax, umax thread)
     !$omp end critical
     !$omp barrier
     if (umax > 100) exit
     !$omp barrier
     enddo
!$omp end parallel
```

## do loop in parallel block:

```
do m=1, nsteps
    umax thread = 0.d0
    !$omp single
      umax = 0.d0
    !$omp end single
    do i=istart, iend
        u(i) = (1.d0 + c(i)*dt) * u(i)
        umax thread = max(umax thread, u(i))
        enddo
    !$omp critical
      umax = max(umax, umax thread)
    !$omp end critical
    !$omp barrier
    if (umax > 100) exit
    !$omp barrier
    enddo
```

### If there were **no** barriers, the following could happen:

Thread 0 executes critical section first, setting umax to 0.5.

Thread 0 checks if umax > 100. False, starts next iteration.

Thread 1 executes critical section, updating umax to 110.

Thread 1 checks if umax > 100. True, so it exits.

Thread 0 next sets umax to 0.4.

Thread 0 might never reach umax > 100. Runs forever.

### If there were **no** barriers, the following could happen:

Thread 0 executes critical section first, setting  ${\tt umax}\$  to 0.5.

Thread 0 checks if umax > 100. False, starts next iteration.

Thread 1 executes critical section, updating umax to 110.

Thread 1 checks if umax > 100. True, so it exits.

Thread 0 next sets umax to 0.4.

Thread 0 might never reach umax > 100. Runs forever.

### With only first barrier, the following could happen:

umax < 100 in iteration m.

Thread 1 checks if umax > 100. Go to iteration m + 1.

Thread 1 does iteration on i and sets umax > 100, Stops at first barrier.

Thread 0 (iteration m) checks if umax > 100. True, Exits.

Thread 0 never reaches first barrier again, code hangs.