

v2.0 User Manual

What is Cinemachine?

Cinemachine is a suite of 'smart' procedural modules which allow you to define the shot and they'll dynamically follow your direction. Setup shots which track and compose motion in realtime, like Al camera operators. The procedural nature makes them bug-resistant as they always work to make the shot based on your direction. That's great for gameplay, but they're also amazingly fast for cutscenes. Change an animation, a vehicle speed, ground terrain - whatever - and Cinemachine will dynamically make the shot. You can use really telephoto lenses and not have to update the cutscene if things change

History

Cinemachine has been in development over a number of years across multiple projects We've been designing camera systems for almost 20 years and have shipped millions of AAA titles across numerous genres. The Cinemachine team has an award winning cinematographer and a senior engineer with heavy math skills. Also, we love this stuff to bits.

Mission

Our mission with Cinemachine is built to be an entirely unified camera system bridging gameplay, cutscenes, from fully procedural cameras to entirely canned sequences and everything in between.

Forums

We have a busy discussion area on the forums. https://forum.unity3d.com/forums/timeline-cinemachine.127/



Table of Contents

What is Cinemachine?	1
History	1
Mission	1
Forums	1
Table of Contents	2
Overview	4
Cinemachine Virtual Camera	4
Cinemachine Brain	4
Installation and Getting Started	5
User Guide	6
Basic Virtual Cameras	6
CinemachineVirtualCamera	7
LensSettings	8
CinemachineComposer	9
CinemachineTransposer	11
CinemachineBasicMultiChannelPerlin	13
NoiseSettings	15
NoiseSettings.NoiseParams	15
NoiseSettings.TransformNoiseParams	15
Brains and Blending	16
CinemachineBrain	16
CinemachineBlendDefinition	18
CinemachineBlenderSettings	19
CinemachineBlenderSettings.CustomBlend	19
Follow Cams and Player Input	20
CinemachineOrbitalTransposer	20
CinemachineOrbitalTransposer.AxisState	22
CinemachineOrbitalTransposer.Recentering	23
CinemachineFreeLook	24
Tracked Dolly	25
CinemachineTrackedDolly	26
CinemachineTrackedDolly.AutoDolly	28
CinemachinePath	28
CinemachinePath.Appearance	29



CinemachinePath.Waypoint	29
State-Driven Camera	30
CinemachineStateDrivenCamera	31
Collision Avoidance and Shot Evaluation	32
CinemachineCollider	32
ClearShot	33
CinemachineClearShot	33
Multiple Target Objects	34
CinemachineTargetGroup	35
CinemachineTargetGroup.Target	36
CinemachineGroupComposer	36
Post-Processing Stack	39
CinemachinePostFX	39
And the Rest	41
CinemachineFollowZoom	41
CinemachineSmoother	41
CinemachineExternalCamera	41
SaveDuringPlay	42
Timeline Integration	42
Special Environments	45
2D Cameras	45
Top-Down Games	45
Split-screen	45
Scripting	45



Overview

Cinemachine is a modular suite of camera tools for Unity which give AAA game quality controls for every camera in your project. It's an easy to install plugin which lets you add functionality to cameras you've already got, or make new ones with amazing behaviors.

Cinemachine has been designed to be the entire unified camera system in your project but can be used alongside your existing cameras as well. If you have a bunch of camera stuff working already and just want to use Cinemachine for cutscenes or something specific, no problem at all. However when you use it across your project it allows you to blend any camera to any other camera in a gameplay-to-cutscene-and-back-seamlessly kind of way.

The heart of Cinemachine is two components; everything else builds on those. They are:

Cinemachine Virtual Camera

The Virtual Camera is a shot, a single camera. It has child modules which you can turn on to make it do things like procedurally track and compose objects, follow things and shake with procedural noise. Together they are a very powerful combination and can yield an unlimited number of results.

These modules have been designed, re-designed and re-designed again to offer the widest range of possibilities with the least number of controls. The math driving these camera behaviours is complex and sophisticated, having gone through many different scenarios across all sorts of games.

The reason for the 'virtual' camera scenario is because Unity renders from the main camera. Out-of-the-box Unity is limited to only one camera being active camera at a time – which makes the blending of two shots effectively impossible. Cinemachine is engineered to solve this and provide a wealth of simple, powerful functionality at the same time, allowing unsurpassed camera behaviors which are fast and easy to setup.

Cinemachine Brain

This is the central Cinemachine component that does all the magic. It's a component attached to the Unity camera and it monitors all the Virtual Cameras in the scene and drives the Unity camera using the shot it likes best.




Installation and Getting Started

Installing Cinemachine is easy.

 Drag the Cinemachine unitypackage onto your assets folder in Unity, OR Install it directly: Assets->Import Package ->Custom Package... and point to the Cinemachine unitypackage.




- Setup the Cinemachine Virtual Camera environment Cinemachine-> Create Virtual Camera. This is also the way to create additional Cinemachine shots.
- 3. That's it! You now have Cinemachine installed on your machine.



You will notice two changes to your scene:

- The main camera has a little icon next to it in the scene hierarchy. This indicates that your camera has been Cinemachine-enabled using a new component: the CinemachineBrain.
- 2. A new GameObject *CM vcam1* with a CinemachineVirtualCamera component, which is a single camera or shot.



There's more info below on how to use these new things. Don't forget to check out the example scenes included in Cinemachine/Examples/Scenes, and please visit our user forum at https://forum.unity3d.com/forums/timeline-cinemachine.127/



User Guide

This guide is organized in logical sections that cover the ground from simple basic setups all the way through to advanced cinematic features of Cinemachine. Each of the classes and behaviours that make up Cinemachine are described in detail.

Cinemachine is by no means limited to the classes and behaviours described here. It has an open pipeline architecture, and we look forward to seeing the exciting new behaviours and intelligence that our users will build into the system.




Basic Virtual Cameras

Each virtual camera is a 'shot', or a single camera. You can animate them directly or blend two together to create camera moves. The reason they are 'virtual' cameras is to allow for blending, camera selection based on priorities and the ability to have Cinemachine hold multiple cameras in memory with the final product being presented to the current active Unity camera(s) which are rendering.

Cinemachine allows you to create an unlimited number of virtual cameras, blend them together with the result being presented to the single Unity camera. It does all this automatically.

Key components of the Virtual Camera are:

- **Priority:** The priority of this shot. Equal or Higher value camera priorities compared to the current camera priority will be activated. This allows for camera state machine setups where cameras are called based on trigger volumes, animations, health states, etc. Important cameras will trigger over lower priority ones.
- Lens Settings: What kind of lens to use for this shot: FOV, clipping planes, and dutch (camera roll). Post-processing effects can also be included here.
- **Aim:** What the camera looks at, and procedural ways to track and compose any subject.
- **Body:** Where the camera is placed in your scene, and procedural ways to 'mount' your camera to any object and move the camera with it.
- **Noise:** Procedural Perlin multi-layered noise system for handheld behaviors, shakes, and vibrations.



The **Solo Button** in the Virtual Camera inspector panel will make the virtual camera temporarily Live so that you can have immediate visual feedback in the game view when tweaking the



behavioural parameters of the camera.

The following sections describe the behaviours and classes that make up the Cinemachine Virtual Camera, and some of its standard procedural components.

CinemachineVirtualCamera

This behaviour is intended to be attached to an empty Transform GameObject, and it represents a Virtual Camera within the Unity scene.

The Virtual Camera will animate its Transform according to the rules contained in its CinemachineComponent pipeline (Aim, Body, and Noise). When the virtual camera is Live, the Unity camera will assume the position and orientation of the virtual camera.

A virtual camera is not a camera. Instead, it can be thought of as a camera controller, not unlike a cameraman. It can drive the Unity Camera and control its position, orientation, lens settings, and PostProcessing effects. Each Virtual Camera owns its own Cinemachine Component Pipeline, through which you provide the instructions for dynamically tracking specific game objects.

A virtual camera is very lightweight, and does no rendering of its own. It merely tracks interesting GameObjects, and positions itself accordingly. A typical game can have dozens of virtual cameras, each set up to follow a particular character or capture a particular event.

A Virtual Camera can be in any of three states:

- **Live**: The virtual camera is actively controlling the Unity Camera. The virtual camera is tracking its targets and being updated every frame.
- **Standby**: The virtual camera is tracking its targets and being updated every frame, but no Unity Camera is actively being controlled by it. This is the state of a virtual camera that is enabled in the scene but perhaps at a lower priority than the Live virtual camera.
- **Disabled**: The virtual camera is present but disabled in the scene. It is not actively tracking its targets and so consumes no processing power. However, the virtual camera can be made live from the Timeline.

The Unity Camera can be driven by any virtual camera in the scene. The game logic can choose the virtual camera to make live by manipulating the virtual cameras' enabled flags and their priorities, based on game logic.

In order to be driven by a virtual camera, the Unity Camera must have a CinemachineBrain behaviour, which will select the most eligible virtual camera based on its priority or on other criteria, and will manage blending.

ı y	ļ!	Type	Description	า			



Look At	Transform	The object that the camera wants to look at (the Aim target). If this is null, then the vcam's Transform orientation will define the camera's orientation.
Follow	Transform	The object that the camera wants to move with (the Body target). If this is null, then the vcam's Transform position will define the camera's position.
Lens	LensSettings	Specifies the lens properties of this Virtual Camera. This generally mirrors the Unity Camera's lens settings, and will be used to drive the Unity camera when the vcam is active.
Priority	Int32	The priority will determine which camera becomes active based on the state of other cameras and this camera. Higher numbers have greater priority.

LensSettings

Describes the FOV and clip planes for a camera. This generally mirrors the Unity Camera's lens settings, and will be used to drive the Unity camera when the vcam is active.

Setting	Туре	Description
Field Of View	Single	This is the camera view in vertical degrees. For cinematic people, a 50mm lens on a super-35mm sensor would equal a 19.6 degree FOV.
Orthographic Size	•	When using an orthographic camera, this defines the half-height, in world coordinates, of the camera view.
Near Clip Plane	Single	This defines the near region in the renderable range of the camera frustum. Raising this value will stop the game from drawing things near the camera, which can sometimes come in handy. Larger values will also increase your shadow resolution.
Far Clip Plane	•	This defines the far region of the renderable range of the camera frustum. Typically you want to set this value as low as possible without cutting off desired distant objects.
Dutch	Single	Camera Z roll, or tilt, in degrees.

CinemachineComposer


This is a CinemachineComponent in the Aim section of the component pipeline. Its job is to aim



the camera at the vcam's LookAt target object, with configurable offsets, damping, and composition rules.

The composer does not change the camera's position. It will only pan and tilt the camera where it is, in order to get the desired framing. To move the camera, you have to use the virtual camera's Body section.

The vcam's LookAt target is the Composer's target. Common Composer targets: include bones on a character like the upper spine or head bone, vehicles, or dummy objects which are controlled or animated programmatically.



Once you've set the vcam's LookAt target and are tracking something, you need to define where you'd like it to be on the screen and how aggressively you'd like to camera to track it. The degree of lag, or how tightly the camera follows the subject is defined by the two controls:

Horizontal/Vertical Soft Damping: Setting these values to zero means the camera will hard track the subject and the blue regions above will act as rigid barriers locking the camera movement to keep the target inside those values. Setting the larger will allow the target to 'squish' into the blue regions, giving you some really nice camera weight and lag. This is what real camera operators do!. The vertical and horizontal values are separated so you can let the camera squish more left to right or follow tighter up and down, etc.

SoftZone/DeadZone: Tune these to define where you want the subject to be onscreen. These controls are incredibly versatile. The blue areas are the 'squishy' areas based on how much horizontal/vertical damping you have, and the red areas define the 'no pass' limits where the camera will always track the subject. Opening up the soft areas to create a 'dead zone' in the middle allows you to make areas of the screen immune to target motion, handy for things like animation cycles where you don't want the camera to track the target if it moves just a little.

Setting	Type	Description	
Setting	li ype	Description	
		·	



Show Guides	Boolean	This displays the Composer overlay in the Game window. You can adjust colours and opacity in Edit/Preferences/Cinemachine.	
Tracked Object Offset	Vector3	Target offset from the target object's center in target-local space. Use this to fine-tune the tracking target position when the desired area is not the tracked object's center.	
Horizontal Damping	Single	How aggressively the camera tries to follow the target in the screen-horizontal direction. Small numbers are more responsive, rapidly orienting the camera to keep the target in the dead zone. Larger numbers give a more heavy slowly responding camera. Using different vertical and horizontal settings can yield a wide range of camera behaviors.	
Vertical Damping	Single	How aggressively the camera tries to follow the target in the screen-vertical direction. Small numbers are more responsive, rapidly orienting the camera to keep the target in the dead zone. Larger numbers give a more heavy slowly responding camera. Using different vertical and horizontal settings can yield a wide range of camera behaviors.	
Screen X	Single	Horizontal screen position for target. The camera will rotate to position the tracked object here.	
Screen Y	Single	Vertical screen position for target, The camera will rotate to position the tracked object here.	
Dead Zone Width	Single	Camera will not rotate horizontally if the target is within this range of the position.	
Dead Zone Height	Single	Camera will not rotate vertically if the target is within this range of the position.	
Soft Zone Width	Single	When target is within this region, camera will gradually rotate horizontally to re-align towards the desired position, depending on the damping speed.	
Soft Zone Height	Single	When target is within this region, camera will gradually rotate vertically to re-align towards the desired position, depending on the damping speed.	
Bias X	Single	A non-zero bias will move the target position horizontally away from the center of the soft zone.	
Bias Y	Single	A non-zero bias will move the target position vertically away from the center of the soft zone.	



CinemachineTransposer

This is a CinemachineComponent in the Body section of the component pipeline. Its job is to position the camera in a fixed relationship to the vcam's Follow target object, with offsets and damping.

The Tansposer will only change the camera's position in space. It will not re-orient or otherwise aim the camera. To to that, you need to instruct the vcam in the Aim section of its pipeline.

Transposer is a component which mounts a camera to any object. It has a number of advantages over just putting the camera under the object you want to have the camera follow. Hood Cam, Door Cam, POV Cam, Missile Cam - if you want to mount the camera to something, use Transposer.

Using Transposer for your camera body motion has advantages:

- The position tuning is kept, even if the game is running. Tune a regular camera in game mode and the position is lost once you quit, not with Transposer. Tune it up while the game is running and you're done.
- Add damping to the camera if your camera follows something, the damping values can give you some 'weight' to the camera so they feel smoother.
- Organization: Put all your cameras in one place, instead of having them hidden under all sorts of assets in your project - you pick their targets vs. put the camera under them in the hierarchy.


Follow Offset: The camera will go to the centre of the object you're targeting in the Transposer Camera Target, so if you want the camera to be further behind, put in some offsets. We default at -10 so the camera is behind whatever you're targeting.

Damping: Per channel damping which will cause the camera to lag behind the target.

Binding Mode: There's options in the relationship between the camera and the target object.

- Lock To Target interprets the camera offset in target-local coords. As the target rotates, the camera rotates around it to maintain the offset.
- Lock to Target With World Up is the same as the above but it keeps the camera pointing up. Handy if your target flips over.
- Lock to Target On Target Assign mounts the camera relative to the target's local coordinate system at the time the camera is initialized. This offset remains constant in world space, and the camera will not rotate along with the target
- World Space offsets positions the camera relative to the target in world coords no matter what direction the target object is facing.






These different modes do incredibly different things, so try them out and one should work well for whatever your requirements are. The 'Door Cam' or 'Hood Cam' ideas would use *Local Space Locked To Target*.

Setting	Туре	Description
Follow Offset		The distance vector that the transposer will attempt to maintain from the Follow target.
X Damping		How aggressively the camera tries to maintain the offset in the X-axis. Small numbers are more responsive, rapidly translating the camera to keep the target's x-axis offset. Larger numbers give a more heavy slowly responding camera. Using different settings per axis can yield a wide range of camera behaviors.
Y Damping		How aggressively the camera tries to maintain the offset in the Y-axis. Small numbers are more responsive, rapidly translating the camera to keep the target's y-axis offset. Larger numbers give a more heavy slowly responding camera. Using different settings per axis can yield a wide range of camera behaviors.
Z Damping		How aggressively the camera tries to maintain the offset in the Z-axis. Small numbers are more responsive, rapidly translating the camera to keep the target's z-axis offset. Larger numbers give a more heavy slowly responding camera. Using different settings per axis can yield a wide range of camera behaviors.
Binding Mode	setType	The coordinate space to use when interpreting the offset from the target. This is also used to set the camera's Up vector, which will be maintained when aiming the camera.





CinemachineBasicMultiChannelPerlin

As a part of the Cinemachine Pipeline implementing the Noise stage, this component adds Perlin Noise to the Camera state, in the Correction channel.

The noise is created by using a predefined noise profile asset. This defines the shape of the noise over time. You can scale this in amplitude or in time, to produce a large family of different noises using the same profile.

The Noise is a multi-layered Perlin noise function which is applied after the Composer and adds additional transforms. It has controls for Position and Orientation. You can add as many layers as you want by increasing the profile's Size value.

Procedural noise is a complex thing to make look real. Convincing hand-held motion is a mixture of low, medium and high frequency wobbles which together combine to create something believable.

Position / Orientation Size: This is how many noise functions you'd like to blend together for the Position or Orientation or both. Mix at least 3 Orientation channels together for some realistic hand-held motion.

Amplitude defines the amount of noise in degrees. Wider lenses will need larger degree values in order to 'see' the shake. Telephoto lenses use smaller values as that small setting appears amplified through narrower FOV lenses.

Frequency defines the speed of the noise in Hz. Typically a 'low' frequency value might be around 0.1. Consider that your game is running at 30 or 60hz, so settings higher than that will be 'on the other side' of the Nyquest frequency meaning that they will not be directly tracked. A



setting of 100 will be higher than what the camera can 'follow' as your game is only running at say 60hz. It can look kind of choppy since the camera can't track something which is sampling faster than what the game is running at. It can also look kind of cool, but rarely. Experiment. Typically, for most hand-held setups, the low is around 0.1-0.5, the mid maybe .8-1.5 and the high around 3-4. That's 3-4 shakes back and forth per second.

The most convincing camera shakes are typically done with Orientation noise as that's where the camera is aiming. Handheld camera operators tend shake more rotationally than they do positionally, but of course feel free to mix in some Position noise, just remember it's probably best to start with the Orientation.

We've included a number of presets to get you going, under Assets/Cinemachine/Examples/Presets/Noise and of course you can add as many of your own as you wish, just right click in the Asset window Create->Cinemachine->Noise, and drag that asset into the Noise Settings window under that Virtual Camera. You can also animate the Noise through the Amplitude Gain and Frequency Gain settings to ramp the effect up and down.

Setting	Туре	Description
Definition	NoiseSettings	The shared asset containing the Noise Profile. Define the frequencies and amplitudes there to make a characteristic noise profile. Make your own or just use one of the many presets.
Amplitude Gain	Single	Gain to apply to the amplitudes defined in the NoiseSettings asset. 1 is normal. Setting this to 0 completely mutes the noise.
Frequency Gain	Single	Scale factor to apply to the frequencies defined in the NoiseSettings asset. 1 is normal. Larger magnitudes will make the noise shake more rapidly.

NoiseSettings

This is an asset that defines a noise profile. A noise profile is the shape of the noise as a function of time. You can build arbitrarily complex shapes by combining different base perlin noise frequencies at different amplitudes.

The frequencies and amplitudes should be chosen with care, to ensure an interesting noise quality that is not obviously repetitive.

As a mathematical side-note, any arbitrary periodic curve can be broken down into a series of fixed-amplitude sine-waves added together. This is called fourier decomposition, and is the basis of much signal processing. It doesn't really have much to do with this asset, but it's super interesting!



Setting	Туре	Description
Position	TransformNoiseParams[]	These are the noise channels for the virtual camera's position. Convincing noise setups typically mix low, medium and high frequencies together, so start with a size of 3.
Orientation	TransformNoiseParams[]	These are the noise channels for the virtual camera's orientation. Convincing noise setups typically mix low, medium and high frequencies together, so start with a size of 3.

NoiseSettings.NoiseParams

Describes the behaviour for a channel of noise.

Setting	Туре	Description
Amplitude	Single	The amplitude of the noise for this channel. Larger numbers vibrate
Frequency	Single	higher. The frequency of noise for this channel. Higher magnitudes vibrate
roquonoy	Cirigio	faster.

NoiseSettings.TransformNoiseParams

Contains the behaviour of noise for the noise module for all 3 cardinal axes of the camera.

Setting	Туре	Description
X	NoiseParams	Noise definition for X-axis.
Υ	NoiseParams	Noise definition for Y-axis.
Z	NoiseParams	Noise definition for Z-axis.



Brains and Blending

The **CinemachineBrain** is the central Cinemachine component that does all the magic. It's a component attached to the Unity camera and it monitors all the Virtual Cameras in the scene and drives the Unity camera using the shot it likes best.

When it's time to transition from one shot to another, you can choose how this transition is accomplished. It can be a camera cut, or a Cinemachine blend. Cinemachine Blends are special: they are not fades, or wipes, or dissolves. Rather, they are an interpolation of one camera's settings to another. Think of a blend more as if one cameraman smoothly passed the camera to another cameraman in a different position, to elegantly transition the shot without a cut.

CinemachineBrain


CinemachineBrain is the link between the Unity Camera and the Cinemachine Virtual Cameras in the scene. It monitors the priority stack to choose the current Virtual Camera, and blend with another if necessary. Finally and most importantly, it applies the Virtual Camera state to the attached Unity Camera.

The CinemachineBrain is also the place where rules for blending between virtual cameras are defined. Camera blending is an interpolation over time of one virtual camera position and state to another. If you think of virtual cameras as cameramen, then blending is a little like one cameraman smoothly passing the camera to another cameraman. You can specify the time over which to blend, as well as the blend curve shape. Note that a camera cut is just a zero-time blend.

The Brain hold the following key settings:

- **Blend Settings:** This is the array which defines how any shot blends to any other shot. You can have a 4 second blend from CameraA to CameraB, but a 1 second blend from CameraB back to CameraA. This is very powerful when used in a state machine type setup. **If a specific blend between two cameras isn't defined, it uses the Default Blend** which by default is a smooth 2-second blend (but you can change this).
- Layer Filter: The Brain will only notice those virtual cameras that pass its Unity Camera's culling mask. You can set up split-screen environments by assigning different Virtual Cameras to different layers, and using the culling mask to filter them.
- **Event Dispatching**: The brain will fire events when the shot changes, in case you need to monitor this. There in an event for whenever a Virtual Camera goes live, and another event for when the camera cuts (so that temporal post effects can be reset).





Setting	Туре	Description
Show Debug Text	Boolean	When enabled, the current camera and blend will be indicated in the game window, for debugging.
Show Camera Frustum	Boolean	When enabled, the camera's frustum will be shown at all times in the scene view.
World Up Override	Transform	If set, this object's Y axis will define the worldspace Up vector for all the virtual cameras. This is useful for instance in top-down game environments. If not set, Up is worldspace Y. Setting this appropriately is important, because Virtual Cameras don't like looking straight up or straight down.
Update Method	UpdateMethod	Use FixedUpdate if all your targets are animated during FixedUpdate (e.g. RigidBodies), LateUpdate if all your targets are animated during the normal Update loop, and SmartUpdate if you want Cinemachine to do the appropriate thing on a per-target basis. SmartUpdate is the recommended



I	T
	setting.
	Possible Values:
	- Fixed Update : Virtual cameras are updated in sync with the Physics module, in FixedUpdate.
	- Late Update : Virtual cameras are updated in MonoBehaviour LateUpdate.
	- Smart Update : Virtual cameras are updated according to how the target is updated.
	The blend that is used in cases where you haven't explicitly defined a blend between two Virtual Cameras.
CinemachineBlen	This is the asset that contains custom settings for blends
	between specific virtual cameras in your scene.
•	This event will fire whenever a virtual camera goes live and there is no blend.
	This event will fire whenever a virtual camera goes live. If a blend is involved, then the event will fire on the first frame of the blend.
	CinemachineBlen dDefinition CinemachineBlen derSettings UnityEvent UnityEvent

CinemachineBlendDefinition

Definition of a Camera blend. This struct holds the information necessary to generate a suitable AnimationCurve for a Cinemachine Blend.


Setting	Туре	Description
Style	Style	Shape of the blend curve. Possible Values:
		- Cut: Zero-length blend.
		- Ease In Out : S-shaped curve, giving a gentle and smooth transition.
		- Ease In : Linear out of the outgoing shot, and easy into the incoming.
		 Ease Out: Easy out of the outgoing shot, and linear into the incoming.



Time	Single	Duration (in seconds) of the blend.
		- Linear: Linear blend. Mechanical-looking.
		- Hard Out : Hard out of the outgoing, and easy into the incoming.
		- Hard In : Easy out of the outgoing, and hard into the incoming.

CinemachineBlenderSettings

Asset that defines the rules for blending between Virtual Cameras.



The From and To settings are name-based, which means that cameras are found by matching their names to the settings. They are not linked to specific game objects.

Blender supports wildcards called **ANY CAMERA**, which you can use on the input or output of blends so that no matter what camera you're in, you only have to specify one blend to a particular shot if you always want to blend into or out of that shot the same way.

Setting	Туре	Description
Custom Blends		The array containing explicitly defined blends between two Virtual Cameras.

CinemachineBlenderSettings.CustomBlend

Container specifying how two specific Cinemachine Virtual Cameras blend together.

Setting	Type	Description
From	String	When blending from this camera.



То	String	When blending to this camera.
	CinemachineBlend Definition	Blend curve definition.



Follow Cams and Player Input

In the previous sections of the manual we discussed basic virtual cameras. They are great for cinematics and composition, but it's hard to set up a camera that follows in the path of a moving target, and up to now there has been no consideration of cameras that position themselves in response to player input.

Because Cinemachine is a modular system, it's easy to replace the Transposer in the Body section with a different component - one that considers the velocity of the Follow target, and player input coming from various HIDs. One such component is the **OrbitalTransposer**.

Building on the OrbitalTransposer, the **CinemachineFreeLook** camera is a complex rig that allows the player to position the camera in 2 dimensions: horizontally using the OrbitalTransposer, and vertically using a super-powerful custom blending of 3 interrelated child rigs.

Player input is accomplished either by setting up axes in the Unity Input Manager, or you can drive the values directly using any custom or proprietary input system.

CinemachineOrbitalTransposer

This is a CinemachineComponent in the Body section of the component pipeline. Its job is to position the camera in a variable relationship to a the vcam's Follow target object, with offsets and damping.

This component is typically used to implement a camera that follows its target. It can accept player input from an input device, which allows the player to dynamically control the relationship between the camera and the target, for example with a joystick.

The OrbitalTransposer introduces the concept of **Heading**, which is the direction in which the target is moving, and the OrbitalTransposer will attempt to position the camera in relationship to the heading, which is by default directly behind the target. You can control the default relationship by adjusting the Heading Bias setting.

If you attach an input controller to the OrbitalTransposer, then the player can also control the way the camera positions itself in relation to the target heading. This allows the camera to move to any spot on an orbit around the target. You can configure the OrbitalTransposer to take its input from any axis previously set up in the Input Manager, or you can control the value directly using any custom input system.

Another feature of the OrbitalTransposer is automatic recentering. When enabled, it will automatically move the camera back to the default target heading after is has detected no user input for a specified time.



Body	Orbital Transposer	13
Radius	10	
Height Offset	0	
X Damping	-0-	1
Y Damping	-0-	1
Z Damping	~	1
Damping Style	Polar	
Heading Bias		0
▼ X Axis		
Value	0	
Max Speed	3000	
Accel Time	2	
Decel Time	1	
Input Axis Nam	e Mouse X	
Input Axis Valu	e 0	
▼ Recenter To Targ	et Heading	
Enabled	✓	
Recenter Wait	Time 1	
Recentering Tir	ne 2	
Heading Definit	ion Target Forward	
Velocity Filter S	trength	4

Setting	Туре	Description
Radius	Single	The distance which the transposer will attempt to maintain from the Follow target.
Height Offset	Single	The vertical offset from the target.
X Damping	Single	How aggressively the camera tries to maintain the offset in the X-axis. Small numbers are more responsive, rapidly translating the camera to keep the target's x-axis offset. Larger numbers give a more heavy slowly responding camera. Using different settings per axis can yield a wide range of camera behaviors.
Y Damping	Single	How aggressively the camera tries to maintain the offset in the Z-axis. Small numbers are more responsive, rapidly translating the camera to keep the target's y-axis offset. Larger numbers give a more heavy slowly responding camera. Using different settings per axis can yield a wide range of camera behaviors.
Z Damping	Single	How aggressively the camera tries to maintain the offset in the Z-axis. Small numbers are more responsive, rapidly translating the camera to keep the target's z-axis offset. Larger numbers give a more heavy slowly responding camera. Using different



	1	
		settings per axis can yield a wide range of camera behaviors.
Damping Style	DampingStyle	How the damping values will be interpreted. Polar will attempt to preserve a constant distance from the target, subject to Z damping.
		Possible Values:
		- Cartesian: X, Y, and Z are along the local axes of the target.
		- Polar : X and Y are rotations around the target in the horizontal and vertical directions, respectively. Z is the distance from the target.
Heading Bias	Single	Where the camera is placed when the X-axis value is zero. This is a rotation in degrees around the Y axis. When this value is 0, the camera will be placed behind the target. Nonzero offsets will rotate the zero position around the target.
X Axis	AxisState	Heading Control. The settings here control the behaviour of the camera in response to the player's input.
Recenter To Target Heading	Recentering	Automatic heading recentering. The settings here defines how the camera will reposition itself in the absence of player input.

${\bf Cinemachine Orbital Transposer. Axis State}$

Axis state for defining how this CinemachineOrbitalTransposer reacts to player input. The settings here control the responsiveness of the axis to player input.

Setting	Туре	Description
Value	Single	The current value of the axis.
Max Speed	Single	The maximum speed of this axis in units/second.
Accel Time	Single	The amount of time in seconds it takes to accelerate to MaxSpeed with the supplied Axis at its maximum value.
Decel Time	Single	The amount of time in seconds it takes to decelerate the axis to zero if the supplied axis is in a neutral position.
Input Axis Name	String	The name of this axis as specified in Unity Input manager. Setting to an empty string will disable the automatic updating of this axis.



Input Axis	Single	The value of the input axis. A value of 0 means no input. You can
Value		drive this directly from a custom input system, or you can set the Axis Name and have the value driven by the internal Input
		Manager.

CinemachineOrbitalTransposer.Recentering

Controls how automatic orbit recentering occurs.

Setting	Туре	Description
Enabled	Boolean	If checked, will enable automatic recentering of the camera based on the heading definition. If unchecked, recenting is disabled.
Recenter Wait Time	Single	If no input has been detected, the camera will wait this long in seconds before moving its heading to the zero position.
Recentering Time	Single	Maximum angular speed of recentering. Will accelerate into and decelerate out of this.
_	ationMode	How 'forward' is defined. The camera will be placed by default behind the target. PositionDelta will consider 'forward' to be the direction in which the target is moving. Possible Values: - Position Delta: Target heading calculated from the difference between its position on the last update and current frame. - Velocity: Target heading calculated from its Rigidbody's velocity. If no Rigidbody exists, it will fall back to HeadingDerivationMode.PositionDelta. - Target Forward: Target heading calculated from the Target Transform's euler Y angle. - World Forward: Default heading is a constant world space heading.
Velocity Filter Strength		Size of the velocity sampling window for target heading filter. This filters out irregularities in the target's movement. Used only if deriving heading from target's movement (PositionDelta or Velocity).



CinemachineFreeLook

The FreeLook is a Cinemachine Camera geared towards a 3rd person camera experience. The camera orbits around its subject with three separate camera rigs defining rings around the target. Each rig has its own radius, height offset, composer, and lens settings. Depending on the camera's position along the spline connecting these three rigs, these settings are interpolated to give the final camera position and state.

Player input is supplied along 2 axes: the X axis which controls the orbital position (see CinemachineOrbitalTransposer), and the Y axis which controls the vertical position on the spline connecting the 3 child rigs.

Each child rig can have its own LookAt and Follow targets and Lens settings, or common shared values can be used. Additionally, each child rig can have its own Composer and Noise settings.

Setting	Туре	Description
Look At	Transform	Default object for the camera children to look at (the aim target), if not specified in a child rig. May be empty if LookAt targets are specified in the child rigs.
Follow	Transform	Default object for the camera children wants to move with (the body target), if not specified in a child rig. May be empty if Follow targets are specified in the child rigs.
Damping Style	DampingStyle	How the damping values will be interpreted. Polar will attempt to preserve a constant distance from the target, subject to Z damping. Possible Values: - Cartesian: X, Y, and Z are along the local axes of the target. - Polar: X and Y are rotations around the target in the horizontal and vertical directions, respectively. Z is the distance from the target.
Heading Bias	Single	Additional Y rotation applied to the target heading. When this value is 0, the camera will be placed behind the target.
Use Common Lens Setting	Boolean	If enabled, this lens setting will apply to all three child rigs, otherwise the child rig lens settings will be used.




Lens		Specifies the lens properties of this Virtual Camera. This generally mirrors the Unity Camera's lens settings, and will be used to drive the Unity camera when the vcam is active.
X Axis	AxisState	The Horizontal axis. Value is 0359. This is passed on to the rigs' OrbitalTransposer component.
Y Axis	AxisState	The Vertical axis. Value is 01. Chooses how to blend the child rigs.
Recenter To Target Heading	Recentering	Controls how automatic recentering of the X axis is accomplished.
Spline Tension	Single	Controls how taut is the line that connects the rigs' orbits, which determines final placement on the Y axis.
Priority	Int32	The priority will determine which camera becomes active based on the state of other cameras and this camera. Higher numbers have greater priority.




Tracked Dolly

If you need your camera's position to be confined to a dolly track, this can be done with a combination of a CinemachinePath for the track, and a TrackedDolly for the Body component of the virtual camera. There is a shortcut for creating this pair in the Cinemachine menu:



The path itself is defined by positioning waypoints. The CinemachinePath inspector provides a simple interface for doing this. The waypoints are connected using a bezier, and you can control how the interpolation occurs by manipulating the curve tangents at the waypoints. The result of this is a camera track, drawn in the scene view in a manner resembling a railroad track. It will not be drawn in the game view.





CinemachineTrackedDolly

A Cinemachine Virtual Camera Body component that constrains camera motion to a CinemachinePath. The camera can move along the path.

This behaviour can operate in two modes: manual positioning, and Auto-Dolly positioning. In Manual mode, the camera's position is specified by animating the Path Position field. In Auto-Dolly mode, the Path Position field is animated automatically every frame by finding the position on the path that's closest to the virtual camera's Follow target.

Setting	Туре	Description
Path	Cinemachin ePathBase	The path to which the camera will be constrained. This must be non-null.
Path Position	Single	The position along the path at which the camera will be placed. This can be animated directly, or set automatically by the Auto-Dolly feature to get as close as possible to the Follow target. Values are as follows: 0 represents the first waypoint on the path, 1 is the second, and so on. Values in-between are points on the path in between the waypoints.
Path Offset	Vector3	Where to put the camera relative to the path position. X is perpendicular to the path, Y is up, and Z is parallel to the path. This allows the camera to be offset from the path itself (as if on a tripod, for example).
X Damping	Single	How aggressively the camera tries to maintain its position in a direction perpendicular to the path. Small numbers are more responsive, rapidly translating the camera to keep the target's x-axis offset. Larger numbers give a more heavy slowly responding camera. Using different settings per axis can yield a wide range of camera behaviors.
Y Damping	Single	How aggressively the camera tries to maintain its position in the path-local up direction. Small numbers are more responsive, rapidly translating the camera to keep the target's y-axis offset. Larger numbers give a more heavy slowly responding camera. Using different settings per axis can yield a wide range of camera behaviors.
Z Damping	Single	How aggressively the camera tries to maintain its position in a direction parallel to the path. Small numbers are more responsive, rapidly translating the camera to keep the target's z-axis offset. Larger numbers give a more heavy slowly responding camera. Using different settings per axis can yield a wide range of camera



		behaviors.
-	CameraUp Mode	How to set the virtual camera's Up vector. This will affect the screen composition, because the camera Aim behaviours will always try to respect the Up direction. Possible Values:
		- Default : Leave the camera's up vector alone.
		- Path : Take the up vector from the path's up vector at the current point.
		- Path No Roll: Take the up vector from the path's up vector at the current point, but with the roll zeroed out.
		- Follow Target : Take the up vector from the Follow target's up vector.
		- Follow Target No Roll: Take the up vector from the Follow target's up vector, but with the roll zeroed out.
Auto Dolly	AutoDolly	Controls how automatic dollying occurs. A Follow target is necessary to use this feature.

CinemachineTrackedDolly.AutoDolly

Controls how automatic dollying occurs.

Setting	Туре	Description
Enabled	Boolean	If checked, will enable automatic dolly, which chooses a path position that is as close as possible to the Follow target. Note: this can have significant performance impact.
Search Radius	Int32	How many segments on either side of the current segment. Use 0 for Entire path.
Steps Per Segment	Int32	We search a segment by dividing it into this many straight pieces. The higher the number, the more accurate the result, but performance is proportionally slower for higher numbers.

CinemachinePath

Defines a world-space path, consisting of an array of waypoints, each of which has position,



tangent, and roll settings. Bezier interpolation is performed between the waypoints, to get a smooth and continuous path.

Setting	Туре	Description
Appearance	Appearance	The settings that control how the path will appear in the editor scene view.
Looped	Boolean	If checked, then the path ends are joined to form a continuous loop.
Waypoints	Waypoint[]	The waypoints that define the path. They will be interpolated using a bezier curve.

CinemachinePath.Appearance

This class holds the settings that control how the path will appear in the editor scene view. The path is not visible in the game view.

Setting	Туре	Description
Path Color	Color	The color of the path itself when it is active in the editor.
Inactive Path Color	Color	The color of the path itself when it is inactive in the editor.
Handle Color	Color	The color of tangent controls on the waypoints.
Width	Single	The width of the railroad-tracks that are drawn to represent the path.
Steps	Int32	How many steps are taken between the waypoints when the path is drawn in the editor. Each step is marked by a perpendicular line, like a railway tie.

CinemachinePath.Waypoint

A waypoint along the path.

Setting	Туре	Description



Position	Vector3	Position in path-local space.
Tangent		Offset from the position, which defines the tangent of the curve at the waypoint. The length of the tangent encodes the strength of the bezier handle. The same handle is used symmetrically on both sides of the waypoint, to ensure smoothness.
Roll	_	Defines the roll of the path at this waypoint. The other orientation axes are inferred from the tangent and world up.



State-Driven Camera

The State-Driven Camera is an implementation of a simple yet powerful concept: activate specific shots when the subject enters specific animations states.

Even better, the blending between shots within the state-driven rig can be customized and tuned to maximize the emotional punch of the transitions.

Using Cinemachine it's possible to set up world-class 3rd person action adventure camera systems. For example, you can create a unique Free-Look camera for events like this: Stand / Walk, Run, Sprint, etc. Link the appropriate Cinemachine Free-Look camera up to that animation state, so when the animation state is triggered it turns on that Cinemachine camera.

The idea is to simply blend into the right Free-Look camera for each animation state. Your 'Sprint' Free-Look gets in closer, the lens is wider and there is a ton of handheld noise. Boom, you now have a 'Roadie Run' camera. This concept has been used to set up a complex camera rig that had over 40 Free-Look cameras for a character's local-motion and combat system, all set up so quickly and all tuneable in real-time.

Available vcams are the GameObject children of the State-Driven Camera. Make as many as you like. These vcams will only be visible to the State-Driven Camera parent, and will consume no processing resources until they are activated by the parent.

Once you have set the Animated Target setting to point to a target object that has animation states, the inspector editor will scan the target object for animation states and populate its menus so that you can quickly and easily map available animation states to child vcams.



CinemachineStateDrivenCamera

This is a virtual camera "manager" that owns and manages a collection of child Virtual Cameras.



These child vcams are mapped to individual states in an animation state machine, allowing you to associate specific vcams to specific animation states. When that state is active in the state machine, then the associated camera will be activated.

You can define custom blends and transitions between child cameras.

In order to use this behaviour, you must have an animated target (i.e. an object animated with a state machine) to drive the behaviour.

Setting	Туре	Description
Look At	Transform	Default object for the camera children to look at (the aim target), if not specified in a child camera. May be empty if all of the children define targets of their own.
Follow	Transform	Default object for the camera children wants to move with (the body target), if not specified in a child camera. May be empty if all of the children define targets of their own.
Show Debug Text	Boolean	When enabled, the current child camera and blend will be indicated in the game window, for debugging.
Enable All Child Cameras	Boolean	Force all child cameras to be enabled. This is useful if animating them in Timeline, but consumes extra resources.
Animated Target	Animator	The state machine whose state changes will drive this camera's choice of active child.
Layer Index	Int32	Which layer in the target state machine to observe.
Instruction s	Instruction[]	The set of instructions associating virtual cameras with states. These instructions are used to choose the live child at any given moment.
Default Blend	CinemachineBl endDefinition	The blend which is used if you don't explicitly define a blend between two Virtual Camera children.
Custom Blends	CinemachineBl enderSettings	This is the asset which contains custom settings for specific child blends.
Priority	Int32	The priority will determine which camera becomes active based on the state of other cameras and this camera. Higher numbers have greater priority.



Collision Avoidance and Shot Evaluation

When characters move around in complex environments, sometimes obstacles in the scene can come between a camera and its subject. Similarly, it can also happen that scene obstacles will inconveniently find themselves to be exactly where a camera wants to be. Cinemachine provides a mechanism to handle these situations.

The Collider module can be added to any Cinemachine Virtual Camera (including complex camera types such as FreeLook, State-Driven-Camera, and ClearShot). It does some or all of several things:

- Pushes the camera out of intersecting obstacles in the scene.
- Puts the camera in front of obstacles that come between the camera and its LookAt target.
- Evaluates shot quality (has the camera been moved away from where it wants to be?
 does the camera have a clear view of its target? is the camera at a desirable distance
 from its target?). This shot evaluation becomes part of the state information of the vcam,
 and is available for use by modules that perform actions based on shot quality (see
 ClearShot, for example).
- Gaussian smoothing of camera position.

The collider uses Physics Raycasts to do these things, hence obstacles in the scene must have collider volumes in order to be visible to the CinemachineCollider. Furthermore, there is an associated performance cost related to this. If your game is such that the cost of using physics is prohibitive, then you might prefer to implement this functionality in a different way.

CinemachineCollider

An add-on module for Cinemachine Virtual Camera that post-processes the final position of the virtual camera. Based on the supplied settings, the CinemachineCollider will attempt to preserve the line of sight with the compositional target of the Cinemachine Virtual Camera and/or keep a certain distance away from objects around the Cinemachine Virtual Camera.

Additionally, the Collider can be used to assess the shot quality and report this as a field in the camera State.

Setting	Туре	Description
Collide Against	LayerMask	The Unity layer mask by which the collider will raycast against.
Preserve Line Of		When enabled, will move the camera in front of anything which intersects the Line of Sight feeler.



Sight		
Line Of Sight Feeler Distance		The raycast distance to test for when checking if the line of sight to this camera's target is clear. If the setting is 0 or less, the current actual distance to target will be used.
Minimum Distance From Target		Never get closer to the target than this.
Minimum Distance From Camera	Single	Ignore obstacles that are closer to the camera than this.
Use Curb Feelers		When enabled, will push the camera away from any object touching a curb feeler.
Curb Feeler Distance	•	The raycast distance used to check if the camera is colliding against objects in the world.
Curb Resistance	Single	The firmness with which the collider will push back against any object.
Position Smoothing	Single	The strength of the jitter reduction for position. Higher numbers smooth more but reduce performance and introduce lag.
Optimal Target Distance	•	If greater than zero, a higher score will be given to shots when the target is closer to this distance. Set this to zero to disable this feature.



ClearShot

CinemachineClearShot

Cinemachine ClearShot is a "manager camera" that owns and manages a set of Virtual Camera GameObject children. When Live, the ClearShot will check the children, choose the one with the best quality shot, and make it Live.

This can be a very powerful tool. If the child cameras have CinemachineCollider extensions, they will analyze the scene for target obstructions, optimal target distance, and other items, and report their assessment of shot quality back to the ClearShot parent, who will then choose the best one. You can use this to set up complex multi-camera coverage of a scene, and be assured that a clear shot of the target will always be available.

If multiple child cameras have the same shot quality, the one with the highest priority will be chosen.

You can also define custom blends between the ClearShot children.

Setting	Туре	Description
Look At		Default object for the camera children to look at (the aim target), if not specified in a child camera. May be empty if all children specify targets of their own.
Follow	Transform	Default object for the camera children wants to move with (the body target), if not specified in a child camera. May be empty if all children specify targets of their own.
Show Debug Text	Boolean	When enabled, the current child camera and blend will be indicated in the game window, for debugging.
Activate After	Single	Wait this many seconds before activating a new child camera.
Min Duration	•	An active camera must be active for at least this many seconds, unless a higher-priority camera wants to activate.
Randomiz e Choice		If checked, camera choice will be randomized if multiple cameras are equally desirable. Otherwise, child list order and child camera priority will be used.
Default Blend		The blend which is used if you don't explicitly define a blend between two Virtual Cameras.



Priority	Int32	The priority will determine which camera becomes active based on
		the state of other cameras and this camera. Higher numbers have
		greater priority.



Multiple Target Objects

If you have multiple LookAt targets and you want to keep them all in the frame, Cinemachine can do this too. It's a 2-step process:

- 1. Define a target group. This is a list of target objects, each with a weight and radius. The weight says how important the group member is, and the radius is a rough indication of its physical size.
- 2. Create a vcam with a GroupComposer, and assign the LookAt target to the target group. The GroupComposer will make sure that all group members remain in the frame.

There is a shortcut in the Cinemachine menu to set this up and get you going.



CinemachineTargetGroup

Defines a group of target objects, each with a radius and a weight. The weight is used when calculating the average position of the target group. Higher-weighted members of the group will count more. The bounding box is calculated by taking the member positions and radii into account, but not weight.

Setting	Туре	Description
Position Mode	PositionMode	How the group's position is calculated. Select GroupCenter for the center of the bounding box, and GroupAverage for a weighted average of the positions of the members.
		Possible Values:Group Center: Group position will be the center of the group's axis-aligned bounding box.
		- Group Average: Group position will be the weighted



		average of the positions of the members.
Rotation Mode	RotationMode	How the group's rotation is calculated. Select Manual to use the value in the group's transform, and GroupAverage for a weighted average of the orientations of the members.
		Possible Values:
		- Manual: Manually set in the group's transform.
		- Group Average : Weighted average of the orientation of its members.
Targets	Target[]	The target objects, together with their weights and radii, that will contribute to the group's average position, orientation, and size.

CinemachineTargetGroup.Target

Holds the information that represents a member of the group.

Setting	Туре	Description
Target	Transform	The target objects. This object's position and orientation will contribute to the group's average position and orientation, in accordance with its weight.
Weight	Single	How much weight to give the target when averaging. Cannot be negative.
Radius	Single	The radius of the target, used for calculating the bounding box. Cannot be negative.

CinemachineGroupComposer

This is a CinemachineComponent in the Aim section of the component pipeline. Its job is to aim the camera at a target object, with configurable offsets, damping, and composition rules.

In addition, if the target is a CinemachineTargetGroup, the behaviour will adjust the FOV and the camera distance to ensure that the entire group of targets is framed properly.

Setting	Туре	Description



Group Framing Size	Single	The bounding box of the targets should occupy this amount of the screen space. 1 means fill the whole screen. 0.5 means fill half the screen, etc.
Framing Mode	FramingMode	What screen dimensions to consider when framing. Can be Horizontal, Vertical, or both.
		Possible Values:
		- Horizontal : Consider only the horizontal dimension. Vertical framing is ignored.
		- Vertical : Consider only the vertical dimension. Horizontal framing is ignored.
		- Horizontal And Vertical: The larger of the horizontal and vertical dimensions will dominate, to get the best fit.
Frame Damping	Single	How aggressively the camera tries to frame the group. Small numbers are more responsive, rapidly adjusting the camera to keep the group in the frame. Larger numbers give a more heavy slowly responding camera.
Adjustment Mode	AdjustmentMode	How to adjust the camera to get the desired framing. You can zoom, dolly in/out, or do both.
		Possible Values:
		- Zoom Only : Do not move the camera, only adjust the FOV.
		- Dolly Only : Just move the camera, don't change the FOV.
		- Dolly Then Zoom : Move the camera as much as permitted by the ranges, then adjust the FOV if necessary to make the shot.
Max Dolly In	Single	The maximum distance toward the target that this behaviour is allowed to move the camera.
Max Dolly Out	Single	The maximum distance away the target that this behaviour is allowed to move the camera.
Minimum Distance	Single	Set this to limit how close to the target the camera can get.
Maximum Distance	Single	Set this to limit how far from the target the camera can get.
Minimum FOV	Single	If adjusting FOV, will not set the FOV lower than this.



Maximum FOV	Single	If adjusting FOV, will not set the FOV higher than this.
Show Guides	Boolean	This displays the Composer overlay in the Game window. You can adjust colours and opacity in Edit/Preferences/Cinemachine.
Tracked Object Offset	Vector3	Target offset from the target object's center in target-local space. Use this to fine-tune the tracking target position when the desired area is not the tracked object's center.
Horizontal Damping	Single	How aggressively the camera tries to follow the target in the screen-horizontal direction. Small numbers are more responsive, rapidly orienting the camera to keep the target in the dead zone. Larger numbers give a more heavy slowly responding camera. Using different vertical and horizontal settings can yield a wide range of camera behaviors.
Vertical Damping	Single	How aggressively the camera tries to follow the target in the screen-vertical direction. Small numbers are more responsive, rapidly orienting the camera to keep the target in the dead zone. Larger numbers give a more heavy slowly responding camera. Using different vertical and horizontal settings can yield a wide range of camera behaviors.
Screen X	Single	Horizontal screen position for target. The camera will rotate to position the tracked object here.
Screen Y	Single	Vertical screen position for target, The camera will rotate to position the tracked object here.
Dead Zone Width	Single	Camera will not rotate horizontally if the target is within this range of the position.
Dead Zone Height	Single	Camera will not rotate vertically if the target is within this range of the position.
Soft Zone Width	Single	When target is within this region, camera will gradually rotate horizontally to re-align towards the desired position, depending on the damping speed.
Soft Zone Height	Single	When target is within this region, camera will gradually rotate vertically to re-align towards the desired position, depending on the damping speed.
Bias X	Single	A non-zero bias will move the target position horizontally away from the center of the soft zone.
Bias Y	Single	A non-zero bias will move the target position vertically away
	•	•



from the center of the soft zone.	



Post-Processing Stack

If you have Unity's Post-Processing Stack as an asset in your project (and if you don't, you should, because this is an amazing tool that gives world-class results), you can easily assign custom post-effects to any shot in your scene, even though it's a virtual camera and not a real one.

Just define a Post-Processing profile for your vcam, and connect it by attaching a CinemachinePostFX component to your vcam. To complete the connection, you will also need a CinemachinePostFX component on the Unity camera, alongside the CinemachineBrain. That's all you have to do. Now, whenever the vcam is activated, its custom Post-Processing profile will be applied to the Unity camera.

CinemachinePostFX

This behaviour is a liaison between Cinemachine with the Post-Processing module. You must have the Post-Processing Stack unity package installed in order to use this behaviour.

It's used in 2 ways:

- As a component on the Unity Camera: it serves as the liaison between the camera's CinemachineBrain and the camera's Post-Processing behaviour. It listens for camera Cut events and resets the Post-Processing stack when they occur. If you are using Post-Processing, then you should add this behaviour to your camera alongside the CinemachineBrain, always.
- As a component on the Virtual Camera: In this capacity, it holds a Post-Processing Profile
 asset that will be applied to the camera whenever the Virtual camera is live. It also has
 the (temporary) optional functionality of animating the Focus Distance and DepthOfField
 properties of the Camera State, and applying them to the current Post-Processing profile.

Setting	Туре	Description
Profile		When this behaviour is on a Unity Camera, this setting is the default Post-Processing profile for the camera, and will be applied whenever it is not overridden by a virtual camera. When the behaviour is on a virtual camera, then this is the Post-Processing profile that will become active whenever this virtual camera is live.
Focus Tracks Target		If checked, then the Focus Distance will be set to the distance between the camera and the LookAt target.



Focus Offset	Single	Offset from target distance, to be used with Focus
		Tracks Target.

B

Post Processing Stack Main Camera

The main scene camera has a Cinemachine Brain on it That's how Cinemachine works. Create as many virtual cameras as you want and have them blend and cut and those final transforms are sent to the main camera.



Post Processing Behavior and Cinemachine Post FX component on the main camera




Post Processing Stack Cinemachine cameras

You can have custom Post FX on each/any Cinemachine camera by simply adding a Cinemachine Post FX component and using a different PostProcessingProfile

B

Set the focus distance to automatically track the target and adjust focus plane

Animate the Focus Offset on Timeline for nice rack focuses or some human error micro adjust mojo





And the Rest

CinemachineFollowZoom

An add-on module for Cinemachine Virtual Camera that adjusts the FOV of the lens to keep the target object at a constant size on the screen, regardless of camera and target position.

Setting	Туре	Description
Width	Single	The shot width to maintain, in world units, at target distance.
Damping	Single	Increase this value to soften the aggressiveness of the follow-zoom. Small numbers are more responsive, larger numbers give a more heavy slowly responding camera.
Min FOV	Single	Lower limit for the FOV that this behaviour will generate.
Max FOV	Single	Upper limit for the FOV that this behaviour will generate.

CinemachineSmoother

An add-on module for Cinemachine Virtual Camera which post-processes the final position and orientation of the virtual camera, as a kind of low-pass filter.

Setting	Туре	Description
Position Smoothing	Single	The strength of the smoothing for position. Higher numbers smooth more but reduce performance and introduce lag.
Look At Smoothing	Single	The strength of the smoothing for the LookAt target. Higher numbers smooth more but reduce performance and introduce lag.
Rotation Smoothing	Single	The strength of the smoothing for rotation. Higher numbers smooth more but reduce performance and introduce lag.

CinemachineExternalCamera

This component will expose a non-Cinemachine camera to the Cinemachine system, allowing it to participate in blends. Just add it as a component alongside an existing Unity Camera component.



Setting	Туре	Description
Priority		The priority will determine which camera becomes active based on the state of other cameras and this camera. Higher numbers have greater priority.

SaveDuringPlay

Cameras need to be tweaked in context - often that means while the game is playing. Normally, Unity does not propagate those changes to the scene once play mode is exited. Cinemachine has implemented a special feature to preserve parameter tweaks made during game play. It won't save structural changes (like adding or removing a behaviour), but it will keep the tweaks. Cinemachine behaviours have a special attribute **[SaveDuringPlay]** to enable this functionality. Feel free to use it on your own scripts too if you need it.

It works by scanning the scene after Play exits and applying any changed parameters back to the scene. This kicks in a second or so after exit. You can always hit Undo to revert the changes.


If there are specific settings within a behaviour that you want to exclude from Play-Mode save, you can add the **[NoSaveDuringPlay]** attribute to them, and they will be skipped.




Timeline Integration


- 1. Drag a Cinemachine-enabled Unity camera (i.e. one with a CinemachineBrain component) onto the timeline, select **Create Cinemachine Track** from the popup menu.
- 2. The Cinemachine track is an enable/disable style track, which means that the clips will enable Cinemachine Virtual Cameras while they are active in the timeline.
- 3. Overlapping Cinemachine Shot Clips will produce blends.
- 4. Create a Cinemachine shot by right-clicking on the Cinemachine Track and selecting Create Cinemachine Shot Clip.
- 5. Drag a virtual camera from the scene onto the Cinemachine Shot Clip inspector. That will associate the shot clip with the virtual camera.
- 6. The virtual camera does not need to be enabled in the scene. While the clip is active in the timeline, that camera will become enabled.

The following slides will serve as a brief introduction to get you started.











Special Environments

2D Cameras

Cinemachine supports Orthographic cameras. When you set the Unity Camera's style to Orthographic, Cinemachine will adjust to accommodate it. FOV will be replaced by Orthographic Size in the Lens settings. Note that settings related to FOV and certain FOV-oriented behaviours such as FollowZoom will not have any effect if the camera is orthographic.

Top-Down Games

Cinemachine Virtual Cameras are modeled after human camera operators. As such, they have a sensitivity to the up/down axis, and will always try to avoid introducing roll into the camera framing - unless you deliberately introduce it via such settings as dutch. Because of this sensitivity, virtual cameras do not like to look straight up or down for extended periods. They will do it in passing, but if the LookAt target is often straight up or down, they will not always give the desired results.

If you are building a top-down game, the best practice is to redefine the up direction, for the purposes of the camera. You do this by setting the **World Up Override** in the CinemachineBrain to a game object whose local up points in the direction that you want the Camera's up to normally be. This will be applied to all virtual cameras connected to that brain.

Split-screen

You can set up a multi-camera split-screen with Cinemachine 2.0:

- 1. Make 2 Unity Cameras, give each one its own CinemachineBrain, and set up their viewports.
- 2. Now make 2 virtual cameras to follow the players. Assign those virtual cameras to different layers. We'll call them layer A and layer B.
- 3. Go back to the two Unity cameras, and set their culling masks so that one camera sees layer A but not layer B, and the other camera does the opposite.
- 4. That's it! Camera A will be driven by virtual cameras on layer A, and camera B will be driven by virtual cameras on layer B. They will do their blending etc independently.
- 5. Add as many layers and cameras as you like.



Scripting

Cinemachine is a pure-csharp implementation and is completely accessible to scripting. All of the settings visible in the inspector have corresponding fields in the csharp classes. In addition there is a full scripting API which you can discover either by examining the well-commented sources in the implementation, or by looking at the scripting scene in the examples, or by consulting the API documentation shipped with Cinemachine and available online.