ARCOS Group

uc3m Universidad Carlos III de Madrid

L3: Fundamentals of assembler programming Computer Structure


Bachelor in Computer Science and Engineering
Bachelor in Applied Mathematics and Computing
Dual Bachelor in Computer Science and Engineering and Business Administration




Contents

- 1. Basic concepts on assembly programming
 - Motivations and goals
 - Introduction to RISC-V32
- RISC-V32 assembly language, memory model and data representation
- 3. Instruction formats and addressing modes
- 4. Procedure calls and stack convention


Data representation...



Binary data representation.




- What about the instructions?
 - Machine instructions, properties and format




Machine instructions

▶ There are not complex instructions...




Machine instructions

but very simple tasks...




Machine instruction: definition

- Machine instruction: elementary operation that can be executed directly by the processor.
- Example: instruction of immediate add (addi) for 32 bits
 - (d) = register (s) + immediate value (i)




Machine instruction: properties

- Perform a single, simple task
- Operate on a fixed number of operands
- Include all the information necessary for its execution




Machine instruction: included information

- The operation to be performed.
- Where the operands are located:
 - In registers
 - In memory
 - In the instruction itself (immediate)
- Where to leave the results (as operand)
- A reference to the next instruction to be executed
 - Implicitly: the following instruction
 - A program is a consecutive sequence of machine instructions.
 - Explicitly in branching instructions (as operand)




- What about the instructions?
 - Program, assembly language, ISA




Definition of program

Program: Ordered sequence of machine instructions that are executed by default in order.



Assembly language definition

▶ **Assembly language**: programmer-readable language that is the most direct representation of architecture-specific machine code.



Assembly language definition

- Assembly language: programmer-readable language that is the most direct representation of architecture-specific machine code.
 - Uses symbolic codes to represent instructions
 - ▶ add addition
 - ▶ lw Load a memory data
 - Uses symbolic codes for data and references
 - ▶ t0 − register
 - ▶ There is an assembly instruction per machine instruction
 - add t1, t2, t3

Languages levels

```
High level language
    (Eg: C, C++)
          Compiler
Assembly language
    (Eg: RISC-V)
          Assembler
Machine language
      (RISC-V)
```

0101 1000 0000 1001 1100 0110 1010 1111

Instruction sets

- Instruction Set Architecture (ISA)
 - Instruction set of a processor
 - Boundary between hardware and software

Examples:

- ▶ 80×86
- ARM
- MIPS
- RISC-V
- PowerPC
- Etc.

Characteristics of an instruction set (1/2)

Format and coding of the instruction set:

- Fixed or variable length instructions
 - ▶ 80x86: variable (from 1 up to 18 bytes)
 - MIPS, ARM: fixed

Operands:

Registers, memory, the instruction itself

Type and size of operands:

- bytes: 8 bits
- integers: 16, 32, 64 bits
- floating-point numbers: single precision, double precision, etc.

Addressing modes:

They specify where and how to access operands (register, memory or the instruction itself)

Characteristics of an instruction set (2/2)

Operations:

Arithmetic, logic, transfer, control, control, etc.

Flow control instructions:

- Unconditional jumps
- Conditional jumps
- Procedure calls

Memory addressing:

- Most of them use byte addressing
- They provide instructions for accessing multi-byte elements from a given position

Programming model of a computer

- ▶ A computer offers a programming model that consists of:
 - Instruction set (assembly language)
 - ▶ ISA: Instruction Set Architecture
 - An instruction includes:
 - □ Operation code
 - □ Other elements: registers, memory address, numbers
 - Storing elements
 - Registers
 - Memory
 - ▶ Registers of I/O controllers
 - Execution modes

Motivation to learn assembly

High-level language

Assembly language

Machine language

```
#include <stdio.h>

#define PI 3.1416
#define RADIO 20

int main ()
{
  int I;

  l=2*PI*RADIO;
  printf("long: %d\n",I);
  return (0);
}
```



```
.data
Pl: .word 3.14156
RADIO: .word 20

.text
li a0 2
la t0 Pl
lw t0 ($t0)
la t1 RADIO
lw t1 (t1)
mul a0 a0 t0
mul a0 a0 t1

li a7 1
ecall
```



Motivation to learn assembly

```
#include <stdio.h>
         #define PI 3.1416
          #define RADIUS 20
data
  PI: .WO
  RADIUS
          int main ()
text
             register int I;
      a0
      t0 P
              I=2*PI*RADIUS;
              printf("long: %d\n",l);
               return (0);
    mul a0
    mul a0
    li a7
     ecall
```

- Understand how high-level languages are executed
 - C, C++, Python, Java, ...
- Analyze the execution time of high-level instructions.
- Useful in specific domains:
 - Compilers
 - Operating Systems
 - Games
 - Embedded systems
 - Etc.

Goals


- Know how the elements of a highlevel assembly language are represented.:
 - Data types (int, char, ...)
 - ► Control structures (if, while, ...)
- Be able to write small programs in assembler

```
.data
PI: .word 3.14156
RADIUS: .word 20

.text
li a0 2
la t0 PI
lw t0 (t0)
la t1 RADIUS
lw t1 (t1)
mul a0 a0 t0
mul a0 a0 t1

li a7 1
ecall
```

Motivation to use CREATOR simulator




https://creatorsim.github.io/

- CREATOR: didaCtic geneRic assEmbly progrAmming simulaTOR
- CREATOR can simulate MIPS₃₂ and RISC-V architectures
- CREATOR can be executed from Firefox, Chrome, Edge or Safari

Motivations to use RISC-V

- RISC processor (Reduced Instruction Set Computer)
- Examples of RISC processors:
 - RISC-V, ARM, MIPS, etc.



Advantages of using RISC-V

- Open hardware architecture:
 - Allows anyone to design, manufacture and sell RISC-V chips and software
- Small and simple set of instructions
 - ▶ RV32I -> ~47 instructions, RV32IMAF -> ~76
 - Difference with x86 architecture instructions



Contents

- 1. Basic concepts on assembly programming
 - Motivations and goals
 - Introduction to RISC-V32
- RISC-V32 assembly language, memory model and data representation
- 3. Instruction formats and addressing modes
- 4. Procedure calls and stack convention

RISC-V instruction set

Instruction sets:

- ▶ RV32I: Set of instructions on integers. 32 bits
- ▶ RV64I: Set of instructions on integers. 64 bits
- RV1281: Set of instructions about integers. 128 bits
- On each of them there are different extensions:
 - M: instructions for integer multiplication and division
 - F: instructions for single-precision floating point
 - D: double precision floating-point instructions
 - G: Includes M, F and D
 - Q: quadruple-precision floating-point instructions
 - Etc.
- Example: RV64IF: RISC-V 64-bits processor with simpleprecision floating-point instructions

RISC-V instruction sets to be described


Instruction sets:

- ▶ RV32I: Set of instructions on integers. 32 bits
- ▶ RV64I: Set of instructions on integers. 64 bits
- ▶ RV128I: Set of instructions on integers. 128 bits


Each of them has different extensions:

- M: instructions for integer multiplication and division
- F: instructions for single-precision floating point
- D: double precision floating-point instructions

RISC-V register file



CREATOR



Register File (integers)

ABI Name	Number	Uso
zero	×0	Constant 0
ra	хI	Return address (routines)
sp	×2	Stack pointer
gp	×3	Global pointer
tp	×4	Thread pointer
t0t2	×5×7	Temporary (NON-kept between calls)
s0/fp	×8	Temporary (kept between calls) / Frame stack pointer
sl	×9	Temporary (kept between calls)
a0a1	xI0xII	Input argument for routines/returned values
a2a7	x12x17	Input argument for routines
s2s11	x18x27	Temporary (kept between calls)
t3t6	x28x31	Temporary (<u>NON</u> -kept between calls)

▶ There are 32 registers

- Size of 4 bytes (one word)
- Dual name:
 - Logical: ABI name (Application Binary Interface)
 - Numeric: starting with x at the beginning

Use agreement

- Reserved
- Arguments
- Results
- Temporary
- Pointers


Data transfer (integer registers)

Copy data:

- Between registers
- Between registers and memory (later)

Examples:


- Copy from register to register
 mv a0 t0
- li t0 5



```
mv a0 t0 # a0 \leftarrow t0
li t0 5 # t0 \leftarrow 000....00101
```

Arithmetic instructions (integer registers)


- Performs the arithmetic integer operations in two complement.
- Examples (ALU):
 - Addition add t0 t1 t2 # t0 ← t1 + t2 addi t0 t1 5 # t0 ← t1 + 5
 - Subtraction sub t0 t1 t2 # t0 \leftarrow t1 t2
 - Multiplication mul t0 t1 t2 # t0 ← t1 * t2
 - Integer division (5 / 2=2) div t0 t1 t2 # t0 ← t1 / t2
 - Division remainder (5 % 2=1)rem t0 t1 t2 # t0 \leftarrow t1 % t2



Example

```
int a = 5;
int b = 7;
int c = 8;
int i;
```

$$i = a * (b + c)$$





Example

```
int a = 5;
int b = 7;
int c = 8;
int i;
```

```
i = a * (b + c)
```


```
li t1 5
li t2 7
li t3 8
```

```
add t4 t2 t3 mul t4 t4 t1
```

Exercise

```
int a = 5;
int b = 7;
int c = 8;
int i;

i = -(a * (b - 10) + c)
```





```
int a = 5;
int b = 7;
int c = 8;
int i;
```


```
i = -(a * (b - 10) + c)
```

```
li t1 5
li t2 7
li t3 8
li t0 10
sub t4 t2 t0
mul t4 t4 t1
add t4 t4 t3
li t0 -1
mul t4 t4 t0
```

Exercise

```
li t1 5
li t2 7
li t3 8
                                 Can be performed by using
                                     less instrucciones?
li
    t0 10
sub t4 t2 t0
mul t4 t4 t1
add t4 t4 t3
li
    t0 -1
mul t4 t4 t0
```





Register File (floating-point)

ABI Name	Name	Usage	
ft0ft7	f0 f7	Temporals	(like t)
fs0fs1	f8 f9	There are saved	(like s)
fa0fa1	f10 f11	Arguments/return	ı (like a)
fa2fa7	f12 f17	Arguments	(like a)
fs2fs11	f18 f27	There are saved	(like s)
ft8ft11	f28 f3 I	Temporals	(like t)

- ▶ There are 32 registers
- The ft0 register does not have its value set to 0.
- In the single precision extension, the registers are 32 bits (4 bytes).
- In the double precision extension, the registers are 64 bits (8 bytes) and can store:
 - Single precision values in the lower32 bits of the register
 - Double precision values in the 64 bits of the register

Floating-point register file

- ▶ There are 32 floating-point registers in addition to the integer registers:
 - From f0 to f3 l


41

- Copy registers (.s .d):
 - fmv.s rd rs # rd = rs
- Common arithmetic operations (.s .d):
 - ightharpoonup fadd.s rd rsl rs2 # rd = rsl + rs2
 - ightharpoonup fsub.s rd rsl rs2 # rd = rsl rs2

 - fdiv.s rd rs1 rs2 # rd = rs1 / rs2

 - fsqrt.s rd rsl # rd = sqrt(rsl)
 - ightharpoonup fmadd.s rd rs1 rs2 rs3 # rd = rs1 x rs2 + rs3
 - ightharpoonup fmsub.s rd rsl rs2 rs3 # rd = rsl x rs2 rs3

 - ▶ fneg.s rd rs # rd = -rs




Copy instructions

(integer registers<-> floating-point registers)


fmv.w.x rd rs

 Copy from integer register rs to a floating register rd (single precisión)



fmv.x.w rd rs

 Copy from floating register rs (single precision) to a integer register rd



Conversion operations (1/3)

integer <-> simple precision

- ▶ fcvt.w.s rd, rs
 - Convert from simple precision (value in floating register rs) to a 32-bit integer 32 with sign (integer register rd).
- ▶ fcvt.wu.s rd, rs
 - Convert from simple precision (value in floating register rs) to a 32-bit integer 32 withou sign (integer register rd).
- ▶ fcvt.s.w rd, rs
 - Convert a 32-bit integer 32 with sign (value in integer register rs) to a simple precision (floating register rd).
- fcvt.s.wu rd, rs
 - Convert a 32-bit integer 32 without sign (value in integer register rs) to a simple precision (floating register rd).

Conversion operations (2/3)

integer <-> double precision

- fcvt.w.d rd, rs
 - Convert from double precision (value in floating register rs) to a 32-bit integer 32 with sign (integer register rd).
- fcvt.wu.d rd, rs
 - Convert from double precision (value in floating register rs) to a 32-bit integer 32 withou sign (integer register rd).
- ▶ fcvt.d.w rd, rs
 - Convert a 32-bit integer 32 with sign (value in integer register rs) to a double precision (floating register rd).
- fcvt.d.wu rd, rs1
 - Convert a 32-bit integer 32 without sign (value in integer register rs) to a double precision (floating register rd).

Conversion operations (3/3)

double precision <-> simple precision

- ▶ fcvt.s.d rd, rs1
 - Convert from double precision (value in floating register rs) to simple precision (floating register rd).
- fcvt.d.s rd, rs
 - Convert from simple precision (value in floating register rs) to double precision (floating register rd).

Classification of floating-point numbers

- fclass.s rd, rs1 (simple precision)
- fclass.d rd, rs1 (doble precision)
- Save in rd the type of the floating-point number of the register rs1:


Value in rd	Meaning	
0	-Inf	
I	Negative normalized number	
2	Negative non-normalized number	
3	-0	
4	+0	
5	Positive non-normalized number	
6	Positive normalized number	
7	+Inf	
8	8 NaN (non-quiet)	
9	NaN (quit)	



Example

```
float PI = 3,1415;
int radio = 4;
float length;


length = PI * radio;
```





```
.text
main:
  li t0, 0x40490E56
     # does not exist li.s
     # 0x40490E56 is the
     # representation IEEE754
     # in hexadecimal for 3.1415
   fmv.w.x ft0, t0 # ft0 \leftarrow t0
  1i
      t1 4 # 4 in Ca2
   fcvt.s.w ft1, t1 # 4 in ieee754
   fmul.s ft0, ft0, ft1
```


Logical instructions

- Boolean operations
- Examples:
 - AND
 and t0 tl t2 (t0 = tl & t2)
 andi t0 tl t2 (t0 = tl & t2)
 - OR
 or t0 tl t2 (t0 = tl | t2)
 ori t0 tl 80 (t0 = tl | 80)
 - NOT not t0 tl (t0 = ! tl) xori t0 tl -l
 - XOR
 xor t0 tl t2 (t0 = tl ^ t2)










Exercise

li t0, 5 li t1, 8

and t2, t1, t0

What will be the value of t2?



Exercise

li t0, 5
li t1, 0x007FFFFF

and t2, t1, t0

What does an "and" with 0x007FFFFF allow to do?

li t0, 5
li t1, 0x007FFFFF

and t2, t1, t0

What does an "and" with 0x007FFFFF allow to do?

Obtain the 23 least significant bits

The constant used for bit selection is called a mask.

Shift instructions

- Bits movement
- Examples:
 - Shift right logical srl t0 t0 4 (t0 = t0 >> 4 bits)
 - Shift left logical sll t0 t0 5 (t0 = t0 << 5 bits)</p>
 - Shift right arithmetic sra t0 t0 2 (t0 = t0 >> 2 bits)







```
li t0, 5 li t1, 6
```

srai t0, t1, 1

slli t0, t1, 1



• What is the value of t0?

```
000 .... 0110 t1

shift one bit to right (/2)
000 .... 0011 t0
```



• What is the value of \$t0?

```
000 .... 0110 t1

Shit one bit to left (x2)
000 .... 1100 t0
```

Exercise

Make a program that detects the sign of a stored number t0 and leaves in t1 a 1 if it is negative and a 0 if it is positive.







Make a program that detects the sign of a stored number t0 and leaves in t1 a 1 if it is negative and a 0 if it is positive.



li t0 -3

srli t1 t0 31

Comparison instructions (integer registers)

```
▶ slt rd, rs1, rs2
                        if (s(rs1) < s(rs2))
                                              rd = I; else rd = 0
                        if (u(rs1) < u(rs2)) rd = 1; else rd = 0
▶ sltu rd, rs I, rs2
▶ slti rd, rs l, 5
                        if (s(rs1) < s(5))
                                              rd = I; else rd = 0
▶ sltiu rd, rs I, 5
                        if (u(rs 1) < u(5))
                                              rd = I; else rd = 0
                        if (rs I == 0)
seqz rd, rs l
                                              rd = I; else rd = 0
                                              rd = I; else rd = 0
> snez rd, rsl
                        if (rs I != 0)
                        if (rsl > 0)
                                              rd = I; else rd = 0
sgtz rd, rs l
                        if (rs I < 0)
                                              rd = I; else rd = 0
▶ sltz rd, rs l
```

Comparison instructions (floating-point registers)

Simple precision

- ▶ feq.s rd, rs1, rs2
- ▶ fle.s rd, rs1, rs2
- ▶ flt.s rd, rs1, rs2

- if (rsl == rs2) rd= 1; else rd = 0
- if $(rs I \le rs 2)$ rd= I; else rd = 0
- if (rs I < rs 2) rd= I; else rd = 0

Doble precision:


- ▶ feq.d rd, rs1, rs2
- ▶ fle.d rd, rs1, rs2
- ▶ flt.d rd, rs1, rs2


- if (rsl == rs2) rd= 1; else rd = 0
- if $(rs I \le rs 2)$ rd= I; else rd = 0
- if (rs I < rs 2) rd= I; else rd = 0

Control flow

- Change the sequence of instructions to be executed
- Several types:
 - Conditional branches:
 - Branch if value match condition
 - ▶ E.g.: bne t0 t1 label1
 - Unconditional branches:
 - Always branchE.g.: j etiqueta2
 - ▶ Function calls:
 - Branch with return
 - ▶ E.g.: jal ra subrutina l jr ra







Branch instructions

Conditional (only with integer registers):

```
t0
            t1
                label1 # jump to label1 if t0 == t1
bea
                        # jump to label1 if t0 != t1
▶ bne t0 t1 label1
▶ blt t0 t1 label1 # jump to label1 if t0 < t1
▶ bltu t0 t1 label1 # jump to label1 if t0 < t1 (unsigned)</pre>
▶ bge t0 t1 label1
                        # jump to label1 if t0 >= t1
▶ bgeu t0 t1 label1
                        # jump to label1 if t0 >= t1 (unsigned)
(as pseudo-instructions)
            t1 label1 # jump to label1 if t0 > t1
bgt
       t0
ble t0 t1 label1
                        # jump to label1 if t0 <= t1</pre>
```

Branch instructions

jump label

Conditional (only with integer registers):

```
t0
           t1
                label1
                        # jump to label1 if t0 == t1
bea
                        # jump to label1 if t0 != t1
bne
     t0 t1 label1
▶ blt t0 t1 label1 # jump to label1 if t0 < t1
▶ bltu t0 t1 label1 # jump to label1 if t0 < t1 (unsigned)</pre>
bge
     t0 t1 label1 # jump to label1 if t0 >= t1
▶ bgeu t0 t1 label1
                        # jump to label1 if t0 >= t1 (unsigned)
bgt t0 t1 label1 # jump to label1 if t0 > t1
▶ ble
       t0 t1 label1 # jump to label1 if t0 <= t1
```

Unconditional:

▶ j label1 # jump to label1. Equivalent to beq x0 x0 label1

label1 refers to an instruction (represents a memory address where the instruction is located) which is skipped:


```
add t1, t2, t3
j jump_addr
add t2, t3, t4
li t4, 1
jump_addr: 11 t0, 4
```

```
Control flow if
```

```
beq t1 = t0
bne t1 != t0
bge t1 >= t0
ble t0 <= t1
blt t1 < t0
bgt t0 > t1
```

```
int a=1;
int b=2;

main ()
{
   if (a < b) {
        a = b;
   }
   ...
}</pre>
```



Control flow if

```
beq t1 = t0 bne t1 != t0 bge t1 >= t0 ble t0 <= t1 blt t1 < t0 bgt t0 > t1
```

```
int a=1;
int b=2;

main ()
{
   if (a < b) {
        a = b;
   }
   ...
}</pre>
```

```
li t1 1
        li t2 2
if 1:
       blt t1 t2 then 1
            fin 1
then 1: mv t1 t2
fin_1:
```

Control flow if

```
      beq
      t1 = t0

      bne
      t1 != t0

      bge
      t1 >= t0

      ble
      t0 <= t1</td>

      blt
      t1 < t0</td>

      bgt
      t0 > t1
```

```
int a=1;
int b=2;

main ()
{
   if (a < b) {
      a = b;
   }
   ...
}</pre>
```

```
li t1 1
        li t2 2
       bge t1 t2 fin 2
if 2:
then 2: mv t1 t2
fin 2: ...
```

Control flow if-else

```
      beq
      t1 = t0

      bne
      t1 != t0

      bge
      t1 >= t0

      ble
      t0 <= t1</td>

      blt
      t1 < t0</td>

      bgt
      t0 > t1
```


```
int a=1;
int b=2;
main ()
  if (a < b) {
      // action 1
  } else {
      // action 2
```

```
li t1 1
        li t2 2
if 3:
        bge t1 t2 else 3
them 3: # action 1
            fi_3
else 3: # action 2
fi 3: ...
```

Exercise

```
int b1 = 4;
int b2 = 2;

if (b2 == 8) {
    b1 = 1;
}
...
```





```
int b1 = 4;
int b2 = 2;

if (b2 == 8) {
    b1 = 1;
}
...
```

```
li
          t0 4
       1i
          t1 2
      li t2 8
      bne
           t0 t2
                  fin1
      1i
           t1 1
fin1:
```

Branches with floating-point numbers

```
Jump to label if ft1 < ft2
```

```
flt t0, ft1, ft2
bne t0, x0, label
. . . .
label:
```

Control flow while

```
beq t1 = t0
bne t1 != t0
bge t1 >= t0
ble t0 <= t1
blt t1 < t0
bgt t0 > t1
```

```
int i;
main ()
{
    i=0;
    while (i < 10) {

        /* action */
        i = i + 1;
    }
}</pre>
```

Control flow while



```
beq t1 = t0
bne t1 != t0
bge t1 >= t0
ble t0 <= t1
blt t1 < t0
bgt t0 > t1
```

```
int i;
main ()
   i=0;
   while (i < 10) {
     /* action */
     i = i + 1;
```

```
li
             t0 0
            t1 10
         li
while:
         bge t0 t1 (fin
         # action
         addi t0 t0 1
              (while)
fin:
```

Exercise

Make a program that calculates the sum of the first ten numbers and leaves this value in register a0



Make a program that calculates the sum of the first ten numbers and leaves this value in register a0





```
lia00adda0a01adda0a02adda0a03adda0a04adda0a05adda0a06adda0a07adda0a08adda0a09
```

```
Make a program that calculates the sum of the first ten numbers and leaves this value in register a0
```

```
int i, s;

s=0;
i=0;
while (i <= 10)
{
    s = s + i ;
    i = i + 1 ;
}</pre>
```





Make a program that calculates the sum of the first ten numbers and leaves this value in register a0

```
int i, s;

s=0;
i=0;
while (i <= 10)
{
    s = s + i ;
    i = i + 1 ;
}</pre>
```

```
li t0 0
        li a0 0
        li t2 10
while1:
        bgt t0 t2 fin1
        add a0 a0 t0
        addi t0 t0 1
             while1
        j
fin1:
```

Exercise

Calculate the number of 1's of a register (t0). Result in t3.

Calculate the number of I's of a register (t0). Result in t3.

```
i = 0;
n = 45; # number
s = 0;
while (i < 32)
  b = first bit of n
  s = s + b;
   shift the contents of
   of n one bit to the
   right
  i = i + 1;
```

Calculate the number of I's of a register (t0). Result in t3.

```
i = 0;
n = 45; # number
s = 0;
while (i < 32)
  b = first bit of n
  s = s + b;
   shift the contents of
   of n one bit to the
   right
  i = i + 1;
```

77

```
i = 0;
n = 45; # number
s = 0;
while (i < 32)
  b = n & 1;
  s = s + b;
  n = n >> 1;
  i = i + 1;
```




Calculate the number of I's of a register (t0). Result in t3.

```
i = 0;
n = 45; # number
s = 0;
while (i < 32)
  b = n \& 1;
  s = s + b;
  n = n >> 1;
  i = i + 1;
```

```
li t0,0 #i
       li t1, 45 #n
       li t2, 32
      li t3, 0 #s
while: bge t0, t2, fin
       andi t4, t1, 1
       add t3, t3, t4
       srli t1, t1, 1
       addi t0, t0, 1
       j while
fin:
```

Types of instructions summary

- Data transfer
- Arithmetic
- Logical
- Shifting and rotation
- Comparison
- Control flow (branches, ...)
- Conversion
- Input/output
- System calls



Typical faults

- 1) Poorly designed program
 - Does not do what is requested
 - Incorrectly does what is requested
- 2) Programming directly in assembler
 - Do not code in pseudo-code the algorithm to be implemented
- 3) Write unreadable code
 - Do not tabulate the code
 - Do not comment the assembly code or make reference to the algorithm initially proposed.

ARCOS Group

uc3m Universidad Carlos III de Madrid

L3: Fundamentals of assembler programming Computer Structure

Bachelor in Computer Science and Engineering
Bachelor in Applied Mathematics and Computing
Dual Bachelor in Computer Science and Engineering and Business Administration

