

Funambol v6 to v6.5 Migration Guide

Revision History

Name	Date	Reason for Change	Ver./Rev.
G. Migliavacca	17 July 2007	First draft	1.0
S. Nichele	26 July 2007	Added server section	1.1
S. Nichele	02 August 2007	Added section about PimListener	1.2
		and InboxListener configuration	
S. Nichele	31 August 2007	Updated according to v.6.5.1 and	1.3
		added section Database migration	
		script	
S. Nichele	25 September 2007	Updated according to PimListener	1.4
		6.5.3	
S. Nichele	20 October 2007	Added section about Foundation	1.5
		Connector	
P. Maggi	5 November 2007	Modified database migration script	1.6
P. Maggi	15 November 2007	Database migration script: changed	1.7
		type of column 'principal' in	
		fnbl_email_cache,fnbl_email_folder,	
		fnbl_email_sentpop tables; added	
		insertion of Hotmail mail server to	
		the public mail servers list. Revised	
		'Database changes' section.	
P. Maggi	30 November 2007	Database migration script: updated	1.8
		ids ofr Yahoo and AOL mail servers;	
		added update of Gmail mail server	
		to imap protocol; added update of	
		server type and folder names for	
		AOL mail server; added insertion of	
		Google Mail mail servers.	
G. Zanchi	10 Dicembre 2007	Minor revision	1.9
S.Nichele	05 January 2008	Added Step-by-step migration data	1.10
		instructions	

Table of Contents

1.Introduction	4
1.1. Purpose of this Document	4
2.DS Server	5
3.PIMListener	6
3.1. Cluster architecture	6
3.2. Database changes	6
4.Foundation connector	7
4.1. Database changes	7
5.Email Connector / Inbox Listener Migration	8
5.1. Inbox Listener configuration	8
5.2. Cluster architecture	8
5.3. Database changes	8
5.4. Account Migration steps	9
6.Step-by-step migration data instructions	10
6.1. Migration steps on Postgresql	10
6.1.1. Updating public mail servers	10
6.2. Migration steps on MySQL	10
6.2.1. Updating public mail servers	
6.3. Migration steps on Hypersonic (default bundle installation)	
6.3.1. Updating public mail servers	11

1. Introduction

1.1. Purpose of this Document

The purpose of this document is to describe how to migrate data and configuration from Funambol v6 to Funambol v6.5. The document details the migration procedure for single components, such as: DS Server, Email Connector, PIM Listener, etc.

The last sections contain step-by-step instructions about migrate data for hypersonic, mysql and postgres providing moreover the links for the migration script files.

2. DS Server

In this chapter we will show the steps in order to migrate users from a v6.0 installation to a v6.5 version. The tables used in the authentication phase (<code>fnbl_user</code>, <code>fnbl_device</code>, <code>fnbl_user_role</code>, <code>fnbl_principal</code>) have not changed but, in this version, the passwords are stored in the database in an encrypted form.

So, in order to use an already existing user db, the v6.5 DS Server distribution provides a simple script (encryptPasswords.sh[.cmd]) that updates all user passwords encrypting them. The utility reads the user from the DS Server database reading the database information (such as the URL, the driver or the username) in the *install.properties* file located under Funambol/ds-server.

The script tries to understand if the passwords are already encrypted, and a confirmation is required for the users that maybe already have an encrypted password (maybe you already ran this script or you imported old users so that some users already have an encrypted password and others don't).

3. PIMListener

In the new PIM Listener, the configuration bean file has been changed from:

com/funambol/pushlistener/PushListenerConfiguration.xml

to:

com/funambol/pimlistener/PIMListenerConfiguration.xml

Moreover, the configuration file can be specified in the starting script files (.cmd and .sh) using the system property: funambol.pushlistener.config.bean

3.1. Cluster architecture

In v6.5, a new cluster architecture based on JGroups has been introduced. With this new architecture, the entries are automatically partitioned between the push listener instances based on the cluster size (number of servers in the cluster) and on the server index. If there is just one server, all entries are handled by that. This makes the field <code>id_push_listener</code> in the table <code>fnbl_push_listener_registry</code> not needed, and so it has been removed (it was used to segment the entries in the db).

3.2. Database changes

The length of the field fnbl_pim_listener_registry has been increased to 255.

4. Foundation connector

4.1. Database changes

A new table <code>fnbl_pim_contact_photo</code> has been added to store the contact photos.

A new field *photo_type* (*smallint*) has been added to *fnbl_pim_contact* to indicate if the contact has a photo and its type (EMPTY, IMAGE, URL).

5. Email Connector / Inbox Listener Migration

In this chapter we will show the steps required to migrate accounts from the v6.0 installation to the v6.5 version.

5.1. Inbox Listener configuration

In the new Inbox Listener, the configuration bean file has been changed from:

com/funambol/pushlistener/PushListenerConfiguration.xml

to:

com/funambol/email/inboxlistener/InboxListenerConfiguration.xml

Moreover, the configuration file can be specified in the starting script files (.cmd and .sh) using the system property: funambol.pushlistener.config.bean

5.2. Cluster architecture

In v6.5, a new cluster architecture based on JGroups has been introduced. With this new architecture, the accounts are automatically partitioned between the Inbox Listener instances based on the cluster size (number of servers in the cluster) and on the server index. If there is just one server, all accounts are handled by that.

5.3. Database changes

The table below shows the differences between the v6 and v6.5 mail handling schemas:

V6 Schema	V6.5 Schema	Note
fnbl_email_cache		Added foreign key to fnbl_principal. Changed type of column 'principal' to 'bigint'.
fnbl_email_inbox	unchanged	
fnbl_email_folder		Added foreign key to fnbl_principal.Changed type of column 'principal' to 'bigint'.
fnbl_email_sentpop		Added foreign key to fnbl_principal. Changed type of column 'principal' to 'bigint'.
fnbl_email_enable_ account	unchanged	
fnbl_email_account	modified	Added columns: - ms_mailboxname
		Removed columns:
		- listener_id - activation
		- refresh_time
		- keystore_path
		- keystore_pwd

fnbl_email_push_r egistry	New (new table used by the push framework)	Columns - id: (related to fnbl_email_account.account_id) - period (ex refresh_time) - active (ex activation) - last_update - status - task_bean_file
fnbl_email_mailser ver	modified	Removed columns: - keystore_path - keystore_pwd

5.4. Account Migration steps

Read from:

- fnbl_email_enable_account
- fnbl_email_account

Insert into the tables:

- fnbl_email_enable_account
 - o set all columns
- fnbl_email_account
 - o set all columns except: listener_id, activation, refresh_time
- fnbl_email_push_registry
 - o id = account_id
 - o period = fnbl_email_account.refresh_time
 - o active = fnbl_email_account.activation
 - o last_update = now
 - o status = "N"
 - o task_bean_file = "com/funambol/email/inboxlistener/task/InboxListenerTask.xml"

Note: the value of keystore_path and keystore_pwd must be ignored.

6. Step-by-step migration data instructions

6.1. Migration steps on Postgresql

In order to migrate your data, follow these steps:

- 1. Stop the Funambol services (ds-server, inbox-listener, pim-listener)
- 2. Backup your database (see Postgresql documentation)
- 3. Download migration script files from: http://cvs.forge.objectweb.org/cgibin/viewcvs.cgi/sync4j/3x/docs/ds-server/migrate-v6-to-v65-script-files/postgresql/? only with tag=b v65
- 4. Using postgresql tools (like pgAdmin or psql command line tool) run the script migrate v6 to v65 postgresql.sql
- 5. Open a shell and change directory to Funambol/ds-server/bin6. Run encryptPasswords.sh[.cmd]

6.1.1. Updating public mail servers

Funambol V6.5 adds support to Hotmail and to GoogleMail. Moreover Gmail is now configured as IMAP server.

In order to help you in the mail servers upgrade, Funambol provides the script migrate public mailservers postgresql.sql. It contains the queries to upgrade the V6 public mail servers to the V65 ones, but if you added your own mail servers or if you changed the configuration of the existing ones, Funambol suggests you to compare the data in fnbl email mailserver with the V65 init script file:

http://cvs.forge.objectweb.org/cgi-

bin/viewcvs.cgi/sync4j/3x/modules/emailconnector/src/sql/postgresql/init_schema.sql? only with tag=b v65

6.2. Migration steps on MySQL

MySql was not fully supported in V6, but instructions are available for those who may need them, at: https://wiki.objectweb.org/sync4j/Wiki.jsp?page=Funambol60onMysql

In order to migrate your data, follow these steps:

- 1. Stop the Funambol services (ds-server, inbox-listener, pim-listener)
- 2. Backup your database (see MySQL documentation)
- Download the migration script files from: http://cvs.forge.objectweb.org/cgibin/viewcvs.cgi/sync4j/3x/docs/ds-server/migrate-v6-to-v65-script-files/mysql/? only with tag=b v65
- 4. Using MySQL tools run the script: migrate v6 to v65 mysql.sql
- 5. Open a shell and change directory to Funambol/ds-server/bin6. Run encryptPasswords.sh[.cmd]

6.2.1. Updating public mail servers

Funambol V6.5 adds support to Hotmail and to GoogleMail. Moreover Gmail is now configured as IMAP server.

In order to help you in the mail servers upgrade, Funambol provides the script migrate public mailservers mysgl.sql. It contains the queries to upgrade the V6 public mail servers to the V65 ones, but if you added your own mail servers or if you changed the configuration of the existing ones, Funambol suggests you to compare the data in fnbl_email_mailserver with the V65 init script file: http://cvs.forge.objectweb.org/cgi-

bin/viewcvs.cgi/sync4j/3x/modules/emailconnector/src/sql/mysql/init_schema.sgl?only_with_tag=b_v65

6.3. Migration steps on Hypersonic (default bundle installation)

In order to migrate your data, follow these steps (FunambolV6 indicates the root directory of the V6 installation, FunambolV65 indicates the root directory of the V65):

- 1. Stop the Funambol V6 services (ds-server, inbox-listener, pim-listener, hypersonic)
- 2. Backup your database copying the files in FunambolV6/tools/hypersonic/data
- 3. Download the migration script files from http://cvs.forge.objectweb.org/cgi-bin/viewcvs.cgi/sync4j/3x/docs/ds-server/migrate-v6-to-v65-script-files/hypersonic/?
 only with tag=b v65 and copy it in the Funambol root directory.
- 4. Start the Funambol V6 services (in this way also hypersonic will be started).
- 5. Run:

```
tools\jre-1.5.0\jre\bin\java org.hsqldb.util.SqlTool --autocommit --inlineRc
URL=jdbc:hsqldb:hsql://localhost/funambol,USER=sa
migrate_v6_to_v65_hypersonic.sql
```

Press <Enter> when the password for user sa is required since by default it is empty...

- 6. Stop the Funambol V6 services (ds-server, inbox-listener, pim-listener, hypersonic)
- 7. Copy data files from FunambolV6/tools/hypersonic/data to FunambolV65/tools/hypersonic/data
- 8. Start the Funambol V65 services (ds-server, inbox-listener, pim-listener, hypersonic)
- 9. Open a shell and change directory to FunambolV65/ds-server/bin
- 10. Run encryptPasswords.sh[.cmd]

6.3.1. Updating public mail servers

Funambol V6.5 adds support to Hotmail and to GoogleMail. Moreover Gmail is now configured as IMAP server.

In order to help you in the mail servers upgrade, Funambol provides the script migrate_public_mailservers_hypersonic.sql. It contains the queries to upgrade the V6 public mail servers to the V65 ones, but if you added your own mail servers or if you changed the configuration of the existing ones, Funambol suggests you to compare the data in fnbl_email_mailserver with the V65 init script file:

http://cvs.forge.objectweb.org/cgi-

bin/viewcvs.cgi/sync4j/3x/modules/emailconnector/src/sql/hypersonic/init_schema.sql? only with tag=b v65