

Alcyon 3iV - Seraing

Comment : Fields indicated with * are in use.

Message: **REQU_USERCONTEXT**

Description : REQU_USERCONTEXT

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	REQU_USERCONTEXT
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	contextType	NUMERIC	Indicator what kind of signing on is done 1 = Sign On 2 = Sign Off	1
11	requestType	NUMERIC	Type of PickHeader request 0=request pending PickHeader 1=request new PickHeader	1
* 12	scenarioStatus	STRING	Scenario Status 01=SignOn	01
13	Cri01	STRING	Spoken or scanned value	12
14	Cri02	STRING	Spoken or scanned value	
15	Cri03	STRING	Spoken or scanned value	
16	Cri04	STRING	Spoken or scanned value	
17	Cri05	STRING	Spoken or scanned value	
18	Usf01	STRING	Userfield 01	987692
19	Usf02	STRING	Userfield 02	
20	Usf03	STRING	Userfield 03	
21	Usf04	STRING	Userfield 04	
22	Usf05	STRING	Userfield 05	

Field	Name	Format	Description	Example
23	Usf06	STRING	Userfield 06	
24	Usf07	STRING	Userfield 07	
25	Usf08	STRING	Userfield 08	
26	Usf09	STRING	Userfield 09	
27	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,REQU_USERCONTEXT,12345,1,20070721,103011,20070621103011,1,1,01,12,,,,,987692
,,,,,,>

Message: **RESP_USERCONTEXT**

Description : RESP_USERCONTEXT

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	RESP_USERCONTEXT
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	respCode	NUMERIC	Response Result Code. 0=OK 1=OK with warning in RespMsg 2..9=by default equal to OK, customizable values 10=NOK 11..999=by default equal to NOK, customizable values 1000..1999=3iV Connector Errors 2000..2999=3iV Connector Warnings	0

Field	Name	Format	Description	Example
* 11	respMsg	STRING	Response message When errorcode greater then 0, this message is spoken	
* 12	contextType	NUMERIC	Indicator what kind of signing on is done 1 = Sign On 2 = Sign Off 3 = Activity 4 = Start Pause 5 = Stop Pause 6 = Suspend 7..99=customizable values, by default not used	1
* 13	scenarioStatus	STRING	Scenario Status 01=SignOn 02=Request 03=Preparation 04=Execution 05=Closing 06=Finished	01
14	responseType	NUMERIC	Type of PickHeader response 0=response pending Pick Header 1=response new Pick Header 2=response no more Pick Headers	1
* 15	assignmentType	NUMERIC	Assignment Type 1=Picking	1
* 16	operName	STRING	Operator Name	James Bond
17	operType	NUMERIC	Operator Type 1=beginner 2=staff 3=performer	1
* 18	unitSlam	NUMERIC	Unit slam detection 0=no unit slam detected 1=unit slam detected (still work open for this user).	1
* 19	Usf01	STRING	In case of unitSlam : Groupnum of the slammed assignment. Otherwise : (empty)	999999
20	Usf02	STRING	Userfield 02	
21	Usf03	STRING	Userfield 03	
22	Usf04	STRING	Userfield 04	
23	Usf05	STRING	Userfield 05	
24	Usf06	STRING	Userfield 06	
25	Usf07	STRING	Userfield 07	
26	Usf08	STRING	Userfield 08	
27	Usf09	STRING	Userfield 09	
28	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,RESP_USERCONTEXT,12345,1,20070721,103011,20070621103011,0,,1,01,1,1,James·Bond,1,1,999999,,,,,,,,,>

Message: RESU_USERCONTEXT

Description : RESU_USERCONTEXT

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	Type of the Message, eg. RESU_USERCONTEXT	RESU_USERCONTEXT
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	contextType	NUMERIC	Indicator what kind of signing on is done 1 = Sign On 2 = Sign Off 4 = Start Pause 5 = Stop Pause 6 = Suspend	1
* 11	scenarioStatus	STRING	Scenario Status 01=SignOn 02=Request 03=Preparation 04=Execution 05=Closing 06=Finished	01
12	requestType	NUMERIC	Type of PickHeader request 0=request pending PickHeader 1=request new PickHeader	1

Field	Name	Format	Description	Example
* 13	assignmentType	NUMERIC	Assignment Type 1=Picking 2=XDock 3=Inventory 4=Moving 5..9=customizable values, by default not used	1
* 14	operName	STRING	Operator Name	James Bond
15	operType	NUMERIC	Operator Type 1=beginner 2=staff 3=performer	1
16	Usf01	STRING	Userfield 01	987692
17	Usf02	STRING	Userfield 02	
18	Usf03	STRING	Userfield 03	
19	Usf04	STRING	Userfield 04	
20	Usf05	STRING	Userfield 05	
21	Usf06	STRING	Userfield 06	
22	Usf07	STRING	Userfield 07	
23	Usf08	STRING	Userfield 08	
24	Usf09	STRING	Userfield 09	
25	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,RESU_USERCONTEXT,12345,1,20070721,103011,20070621103011,1,01,1,1,James·Bond,1,987692,,,,,,,,,>

Message: **REQU_REFDATA**

Description : REQU_REFDATA - to be evaluated if used or not (could be replaced by .TXT file, but will require synchronisation with WMS data then).

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	REQU_REFDATA
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721

Field	Name	Format	Description	Example
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
10	assignmentType	NUMERIC	Assignment Type 1=Picking 2=XDock 3=Inventory 4=Moving 5..9=customizable values, by default not used	1
11	scenarioStatus	STRING	Scenario Status 01=SignOn 02=Request 03=Preparation 04=Execution 05=Closing 06=Finished	01
12	dataTypeList	STRING	List representing which data type is requested. Eg. : 1=warehouse only 11=zone and warehouse 10=zone and no warehouse 101=equipmenttype and warehouse	10000
13	Cri01	STRING	Spoken or scanned value	12
14	Cri02	STRING	Spoken or scanned value	
15	Cri03	STRING	Spoken or scanned value	
16	Cri04	STRING	Spoken or scanned value	
17	Cri05	STRING	Spoken or scanned value	
18	Cri06	STRING	Spoken or scanned value	
19	Cri07	STRING	Spoken or scanned value	
20	Cri08	STRING	Spoken or scanned value	
21	Cri09	STRING	Spoken or scanned value	
22	Cri10	STRING	Spoken or scanned value	
23	Usf01	STRING	Userfield 01	987692
24	Usf02	STRING	Userfield 02	
25	Usf03	STRING	Userfield 03	
26	Usf04	STRING	Userfield 04	
27	Usf05	STRING	Userfield 05	
28	Usf06	STRING	Userfield 06	
29	Usf07	STRING	Userfield 07	
30	Usf08	STRING	Userfield 08	
31	Usf09	STRING	Userfield 09	
32	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,REQU_REFDATA,12345,1,20070721,103011,20070621103011,1,01,10000,12,,,,,,,,,,987692,,,,,,,,,>

Message: *RESP_REFDATA*

Description : RESP_REFDATA - to be evaluated if used or not (could be replaced by .TXT file, but will require synchronisation with WMS data then).

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	RESP_REFDATA
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	respCode	NUMERIC	Response Result Code. 0=OK 1=OK with warning in RespMsg 2..9=by default equal to OK, customizable values 10=NOK 11..999=by default equal to NOK, customizable values 1000..1999=3iV Connector Errors 2000..2999=3iV Connector Warnings	0
* 11	respMsg	STRING	Response message When errorcode greater then 0, this message is spoken	

Field	Name	Format	Description	Example
* 12	dataType	NUMERIC	Predefined Data type 1 = Warehouse 2 = Zone ID *** 3 = Equipment Type 4 = Carrier Type 5 = Printer Number 6..99 = customizable data types 6 = REASON CODES ***	2
* 13	operValue	STRING	Value dataType=2 (zone) : zone code (2 digits) dataType=6 (reason code) : reason code (1 digit)	01
* 14	promptInfo	STRING	Value dataType=2 (zone) : zone description dataType=6 (reason code) : reason description	médicaments
15	hostValue	STRING	Value known by the WMS/HOST	P10
16	Usf01	STRING	Userfield 01	987692
17	Usf02	STRING	Userfield 02	
18	Usf03	STRING	Userfield 03	
19	Usf04	STRING	Userfield 04	
20	Usf05	STRING	Userfield 05	
21	Usf06	STRING	Userfield 06	
22	Usf07	STRING	Userfield 07	
23	Usf08	STRING	Userfield 08	
24	Usf09	STRING	Userfield 09	
25	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,RESP_REFDATA,12345,1,20070721,103011,20070621103011,0,,2,01,médicaments,P10,987692,,,,,,,,,>

Message: **REQU_ASSIGNMENT**

Description : REQU_ASSIGNMENT

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	REQU_ASSIGNMENT
* 5	operId	STRING	Operator ID or number	12345

Field	Name	Format	Description	Example
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	assignmentType	NUMERIC	Assignment Type 1=Picking	1
* 11	requestType	NUMERIC	Type of PickHeader request 0=request pending PickHeader 1=request new PickHeader	1
* 12	tripCounter	NUMERIC	Stage the current assignment request is in. 1=initial request 2=revisit 3=second revisit	1
* 13	Cri01	STRING	zone for which work is requested	10
* 14	Cri02	STRING	Standard assignment request : (empty). In case of unit slam : Groupnum of the slammed assignment.	
15	Cri03	STRING	Spoken or scanned value	
16	Cri04	STRING	Spoken or scanned value	
17	Cri05	STRING	Spoken or scanned value	
18	Cri06	STRING	Spoken or scanned value	
19	Cri07	STRING	Spoken or scanned value	
20	Cri08	STRING	Spoken or scanned value	
21	Cri09	STRING	Spoken or scanned value	
22	Cri10	STRING	Spoken or scanned value	
23	Cri11	STRING	Spoken or scanned value	
24	Cri12	STRING	Spoken or scanned value	
25	Cri13	STRING	Spoken or scanned value	
26	Cri14	STRING	Spoken or scanned value	
27	Cri15	STRING	Spoken or scanned value	
28	Cri16	STRING	Spoken or scanned value	
29	Cri17	STRING	Spoken or scanned value	
30	Cri18	STRING	Spoken or scanned value	
31	Cri19	STRING	Spoken or scanned value	
32	Cri20	STRING	Spoken or scanned value	
33	Cri21	STRING	Spoken or scanned value	

Field	Name	Format	Description	Example
34	Cri22	STRING	Spoken or scanned value	
35	Cri23	STRING	Spoken or scanned value	
36	Cri24	STRING	Spoken or scanned value	
37	Cri25	STRING	Spoken or scanned value	
38	Cri26	STRING	Spoken or scanned value	
39	Cri27	STRING	Spoken or scanned value	
40	Cri28	STRING	Spoken or scanned value	
41	Cri29	STRING	Spoken or scanned value	
42	Cri30	STRING	Spoken or scanned value	
43	Usf01	STRING	Userfield 01	987692
44	Usf02	STRING	Userfield 02	
45	Usf03	STRING	Userfield 03	
46	Usf04	STRING	Userfield 04	
47	Usf05	STRING	Userfield 05	
48	Usf06	STRING	Userfield 06	
49	Usf07	STRING	Userfield 07	
50	Usf08	STRING	Userfield 08	
51	Usf09	STRING	Userfield 09	
52	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,REQU_ASSIGNMENT,12345,1,20070721,103011,20070621103011,1,1,1,10,,,,,,,,,,,,,
,,,,,,,,,,,,,987692,,,,,,,,,>

Message: **RESP_ASSIGNMENT**

Description : RESP_ASSIGNMENT

	Field	Name	Format	Description	Example
*	1	serNum	STRING	Serial number of the voice client device	987654321
*	2	verNum	STRING	verNum	2.2.3
*	3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
*	4	msgType	STRING	type	RESP_ASSIGNMENT
*	5	operId	STRING	Operator ID or number	12345
*	6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
*	7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721

Field	Name	Format	Description	Example
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageld	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	respCode	NUMERIC	Response Result Code. 0=OK 1=OK with warning in RespMsg 2..9=by default equal to OK, customizable values 10=NOK 11..999=by default equal to NOK, customizable values 1000..1999=3iV Connector Errors 2000..2999=3iV Connector Warnings	0
* 11	respMsg	STRING	Response message When errorcode greater then 0, this message is spoken	
* 12	assignmentType	NUMERIC	Assignment Type 1=Picking 2=XDock 3=Inventory 4=Moving 5..9=customizable values, by default not used	1
	responseType	NUMERIC	Type of PickHeader response 0=response pending Pick Header 1=response new Pick Header 2=response no more Pick Headers	1
* 14	groupNum	STRING	Picklist number	99999999
	groupSubNum	STRING	Optional number to identify the instance of the group	001
* 16	assignmentStatus	STRING	Assignment Status (leading zero is obliged) 00=NEW	01
* 17	Usf01	STRING	If new assignment : (empty). If previously started assignment : check digit of the picklist document accompanying the suspended work (99, leading zeroes).	25
* 18	Usf02	STRING	Client type	vétérinaire
* 19	Usf03	STRING	Trip number (tourn�e)	18
* 20	Usf04	STRING	Overpick allowed 0 = no 1 = yes	0
* 21	Usf05	STRING	Unique batches required 0 = no 1 = yes	0

Field	Name	Format	Description	Example
* 22	Usf06	STRING	Staging type C = contrôle E = emballage (empty or blank) = no staging information	
23	Usf07	STRING	Userfield 07	
24	Usf08	STRING	Userfield 08	
25	Usf09	STRING	Userfield 09	
26	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,RESP_ASSIGNMENT,12345,1,20070721,103011,20070621103011,0,,1,1,99999999,001,01,25,vétérinaire,18,0,0,,,,,>

Message: **RESU_ASSIGNMENT**

Description : RESU_ASSIGNMENT

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	RESU_ASSIGNMENT
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	groupNum	STRING	Picklist number	99999999
11	groupSubNum	STRING	Optional number to identify the instance of the group	001
12	headerNum	STRING	Unique number identifying the header	123456

Field	Name	Format	Description	Example
13	headerSubNum	STRING	Header subnumber	001
* 14	assignmentStatus	STRING	Assignment Status (leading zero is obliged) 01=START 02=ACTIVE 04=DONE (all single lines) 05=CANCELLED 08=FINISHED 01=02 ; 04=08	01
15	Usf01	STRING	Userfield 01	987692
16	Usf02	STRING	Userfield 02	
17	Usf03	STRING	Userfield 03	
18	Usf04	STRING	Userfield 04	
19	Usf05	STRING	Userfield 05	
20	Usf06	STRING	Userfield 06	
21	Usf07	STRING	Userfield 07	
22	Usf08	STRING	Userfield 08	
23	Usf09	STRING	Userfield 09	
24	Usf10	STRING	Userfield 10	

.... |1.... |2.... |3.... |4.... |5.... |6.... |7.... |8.... |9.... |0

Example Delimited :

<987654321,2.2.3,3iV_101,RESU_ASSIGNMENT,12345,1,20070721,103011,20070621103011,99999999,001,123456,001,01,987692,,,,,,,,,>

Message: **REQU_ITEMPICK**

Description : REQU_ITEMPICK

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	REQU_ITEMPICK
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011

Field	Name	Format	Description	Example
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	groupNum	STRING	Picklist number	99999999
11	groupSubNum	STRING	Optional number to identify the instance of the group	001
12	headerNum	STRING	Unique number identifying the header	123456
13	headerSubNum	STRING	Header subnumber	001
* 14	tripCounter	NUMERIC	Stage the current assignment request is in. 1=initial request 2=revisit 3=second revisit	1
* 15	Cri01	STRING	Pick list sequence 0 = ascending 1 = descending	0
16	Cri02	STRING	Spoken or scanned value	
17	Cri03	STRING	Spoken or scanned value	
18	Cri04	STRING	Spoken or scanned value	
19	Cri05	STRING	Spoken or scanned value	
20	Cri06	STRING	Spoken or scanned value	
21	Cri07	STRING	Spoken or scanned value	
22	Cri08	STRING	Spoken or scanned value	
23	Cri09	STRING	Spoken or scanned value	
24	Cri10	STRING	Spoken or scanned value	
25	Usf01	STRING	Userfield 01	987692
26	Usf02	STRING	Userfield 02	
27	Usf03	STRING	Userfield 03	
28	Usf04	STRING	Userfield 04	
29	Usf05	STRING	Userfield 05	
30	Usf06	STRING	Userfield 06	
31	Usf07	STRING	Userfield 07	
32	Usf08	STRING	Userfield 08	
33	Usf09	STRING	Userfield 09	
34	Usf10	STRING	Userfield 10	

....|...1....|...2....|...3....|...4....|...5....|...6....|...7....|...8....|...9....|...0

Example Delimited :

<987654321,2.2.3,3iV_101,REQU_ITEMPICK,12345,1,20070721,103011,20070621103011,99999999,001,123456,001,1,0,,,,,,,,,987692,,,,,,,,,>

Message: RESP_ITEMPICK

Description : RESP_ITEMPICK

Field	Name	Format	Description	Example
-------	------	--------	-------------	---------

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	RESP_ITEMPICK
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ###	20070621103011
* 10	respCode	NUMERIC	Response Result Code. 0=OK 1=OK with warning in RespMsg 2..9=by default equal to OK, customizable values 10=NOK 11..999=by default equal to NOK, customizable values 1000..1999=3iV Connector Errors 2000..2999=3iV Connector Warnings	0
* 11	respMsg	STRING	Response message When errorcode greater then 0, this message is spoken	
* 12	groupNum	STRING	Picklist number	99999999
	groupSubNum	STRING	Optional number to identify the instance of the group	001
	headerNum	STRING	Unique number identifying the header	123456
	headerSubNum	STRING	Header subnumber	001
* 16	itemPickSeqNum	NUMERIC	Sequence number of the detailline within the header	1
* 17	pickLineId	STRING	Unique number identifying the pick line	989898989801
* 18	tripCounter	NUMERIC	Stage the current assignment request is in. 1=initial request 2=revisit 3=second revisit	1
* 19	reqDestCarSeqNum	NUMERIC	Sequence number of the destination carrier FIXED VALUE 1	1
	reqDestCarSeqCD	STRING	Check digit of the destination carrier	23

Field	Name	Format	Description	Example
* 21	sourceLC1	STRING	Source location coordinate 1 - ZONE	M
* 22	sourceLC2	STRING	Source location coordinate 2 - ALLEE	A
* 23	sourceLC3	STRING	Source location coordinate 3 - TRAVEE	B
* 24	sourceLC4	STRING	Source location coordinate 4 - NIVEAU	2
* 25	sourceLC5	STRING	Source location coordinate 5 - EMPLACEMENT+BIN	12
* 26	sourceLCCD	STRING	Check digit of the location	56
* 27	sourceLCBarcode	STRING	Source location barcode	1124500
28	altSourceLC1	STRING	Alternative source location coordinate 1. Eg,Zone	1
29	altSourceLC2	STRING	Alternative source location coordinate 2. Eg, Aisle	20
30	altSourceLC3	STRING	Alternative source location coordinate 3. Eg,Slot	23
31	altSourceLC4	STRING	Alternative source location coordinate 4. Eg,Level	2
32	altSourceLC5	STRING	Alternative source location coordinate 5. Eg,Bin	3
33	altSourceLCCD	STRING	Alternative check digit of the location	98
34	altSourceLCBarcode	STRING	Alternative source location barcode	1202323
35	lineIndicator	NUMERIC	Indicator determining the type of detailline 0=normal line 1=last line	0
* 36	reqQty	NUMERIC	Requested Quantity	1
* 37	effQty	NUMERIC	Quantity effectively moved by operator. Fixed value 000000.	000000
* 38	pickStatus	STRING	Status of the ItemPick line (leading zero is obliged) 00=NEW (default)	00
* 39	promptInfo	STRING	Extra info at the prompt	keep it frozen
40	unitOfMeasure	STRING	Unit of measure code of this itempick line (leading zero is obliged) 01=SINGLE UNIT 02=PACK 03=COLIS 04=LAYER 05=CARRIER 06..99=customizable values, by default not used	03
* 41	productCode	STRING	Productcode	5400141050912
* 42	productDescription	STRING	Productdescription	Vanilla Icecream 500 gram
43	productGroupCode	STRING	Code indicating the productgroup	1
* 44	productProperty1	STRING	Fardelage : how many of this UOM go in a higher UOM.	10
* 45	productProperty2	STRING	Printing of shipping label required during picking. 0 = no 1 = yes	0
46	productProperty3	STRING	Specific property for this product	26

Field	Name	Format	Description	Example
* 47	lessQtyAllowed	NUMERIC	Flag indicating whether picking short is allowed 0 = shortpick not allowed 1 = shortpick allowed FIXED VALUE 1	1
* 48	moreQtyAllowed	NUMERIC	Flag indicating whether picking more is allowed 0 = overpick not allowed 1 = overpick allowed	0
* 49	catchWeightFlag	NUMERIC	Flag indicating whether catching weight is needed 0 = No CW needed 1 = CW needed FIXED VALUE 0	0
* 50	cycleCountFlag	NUMERIC	Flag indicating whether cycle counting is needed 0 = no 1 = yes FIXED VALUE 0	0
* 51	lotTrackingFlag	NUMERIC	Flag indicating whether lot number recording is required 0 = no 1 = yes	0
* 52	expiryDateCheckFlag	NUMERIC	Flag indicating whether expiry date checking is needed 0 = no 1 = yes FIXED VALUE 0	0
53	lotNumber	STRING	Lot number	991122119934
* 54	UOMPrompt	STRING	Unit of measure to prompt at countprompt. Empty if not needed	box
55	singlesInUOM	NUMERIC	Number of singles in 1 Unit of Measure	12
56	minBlockCW	NUMERIC	Minimum CW that is allowed to be declared	9
57	maxBlockCW	NUMERIC	Maximum CW that is allowed to be declared	10.8
58	minAllowedCW	NUMERIC	Minimum CW that can be declared for this article without receiving a warning	9,1
59	maxAllowedCW	NUMERIC	Maximum CW that can be declared for this article receiving a warning	10.5
60	expiryDate	STRING	Expiry date of this article	20070615121301
* 61	productBarcode	STRING	Barcode of this item	5400141050912
* 62	scanProductBarcode	NUMERIC	Flag indicating whether productbarcode need to be scanned 0 = No scanning needed 1 = Scanning needed FIXED VALUE 0	0
* 63	Usf01	STRING	Lot number that exists in stock, 1st in FEFO order.	123
* 64	Usf02	STRING	Lot number that exists in stock, 2nd in FEFO order.	456
* 65	Usf03	STRING	Lot number that exists in stock, 3rd in FEFO order.	
* 66	Usf04	STRING	Lot number that exists in stock, 4st in FEFO order.	
* 67	Usf05	STRING	Lot number that exists in stock, 5th in FEFO order.	

Field	Name	Format	Description	Example
68	Usf06	STRING	Userfield 06	
69	Usf07	STRING	Userfield 07	
70	Usf08	STRING	Userfield 08	
71	Usf09	STRING	Userfield 09	
72	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

```
<987654321,2.2.3,3iV_101,RESP_ITEMPICK,12345,1,20070721,103011,20070621103011,0,,99999999,001,123456,001,1,989898989801,1,1,23,M,A,B,2,12,56,1124500,1,20,23,2,3,98,1202323,0,1,000000,00,keep.it.frozen,03,5400141050912,Vanilla.Icecream.500.gram,1,10,0,26,1,0,0,0,0,991122119934,box,12,9,10.8,9,1,10.5,20070615121301,5400141050912,0,123,456,,,,,,,,,>
```

Message: RESU_ITEMPICK

Description : RESU_ITEMPICK

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	RESU_ITEMPICK
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	groupNum	STRING	Picklist number	99999999
11	groupSubNum	STRING	Optional number to identify the instance of the group	001
12	headerNum	STRING	Unique number identifying the header	123456
13	headerSubNum	STRING	Header subnumber	001

Field	Name	Format	Description	Example
* 14	itemPickSeqNum	NUMERIC	Sequence number of the detailline within the header	1
* 15	pickLineId	STRING	Unique number identifying the pick line	989898989801
16	lineIndicator	NUMERIC	Indicator determining the type of detailline 0=normal line 1=last line	0
* 17	reqQty	NUMERIC	Requested Quantity	1
* 18	effQtySourceLC	NUMERIC	Quantity effectively picked by operator	000005
19	effQtyAltSourceLC	NUMERIC	Quantity effectively picked by operator from the alternative location	000000
* 20	pickStatus	STRING	Status of the ItemPick line (leading zero is obliged) 01=PICKED 02=SHORTPICKED 03=SKIPPED 04=CUT 05=CANCEL 02=04	00
* 21	tripCounter	NUMERIC	Stage the current assignment request is in. 1=initial request 2=revisit 3=second revisit	1
22	unitOfMeasure	STRING	Unit of measure code of this itempick line (leading zero is obliged) 01=SINGLE UNIT 02=PACK 03=COLIS 04=LAYER 05=CARRIER 06..99=customizable values, by default not used	03
23	totalCatchWeight	NUMERIC	Total of all weights caught	56.89
24	lotNumber	STRING	Lot number	991122119934
* 25	productBarcode	STRING	Barcode of this item	5400141050912
* 26	sourceLCBarcode	STRING	Source location barcode	1124500
27	altSourceLCBarcode	STRING	Alternative source location barcode	1202323
28	effQtyDestCar01	NUMERIC	Effective quantity on destination carrier 01	000000
29	effQtyDestCar02	NUMERIC	Effective quantity on destination carrier 02	000000
30	effQtyDestCar03	NUMERIC	Effective quantity on destination carrier 03	000000
31	effQtyDestCar04	NUMERIC	Effective quantity on destination carrier 04	000000
32	effQtyDestCar05	NUMERIC	Effective quantity on destination carrier 05	000000
33	effQtyDestCar06	NUMERIC	Effective quantity on destination carrier 06	000000
34	effQtyDestCar07	NUMERIC	Effective quantity on destination carrier 07	000000
35	effQtyDestCar08	NUMERIC	Effective quantity on destination carrier 08	000000
36	effQtyDestCar09	NUMERIC	Effective quantity on destination carrier 09	000000

Field	Name	Format	Description	Example
37	effQtyDestCar10	NUMERIC	Effective quantity on destination carrier 10	000000
38	effDestCarId01	STRING	Destination carrier 01	1001
39	effDestCarId02	STRING	Destination carrier 02	1002
40	effDestCarId03	STRING	Destination carrier 03	1003
41	effDestCarId04	STRING	Destination carrier 04	1004
42	effDestCarId05	STRING	Destination carrier 05	1005
43	effDestCarId06	STRING	Destination carrier 06	1006
44	effDestCarId07	STRING	Destination carrier 07	1007
45	effDestCarId08	STRING	Destination carrier 08	1008
46	effDestCarId09	STRING	Destination carrier 09	1009
47	effDestCarId10	STRING	Destination carrier 10	1010
48	Usf01	STRING	number of colli labels printed	5
49	Usf02	STRING	Userfield 02	
50	Usf03	STRING	Userfield 03	
51	Usf04	STRING	Userfield 04	
52	Usf05	STRING	Userfield 05	
53	Usf06	STRING	Userfield 06	
54	Usf07	STRING	Userfield 07	
55	Usf08	STRING	Userfield 08	
56	Usf09	STRING	Userfield 09	
57	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

```
<987654321,2.2.3,3iV_101,RESU_ITEMPICK,12345,1,20070721,103011,20070621103011,99999999,001,123456,001,1,989898989801,0,1,000005,000000,00,1,03,56.89,991122119934,5400141050912,1124500,1202323,000000,000000,000000,000000,000000,000000,000000,000000,000000,1001,1002,1003,1004,1005,1006,1007,1008,1009,1010,5,,,,,,,,,>
```

Message: **REQU_CATCHWEIGHT**

Description : REQU_CATCHWEIGHT

	Field	Name	Format	Description	Example
*	1	serNum	STRING	Serial number of the voice client device	987654321
*	2	verNum	STRING	verNum	2.2.3
*	3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
*	4	msgType	STRING	type	REQU_CATCHWEIGHT
*	5	operId	STRING	Operator ID or number	12345

Field	Name	Format	Description	Example
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	groupNum	STRING	Picklist number	99999999
11	groupSubNum	STRING	Optional number to identify the instance of the group	001
12	headerNum	STRING	Unique number identifying the header	123456
13	headerSubNum	STRING	Header subnumber	001
* 15	itemPickSeqNum	NUMERIC	Sequence number of the detail line within the header	1
* 16	pickLineId	STRING	Unique number identifying the pick line	989898989801
* 18	sourceLC1	STRING	Source location coordinate 1 - ZONE	M
* 19	sourceLC2	STRING	Source location coordinate 2 - ALLEE	A
* 20	sourceLC3	STRING	Source location coordinate 3 - TRAVEE	B
* 21	sourceLC4	STRING	Source location coordinate 4 - NIVEAU	2
* 22	sourceLC5	STRING	Source location coordinate 5 - EMPLACEMENT+BIN	12
* 23	productCode	STRING	Productcode	5400141050912
* 24	Cri01	STRING	(part of) lot number as spoken by the operator. Empty if input was unambiguously determined as valid input based on existing lot numbers.	456
* 26	Cri02	STRING	Status of the ItemPick line (leading zero is obliged) * 01=PICKED 02=SHORTPICKED 03=SKIPPED * 04=CUT	
27	Cri03	STRING	Spoken or scanned value	
28	Cri04	STRING	Spoken or scanned value	
29	Cri05	STRING	Spoken or scanned value	
32	Cri06	STRING	Spoken or scanned value	
55	Cri07	STRING	Spoken or scanned value	
56	Cri08	STRING	Spoken or scanned value	
57	Cri09	STRING	Spoken or scanned value	

Field	Name	Format	Description	Example
58	Cri10	STRING	Spoken or scanned value	
* 59	effQty	NUMERIC	Quantity effectively moved by operator.	000000
60	totalCatchWeight	NUMERIC	Total of all weights caught	56.89
* 61	lotNumber	STRING	Lot number that was unambiguously determined based on operator input and known existing lot numbers. Empty if input was not found withing existing lot number data.	123456
62	Usf01	STRING	Userfield 01	987692
63	Usf02	STRING	Userfield 02	
64	Usf03	STRING	Userfield 03	
65	Usf04	STRING	Userfield 04	
66	Usf05	STRING	Userfield 05	
67	Usf06	STRING	Userfield 06	
68	Usf07	STRING	Userfield 07	
69	Usf08	STRING	Userfield 08	
70	Usf09	STRING	Userfield 09	
71	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,REQU_CATCHWEIGHT,12345,1,20070721,103011,20070621103011,99999999,001,123456,001,1,989898989801,M,A,B,2,12,5400141050912,456,,,,,,,,,000000,56.89,123456,987692,,,,,,,,,>

Message: RESP_CATCHWEIGHT

Description : RESP_CATCHWEIGHT

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	RESP_CATCHWEIGHT
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721

Field	Name	Format	Description	Example
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	respCode	NUMERIC	Response Result Code. 0=OK 1=OK with warning in RespMsg 2..9=by default equal to OK, customizable values 10=NOK 11..999=by default equal to NOK, customizable values 1000..1999=3iV Connector Errors 2000..2999=3iV Connector Warnings	0
* 11	respMsg	STRING	Response message When errorcode greater then 0, this message is spoken	
* 12	groupNum	STRING	Picklist number	99999999
13	groupSubNum	STRING	Optional number to identify the instance of the group	001
14	headerNum	STRING	Unique number identifying the header	123456
15	headerSubNum	STRING	Header subnumber	001
* 16	itemPickSeqNum	NUMERIC	Sequence number of the detailline within the header	1
* 17	pickLineId	STRING	Unique number identifying the pick line	989898989801
* 18	productCode	STRING	Productcode	5400141050912
* 19	effQty	NUMERIC	Quantity for which the RESP message responds.	
20	totalCatchWeight	NUMERIC	Total of all weights caught	56.89
* 21	lotNumber	STRING	Effective lot number (as found in existing lot numbers).	991122119934
22	Usf01	STRING	Userfield 01	987692
23	Usf02	STRING	Userfield 02	
24	Usf03	STRING	Userfield 03	
25	Usf04	STRING	Userfield 04	
26	Usf05	STRING	Userfield 05	
27	Usf06	STRING	Userfield 06	
28	Usf07	STRING	Userfield 07	
29	Usf08	STRING	Userfield 08	
30	Usf09	STRING	Userfield 09	
31	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,RESP_CATCHWEIGHT,12345,1,20070721,103011,20070621103011,0,,99999999,001,123456,001,1,989898989801,5400141050912,,56.89,991122119934,987692,,,,,,,,,>

Message: RESU_CATCHWEIGHT

Description : RESU_CATCHWEIGHT

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	RESU_CATCHWEIGHT
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	groupNum	STRING	Picklist number	99999999
	groupSubNum	STRING	Optional number to identify the instance of the group	001
	headerNum	STRING	Unique number identifying the header	123456
	headerSubNum	STRING	Header subnumber	001
* 14	itemSeqNum	NUMERIC	Item Sequence Number	2
* 15	lineId	STRING	LineID	989898988801
	assignmentType	NUMERIC	Assignment Type 1=Picking 2=XDock 3=Inventory 4=Moving 5..9=customizable values, by default not used	1
	unitOfMeasure	STRING	Unit of measure code of this itempick line (leading zero is obliged) 01=SINGLE UNIT 02=PACK 03=COLIS 04=LAYER 05=CARRIER 06..99=customizable values, by default not used	03
	seqWeightInput	NUMERIC	Sequence number of weight input for current item line	1
	weight	NUMERIC	Weight of this item	6.010

Field	Name	Format	Description	Example
20	barcode	STRING	Barcode of the item	54400141050912
22	expiryDate	STRING	Expiry date of this article	20070615121301
23	destCarSeqNum	NUMERIC	Sequence number of carrier	1
24	destCarId	STRING	CarrierID	A23
25	lineIndicator	NUMERIC	Indicator determining the type of detail line 0=normal line 1=last line	0
* 26	Usf01	STRING	Effective lot number	987692
* 27	Usf02	STRING	Quantity effectively picked for this lot number.	5
28	Usf03	STRING	Userfield 03	
29	Usf04	STRING	Userfield 04	
30	Usf05	STRING	Userfield 05	
31	Usf06	STRING	Userfield 06	
32	Usf07	STRING	Userfield 07	
33	Usf08	STRING	Userfield 08	
34	Usf09	STRING	Userfield 09	
35	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,RESU_CATCHWEIGHT,12345,1,20070721,103011,20070621103011,99999999,001,123456,001,2,989898988801,1,03,1,6.010,54400141050912,20070615121301,1,A23,0,987692,5,,,,,,,,,>

Message: **REQU_PRINT**

Description : REQU_PRINT

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	Type of the Message, eg. REQU_PRINT	REQU_PRINT
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721

Field	Name	Format	Description	Example
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageld	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	groupNum	STRING	Picklist number	99999999
11	groupSubNum	STRING	Optional number to identify the instance of the group	001
12	headerNum	STRING	Unique number identifying the header	123456
13	headerSubNum	STRING	Header subnumber	001
14	assignmentType	NUMERIC	Assignment Type 1=Picking 2=XDock 3=Inventory 4=Moving 5..9=customizable values, by default not used	1
* 15	printType	STRING	(leading zero is obliged) 01=LABEL 02..99=customizable values, by default not used * 02 = Colli shipping label (étiquette colli) * 03 = Assignment label (passeport) * 04 = Carrier shipping label + packing labels (étiquette de transport + étiquettes d'instruction d'emballage) 02 : Zetes 03-04 : Sylis	02
* 16	printerNum	STRING	Printer ID on which the label should be printed (not used by WMS)	10.2.34.15
17	destLocationId	STRING	CarrierID	101
18	destCarSeqNum	NUMERIC	Sequence number of carrier	1
19	destCarId	STRING	CarrierID	A23
20	Usf01	STRING	Quantity of labels to be printed (only for printType=02)	5
21	Usf02	STRING	Userfield 02	
22	Usf03	STRING	Userfield 03	
23	Usf04	STRING	Userfield 04	
24	Usf05	STRING	Userfield 05	
25	Usf06	STRING	Userfield 06	
26	Usf07	STRING	Userfield 07	
27	Usf08	STRING	Userfield 08	
28	Usf09	STRING	Userfield 09	
29	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,REQU_PRINT,12345,1,20070721,103011,20070621103011,99999999,001,123456,001,1,02,10.2.34.15,101,1,A23,5,,,,,,,,,>

Message: RESP_PRINT

Description : RESP_PRINT

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	RESP_PRINT
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	respCode	NUMERIC	Response Result Code. 0=OK 1=OK with warning in RespMsg 2..9=by default equal to OK, customizable values 10=NOK 11..999=by default equal to NOK, customizable values 1000..1999=3iV Connector Errors 2000..2999=3iV Connector Warnings	0
* 11	respMsg	STRING	Response message When errorcode greater then 0, this message is spoken	
12	groupNum	STRING	Picklist number	99999999
13	groupSubNum	STRING	Optional number to identify the instance of the group	001
14	headerNum	STRING	Unique number identifying the header	123456

Field	Name	Format	Description	Example
15	headerSubNum	STRING	Header subnumber	001
* 16	printerNum	STRING	Printernumber on which the label should be printed	10
17	destLocationId	STRING	CarrierID	101
18	destLocationCD	STRING	Check digit of the carrier to stage	27
19	destCarSeqNum	NUMERIC	Sequence number of carrier	1
20	destCarId	STRING	CarrierID	A23
21	numOfLabels	STRING	Number of labels	1
* 22	labelCD	STRING	CheckDigit for the label	45
23	Usf01	STRING	Userfield 01	987692
24	Usf02	STRING	Userfield 02	
25	Usf03	STRING	Userfield 03	
26	Usf04	STRING	Userfield 04	
27	Usf05	STRING	Userfield 05	
28	Usf06	STRING	Userfield 06	
29	Usf07	STRING	Userfield 07	
30	Usf08	STRING	Userfield 08	
31	Usf09	STRING	Userfield 09	
32	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,RESP_PRINT,12345,1,20070721,103011,20070621103011,0,,99999999,001,123456,001,10,101,27,1,A23,1,45,987692,,,,,,,,,>

Message: **REQU_LOCATION**

Description : REQU_LOCATION

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	REQU_LOCATION
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721

Field	Name	Format	Description	Example
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageld	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	groupNum	STRING	Picklist number	99999999
11	groupSubNum	STRING	Optional number to identify the instance of the group	001
12	headerNum	STRING	Unique number identifying the header	123456
13	headerSubNum	STRING	Header subnumber	001
* 14	lineId	STRING	LineID	989898988801
15	itemSeqNum	NUMERIC	Item Sequence Number	2
16	assignmentType	NUMERIC	Assignment Type 1=Picking 2=XDock 3=Inventory 4=Moving 5..9=customizable values, by default not used	1
* 17	Cri01	STRING	Source location coordinate 1	12
* 18	Cri02	STRING	Source location coordinate 2	
* 19	Cri03	STRING	Source location coordinate 3	
* 20	Cri04	STRING	Source location coordinate 4	
* 21	Cri05	STRING	Source location coordinate 5	
* 22	Cri06	STRING	Product code	
* 23	Cri07	STRING	(part of) lot number as spoken by the operator	
* 24	Cri08	STRING	effective lot number as found in existing lot numbers (or empty of not found)	
25	Cri09	STRING	Spoken or scanned value	
26	Cri10	STRING	Spoken or scanned value	
27	Usf01	STRING	Userfield 01	987692
28	Usf02	STRING	Userfield 02	
29	Usf03	STRING	Userfield 03	
30	Usf04	STRING	Userfield 04	
31	Usf05	STRING	Userfield 05	
32	Usf06	STRING	Userfield 06	
33	Usf07	STRING	Userfield 07	
34	Usf08	STRING	Userfield 08	
35	Usf09	STRING	Userfield 09	
36	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

<987654321,2.2.3,3iV_101,REQU_LOCATION,12345,1,20070721,103011,20070621103011,99999999,001,123456,001,989898988801,2,1,12,,,,,,,,,987692,,,,,,,,,>

Message: RESP_LOCATION

Description : RESP_LOCATION

Field	Name	Format	Description	Example
* 1	serNum	STRING	Serial number of the voice client device	987654321
* 2	verNum	STRING	verNum	2.2.3
* 3	appNum	STRING	Application name or number (eg. name of the task)	3iV_101
* 4	msgType	STRING	type	RESP_LOCATION
* 5	operId	STRING	Operator ID or number	12345
* 6	langId	STRING	Language used by the device for prompting to the operator 1 = English 2 = French 3 = German 4 = Dutch 5 = Spanish 6 = Italian 7 = Portuguese 8 = Swedish 9 = Finnish	1
* 7	msgDate	NUMERIC	Date of the message that is exchanged.	20070721
* 8	msgTime	NUMERIC	Time of the message that is exchanged	103011
* 9	packageId	STRING	Unique value identifying a message pair, eg. voice client sends a REQU with packageid and HOST response back with same packageid. ## Use device serial number + message type. ##	20070621103011
* 10	respCode	NUMERIC	Response Result Code. 0=OK 1=OK with warning in RespMsg 2..9=by default equal to OK, customizable values 10=NOK 11..999=by default equal to NOK, customizable values 1000..1999=3iV Connector Errors 2000..2999=3iV Connector Warnings	0
* 11	respMsg	STRING	Response message When errorcode greater then 0, this message is spoken	
12	groupNum	STRING	Picklist number	99999999
13	groupSubNum	STRING	Optional number to identify the instance of the group	001
* 14	headerNum	STRING	Unique number identifying the header	123456
15	headerSubNum	STRING	Header subnumber	001
16	lineId	STRING	LineID	989898988801
17	itemSeqNum	NUMERIC	Item Sequence Number	2
* 18	locationStatus	STRING	Status of the location (leading zero is obliged) 00=FREE	00
* 19	IC1	STRING	Location coordinate 1. Eg:Zone	1
* 20	IC2	STRING	Location coordinate 2. Eg Aisle	12

Field	Name	Format	Description	Example	
*	21	IC3	STRING	Location coordinate 3. Eg Slot	45
*	22	IC4	STRING	Location coordinate 4. Eg Level	0
*	23	IC5	STRING	Location coordinate 5. Eg Bin	0
*	24	ICCD	STRING	Check digit of the location	56
*	25	ICBarcode	STRING	Source location barcode	1124500
*	26	quantity	NUMERIC	Total quantity in stock for this product (unreserved + reserved).	1
	27	promptInfo	STRING	Extra info at the prompt	keep it frozen
*	28	unitOfMeasure	STRING	Unit of measure code of this itempick line (leading zero is obliged) 01=SINGLE UNIT 02=PACK 03=COLIS 04=LAYER 05=CARRIER 06..99=customizable values, by default not used	03
*	29	productCode	STRING	Productcode	5400141050912
*	30	productDescription	STRING	Productdescription	Vanilla Icecream 500 gram
	31	productGroupCode	STRING	Code indicating the productgroup	1
	32	productProperty1	STRING	Specific property for this product	1.5
	33	productProperty2	STRING	Specific property for this product	20
	34	productProperty3	STRING	Specific property for this product	26
*	35	productBarcode	STRING	Barcode of this item	5400141050912
*	36	Usf01	STRING	Lot number that exists in stock, 1st in FEFO order.	987692
*	37	Usf02	STRING	Lot number that exists in stock, 2nd in FEFO order.	
*	38	Usf03	STRING	Lot number that exists in stock, 3rd in FEFO order.	
*	39	Usf04	STRING	Lot number that exists in stock, 4th in FEFO order.	
*	40	Usf05	STRING	Lot number that exists in stock, 5th in FEFO order.	
*	41	Usf06	STRING	Unambiguous lot number that exists in stock, higher than 5th in FEFO order, based on user lot number input. Empty if input lot number is one of the 5 first lot numbers in stock.	
*	42	Usf07	STRING	Total quantity available for picking (unreserved stock).	4
	43	Usf08	STRING	Userfield 08	
	44	Usf09	STRING	Userfield 09	
	45	Usf10	STRING	Userfield 10	

....|....1....|....2....|....3....|....4....|....5....|....6....|....7....|....8....|....9....|....0

Example Delimited :

```
<987654321,2.2.3,3iV_101,RESP_LOCATION,12345,1,20070721,103011,20070621103011,0,,99999999,001,123456,001,989898988801,2,00,1,12,45,0,0,56,1124500,1,keep it frozen,03,5400141050912,Vanilla Icecream 500 gram,1,1.5,20,26,5400141050912,987692,,,,,4,,,>
```