

# Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- **Principles of congestion control**
- TCP congestion control
- Evolution of transport-layer functionality



# Principles of congestion control

## Congestion:

- informally: “too many sources sending too much data too fast for *network* to handle”
- manifestations:
  - long delays (queueing in router buffers)
  - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!




**congestion control:**  
too many senders,  
sending too fast

**flow control:** one sender  
too fast for one receiver



# Causes/costs of congestion: scenario 1

Simplest scenario:

- one router, infinite buffers
- input, output link capacity:  $R$
- two flows
- no retransmissions needed




**Q:** What happens as arrival rate  $\lambda_{in}$  approaches  $R/2$ ?



# Causes/costs of congestion: scenario 2



- one router, *finite* buffers
- sender retransmits lost, timed-out packet
  - application-layer input = application-layer output:  $\lambda_{in} = \lambda_{out}$
  - transport-layer input includes *retransmissions* :  $\lambda'_{in} \geq \lambda_{in}$



# Causes/costs of congestion: scenario 2

Idealization: perfect knowledge


- sender sends only when router buffers available



# Causes/costs of congestion: scenario 2

Idealization: *some* perfect knowledge



- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet *known* to be lost



# Causes/costs of congestion: scenario 2

Idealization: *some* perfect knowledge



- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet *known* to be lost



# Causes/costs of congestion: scenario 2

## Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending *two* copies, *both* of which are delivered




# Causes/costs of congestion: scenario 2

## Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending *two* copies, *both* of which are delivered

## “costs” of congestion:

- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
  - decreasing maximum achievable throughput




# Causes/costs of congestion: scenario 3



- four senders
- multi-hop paths
- timeout/retransmit

**Q:** what happens as  $\lambda_{in}$  and  $\lambda'_{in}$  increase ?

**A:** as red  $\lambda'_{in}$  increases, all arriving blue pkts at upper queue are dropped, blue throughput  $\rightarrow 0$



# Causes/costs of congestion: scenario 3




another “cost” of congestion:

- when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!

# Causes/costs of congestion: insights


- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream



# Approaches towards congestion control

## End-end congestion control:


- no explicit feedback from network
- congestion *inferred* from observed loss, delay
- approach taken by TCP



# Approaches towards congestion control

## Network-assisted congestion control:

- routers provide *direct* feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



# Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- **TCP congestion control**
- Evolution of transport-layer functionality



# TCP congestion control: AIMD


- *approach:* senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

## Additive Increase

increase sending rate by 1 maximum segment size every RTT until loss detected

## Multiplicative Decrease

cut sending rate in half at each loss event



**AIMD** sawtooth behavior: *probing* for bandwidth

# TCP AIMD: more


*Multiplicative decrease* detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

Why AIMD?

- AIMD – a distributed, asynchronous algorithm – has been shown to:
  - optimize congested flow rates network wide!
  - have desirable stability properties

# TCP congestion control: details



TCP sending behavior:


- *roughly*: send  $cwnd$  bytes, wait RTT for ACKS, then send more bytes

$$\text{TCP rate} \approx \frac{cwnd}{RTT} \text{ bytes/sec}$$

- TCP sender limits transmission:  $\text{LastByteSent} - \text{LastByteAcked} \leq cwnd$
- $cwnd$  is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

# TCP slow start

- when connection begins, increase rate exponentially until first loss event:
  - initially **cwnd** = 1 MSS
  - double **cwnd** every RTT
  - done by incrementing **cwnd** for every ACK received
- *summary*: initial rate is slow, but ramps up exponentially fast




# TCP: from slow start to congestion avoidance

**Q:** when should the exponential increase switch to linear?

**A:** when **cwnd** gets to 1/2 of its value before timeout.


## Implementation:

- variable **ssthresh**
- on loss event, **ssthresh** is set to 1/2 of **cwnd** just before loss event




\* Check out the online interactive exercises for more examples: [http://gaia.cs.umass.edu/kurose\\_ross/interactive/](http://gaia.cs.umass.edu/kurose_ross/interactive/)

# Summary: TCP congestion control




# TCP CUBIC

- Is there a better way than AIMD to “probe” for usable bandwidth?
- Insight/intuition:
  - $W_{\max}$ : sending rate at which congestion loss was detected
  - congestion state of bottleneck link probably (?) hasn’t changed much
  - after cutting rate/window in half on loss, initially ramp to  $W_{\max}$  *faster*, but then approach  $W_{\max}$  more *slowly*




# TCP CUBIC

- K: point in time when TCP window size will reach  $W_{\max}$ 
  - K itself is tunable
- increase W as a function of the *cube* of the distance between current time and K
  - larger increases when further away from K
  - smaller increases (cautious) when nearer K
- TCP CUBIC default in Linux, most popular TCP for popular Web servers




# TCP and the congested “bottleneck link”

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the *bottleneck link*




# TCP and the congested “bottleneck link”

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the *bottleneck link*
- understanding congestion: useful to focus on congested bottleneck link



# Delay-based TCP congestion control

Keeping sender-to-receiver pipe “just full enough, but no fuller”: keep bottleneck link busy transmitting, but avoid high delays/buffering



$$\text{measured throughput} = \frac{\text{\# bytes sent in last RTT interval}}{\text{RTT}_{\text{measured}}}$$

## Delay-based approach:

- $\text{RTT}_{\min}$  - minimum observed RTT (uncongested path)
- uncongested throughput with congestion window  $cwnd$  is  $cwnd/\text{RTT}_{\min}$ 
  - if measured throughput “very close” to uncongested throughput  
increase  $cwnd$  linearly /\* since path not congested \*/
  - else if measured throughput “far below” uncongested throughput  
decrease  $cwnd$  linearly /\* since path is congested \*/


# Delay-based TCP congestion control

- congestion control without inducing/forcing loss
- maximizing throughout (“keeping the just pipe full... ”) while keeping delay low (“...but not fuller”)
- a number of deployed TCPs take a delay-based approach
  - BBR deployed on Google’s (internal) backbone network

# Explicit congestion notification (ECN)


TCP deployments often implement *network-assisted* congestion control:

- two bits in IP header (ToS field) marked *by network router* to indicate congestion
  - *policy* to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)



# TCP fairness


**Fairness goal:** if  $K$  TCP sessions share same bottleneck link of bandwidth  $R$ , each should have average rate of  $R/K$



# Q: is TCP Fair?

Example: two competing TCP sessions:

- additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



*Is TCP fair?*

**A:** Yes, under idealized assumptions:

- same RTT
- fixed number of sessions only in congestion avoidance

# Fairness: must all network apps be “fair”?

## Fairness and UDP

- multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- instead use UDP:
  - send audio/video at constant rate, tolerate packet loss
- there is no “Internet police” policing use of congestion control

## Fairness, parallel TCP connections

- application can open *multiple* parallel connections between two hosts
- web browsers do this , e.g., link of rate R with 9 existing connections:
  - new app asks for 1 TCP, gets rate R/10
  - new app asks for 11 TCPs, gets R/2