




Operating Systems

Process/Thread Scheduling

Hubertus Franke frankeh@cs.nyu.edu




Scheduling: Basic Question

- Whether scheduling is based on processes or threads depends on whether the OS is multi-threading capable.
- Given a group of ready processes or threads, which process/thread to run?

 In this deck/lab2 we use <u>process</u> as the assumption, just be aware that it applies to threads in a multi-threading capable OS.

Scheduling Context

Given a group of ready processes, which process to run?



When to Schedule?

- When a process is created
- When a process exits
- When a process blocks
- When an I/O interrupt occurs

Categories of Scheduling Algorithms

Interactive

- preemption is essential

preemption == a means for the OS to take away the CPU from a currently running process/thread

Batch

- No user impatiently waiting
- mostly non-preemptive, or preemptive with long period for each process

· Real-time

- deadlines

Scheduling Algorithm: Goals and Measures

• Turn Around Time (Batch)

Throughput (e.g. jobs per second)

Response Time (Interactive)

· Average wait times (how long waiting in readyQ)

CPU / IO Burst

• CPU Burst:

a sequence of instructions a process runs without requesting I/O.

Mostly dependent on the program behavior.


IO "Burst":

time required to satisfy an IO request while the Process can not run any code.

Mostly dependent on system behavior (how many other IOs, speed of device, etc.)

 NOTE: these implicitly due to program and system behaviors, NOT something that a user specifies!!

Scheduling – Process Behavior



CPU-Burst and IO-Burst are simple runtime behaviors of applications, they continuously change

Figure 2-38. Bursts of CPU usage alternate with periods of waiting for I/O. (a) A CPU-bound process. (b) An I/O-bound process.

Trick Question: what is the cpu burst of the following program?
int main() {
 int i=0;
 for (;;) i++;
 return i;

Scheduling Algorithms Goals

All systems

Fairness - giving each process a fair share of the CPU
Policy enforcement - seeing that stated policy is carried out
Balance - keeping all parts of the system busy

Batch systems

Throughput - maximize jobs per hour

Turnaround time - minimize time between submission and termination

CPU utilization - keep the CPU busy all the time

Interactive systems


Response time - respond to requests quickly Proportionality - meet users' expectations

Real-time systems

Meeting deadlines - avoid losing data Predictability - avoid quality degradation in multimedia systems

State Transitions and Scheduler Invocations

Almost ALL scheduling algorithms can be described by the following process state transition diagram or a derivative of it (we covered some more sophisticated one in prior lecture)



The OS Scheduler maintains a data structure called "RunQueue" or "ReadyQueue" where all processes that are <ready to run> are maintained (doesn't have to be strictly a queue, think "pool")


Scheduling:

The Simplest Algorithm of them All

- Random() !!!
- Simply maintain a pool and pick one.
- Things to consider:
 - Starvation
 - Fairness


Scheduling in Batch Systems: First-Come First-Served (FIFO / FCFS)

- Non-preemptive (run till I/O or exit)
- Processes ordered as queue
- A new process is added to the end of the queue
- A blocked process that becomes ready added to the end of the queue
- Main disadvantage: Can hurt I/O bound processes or processes with frequent I/O




Scheduling in Batch Systems: Shortest Job First

- Non-preemptive
- Assumes runtime is known in advance (⊗)
- Is only optimal when all the jobs are available simultaneously



Run in original order

Avg-waittime: (0+8+12+16) / 4 = 9



Run in shortest job first

Avg-waittime: (0+4+8+12) / 4 = 6

Scheduling in Batch Systems: Shortest Remaining Time Next

- Scheduler always chooses the process whose remaining time is the shortest
- Runtime has to be known in advance (②)
- Preemptive (see next slide) or non-preemptive (wait till process blocks or is done)
- Note: in lab2 we are using the non-preemptive version of "shortest remaining time next" since we have preemption in other schedulers already.
- This typically reduces average turn-around time

Scheduling in Interactive Systems: Round-Robin

- Each process is assigned a time interval referred to as quantum
- After this quantum, the CPU is given to another process (i.e. CPU is removed from the process/thread aka preemption)
- RR = FIFO + preemption
 or (FIFO = RR with huge quantum) [hint → lab2]
- What is the length of this quantum?
 - too short -> too many process context switches
 lower CPU efficiency
 - too long --> poor response to short interactive
 - quantum longer than typical CPU burst is good (why?)

Round-Robin Scheduling (cont)

• Promotes Fairness (due to preemption)

Current Next process Process (a) Current process Current process (b)


Figure 2-41. Round-robin scheduling.

(a) The list of runnable processes. (b) The list of runnable processes after B uses up its quantum.

Scheduling in Interactive Systems: Priority Scheduling

- · Each process is assigned a priority
- runnable process with the highest priority is allowed to run
- Priorities are assigned statically or dynamically
- Must not allow a process to run forever
 - Can decrease the priority of the currently running process
 - Use time quantum for each process

Scheduling in Interactive Systems: Multiple Level Queuing (MLQ)



- Process::static_priority: it is a parameter of the process (non-changing unless requested through system call)
- Multiple levels of priority (MLQ) plus each level is run round-robin
- Issue: starvation if higher priorities have ALWAYS something to run

Multi-Level Feedback Queueing [MLFQ aka priority decay scheduler]

- Multiple levels of priority MLQ, but
- Process::dynamic_priority: [0..p->static_priority 1]
 (this changes constantly based on current state of process)
- If process has to be preempted, moves to (dynamic_priority--).
- When it reaches "-1", dynamic priority is reset to (static_priority-1)
 This creates some issues when high prio is reset before other low prio is executing.
- When a process is made ready (from blocked):
 it's dynamic priority is reset to (static priority-1)
- What kind of process should be in bottom queue?
 - Best to assign a higher priority to IO-Bound tasks
 - Best to assign a lower priority to CPU-Bound tasks
- Discussion:

Lottery Scheduling

- Each runnable entity is given a certain number of tickets.
- The more tickets you have, the higher your odds of winning.
- Trade tickets?
- Problems?

Fair Share Scheduler

- Schedule not only based on individual processes, but process's owner.
- N users, each user may have different # of processes.
- Does this make sense on a PC?

Policy versus Mechanism

- Separate what is <u>allowed</u> to be done from <u>how</u> it is done
- Scheduling algorithm parameterized
 - mechanism in the kernel (e.g. quantum)
 - Context switches

- Parameters filled in by user processes
 - policy set by user process (priority, scheduling type)

Scheduling in Real-Time

- Process must respond to an event within a deadline
- Hard real-time vs soft real-time
- Periodic vs aperiodic events
- Processes must be schedulable
- Scheduling algorithms can be static or dynamic
 - Static: a scheduling table is devised
 - Dynamic: based on event process duration and urgency a priority is devised.

Thread Scheduling

Already covered in previous lecture:


- Two levels of parallelism: processes and threads within processes
- Kernel-based vs. user-space (recall that kernel only schedules threads for kernel based thread model)

SMP Scheduling (SMP = Symmetric Multi Processors)

- One Scheduler Data Structure per CPU (hw-thread)
- Note that modern systems can have 100s of "cpus"
- Each CPU schedules for itself and is also triggered by its own timer interrupt (potential preemption)
 - → This is known as the local scheduler
- New processes (fork) or threads (clone) are typically assigned to the local CPU
- · This "obviously" will lead to imbalances which needs to be dealt with
- Imbalances lead to idle resources and reduce fairness.

Load Balancing (LB)

- Occasionally or when no process is runnable, scheduler[i] looks to steal work elsewhere
- Each scheduler maintains a load average and history to determine stability of its load
- LB typically done in a hierarchy
- Frequency of neighbor check:
 - Level in hierarchy ~ cost to migrate
 - Make "small" changes by pulling work from other cpu




Load[3]

Example Linux Scheduling

- Implementation has changed multiple times
- Dynamic Priority-Based Scheduling (classic)
- Two (static) Priority Ranges:
 - Nice value: -20 to +19, default 0.
 Larger values are lower priority.
 Nice value of -20 receives maximum timeslice, +19 minimum.
 - Real-time priority: By default values range 0 to 99.
 Real-time processes have a higher priority than normal processes (nice).

Linux Timeslice

 The timeslice can also be adjusted based on process/thread behavior



Linux Scheduler Goals

- O(1) scheduling constant time
 - vs O(N) which implies dependent on number of ready processes.
- SMP each processor has its own locking and individual runqueue
- SMP Affinity. Only migrate process from one CPU to another if imbalanced runqueues.
- Good interactive performance
- Fairness
- Optimized for one or two processes but scales

Priority Arrays

- Each runqueue has two priority arrays:
 - (a) active and (b) expired
 [note these are just pointers to arrays]
- · Each priority array contains a bitmap
 - If bit-i is set in bitmap, it indicates there are processes runnable at given priority-i.
- Allows constant retrieval algorithm to find highest set bit (see next slide)

Implementation of Runqueues kernel/sched.c struct runqueue

activeQ - active priority array (note these are NOT vectors) expiredQ - expired priority array

```
Queue<Process*> *activeQ =
    new Queue<Process*> [ maxprios ];
Queue<Process*> *expiredQ =
    new Queue<Process*> [ maxprios ];

OR

Queue<Process*> *activeQ =
    calloc(sizeof(Queue<Process*>), maxprios);
Queue<Process*> *expiredQ =
    calloc(sizeof(Queue<Process*>), maxprios);
Queue<Process*> *expiredQ =
    calloc(sizeof(Queue<Process*>), maxprios);


migration_thread

Other resources
```

migration_thread migration_queue nr_iowait - number of tasks waiting on I/O Other resources (not implemented in lab2)

Scheduler Algorithm

- Maintain bitmap of state of the queues (in three 64-bit words)
- Identify highest prio queue that is not empty:
 - Use ffz() or ffnz() to find first bit that is set/notset supported by hardware instructions.
 - Only needs 3 64-bits to be examined to return correct priority (queue)
- Then dequeue_front from that queue.



ffz(): https://en.wikipedia.org/wiki/Find first set

Scheduler Operations

add_to_runqueue(Process *p)if (p -> dynamic prio < 0)

```
reset and enter  into expireQ else add  to activeQ
```

Process* get_from_runqueue()

```
return activeQ[highest prio].front() // you have to pop() else swap(activeQ,expiredQ) and try again [ swapping means swapping the pointers to array not swapping the entire arrays .. Smart programming ]
```

Calculating Priority and Timeslice

effective_prio() returns task's dynamic priority.


nice value + or - bonus in range -5 to +5

Interactivity measure by how much time a process sleeps. Indicates I/O activity. sleep_avg incremented to max_sleep_avg (10 millisecs) every time it does I/O. If no I/O, decremented.

How to measure interactivity?

How to determine interactivity?

- Sum(cpu_burst) / wall time
- Sum(io_burst) / wall time
- Sum(cpu_burst) / Sum(io_burst)



- Note excludes queue-time in the ready queue
- Need to take "recency" into account:
- Mostly interested in recent history
- Use a weighting mechanism
- value(t) = measure(t) * R + value(t-1) * (1-R) $R \ in \ (0 ... 1).$
- If R == 1 then only the last period counts. The closer R gets to 0 the more history counts