
PHY101: Introduction to Physics I

Monsoon Semester 2024 Lecture 18

Department of Physics, School of Natural Sciences, Shiv Nadar Institution of Eminence, Delhi NCR


Previous Lecture

Damped harmonic motion




This Lecture

Driven harmonic motion



Forced (or Driven) vibration





Restoring force + resistive force + driven force

Forced vibrations are produced in the air inside the box and intensity of sound increases

Applications of forced vibration


- 1. Structural dynamics: To study the response of structures such as bridges, buildings, and towers to wind and earthquake forces.
- 2. **Vibration testing**: To test the structural integrity of products such as aircraft, automobiles, and electronic devices.
- 3. **Manufacturing**: It can shake any loose particles or contaminants on a surface and ensure that a surface or material is homogeneous.
- 4. **Energy Harvesting**: Vibration energy harvesting devices use forced vibration to generate electrical energy. Piezoelectric and electromagnetic materials are used to convert mechanical energy into electrical energy.
- 5. **Medical field**: Vibration therapy is used to help treat conditions such as osteoarthritis and improve muscle strength and flexibility.
- 6. Music: Forced vibration is used in instruments with strings.

Driven harmonic motion

⇒ System under restoring, resistive and driven forces.

The external driving force should be periodic! Let's apply a driving force,

$$F_d(t) = F_d \cos \omega_d t$$



The differential equation,

$$F(x, \dot{x}, t) = -b\dot{x} - kx + F_d \cos \omega_d t$$

$$=> \ddot{x} + 2\gamma \dot{x} + \omega^2 x = F \cos \omega_d t$$

$$= \frac{F}{2} \left(e^{i\omega_d t} + e^{-i\omega_d t} \right)$$

$$F\equiv F_d/m$$
 $\sin x=rac{e^{ix}-e^{-ix}}{2i}$ $\cos x=rac{e^{ix}+e^{-ix}}{2}$

Here, ω is the natural frequency of oscillation of the spring. ω_d is the frequency of applied force. damping parameter $(2\gamma = b/m)$

Solution of the differential equation

$$=> \ddot{x} + 2\gamma \dot{x} + \omega^2 x = \frac{F}{2} \left(e^{i\omega_d t} + e^{-i\omega_d t} \right)$$

Step 1: Taking first part of right hand side (RHS)

$$=> \ddot{x} + 2\gamma \dot{x} + \omega^2 x = \frac{F}{2} \left[e^{i\omega_d t} \right]$$
Trial solution, $x(t) = Ae^{i\omega_d t}$

$$A = \left(\frac{F/2}{-\omega_d^2 + 2i\gamma\omega_d + \omega^2}\right)$$
 Follow steps as before

Step 2: Taking second part of right hand side (RHS)

$$\ddot{x} + 2\gamma \dot{x} + \omega^2 x = \frac{F}{2} e^{-i\omega_d t}$$
Trial solution, $x(t) = Be^{-i\omega_d t}$

$$\mathbf{B} = \left(\frac{F/2}{-\omega_d^2 - 2i\gamma\omega_d + \omega^2}\right)$$

The particular solution, $x_p(t) = Ae^{i\omega_d t} + Be^{-i\omega_d t}$

$$x_p(t) = \left(\frac{F/2}{-\omega_d^2 + 2i\gamma\omega_d + \omega^2}\right)e^{i\omega_d t} + \left(\frac{F/2}{-\omega_d^2 - 2i\gamma\omega_d + \omega^2}\right)e^{-i\omega_d t}.$$

Simplify to,

$$x_p(t) = \left(\frac{F(\omega^2 - \omega_d^2)}{(\omega^2 - \omega_d^2)^2 + 4\gamma^2 \omega_d^2}\right) \cos \omega_d t + \left(\frac{2F\gamma\omega_d}{(\omega^2 - \omega_d^2)^2 + 4\gamma^2 \omega_d^2}\right) \sin \omega_d t.$$

$$\equiv \frac{F}{R} \cos(\omega_d t - \phi)$$


Note: Particular solution given above is not a complete solution.

A more detailed mathematical solution is beyond the scope of this course.

$$R \equiv \sqrt{(\omega^2 - \omega_d^2)^2 + (2\gamma\omega_d)^2}$$

$$x_p(t) = \frac{F}{R} \cos(\omega_d t - \phi)$$

(w-u, - 21) (w-u, - 21) (w-u, - 21) = F/2 (W: - 2) - 21807) (car(Walk) + is inway) + F (wi - wi + 2 is was) (Calust - in was (W-Wa) + 48 Toa - F (W, - W,) Carly - F1. 2i Vy contall + i F/2 62- 52) smart - F/2iYWAisin WAL France Flice Tower + F/ 21 Yes OUL - Mailanismus (U, 7 W) + 48 cg) F(W-W) Con Wat +2F & Wy sin wat (Wo - was) + 48 was = F(W, -wg1) corcupt + 2 FYUd Sinwall (Wi-Wi) +48 WI (Wi-Wi) +48 Wi = F Gs Wat Gold + F Sinuar Sint x (1) - 835. F/n cos (Vas-4)




The Phase

$$\cos \phi = \frac{\omega^2 - \omega_d^2}{R}$$
, $\sin \phi = \frac{2\gamma \omega_d}{R}$ \Longrightarrow $\tan \phi = \frac{2\gamma \omega_d}{\omega^2 - \omega_d^2}$

The Amplitude

$$\frac{F}{R} = \frac{F}{\sqrt{\omega^2 - \omega_d^2}^2 + (2\gamma\omega_d)^2}$$


Triangle describes the relation among all the parameters.



Resonance

$$\frac{F}{R} = \frac{F}{\sqrt{\omega^2 - \omega_d^2)^2 + (2\gamma\omega_d)^2}}$$

- => At values of ω_d less than the ω , the amplitude increases with ω_d .
- \Rightarrow if damping of the system is very small, at resonance, the sharpness of amplitude is maximum for $\omega_d = \omega$. [Homework/Tutorial]



- => At values of ω_d more than ω , the amplitude decreases.
- => The nature depends on **damping parameter** $(2\gamma = b/m)$.
- => For no damping, the applied driving force at resonance frequency, will provide infinite amplitude.

Properties of driven harmonic motion

- The reason for **large-amplitude oscillations** at the resonance frequency is that **energy is being transferred** to the system under the most favourable conditions.
- In the absence of a damping force (b = 0), we see that the steady-state amplitude approaches infinity as ω approaches ω_0 .
- In other words, if there are no losses in the system and we continue to drive an initially motionless oscillator with a periodic force that is in phase with the velocity, the amplitude of motion builds without limit.
- This limitless building does not occur in practice because **some damping** is always present in reality.

Risks factors associated with the driven vibration (Engineering applications)

- 1. Damage to the system: High amplitude vibrations can lead to fatigue failures and other types of damage.
- 2. Noise and vibration: Forced vibrations can generate noise and vibration that can disrupt people and equipment.
- 3. Extra cost: The excitation may incur an extra cost, both in terms of equipment and labour.
- **4.** The complexity of the system: Different loading conditions can make the testing and analysis more complex and difficult to interpret.
- **5. Inaccurate results**: It may give inaccurate results for the system's behaviour, as it may not simulate the real loading conditions of the system.
- **6. Safety hazards**: It can create safety hazards, particularly if the system is not properly secured or the excitation source is not controlled properly.