PHY 102 Introduction to Physics II Spring Semester 2025

Lecture 11

Potential from the line integral of Electric field


Let us calculate the line integral of E from a to b, $\int_a^b E \cdot dl$


For a point charge at origin

$$\boldsymbol{E} = \frac{q}{4\pi\epsilon_0 r^2} \hat{\boldsymbol{r}}$$

Spherical co-ordinates, $d\mathbf{l} = dr\hat{\mathbf{r}} + rd\theta\hat{\boldsymbol{\theta}} + rsin\theta d\varphi\hat{\boldsymbol{\varphi}}$

$$\mathbf{E.\,dl} = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} dr$$





Potential from the line integral of Electric field

Therefore line integral of **E** around a closed path is evidently zero ($r_a = r_b$, in that case)

$$\oint \mathbf{E} \cdot \mathbf{dl} = 0$$

By Stoke's theorem,
$$\nabla \times E = 0$$

Hence,
$$\boldsymbol{E} = -\boldsymbol{\nabla}V$$

True for any static charge distribution due to <u>superposition principle of electric</u> fields

$$\nabla \times \mathbf{E} = \nabla \times (\mathbf{E}_1 + \mathbf{E}_2 + \ldots) = (\nabla \times \mathbf{E}_1) + (\nabla \times \mathbf{E}_2) + \ldots = 0$$

Static electric fields have zero curl


Since $\oint E \cdot dl = 0$, line integral of E from point 'a' to point 'b' is <u>independent of</u> <u>path</u>

Because of path independence of line integral, we define a function

$$V(r) \equiv -\int_{\mathcal{O}}^{r} E. dl$$
, \mathcal{O} is some standard reference point

V(r) depends only on the point r. It is called the electric potential. The line integral of E depends only on the initial and final points.

$$V(b) \equiv -\int_{0}^{b} \mathbf{E}.d\mathbf{l}, \ V(a) \equiv -\int_{0}^{a} \mathbf{E}.d\mathbf{l},$$



The potential difference between two points **a** and **b** is

$$V(\mathbf{b}) - V(\mathbf{a}) = -\int_{\mathcal{O}}^{\mathbf{b}} \mathbf{E} \cdot d\mathbf{l} + \int_{\mathcal{O}}^{\mathbf{a}} \mathbf{E} \cdot d\mathbf{l}$$

$$= -\int_{\mathcal{O}}^{\mathbf{b}} \mathbf{E} \cdot d\mathbf{l} - \int_{\mathbf{a}}^{\mathcal{O}} \mathbf{E} \cdot d\mathbf{l} = -\int_{\mathbf{a}}^{\mathbf{b}} \mathbf{E} \cdot d\mathbf{l}.$$
(ii)


Now, the fundamental theorem for gradients states that

$$V(b) - V(a) = \int_{a}^{b} dV = \int_{a}^{b} \nabla V \cdot dl$$
$$= -\int_{a}^{b} E \cdot dl$$
$$E = -\nabla V$$

$$\boldsymbol{E} = -\boldsymbol{\nabla}V$$

is the differential form of

$$V(r) \equiv -\int_{\mathcal{O}}^{r} E.dl$$



Realization of electric potential in another way

$$\mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int_{(\infty)} \frac{\mathbf{r} - \mathbf{r}'}{|\mathbf{r} - \mathbf{r}'|^3} \, \rho(\mathbf{r}') \, d\tau'$$

Using the identity (you should be able to prove this!)

$$-\nabla\left(\frac{1}{|\mathbf{r}-\mathbf{r}'|}\right) = \frac{\mathbf{r}-\mathbf{r}'}{|\mathbf{r}-\mathbf{r}'|^3}$$

we obtain

$$\mathbf{E}(\mathbf{r}) = -\frac{1}{4\pi\epsilon_0} \int_{(\infty)} \mathbf{\nabla} \left(\frac{1}{|\mathbf{r} - \mathbf{r}'|} \right) \rho(\mathbf{r}') d\tau'$$

Since ∇ involves the derivative with respect to unprimed coordinates, we can pull it out of the integral which involves primed coordinates:

$$\mathbf{E}(\mathbf{r}) = -\mathbf{\nabla} \left(\frac{1}{4\pi\epsilon_0} \int_{(\infty)} \frac{\rho(\mathbf{r}')}{|\mathbf{r} - \mathbf{r}'|} d\tau' \right) \equiv -\mathbf{\nabla} V(\mathbf{r})$$

The scalar potential V

Here $V(\mathbf{r})$ is the scalar electric potential

$$V(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int_{(\infty)} \frac{\rho(\mathbf{r}')}{|\mathbf{r} - \mathbf{r}'|} d\tau'$$

If we have a system of discrete charges q_1 , q_2 ,..., q_n , located at positions \mathbf{r}_1 , \mathbf{r}_2 ,..., \mathbf{r}_n respectively, then

$$\rho(\mathbf{r}') = \sum_{j=1}^{n} q_j \, \delta^3(\mathbf{r}' - \mathbf{r}_j)$$

which, when plugged in the expression for $V(\mathbf{r})$ gives, upon using the property of Dirac-delta function,

$$V(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \sum_{j=1}^{n} \frac{q_j}{|\mathbf{r} - \mathbf{r}_j|} \qquad \int_{\text{all space}} f(\mathbf{r}) \delta^3(\mathbf{r} - \mathbf{a}) \, d\tau = f(\mathbf{a})$$

Comments on Potential

Name

We found that naturally associated with the concept of Electric field is the idea of Electric potential V.

A surface over which the potential is constant is called an equipotential.


Since
$$E = -\nabla V$$

Comments on Potential

Name

Equipotential Surfaces

Field lines and equipotential lines of a point charge




Comments on Potential

Name

Equipotential Surfaces

Field lines and equipotential lines of two equal and opposite

charges



Comments on Potential

Advantage of the potential formulation

- The potential formulation is advantageous in the sense that V is a scalar quantity, and therefore its calculation, in general, will require less effort we don't have to worry about directions.

$$\mathbf{E} = -\nabla V$$

Thus the potential formulation reduces down a vector problem to a scalar one.

Ambiguity in the Electric Potential

We already saw that there is an ambiguity in the definition of electric potential. It is unique up to addition of a constant. If we consider,

$$V_{\text{new}} = V_{\text{old}} + K$$

with K some constant (of appropriate dimension*), then

$$\mathbf{E}_{\text{new}} = -\nabla V_{\text{new}} = -\nabla (V_{\text{old}} + K) = -\nabla V_{\text{old}} + 0 = \mathbf{E}_{\text{old}}$$

Thus the electric field remains unchanged.

*The SI unit of electric potential is Joule/Coulomb (J/C) or Volt.

Comments on Potential

• The reference point O

There is an essential ambiguity in the definition of potential, since the choice of reference point **O** was arbitrary.

Changing reference points amounts to adding a constant K to the potential:

$$V'(\mathbf{r}) = -\int_{\mathcal{O}'}^{\mathbf{r}} \mathbf{E} \cdot d\mathbf{l} = -\int_{\mathcal{O}'}^{\mathcal{O}} \mathbf{E} \cdot d\mathbf{l} - \int_{\mathcal{O}}^{\mathbf{r}} \mathbf{E} \cdot d\mathbf{l} = K + V(\mathbf{r}),$$

where *K* is the line integral of **E** from the old reference point *O* to the new one *O'*

• The reference point O

Thus, we have

$$V_{\text{new}}(\mathbf{r}) = K + V_{\text{old}}(\mathbf{r})$$

where $V_{\text{old}}(\mathbf{r})=V(\mathbf{r})$ refers to the potential defined with respect to the origin reference point \mathcal{O} .

We, therefore, conclude that changing the reference point amounts to shifting the potential by a constant amount, which does not change anything physically—The potential difference between two points remains the same. (The potential difference remains invariant under the shift of the reference point.):

$$V_{\text{new}}(\mathbf{r}_1) - V_{\text{new}}(\mathbf{r}_2) = (K + V_{\text{old}}(\mathbf{r}_1)) - (K + V_{\text{old}}(\mathbf{r}_2)) = V_{\text{old}}(\mathbf{r}_1) - V_{\text{old}}(\mathbf{r}_2)$$

Infinity as the Reference Point

Usually we choose the reference point as infinity, where we set V to be zero. This is reasonable since we expect that as we move away from all sources, the potential should vanish (*This is true for 3-dimensional and higher dimensional space*). Thus under this convention, the potential at any point \mathbf{r} will be given by (setting $\mathbf{b}=\mathbf{r}$, $\mathbf{a}=\mathcal{O}=\infty$ and $V(\infty)=0$),

$$V(\mathbf{r}) = -\int_{\infty}^{\mathbf{r}} \mathbf{E} \cdot d\mathbf{l} = \int_{\mathbf{r}}^{\infty} \mathbf{E} \cdot d\mathbf{l}$$

However, as we will see, this choice is not a good one when we have an infinitely extended source (or if we are working in dimensions less than 3).

Appropriate Reference Point

Consider an infinite sheet of charge with surface density o. The electric field is given by

$$\mathbf{E} = \frac{\sigma}{2\epsilon_0} \hat{\mathbf{n}}$$

Here \mathbf{n} represent the unit normal to the sheet. Thus the potential at a distance r from the sheet in the direction of \mathbf{n} (using infinity as the reference point):

$$V(\mathbf{r}) = -\int_{\infty}^{r} \frac{\sigma}{2\epsilon_0} \hat{\mathbf{n}} \cdot (dl \, \hat{\mathbf{n}}) = \frac{\sigma}{2\epsilon_0} (\infty - r).$$

Now this result does not make much sense. Thus the choice $V(\infty)=0$ is not a good one for this problem.

Appropriate Reference Point

Thus we need to choose some other suitable reference point for this problem: We can consider a position corresponding to some finite value of \mathbf{r} . For example, we can choose $\mathbf{r}=0$ as the reference point, so that V(0)=0. Thus $V(r)[\sigma/2\epsilon_0]$

$$V(\mathbf{r}) = -\int_0^{\mathbf{r}} \frac{\sigma}{2\epsilon_0} \mathbf{n} \cdot dl \mathbf{n} = -\frac{\sigma}{2\epsilon_0} r.$$

This is meaningful now!

-10 -5 5 10^r
-5 -10

In "real life" we don't have infinite charge distributions, and therefore we can safely choose infinity as the reference point. However, for practical electrical circuits, the earth or ground potential is usually taken to be zero and everything is referenced to the earth.

Electric Potential for different Charge Systems

In 3-dimensional space, with the reference point set at infinity, for a system of discrete charges $q_1, q_2,..., q_n$, located at positions $\mathbf{r}_1, \mathbf{r}_2,..., \mathbf{r}_n$ respectively, the electric potential at some position \mathbf{r} is given by

$$V(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \sum_{j=1}^{n} \frac{q_j}{|\mathbf{r} - \mathbf{r}_j|}$$

If, instead, we have a continuous volume charge distribution with density ρ then

$$V(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int_{\mathcal{V}} \frac{\rho(\mathbf{r}')}{|\mathbf{r} - \mathbf{r}'|} d\tau'$$

Similarly, for a surface charge distribution (density: σ), or a line charge distribution (density: λ) we respectively have

$$V(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int_{\mathcal{S}} \frac{\sigma(\mathbf{r}')}{|\mathbf{r} - \mathbf{r}'|} dS' \qquad V(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int_{\mathcal{C}} \frac{\lambda(\mathbf{r}')}{|\mathbf{r} - \mathbf{r}'|} dl'$$

Comments on Potential

Super position Principle

 \bowtie We have the superposition principle for the force acting on a test charge Q:

$$\mathbf{F} = \mathbf{F}_1 + \mathbf{F}_2 + \mathbf{F}_3 + \cdots$$

We then have the superposition principle for electric field, obtained by dividing the above equation by Q:

$$\mathbf{E} = \mathbf{E}_1 + \mathbf{E}_2 + \mathbf{E}_3 + \cdots$$

Finally, choosing an appropriate common reference point and considering the line integral of the above equation gives superposition principle for the electric potential:

$$V = V_1 + V_2 + V_3 + \cdots$$

Comments on Potential

Units of Potential

In our units, force is measured in newtons and charge in coulombs, so electric fields are in newtons per coulomb. Accordingly, potential is newton-meters per coulomb, or joules per coulomb. A joule per coulomb is a **volt**.