GNU Compiler Collection Internals (GCC)

GNU Compiler Collection Internals

by Richard M. Stallman and the GCC Developer Community

Last updated 23 May 2004

for GCC 4.0.0

For GCC Version 4.0.0

Copyright © 1988, 1989, 1992, 1993, 1994, 1995, 1996, 1997, 1998, 1999, 2000, 2001, 2002, 2003, 2004 Free Software Foundation, Inc.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with the Invariant Sections being "GNU General Public License" and "Funding Free Software", the Front-Cover texts being (a) (see below), and with the Back-Cover Texts being (b) (see below). A copy of the license is included in the section entitled "GNU Free Documentation License".

(a) The FSF's Front-Cover Text is:

A GNU Manual

(b) The FSF's Back-Cover Text is:

You have freedom to copy and modify this GNU Manual, like GNU software. Copies published by the Free Software Foundation raise funds for GNU development.

Short Contents

Intro	oduction
1	Contributing to GCC Development
2	GCC and Portability
3	Interfacing to GCC Output 7
4	The GCC low-level runtime library 9
5	Language Front Ends in GCC
6	Source Tree Structure and Build System 19
7	Passes and Files of the Compiler 45
8	Trees: The intermediate representation used by the C and C++
	front ends
9	Analysis and Optimization of GIMPLE Trees 87
10	RTL Representation
11	Control Flow Graph
12	Machine Descriptions
13	Target Description Macros and Functions 247
14	Host Configuration
15	Makefile Fragments
16	collect2
17	Standard Header File Directories
18	Memory Management and Type Information 397
Fun	ding Free Software
The	GNU Project and GNU/Linux
GNU	U GENERAL PUBLIC LICENSE 407
GNU	U Free Documentation License 413
Con	tributors to GCC
Opt	ion Index
Con	cept Index

Table of Contents

lı	ntroduction
1	Contributing to GCC Development 3
2	GCC and Portability 5
3	Interfacing to GCC Output 7
4	The GCC low-level runtime library
5	Language Front Ends in GCC 17
6	Source Tree Structure and Build System 19 6.1 Configure Terms and History
	6.3.7.1 Texinfo Manuals

	6.3.7.2 Man Page Generation	27
	6.3.7.3 Miscellaneous Documentation	27
	6.3.8 Anatomy of a Language Front End	28
	6.3.8.1 The Front End 'language' Directory	
	6.3.8.2 The Front End 'config-lang.in' File	31
	6.3.9 Anatomy of a Target Back End	32
	6.4 Testsuites	
	6.4.1 Idioms Used in Testsuite Code	
	6.4.2 Directives used within DejaGnu tests	
	6.4.3 Ada Language Testsuites	38
	6.4.4 C Language Testsuites	38
	6.4.5 The Java library testsuites	
	6.4.6 Support for testing gcov	
	6.4.7 Support for testing profile-directed optimizations	
	6.4.8 Support for testing binary compatibility	42
7	Passes and Files of the Compiler	45
	7.1 Parsing pass	45
	7.2 Gimplification pass	
	7.3 Pass manager	
	7.4 Tree-SSA passes	47
	7.5 RTL passes	51
8	Trees: The intermediate representation used	by
		55
	8.1 Deficiencies	55
	8.2 Overview	
	8.2.1 Trees	
	8.2.2 Identifiers	
	8.2.3 Containers	
	8.3 Types	
	8.4 Scopes	
	8.4.1 Namespaces	62
	8.4.2 Classes	
	8.5 Declarations	
	8.6 Functions	
	8.6.1 Function Basics	
	8.6.2 Function Bodies	71
	8.6.2.1 Statements	71
	0.0.4.1 Obdbelliento	
	8.7 Attributes in trees	. –

9 Analysis and Optimization of GIMI	
9.1 GENERIC	
9.2 GIMPLE	
9.2.1 Interfaces	
9.2.2 Temporaries	
9.2.3 Expressions	
9.2.3.1 Compound Expressions	
9.2.3.2 Compound Lvalues	
9.2.3.3 Conditional Expressions	
9.2.3.4 Logical Operators	
9.2.4 Statements	
9.2.4.1 Blocks	
9.2.4.2 Statement Sequences	
1 0	
9.2.4.4 Loops	
9.2.4.6 Jumps	
9.2.4.7 Cleanups	
9.2.4.7 Cleanups	
9.2.5 GIMPLE Example	
9.2.6 Rough GIMPLE Grammar	
9.3 Annotations	
9.4 Statement Operands	
9.4.1 Operand Iterators	
9.5 Static Single Assignment	
9.5.1 Preserving the SSA form	
9.5.2 Examining SSA_NAME nodes	
9.5.3 Walking use-def chains	
9.5.4 Walking the dominator tree	
9.6 Alias analysis	
·	
10 RTL Representation	107
10.1 RTL Object Types	107
10.2 RTL Classes and Formats	
10.3 Access to Operands	110
10.4 Access to Special Operands	111
10.5 Flags in an RTL Expression	
10.6 Machine Modes	
10.7 Constant Expression Types	
10.8 Registers and Memory	124
10.9 RTL Expressions for Arithmetic	
10.10 Comparison Operations	
10.11 Bit-Fields	
10.12 Vector Operations	
10.13 Conversions	
10.14 Declarations	
10.15 Side Effect Expressions	135

10.16 Embedded Side-Effects on Addresses	
10.17 Assembler Instructions as Expressions	
10.18 Insns	
10.19 RTL Representation of Function-Call Inst	
10.20 Structure Sharing Assumptions	
10.21 Reading RTL	
G	
11 Control Flow Graph	
11.1 Basic Blocks	155
11.2 Edges	156
11.3 Profile information	
11.4 Maintaining the CFG	
11.5 Liveness information	
10 Mark' Danieliana	1.05
12 Machine Descriptions	
12.1 Overview of How the Machine Description	
12.2 Everything about Instruction Patterns	
12.3 Example of define_insn	
12.4 RTL Template	
12.5 Output Templates and Operand Substituti	
12.6 C Statements for Assembler Output	
12.7 Predicates	
12.7.1 Machine-Independent Predicates	
12.7.2 Defining Machine-Specific Predicates.	
12.8 Operand Constraints	
12.8.1 Simple Constraints	
12.8.2 Multiple Alternative Constraints 12.8.3 Register Class Preferences	
12.8.4 Constraint Modifier Characters	
12.8.5 Constraints for Particular Machines	
12.9 Standard Pattern Names For Generation	
12.10 When the Order of Patterns Matters	
12.11 Interdependence of Patterns	
12.12 Defining Jump Instruction Patterns	
12.13 Defining Looping Instruction Patterns	
12.14 Canonicalization of Instructions	
12.15 Defining RTL Sequences for Code Genera	tion 217
12.16 Defining How to Split Instructions	
12.17 Including Patterns in Machine Description	
12.17.1 RTL Generation Tool Options for Di	
12.18 Machine-Specific Peephole Optimizers	224
12.18.1 RTL to Text Peephole Optimizers	$\dots \dots 225$
12.18.2 RTL to RTL Peephole Optimizers	227
12.19 Instruction Attributes	
12.19.1 Defining Attributes and their Values	
12.19.2 Attribute Expressions	
12.19.3 Assigning Attribute Values to Insns.	
12.19.4 Example of Attribute Specifications.	233

12.19.5 Computing the Length of an Insn	
12.19.6 Constant Attributes	
12.19.7 Delay Slot Scheduling	
12.19.8 Specifying processor pipeline description	
12.20 Conditional Execution	
12.21 Constant Definitions	
12.22 Macros	
12.22.1 Mode Macros	
12.22.1.1 Defining Mode Macros	
12.22.1.2 String Substitution in Mode Macros	
12.22.1.3 Mode Macro Examples	
12.22.2 Code Macros	. 245
13 Target Description Macros and Functions	
	247
13.1 The Global targetm Variable	
13.2 Controlling the Compilation Driver, 'gcc'	
13.3 Run-time Target Specification	
13.4 Defining data structures for per-function information	
13.5 Storage Layout	
13.6 Layout of Source Language Data Types	
13.7 Target Character Escape Sequences	
13.8 Register Usage	
13.8.1 Basic Characteristics of Registers	
13.8.2 Order of Allocation of Registers	
13.8.3 How Values Fit in Registers	
13.8.4 Handling Leaf Functions	
13.8.5 Registers That Form a Stack	
13.9 Register Classes	. 277
13.10 Stack Layout and Calling Conventions	. 285
13.10.1 Basic Stack Layout	. 285
13.10.2 Exception Handling Support	
13.10.3 Specifying How Stack Checking is Done	. 290
13.10.4 Registers That Address the Stack Frame	. 292
13.10.5 Eliminating Frame Pointer and Arg Pointer	
13.10.6 Passing Function Arguments on the Stack	
13.10.7 Passing Arguments in Registers	
13.10.8 How Scalar Function Values Are Returned	
13.10.9 How Large Values Are Returned	
13.10.10 Caller-Saves Register Allocation	
13.10.11 Function Entry and Exit	
13.10.12 Generating Code for Profiling	
13.10.13 Permitting tail calls	
13.11 Implementing the Varargs Macros	
13.12 Trampolines for Nested Functions	
13.13 Implicit Calls to Library Routines	
13.14 Addressing Modes	
13.15 Condition Code Status	. 320

13.16	Describing Relative Costs of Operations	. 322
13.17	1	
13.18	·	
13.19	0 1	
13.20		
	3.20.1 The Overall Framework of an Assembler File	
13	3.20.2 Output of Data	
13	3.20.3 Output of Uninitialized Variables	
13	3.20.4 Output and Generation of Labels	
13	3.20.5 How Initialization Functions Are Handled	
13	3.20.6 Macros Controlling Initialization Routines	
13	3.20.7 Output of Assembler Instructions	
13	3.20.8 Output of Dispatch Tables	
13	3.20.9 Assembler Commands for Exception Regions	
13	3.20.10 Assembler Commands for Alignment	
13.21	Controlling Debugging Information Format	. 359
13	3.21.1 Macros Affecting All Debugging Formats	
13	3.21.2 Specific Options for DBX Output	
13	3.21.3 Open-Ended Hooks for DBX Format	
13	3.21.4 File Names in DBX Format	. 362
13	3.21.5 Macros for SDB and DWARF Output	. 363
13	3.21.6 Macros for VMS Debug Format	. 365
13.22	Cross Compilation and Floating Point	. 365
13.23	Mode Switching Instructions	. 367
13.24	Defining target-specific uses ofattribute	. 368
13.25	Defining coprocessor specifics for MIPS targets	. 369
13.26	Parameters for Precompiled Header Validity Checking	. 370
13.27	C++ ABI parameters	. 370
13.28	Miscellaneous Parameters	. 371
14 F	Iost Configuration	385
14.1	Host Common	
14.2	Host Filesystem	
14.3	Host Misc	
1110	22000 22200	. 55.
15 N	Makefile Fragments	389
15.1	Target Makefile Fragments	. 389
15.2	Host Makefile Fragments	. 391
16 c	ollect2	393
17 S	Standard Header File Directories	395

18 Memory Management and Type Information
18.1 The Inside of a GTY(())
Funding Free Software 403
The GNU Project and GNU/Linux 405
GNU GENERAL PUBLIC LICENSE
GNU Free Documentation License
Contributors to GCC 421
Option Index
Concept Index 435

Introduction

This manual documents the internals of the GNU compilers, including how to port them to new targets and some information about how to write front ends for new languages. It corresponds to GCC version 4.0.0. The use of the GNU compilers is documented in a separate manual. See section "Introduction" in *Using the GNU Compiler Collection (GCC)*.

This manual is mainly a reference manual rather than a tutorial. It discusses how to contribute to GCC (see Chapter 1 [Contributing], page 3), the characteristics of the machines supported by GCC as hosts and targets (see Chapter 2 [Portability], page 5), how GCC relates to the ABIs on such systems (see Chapter 3 [Interface], page 7), and the characteristics of the languages for which GCC front ends are written (see Chapter 5 [Languages], page 17). It then describes the GCC source tree structure and build system, some of the interfaces to GCC front ends, and how support for a target system is implemented in GCC.

Additional tutorial information is linked to from http://gcc.gnu.org/readings.html.

1 Contributing to GCC Development

If you would like to help pretest GCC releases to assure they work well, current development sources are available by CVS (see http://gcc.gnu.org/cvs.html). Source and binary snapshots are also available for FTP; see http://gcc.gnu.org/snapshots.html.

If you would like to work on improvements to GCC, please read the advice at these URLs:

http://gcc.gnu.org/contribute.html http://gcc.gnu.org/contributewhy.html

for information on how to make useful contributions and avoid duplication of effort. Suggested projects are listed at http://gcc.gnu.org/projects/.

2 GCC and Portability

GCC itself aims to be portable to any machine where int is at least a 32-bit type. It aims to target machines with a flat (non-segmented) byte addressed data address space (the code address space can be separate). Target ABIs may have 8, 16, 32 or 64-bit int type. char can be wider than 8 bits.

GCC gets most of the information about the target machine from a machine description which gives an algebraic formula for each of the machine's instructions. This is a very clean way to describe the target. But when the compiler needs information that is difficult to express in this fashion, ad-hoc parameters have been defined for machine descriptions. The purpose of portability is to reduce the total work needed on the compiler; it was not of interest for its own sake.

GCC does not contain machine dependent code, but it does contain code that depends on machine parameters such as endianness (whether the most significant byte has the highest or lowest address of the bytes in a word) and the availability of autoincrement addressing. In the RTL-generation pass, it is often necessary to have multiple strategies for generating code for a particular kind of syntax tree, strategies that are usable for different combinations of parameters. Often, not all possible cases have been addressed, but only the common ones or only the ones that have been encountered. As a result, a new target may require additional strategies. You will know if this happens because the compiler will call abort. Fortunately, the new strategies can be added in a machine-independent fashion, and will affect only the target machines that need them.

3 Interfacing to GCC Output

GCC is normally configured to use the same function calling convention normally in use on the target system. This is done with the machine-description macros described (see Chapter 13 [Target Macros], page 247).

However, returning of structure and union values is done differently on some target machines. As a result, functions compiled with PCC returning such types cannot be called from code compiled with GCC, and vice versa. This does not cause trouble often because few Unix library routines return structures or unions.

GCC code returns structures and unions that are 1, 2, 4 or 8 bytes long in the same registers used for int or double return values. (GCC typically allocates variables of such types in registers also.) Structures and unions of other sizes are returned by storing them into an address passed by the caller (usually in a register). The target hook TARGET_STRUCT_VALUE_RTX tells GCC where to pass this address.

By contrast, PCC on most target machines returns structures and unions of any size by copying the data into an area of static storage, and then returning the address of that storage as if it were a pointer value. The caller must copy the data from that memory area to the place where the value is wanted. This is slower than the method used by GCC, and fails to be reentrant.

On some target machines, such as RISC machines and the 80386, the standard system convention is to pass to the subroutine the address of where to return the value. On these machines, GCC has been configured to be compatible with the standard compiler, when this method is used. It may not be compatible for structures of 1, 2, 4 or 8 bytes.

GCC uses the system's standard convention for passing arguments. On some machines, the first few arguments are passed in registers; in others, all are passed on the stack. It would be possible to use registers for argument passing on any machine, and this would probably result in a significant speedup. But the result would be complete incompatibility with code that follows the standard convention. So this change is practical only if you are switching to GCC as the sole C compiler for the system. We may implement register argument passing on certain machines once we have a complete GNU system so that we can compile the libraries with GCC.

On some machines (particularly the SPARC), certain types of arguments are passed "by invisible reference". This means that the value is stored in memory, and the address of the memory location is passed to the subroutine.

If you use longjmp, beware of automatic variables. ISO C says that automatic variables that are not declared volatile have undefined values after a longjmp. And this is all GCC promises to do, because it is very difficult to restore register variables correctly, and one of GCC's features is that it can put variables in registers without your asking it to.

4 The GCC low-level runtime library

GCC provides a low-level runtime library, 'libgcc.a' or 'libgcc_s.so.1' on some platforms. GCC generates calls to routines in this library automatically, whenever it needs to perform some operation that is too complicated to emit inline code for.

Most of the routines in libgcc handle arithmetic operations that the target processor cannot perform directly. This includes integer multiply and divide on some machines, and all floating-point operations on other machines. libgcc also includes routines for exception handling, and a handful of miscellaneous operations.

Some of these routines can be defined in mostly machine-independent C. Others must be hand-written in assembly language for each processor that needs them.

GCC will also generate calls to C library routines, such as memcpy and memset, in some cases. The set of routines that GCC may possibly use is documented in section "Other Builtins" in *Using the GNU Compiler Collection (GCC)*.

These routines take arguments and return values of a specific machine mode, not a specific C type. See Section 10.6 [Machine Modes], page 118, for an explanation of this concept. For illustrative purposes, in this chapter the floating point type float is assumed to correspond to SFmode; double to DFmode; and long double to both TFmode and XFmode. Similarly, the integer types int and unsigned int correspond to SImode; long and unsigned long to DImode; and long long and unsigned long long to TImode.

4.1 Routines for integer arithmetic

The integer arithmetic routines are used on platforms that don't provide hardware support for arithmetic operations on some modes.

4.1.1 Arithmetic functions

```
int __ashlsi3 (int a, int b)
                                                                     [Runtime Function]
long __ashldi3 (long a, int b)
                                                                     [Runtime Function]
long long __ashlti3 (long long a, int b)
                                                                     [Runtime Function]
     These functions return the result of shifting a left by b bits.
int __ashrsi3 (int a, int b)
                                                                     [Runtime Function]
long __ashrdi3 (long a, int b)
                                                                     [{
m Runtime\ Function}]
long long __ashrti3 (long long a, int b)
                                                                     [Runtime Function]
     These functions return the result of arithmetically shifting a right by b bits.
int __divsi3 (int a, int b)
                                                                     [Runtime Function]
long __divdi3 (long a, long b)
                                                                     [{
m Runtime\ Function}]
long long __divti3 (long long a, long long b)
                                                                     [Runtime Function]
     These functions return the quotient of the signed division of a and b.
int __lshrsi3 (int a, int b)
                                                                     [Runtime Function]
long __lshrdi3 (long a, int b)
                                                                     [Runtime Function]
long long __lshrti3 (long long a, int b)
                                                                     [Runtime Function]
     These functions return the result of logically shifting a right by b bits.
```

```
int __modsi3 (int a, int b)
                                                                   [Runtime Function]
long __moddi3 (long a, long b)
                                                                   [Runtime Function]
long long __modti3 (long long a, long long b)
                                                                   [Runtime Function]
     These functions return the remainder of the signed division of a and b.
int __mulsi3 (int a, int b)
                                                                   [Runtime Function]
long __muldi3 (long a, long b)
                                                                   [{
m Runtime\ Function}]
long long __multi3 (long long a, long long b)
                                                                   [Runtime Function]
     These functions return the product of a and b.
long __negdi2 (long a)
                                                                   [Runtime Function]
long long __negti2 (long long a)
                                                                   [Runtime Function]
     These functions return the negation of a.
                                                                   [Runtime Function]
unsigned int __udivsi3 (unsigned int a, unsigned int b)
unsigned long __udivdi3 (unsigned long a, unsigned long b)
                                                                   [Runtime Function]
unsigned long long __udivti3 (unsigned long long a,
                                                                   [Runtime Function]
          unsigned long long b)
     These functions return the quotient of the unsigned division of a and b.
unsigned long __udivmoddi3 (unsigned long a, unsigned long
                                                                   [Runtime Function]
          b, unsigned long *c)
unsigned long long __udivti3 (unsigned long long a,
                                                                   [Runtime Function]
          unsigned long long b, unsigned long long *c)
     These functions calculate both the quotient and remainder of the unsigned division
     of a and b. The return value is the quotient, and the remainder is placed in variable
```

unsigned int __umodsi3 (unsigned int a, unsigned int b) [Runtime Function]
unsigned long __umoddi3 (unsigned long a, unsigned long b) [Runtime Function]
unsigned long long __umodti3 (unsigned long long a, unsigned long long b)

These functions return the remainder of the unsigned division of a and b.

4.1.2 Comparison functions

pointed to by c.

The following functions implement integral comparisons. These functions implement a low-level compare, upon which the higher level comparison operators (such as less than and greater than or equal to) can be constructed. The returned values lie in the range zero to two, to allow the high-level operators to be implemented by testing the returned result using either signed or unsigned comparison.

4.1.3 Trapping arithmetic functions

The following functions implement trapping arithmetic. These functions call the libc function abort upon signed arithmetic overflow.

```
int __absvsi2 (int a)
                                                                   [Runtime Function]
long __absvdi2 (long a)
                                                                   [Runtime Function]
     These functions return the absolute value of a.
int __addvsi3 (int a, int b)
                                                                   [Runtime Function]
long __addvdi3 (long a, long b)
                                                                   [Runtime Function]
     These functions return the sum of a and b; that is a + b.
int __mulvsi3 (int a, int b)
                                                                   [Runtime Function]
long __mulvdi3 (long a, long b)
                                                                   [Runtime Function]
     The functions return the product of a and b; that is a * b.
int __negvsi2 (int a)
                                                                   [Runtime Function]
                                                                    [Runtime Function]
long __negvdi2 (long a)
     These functions return the negation of a; that is -a.
```

```
int __subvsi3 (int a, int b)
                                                                 [Runtime Function]
long __subvdi3 (long a, long b)
                                                                 [Runtime Function]
```

These functions return the difference between b and a; that is a - b.

4.1.4 Bit operations

```
int __clzsi2 (int a)
                                                                      [Runtime Function]
int __clzdi2 (long a)
                                                                      [{
m Runtime\ Function}]
int __clzti2 (long long a)
                                                                      [Runtime Function]
      These functions return the number of leading 0-bits in a, starting at the most signif-
```

icant bit position. If a is zero, the result is undefined.

```
int __ctzsi2 (int a)
                                                                     [Runtime Function]
int __ctzdi2 (long a)
                                                                     [Runtime Function]
int __ctzti2 (long long a)
                                                                     [Runtime Function]
     These functions return the number of trailing 0-bits in a, starting at the least signif-
```

icant bit position. If a is zero, the result is undefined.

```
int __ffsdi2 (long a)
                                                                [Runtime Function]
int __ffsti2 (long long a)
                                                                [Runtime Function]
```

These functions return the index of the least significant 1-bit in a, or the value zero if a is zero. The least significant bit is index one.

```
int __paritysi2 (int a)
                                                                [Runtime Function]
int __paritydi2 (long a)
                                                                [Runtime Function]
                                                                [Runtime Function]
int __parityti2 (long long a)
```

These functions return the value zero if the number of bits set in a is even, and the value one otherwise.

```
int __popcountsi2 (int a) [Runtime Function]
int __popcountdi2 (long a) [Runtime Function]
int __popcountti2 (long long a) [Runtime Function]
These functions return the number of bits set in a.
```

4.2 Routines for floating point emulation

The software floating point library is used on machines which do not have hardware support for floating point. It is also used whenever '-msoft-float' is used to disable generation of floating point instructions. (Not all targets support this switch.)

For compatibility with other compilers, the floating point emulation routines can be renamed with the DECLARE_LIBRARY_RENAMES macro (see Section 13.13 [Library Calls], page 314). In this section, the default names are used.

Presently the library does not support XFmode, which is used for long double on some architectures.

4.2.1 Arithmetic functions

```
float __addsf3 (float a, float b)
                                                                   [Runtime\ Function]
double __adddf3 (double a, double b)
                                                                   [Runtime Function]
long double __addtf3 (long double a, long double b)
                                                                   [Runtime Function]
long double __addxf3 (long double a, long double b)
                                                                   [Runtime Function]
     These functions return the sum of a and b.
float __subsf3 (float a, float b)
                                                                   [Runtime Function]
double __subdf3 (double a, double b)
                                                                   [Runtime Function]
long double __subtf3 (long double a, long double b)
                                                                   [Runtime Function]
long double __subxf3 (long double a, long double b)
                                                                   [Runtime Function]
     These functions return the difference between b and a; that is, a - b.
                                                                   [Runtime Function]
float __mulsf3 (float a, float b)
double __muldf3 (double a, double b)
                                                                   [{
m Runtime\ Function}]
long double __multf3 (long double a, long double b)
                                                                   [Runtime Function]
long double __mulxf3 (long double a, long double b)
                                                                   [Runtime\ Function]
     These functions return the product of a and b.
float __divsf3 (float a, float b)
                                                                   [Runtime Function]
double __divdf3 (double a, double b)
                                                                   [Runtime Function]
long double __divtf3 (long double a, long double b)
                                                                   [Runtime Function]
long double __divxf3 (long double a, long double b)
                                                                   [Runtime Function]
     These functions return the quotient of a and b; that is, a/b.
float __negsf2 (float a)
                                                                   [Runtime Function]
double __negdf2 (double a)
                                                                   [Runtime Function]
long double __negtf2 (long double a)
                                                                   [Runtime\ Function]
long double __negxf2 (long double a)
                                                                   [Runtime Function]
     These functions return the negation of a. They simply flip the sign bit, so they can
     produce negative zero and negative NaN.
```

4.2.2 Conversion functions

```
double __extendsfdf2 (float a)
                                                                 [Runtime Function]
long double __extendsftf2 (float a)
                                                                 [Runtime Function]
long double __extendsfxf2 (float a)
                                                                 [Runtime Function]
long double __extenddftf2 (double a)
                                                                 [Runtime Function]
long double __extenddfxf2 (double a)
                                                                 [Runtime Function]
     These functions extend a to the wider mode of their return type.
double __truncxfdf2 (long double a)
                                                                 [Runtime Function]
double __trunctfdf2 (long double a)
                                                                 [Runtime Function]
float __truncxfsf2 (long double a)
                                                                 [Runtime Function]
float __trunctfsf2 (long double a)
                                                                 [Runtime Function]
float __truncdfsf2 (double a)
                                                                 [Runtime Function]
     These functions truncate a to the narrower mode of their return type, rounding toward
     zero.
int __fixsfsi (float a)
                                                                 [Runtime Function]
int __fixdfsi (double a)
                                                                 [Runtime Function]
int __fixtfsi (long double a)
                                                                 [Runtime Function]
int __fixxfsi (long double a)
                                                                 [Runtime Function]
     These functions convert a to a signed integer, rounding toward zero.
long __fixsfdi (float a)
                                                                 [Runtime Function]
long __fixdfdi (double a)
                                                                 [Runtime Function]
long __fixtfdi (long double a)
                                                                 [Runtime Function]
long __fixxfdi (long double a)
                                                                 [Runtime Function]
     These functions convert a to a signed long, rounding toward zero.
long long __fixsfti (float a)
                                                                 [Runtime Function]
long long __fixdfti (double a)
                                                                 [Runtime Function]
long long __fixtfti (long double a)
                                                                 [Runtime Function]
long long __fixxfti (long double a)
                                                                 [Runtime Function]
     These functions convert a to a signed long long, rounding toward zero.
unsigned int __fixunssfsi (float a)
                                                                 [Runtime Function]
unsigned int __fixunsdfsi (double a)
                                                                 [Runtime Function]
unsigned int __fixunstfsi (long double a)
                                                                 [Runtime Function]
unsigned int __fixunsxfsi (long double a)
                                                                 [Runtime Function]
     These functions convert a to an unsigned integer, rounding toward zero. Negative
     values all become zero.
unsigned long __fixunssfdi (float a)
                                                                 [Runtime Function]
unsigned long __fixunsdfdi (double a)
                                                                 [Runtime Function]
unsigned long __fixunstfdi (long double a)
                                                                 [Runtime Function]
unsigned long __fixunsxfdi (long double a)
                                                                 [Runtime Function]
     These functions convert a to an unsigned long, rounding toward zero. Negative values
     all become zero.
```

```
unsigned long long __fixunssfti (float a)
                                                                  [Runtime Function]
unsigned long long __fixunsdfti (double a)
                                                                  [Runtime Function]
unsigned long long __fixunstfti (long double a)
                                                                  [Runtime Function]
unsigned long long __fixunsxfti (long double a)
                                                                  [Runtime Function]
     These functions convert a to an unsigned long long, rounding toward zero. Negative
     values all become zero.
float __floatsisf (int i)
                                                                  [Runtime Function]
double __floatsidf (int i)
                                                                  [{
m Runtime\ Function}]
long double __floatsitf (int i)
                                                                  [{
m Runtime\ Function}]
long double __floatsixf (int i)
                                                                  [Runtime Function]
     These functions convert i, a signed integer, to floating point.
float __floatdisf (long i)
                                                                  [Runtime\ Function]
double __floatdidf (long i)
                                                                  [{
m Runtime\ Function}]
long double __floatditf (long i)
                                                                  [Runtime Function]
long double __floatdixf (long i)
                                                                  [Runtime Function]
     These functions convert i, a signed long, to floating point.
float __floattisf (long long i)
                                                                  [Runtime Function]
double __floattidf (long long i)
                                                                  [Runtime Function]
long double __floattitf (long long i)
                                                                  [Runtime Function]
long double __floattixf (long long i)
                                                                  [Runtime Function]
     These functions convert i, a signed long long, to floating point.
```

4.2.3 Comparison functions

There are two sets of basic comparison functions.

```
int __cmpsf2 (float a, float b) [Runtime Function]
int __cmpdf2 (double a, double b) [Runtime Function]
int __cmptf2 (long double a, long double b) [Runtime Function]
These functions calculate a <=> b. That is, if a is less than b, they return -1; if
a is greater than b, they return 1; and if a and b are equal they return 0. If either
argument is NaN they return 1, but you should not roly on this; if NaN is a possibility
```

argument is NaN they return 1, but you should not rely on this; if NaN is a possibility, use one of the higher-level comparison functions.

```
int __unordsf2 (float a, float b) [Runtime Function]
int __unorddf2 (double a, double b) [Runtime Function]
int __unordtf2 (long double a, long double b) [Runtime Function]
These functions return a nonzero value if either argument is NaN, otherwise 0.
```

There is also a complete group of higher level functions which correspond directly to comparison operators. They implement the ISO C semantics for floating-point comparisons, taking NaN into account. Pay careful attention to the return values defined for each set. Under the hood, all of these routines are implemented as

```
if (_unordXf2 (a, b))
  return E;
return __cmpXf2 (a, b);
```

where E is a constant chosen to give the proper behavior for NaN. Thus, the meaning of the return value is different for each set. Do not rely on this implementation; only the semantics documented below are guaranteed.

```
int __eqsf2 (float a, float b)
                                                                    [Runtime Function]
int __eqdf2 (double a, double b)
                                                                     [Runtime Function]
int __eqtf2 (long double a, long double b)
                                                                     [Runtime Function]
     These functions return zero if neither argument is NaN, and a and b are equal.
int __nesf2 (float a, float b)
                                                                     [Runtime Function]
int __nedf2 (double a, double b)
                                                                     [Runtime Function]
int __netf2 (long double a, long double b)
                                                                     [Runtime\ Function]
     These functions return a nonzero value if either argument is NaN, or if a and b are
     unequal.
int __gesf2 (float a, float b)
                                                                     [Runtime Function]
int __gedf2 (double a, double b)
                                                                     [Runtime Function]
int __getf2 (long double a, long double b)
                                                                     [Runtime Function]
     These functions return a value greater than or equal to zero if neither argument is
     NaN, and a is greater than or equal to b.
int __ltsf2 (float a, float b)
                                                                    [Runtime Function]
int __ltdf2 (double a, double b)
                                                                     [Runtime Function]
int __lttf2 (long double a, long double b)
                                                                    [Runtime Function]
     These functions return a value less than zero if neither argument is NaN, and a is
     strictly less than b.
int __lesf2 (float a, float b)
                                                                    [Runtime Function]
int __ledf2 (double a, double b)
                                                                     [Runtime Function]
int __letf2 (long double a, long double b)
                                                                     [Runtime Function]
     These functions return a value less than or equal to zero if neither argument is NaN,
     and a is less than or equal to b.
                                                                    [Runtime Function]
int __gtsf2 (float a, float b)
int __gtdf2 (double a, double b)
                                                                     [Runtime\ Function]
int __gttf2 (long double a, long double b)
                                                                     [Runtime Function]
     These functions return a value greater than zero if neither argument is NaN, and a is
     strictly greater than b.
```

4.3 Language-independent routines for exception handling

document me!

```
_Unwind_DeleteException
_Unwind_Find_FDE
_Unwind_ForcedUnwind
_Unwind_GetGR
_Unwind_GetIP
_Unwind_GetLanguageSpecificData
_Unwind_GetRegionStart
_Unwind_GetTextRelBase
_Unwind_GetDataRelBase
```

```
_{\tt Unwind\_RaiseException}
_Unwind_Resume
_{\tt Unwind\_SetGR}
_{\tt Unwind\_SetIP}
_Unwind_FindEnclosingFunction
_Unwind_SjLj_Register
_Unwind_SjLj_Unregister
_Unwind_SjLj_RaiseException
_Unwind_SjLj_ForcedUnwind
_Unwind_SjLj_Resume
__deregister_frame
__deregister_frame_info
__deregister_frame_info_bases
__register_frame
__register_frame_info
\verb|__register_frame_info_bases|
__register_frame_info_table
\verb|__register_frame_info_table_bases|
__register_frame_table
```

4.4 Miscellaneous runtime library routines

4.4.1 Cache control functions

```
void __clear_cache (char *beg, char *end) [Runtime Function]
This function clears the instruction cache between beg and end.
```

5 Language Front Ends in GCC

The interface to front ends for languages in GCC, and in particular the tree structure (see Chapter 8 [Trees], page 55), was initially designed for C, and many aspects of it are still somewhat biased towards C and C-like languages. It is, however, reasonably well suited to other procedural languages, and front ends for many such languages have been written for GCC.

Writing a compiler as a front end for GCC, rather than compiling directly to assembler or generating C code which is then compiled by GCC, has several advantages:

- GCC front ends benefit from the support for many different target machines already present in GCC.
- GCC front ends benefit from all the optimizations in GCC. Some of these, such as alias analysis, may work better when GCC is compiling directly from source code then when it is compiling from generated C code.
- Better debugging information is generated when compiling directly from source code than when going via intermediate generated C code.

Because of the advantages of writing a compiler as a GCC front end, GCC front ends have also been created for languages very different from those for which GCC was designed, such as the declarative logic/functional language Mercury. For these reasons, it may also be useful to implement compilers created for specialized purposes (for example, as part of a research project) as GCC front ends.

6 Source Tree Structure and Build System

This chapter describes the structure of the GCC source tree, and how GCC is built. The user documentation for building and installing GCC is in a separate manual (http://gcc.gnu.org/install/), with which it is presumed that you are familiar.

6.1 Configure Terms and History

The configure and build process has a long and colorful history, and can be confusing to anyone who doesn't know why things are the way they are. While there are other documents which describe the configuration process in detail, here are a few things that everyone working on GCC should know.

There are three system names that the build knows about: the machine you are building on (build), the machine that you are building for (host), and the machine that GCC will produce code for (target). When you configure GCC, you specify these with '--build=', '--host=', and '--target='.

Specifying the host without specifying the build should be avoided, as **configure** may (and once did) assume that the host you specify is also the build, which may not be true.

If build, host, and target are all the same, this is called a *native*. If build and host are the same but target is different, this is called a *cross*. If build, host, and target are all different this is called a *canadian* (for obscure reasons dealing with Canada's political party and the background of the person working on the build at that time). If host and target are the same, but build is different, you are using a cross-compiler to build a native for a different system. Some people call this a *host-x-host*, *crossed native*, or *cross-built native*. If build and target are the same, but host is different, you are using a cross compiler to build a cross compiler that produces code for the machine you're building on. This is rare, so there is no common way of describing it. There is a proposal to call this a *crossback*.

If build and host are the same, the GCC you are building will also be used to build the target libraries (like libstdc++). If build and host are different, you must have already build and installed a cross compiler that will be used to build the target libraries (if you configured with '--target=foo-bar', this compiler will be called foo-bar-gcc).

In the case of target libraries, the machine you're building for is the machine you specified with '--target'. So, build is the machine you're building on (no change there), host is the machine you're building for (the target libraries are built for the target, so host is the target you specified), and target doesn't apply (because you're not building a compiler, you're building libraries). The configure/make process will adjust these variables as needed. It also sets \$with_cross_host to the original '--host' value in case you need it.

The libiberty support library is built up to three times: once for the host, once for the target (even if they are the same), and once for the build if build and host are different. This allows it to be used by all programs which are generated in the course of the build process.

6.2 Top Level Source Directory

The top level source directory in a GCC distribution contains several files and directories that are shared with other software distributions such as that of GNU Binutils. It also contains several subdirectories that contain parts of GCC and its runtime libraries:

'boehm-gc'

The Boehm conservative garbage collector, used as part of the Java runtime library.

'contrib' Contributed scripts that may be found useful in conjunction with GCC. One of these, 'contrib/texi2pod.pl', is used to generate man pages from Texinfo manuals as part of the GCC build process.

'fastjar' An implementation of the jar command, used with the Java front end.

'gcc' The main sources of GCC itself (except for runtime libraries), including optimizers, support for different target architectures, language front ends, and testsuites. See Section 6.3 [The 'gcc' Subdirectory], page 20, for details.

'include' Headers for the libiberty library.

'libada' The Ada runtime library.

'libcpp' The C preprocessor library.

'libgfortran'

The Fortran runtime library.

'libffi' The libffi library, used as part of the Java runtime library.

'libiberty'

The libiberty library, used for portability and for some generally useful data structures and algorithms. See section "Introduction" in GNU libiberty, for more information about this library.

'libjava' The Java runtime library.

'libmudflap'

The libmudflap library, used for instrumenting pointer and array dereferencing operations.

'libobjc' The Objective-C and Objective-C++ runtime library.

'libstdc++-v3'

The C++ runtime library.

'maintainer-scripts'

Scripts used by the gccadmin account on gcc.gnu.org.

'zlib' The zlib compression library, used by the Java front end and as part of the Java runtime library.

The build system in the top level directory, including how recursion into subdirectories works and how building runtime libraries for multilibs is handled, is documented in a separate manual, included with GNU Binutils. See section "GNU configure and build system" in *The GNU configure and build system*, for details.

6.3 The 'gcc' Subdirectory

The 'gcc' directory contains many files that are part of the C sources of GCC, other files used as part of the configuration and build process, and subdirectories including documentation and a testsuite. The files that are sources of GCC are documented in a separate chapter. See Chapter 7 [Passes and Files of the Compiler], page 45.

6.3.1 Subdirectories of 'gcc'

The 'gcc' directory contains the following subdirectories:

'language'

Subdirectories for various languages. Directories containing a file 'config-lang.in' are language subdirectories. The contents of the subdirectories 'cp' (for C++), 'objc' (for Objective-C) and 'objcp' (for Objective-C++) are documented in this manual (see Chapter 7 [Passes and Files of the Compiler], page 45); those for other languages are not. See Section 6.3.8 [Anatomy of a Language Front End], page 28, for details of the files in these directories.

'config' Configuration files for supported architectures and operating systems. See Section 6.3.9 [Anatomy of a Target Back End], page 32, for details of the files in this directory.

'doc' Texinfo documentation for GCC, together with automatically generated man pages and support for converting the installation manual to HTML. See Section 6.3.7 [Documentation], page 26.

'fixinc' The support for fixing system headers to work with GCC. See 'fixinc/README' for more information. The headers fixed by this mechanism are installed in 'libsubdir/include'. Along with those headers, 'README-fixinc' is also installed, as 'libsubdir/include/README'.

'ginclude'

System headers installed by GCC, mainly those required by the C standard of freestanding implementations. See Section 6.3.6 [Headers Installed by GCC], page 25, for details of when these and other headers are installed.

'intl' GNU libintl, from GNU gettext, for systems which do not include it in libc.

Properly, this directory should be at top level, parallel to the 'gcc' directory.

'po' Message catalogs with translations of messages produced by GCC into various languages, 'language.po'. This directory also contains 'gcc.pot', the template for these message catalogues, 'exgettext', a wrapper around gettext to extract the messages from the GCC sources and create 'gcc.pot', which is run by 'make gcc.pot', and 'EXCLUDES', a list of files from which messages should not be extracted.

'testsuite'

The GCC testsuites (except for those for runtime libraries). See Section 6.4 [Testsuites], page 33.

6.3.2 Configuration in the 'gcc' Directory

The 'gcc' directory is configured with an Autoconf-generated script 'configure'. The 'configure' script is generated from 'configure.ac' and 'aclocal.m4'. From the files 'configure.ac' and 'acconfig.h', Autoheader generates the file 'config.in'. The file 'cstamp-h.in' is used as a timestamp.

6.3.2.1 Scripts Used by 'configure'

'configure' uses some other scripts to help in its work:

- The standard GNU 'config.sub' and 'config.guess' files, kept in the top level directory, are used. FIXME: when is the 'config.guess' file in the 'gcc' directory (that just calls the top level one) used?
- The file 'config.gcc' is used to handle configuration specific to the particular target machine. The file 'config.build' is used to handle configuration specific to the particular build machine. The file 'config.host' is used to handle configuration specific to the particular host machine. (In general, these should only be used for features that cannot reasonably be tested in Autoconf feature tests.) See Section 6.3.2.2 [The 'config.build'; 'config.host'; and 'config.gcc' Files], page 22, for details of the contents of these files.
- Each language subdirectory has a file 'language/config-lang.in' that is used for front-end-specific configuration. See Section 6.3.8.2 [The Front End 'config-lang.in' File], page 31, for details of this file.
- A helper script 'configure .frag' is used as part of creating the output of 'configure'.

6.3.2.2 The 'config.build'; 'config.host'; and 'config.gcc' Files

The 'config.build' file contains specific rules for particular systems which GCC is built on. This should be used as rarely as possible, as the behavior of the build system can always be detected by autoconf.

The 'config.host' file contains specific rules for particular systems which GCC will run on. This is rarely needed.

The 'config.gcc' file contains specific rules for particular systems which GCC will generate code for. This is usually needed.

Each file has a list of the shell variables it sets, with descriptions, at the top of the file.

FIXME: document the contents of these files, and what variables should be set to control build, host and target configuration.

6.3.2.3 Files Created by configure

Here we spell out what files will be set up by 'configure' in the 'gcc' directory. Some other files are created as temporary files in the configuration process, and are not used in the subsequent build; these are not documented.

- 'Makefile' is constructed from 'Makefile.in', together with the host and target fragments (see Chapter 15 [Makefile Fragments], page 389) 't-target' and 'x-host' from 'config', if any, and language Makefile fragments 'language/Make-lang.in'.
- 'auto-host.h' contains information about the host machine determined by 'configure'. If the host machine is different from the build machine, then 'auto-build.h' is also created, containing such information about the build machine.
- 'config.status' is a script that may be run to recreate the current configuration.
- 'configargs.h' is a header containing details of the arguments passed to 'configure' to configure GCC, and of the thread model used.
- 'cstamp-h' is used as a timestamp.

- 'fixinc/Makefile' is constructed from 'fixinc/Makefile.in'.
- 'gccbug', a script for reporting bugs in GCC, is constructed from 'gccbug.in'.
- 'intl/Makefile' is constructed from 'intl/Makefile.in'.
- 'mklibgcc', a shell script to create a Makefile to build libgcc, is constructed from 'mklibgcc.in'.
- If a language 'config-lang.in' file (see Section 6.3.8.2 [The Front End 'config-lang.in' File], page 31) sets outputs, then the files listed in outputs there are also generated.

The following configuration headers are created from the Makefile, using 'mkconfig.sh', rather than directly by 'configure'. 'config.h', 'bconfig.h' and 'tconfig.h' all contain the 'xm-machine.h' header, if any, appropriate to the host, build and target machines respectively, the configuration headers for the target, and some definitions; for the host and build machines, these include the autoconfigured headers generated by 'configure'. The other configuration headers are determined by 'config.gcc'. They also contain the typedefs for rtx, rtvec and tree.

- 'config.h', for use in programs that run on the host machine.
- 'bconfig.h', for use in programs that run on the build machine.
- 'tconfig.h', for use in programs and libraries for the target machine.
- 'tm_p.h', which includes the header 'machine-protos.h' that contains prototypes for functions in the target '.c' file. FIXME: why is such a separate header necessary?

6.3.3 Build System in the 'gcc' Directory

FIXME: describe the build system, including what is built in what stages. Also list the various source files that are used in the build process but aren't source files of GCC itself and so aren't documented below (see Chapter 7 [Passes], page 45).

6.3.4 Makefile Targets

This is the default target. Depending on what your build/host/target configuration is, it coordinates all the things that need to be built.

doc Produce info-formatted documentation and man pages. Essentially it calls 'make man' and 'make info'.

dvi Produce DVI-formatted documentation.

html Produce HTML-formatted documentation.

man Generate man pages.

info Generate info-formatted pages.

mostlyclean

Delete the files made while building the compiler.

clean That, and all the other files built by 'make all'.

distclean

That, and all the files created by configure.

maintainer-clean

Distclean plus any file that can be generated from other files. Note that additional tools may be required beyond what is normally needed to build gcc.

Generates files in the source directory that do not exist in CVS but should go into a release tarball. One example is 'gcc/java/parse.c' which is generated from the CVS source file 'gcc/java/parse.y'.

srcinfo

Srcman Copies the info-formatted and manpage documentation into the source directory usually for the purpose of generating a release tarball.

install Installs gcc.

uninstall

Deletes installed files.

Run the testsuite. This creates a 'testsuite' subdirectory that has various '.sum' and '.log' files containing the results of the testing. You can run subsets with, for example, 'make check-gcc'. You can specify specific tests by setting RUNTESTFLAGS to be the name of the '.exp' file, optionally followed by (for some tests) an equals and a file wildcard, like:

make check-gcc RUNTESTFLAGS="execute.exp=19980413-*"

Note that running the testsuite may require additional tools be installed, such as TCL or dejagnu.

bootstrap

Builds GCC three times—once with the native compiler, once with the native-built compiler it just built, and once with the compiler it built the second time. In theory, the last two should produce the same results, which 'make compare' can check. Each step of this process is called a "stage", and the results of each stage N (N = 1...3) are copied to a subdirectory 'stage N/'.

bootstrap-lean

Like bootstrap, except that the various stages are removed once they're no longer needed. This saves disk space.

bubblestrap

This incrementally rebuilds each of the three stages, one at a time. It does this by "bubbling" the stages up from their subdirectories (if they had been built previously), rebuilding them, and copying them back to their subdirectories. This will allow you to, for example, continue a bootstrap after fixing a bug which causes the stage2 build to crash.

quickstrap

Rebuilds the most recently built stage. Since each stage requires special invocation, using this target means you don't have to keep track of which stage you're on or what invocation that stage needs.

cleanstrap

Removed everything ('make clean') and rebuilds ('make bootstrap').

restrap Like cleanstrap, except that the process starts from the first stage build, not from scratch.

stageN (N = 1...4)

For each stage, moves the appropriate files to the 'stageN' subdirectory.

unstageN (N = 1...4)

Undoes the corresponding stage N.

restageN (N = 1...4)

Undoes the corresponding stage N and rebuilds it with the appropriate flags.

compare Compares the results of stages 2 and 3. This ensures that the compiler is running properly, since it should produce the same object files regardless of how it itself was compiled.

profiledbootstrap

Builds a compiler with profiling feedback information. For more information, see section "Building with profile feedback" in *Installing GCC*. This is actually a target in the top-level directory, which then recurses into the 'gcc' subdirectory multiple times.

6.3.5 Library Source Files and Headers under the 'gcc' Directory

FIXME: list here, with explanation, all the C source files and headers under the 'gcc' directory that aren't built into the GCC executable but rather are part of runtime libraries and object files, such as 'crtstuff.c' and 'unwind-dw2.c'. See Section 6.3.6 [Headers Installed by GCC], page 25, for more information about the 'ginclude' directory.

6.3.6 Headers Installed by GCC

In general, GCC expects the system C library to provide most of the headers to be used with it. However, GCC will fix those headers if necessary to make them work with GCC, and will install some headers required of freestanding implementations. These headers are installed in 'libsubdir/include'. Headers for non-C runtime libraries are also installed by GCC; these are not documented here. (FIXME: document them somewhere.)

Several of the headers GCC installs are in the 'ginclude' directory. These headers, 'iso646.h', 'stdarg.h', 'stdbool.h', and 'stddef.h', are installed in 'libsub-dir/include', unless the target Makefile fragment (see Section 15.1 [Target Fragment], page 389) overrides this by setting USER_H.

In addition to these headers and those generated by fixing system headers to work with GCC, some other headers may also be installed in 'libsubdir/include'. 'config.gcc' may set extra_headers; this specifies additional headers under 'config' to be installed on some systems.

GCC installs its own version of <float.h>, from 'ginclude/float.h'. This is done to cope with command-line options that change the representation of floating point numbers.

GCC also installs its own version of <limits.h>; this is generated from 'glimits.h', together with 'limitx.h' and 'limity.h' if the system also has its own version of <limits.h>. (GCC provides its own header because it is required of ISO C freestanding implementations, but needs to include the system header from its own header as well because other standards such as POSIX specify additional values to be defined in <limits.h>.) The system's limits.h> header is used via 'libsubdir/include/syslimits.h', which is copied from 'gsyslimits.h' if it does not need fixing to work with GCC; if it needs fixing, 'syslimits.h' is the fixed copy.

6.3.7 Building Documentation

The main GCC documentation is in the form of manuals in Texinfo format. These are installed in Info format, and DVI versions may be generated by 'make dvi' and HTML versions may be generated by make html. In addition, some man pages are generated from the Texinfo manuals, there are some other text files with miscellaneous documentation, and runtime libraries have their own documentation outside the 'gcc' directory. FIXME: document the documentation for runtime libraries somewhere.

6.3.7.1 Texinfo Manuals

The manuals for GCC as a whole, and the C and C++ front ends, are in files 'doc/*.texi'. Other front ends have their own manuals in files 'language/*.texi'. Common files 'doc/include/*.texi' are provided which may be included in multiple manuals; the following files are in 'doc/include':

'fdl.texi'

The GNU Free Documentation License.

'funding.texi'

The section "Funding Free Software".

'gcc-common.texi'

Common definitions for manuals.

'gpl.texi'

The GNU General Public License.

'texinfo.tex'

A copy of 'texinfo.tex' known to work with the GCC manuals.

DVI formatted manuals are generated by 'make dvi', which uses texi2dvi (via the Makefile macro \$(TEXI2DVI)). HTML formatted manuals are generated by make html. Info manuals are generated by 'make info' (which is run as part of a bootstrap); this generates the manuals in the source directory, using makeinfo via the Makefile macro \$(MAKEINFO), and they are included in release distributions.

Manuals are also provided on the GCC web site, in both HTML and PostScript forms. This is done via the script 'maintainer-scripts/update_web_docs'. Each manual to be provided online must be listed in the definition of MANUALS in that file; a file 'name.texi' must only appear once in the source tree, and the output manual must have the same name as the source file. (However, other Texinfo files, included in manuals but not themselves the root files of manuals, may have names that appear more than once in the source tree.) The manual file 'name.texi' should only include other files in its own directory or in 'doc/include'. HTML manuals will be generated by 'makeinfo --html' and PostScript manuals by texi2dvi and dvips. All Texinfo files that are parts of manuals must be checked into CVS, even if they are generated files, for the generation of online manuals to work.

The installation manual, 'doc/install.texi', is also provided on the GCC web site. The HTML version is generated by the script 'doc/install.texi2html'.

6.3.7.2 Man Page Generation

Because of user demand, in addition to full Texinfo manuals, man pages are provided which contain extracts from those manuals. These man pages are generated from the Texinfo manuals using 'contrib/texi2pod.pl' and pod2man. (The man page for g++, 'cp/g++.1', just contains a '.so' reference to 'gcc.1', but all the other man pages are generated from Texinfo manuals.)

Because many systems may not have the necessary tools installed to generate the man pages, they are only generated if the 'configure' script detects that recent enough tools are installed, and the Makefiles allow generating man pages to fail without aborting the build. Man pages are also included in release distributions. They are generated in the source directory.

Magic comments in Texinfo files starting '@c man' control what parts of a Texinfo file go into a man page. Only a subset of Texinfo is supported by 'texi2pod.pl', and it may be necessary to add support for more Texinfo features to this script when generating new man pages. To improve the man page output, some special Texinfo macros are provided in 'doc/include/gcc-common.texi' which 'texi2pod.pl' understands:

@gcctabopt

Use in the form '@table @gcctabopt' for tables of options, where for printed output the effect of '@code' is better than that of '@option' but for man page output a different effect is wanted.

@gccoptlist

Use for summary lists of options in manuals.

Use at the end of each line inside '@gccoptlist'. This is necessary to avoid problems with differences in how the '@gccoptlist' macro is handled by different Texinfo formatters.

FIXME: describe the 'texi2pod.pl' input language and magic comments in more detail.

6.3.7.3 Miscellaneous Documentation

In addition to the formal documentation that is installed by GCC, there are several other text files with miscellaneous documentation:

'ABOUT-GCC-NLS'

Notes on GCC's Native Language Support. FIXME: this should be part of this manual rather than a separate file.

'ABOUT-NLS'

Notes on the Free Translation Project.

'COPYING' The GNU General Public License.

'COPYING.LIB'

The GNU Lesser General Public License.

- '*ChangeLog*'
- '*/ChangeLog*'

Change log files for various parts of GCC.

'LANGUAGES'

Details of a few changes to the GCC front-end interface. FIXME: the information in this file should be part of general documentation of the front-end interface in this manual.

'ONEWS' Information about new features in old versions of GCC. (For recent versions, the information is on the GCC web site.)

'README.Portability'

Information about portability issues when writing code in GCC. FIXME: why isn't this part of this manual or of the GCC Coding Conventions?

'SERVICE' A pointer to the GNU Service Directory.

FIXME: document such files in subdirectories, at least 'config', 'cp', 'objc', 'testsuite'.

6.3.8 Anatomy of a Language Front End

A front end for a language in GCC has the following parts:

- A directory 'language' under 'gcc' containing source files for that front end. See Section 6.3.8.1 [The Front End 'language' Directory], page 29, for details.
- A mention of the language in the list of supported languages in 'gcc/doc/install.texi'.
- A mention of the name under which the language's runtime library is recognized by '--enable-shared=package' in the documentation of that option in 'gcc/doc/install.texi'.
- A mention of any special prerequisites for building the front end in the documentation of prerequisites in 'gcc/doc/install.texi'.
- Details of contributors to that front end in 'gcc/doc/contrib.texi'. If the details are in that front end's own manual then there should be a link to that manual's list in 'contrib.texi'.
- Information about support for that language in 'gcc/doc/frontends.texi'.
- Information about standards for that language, and the front end's support for them, in 'gcc/doc/standards.texi'. This may be a link to such information in the front end's own manual.
- Details of source file suffixes for that language and '-x lang' options supported, in 'gcc/doc/invoke.texi'.
- Entries in default_compilers in 'gcc.c' for source file suffixes for that language.
- Preferably testsuites, which may be under 'gcc/testsuite' or runtime library directories. FIXME: document somewhere how to write testsuite harnesses.
- Probably a runtime library for the language, outside the 'gcc' directory. FIXME: document this further.
- Details of the directories of any runtime libraries in 'gcc/doc/sourcebuild.texi'.

If the front end is added to the official GCC CVS repository, the following are also necessary:

• At least one Bugzilla component for bugs in that front end and runtime libraries. This category needs to be mentioned in 'gcc/gccbug.in', as well as being added to the Bugzilla database.

- Normally, one or more maintainers of that front end listed in 'MAINTAINERS'.
- Mentions on the GCC web site in 'index.html' and 'frontends.html', with any relevant links on 'readings.html'. (Front ends that are not an official part of GCC may also be listed on 'frontends.html', with relevant links.)
- A news item on 'index.html', and possibly an announcement on the gcc-announce@gcc.gnu.org mailing list.
- The front end's manuals should be mentioned in 'maintainer-scripts/update_web_docs' (see Section 6.3.7.1 [Texinfo Manuals], page 26) and the online manuals should be linked to from 'onlinedocs/index.html'.
- Any old releases or CVS repositories of the front end, before its inclusion in GCC, should be made available on the GCC FTP site ftp://gcc.gnu.org/pub/gcc/old-releases/.
- The release and 'maintainer-scripts/gcc_release' snapshot generate should be updated appropriate tarballs The 'maintainer-scripts/snapshot-README' end. associated 'maintainer-scripts/snapshot-index.html' files should be updated to list the tarballs and diffs for this front end.
- If this front end includes its own version files that include the current date, 'maintainer-scripts/update_version' should be updated accordingly.
- 'CVSROOT/modules' in the GCC CVS repository should be updated.

6.3.8.1 The Front End 'language' Directory

A front end 'language' directory contains the source files of that front end (but not of any runtime libraries, which should be outside the 'gcc' directory). This includes documentation, and possibly some subsidiary programs build alongside the front end. Certain files are special and other parts of the compiler depend on their names:

'config-lang.in'

This file is required in all language subdirectories. See Section 6.3.8.2 [The Front End 'config-lang.in' File], page 31, for details of its contents

'Make-lang.in'

This file is required in all language subdirectories. It contains targets lang.hook (where lang is the setting of language in 'config-lang.in') for the following values of hook, and any other Makefile rules required to build those targets (which may if necessary use other Makefiles specified in outputs in 'config-lang.in', although this is deprecated). Some hooks are defined by using a double-colon rule for hook, rather than by using a target of form lang.hook. These hooks are called "double-colon hooks" below. It also adds any testsuite targets that can use the standard rule in 'gcc/Makefile.in' to the variable lang_checks.

all.build
all.cross
start.encap
rest.encap

FIXME: exactly what goes in each of these targets?

tags Build an etags 'TAGS' file in the language subdirectory in the source tree.

info Build info documentation for the front end, in the build directory. This target is only called by 'make bootstrap' if a suitable version of makeinfo is available, so does not need to check for this, and should fail if an error occurs.

dvi Build DVI documentation for the front end, in the build directory. This should be done using \$(TEXI2DVI), with appropriate '-I' arguments pointing to directories of included files. This hook is a double-colon hook.

html Build HTML documentation for the front end, in the build directory.

Build generated man pages for the front end from Texinfo manuals (see Section 6.3.7.2 [Man Page Generation], page 27), in the build directory. This target is only called if the necessary tools are available, but should ignore errors so as not to stop the build if errors occur; man pages are optional and the tools involved may be installed in a broken way.

install-normal

FIXME: what is this target for?

install-common

Install everything that is part of the front end, apart from the compiler executables listed in compilers in 'config-lang.in'.

install-info

Install info documentation for the front end, if it is present in the source directory. This target should have dependencies on info files that should be installed. This hook is a double-colon hook.

install-man

Install man pages for the front end. This target should ignore errors.

srcextra Copies its dependencies into the source directory. This generally should be used for generated files such as Bison output files which are not present in CVS, but should be included in any release tarballs. This target will be executed during a bootstrap if '--enable-generated-files-in-srcdir' was specified as a 'configure' option.

srcinfo

srcman Copies its dependencies into the source directory. These targets will be executed during a bootstrap if '--enable-generated-files-in-srcdir' was specified as a 'configure' option.

uninstall

Uninstall files installed by installing the compiler. This is currently documented not to be supported, so the hook need not do anything.

```
mostlyclean
clean
distclean
maintainer-clean
```

The language parts of the standard GNU '*clean' targets. See section "Standard Targets for Users" in GNU Coding Standards, for details of the standard targets. For GCC, maintainer-clean should delete all generated files in the source directory that are not checked into CVS, but should not delete anything checked into CVS.

```
stage1
stage2
stage3
stage4
stageprofile
stagefeedback
```

Move to the stage directory files not included in stagestuff in 'config-lang.in' or otherwise moved by the main 'Makefile'.

'lang.opt'

This file registers the set of switches that the front end accepts on the command line, and their '--help' text. The file format is documented in the file 'c.opt'. These files are processed by the script 'opts.sh'.

'lang-specs.h'

This file provides entries for default_compilers in 'gcc.c' which override the default of giving an error that a compiler for that language is not installed.

'language-tree.def'

This file, which need not exist, defines any language-specific tree codes.

6.3.8.2 The Front End 'config-lang.in' File

Each language subdirectory contains a 'config-lang.in' file. In addition the main directory contains 'c-config-lang.in', which contains limited information for the C language. This file is a shell script that may define some variables describing the language:

language This definition must be present, and gives the name of the language for some purposes such as arguments to '--enable-languages'.

lang_requires

If defined, this variable lists (space-separated) language front ends other than C that this front end requires to be enabled (with the names given being their language settings). For example, the Java front end depends on the C++ front end, so sets 'lang_requires=c++'.

target_libs

If defined, this variable lists (space-separated) targets in the top level 'Makefile' to build the runtime libraries for this language, such as target-libobjc.

lang_dirs

If defined, this variable lists (space-separated) top level directories (parallel to 'gcc'), apart from the runtime libraries, that should not be configured if this front end is not built.

build_by_default

If defined to 'no', this language front end is not built unless enabled in a '--enable-languages' argument. Otherwise, front ends are built by default, subject to any special logic in 'configure.ac' (as is present to disable the Ada front end if the Ada compiler is not already installed).

boot_language

If defined to 'yes', this front end is built in stage 1 of the bootstrap. This is only relevant to front ends written in their own languages.

compilers

If defined, a space-separated list of compiler executables that will be run by the driver. The names here will each end with '\\$(exext)'.

stagestuff

If defined, a space-separated list of files that should be moved to the 'stagen' directories in each stage of bootstrap.

outputs If defined, a space-separated list of files that should be generated by 'configure' substituting values in them. This mechanism can be used to create a file 'language/Makefile' from 'language/Makefile.in', but this is deprecated, building everything from the single 'gcc/Makefile' is preferred.

gtfiles If defined, a space-separated list of files that should be scanned by gengtype.c to generate the garbage collection tables and routines for this language. This excludes the files that are common to all front ends. See Chapter 18 [Type Information], page 397.

need_gmp If defined to 'yes', this frontend requires the GMP library. Enables configure tests for GMP, which set GMPLIBS and GMPINC appropriately.

6.3.9 Anatomy of a Target Back End

A back end for a target architecture in GCC has the following parts:

- A directory 'machine' under 'gcc/config', containing a machine description 'machine.md' file (see Chapter 12 [Machine Descriptions], page 165), header files 'machine.h' and 'machine-protos.h' and a source file 'machine.c' (see Chapter 13 [Target Description Macros and Functions], page 247), possibly a target Makefile fragment 't-machine' (see Section 15.1 [The Target Makefile Fragment], page 389), and maybe some other files. The names of these files may be changed from the defaults given by explicit specifications in 'config.gcc'.
- If necessary, a file 'machine-modes.def' in the 'machine' directory, containing additional machine modes to represent condition codes. See Section 13.15 [Condition Code], page 320, for further details.

- Entries in 'config.gcc' (see Section 6.3.2.2 [The 'config.gcc' File], page 22) for the systems with this target architecture.
- Documentation in 'gcc/doc/invoke.texi' for any command-line options supported by this target (see Section 13.3 [Run-time Target Specification], page 255). This means both entries in the summary table of options and details of the individual options.
- Documentation in 'gcc/doc/extend.texi' for any target-specific attributes supported (see Section 13.24 [Defining target-specific uses of __attribute__], page 368), including where the same attribute is already supported on some targets, which are enumerated in the manual.
- Documentation in 'gcc/doc/extend.texi' for any target-specific pragmas supported.
- Documentation in 'gcc/doc/extend.texi' of any target-specific built-in functions supported.
- Documentation in 'gcc/doc/extend.texi' of any target-specific format checking styles supported.
- Documentation in 'gcc/doc/md.texi' of any target-specific constraint letters (see Section 12.8.5 [Constraints for Particular Machines], page 184).
- A note in 'gcc/doc/contrib.texi' under the person or people who contributed the target support.
- Entries in 'gcc/doc/install.texi' for all target triplets supported with this target architecture, giving details of any special notes about installation for this target, or saying that there are no special notes if there are none.
- Possibly other support outside the 'gcc' directory for runtime libraries. FIXME: reference docs for this. The libstdc++ porting manual needs to be installed as info for this to work, or to be a chapter of this manual.

If the back end is added to the official GCC CVS repository, the following are also necessary:

- An entry for the target architecture in 'readings.html' on the GCC web site, with any relevant links.
- Details of the properties of the back end and target architecture in 'backends.html' on the GCC web site.
- A news item about the contribution of support for that target architecture, in 'index.html' on the GCC web site.
- Normally, one or more maintainers of that target listed in 'MAINTAINERS'. Some existing architectures may be unmaintained, but it would be unusual to add support for a target that does not have a maintainer when support is added.

6.4 Testsuites

GCC contains several testsuites to help maintain compiler quality. Most of the runtime libraries and language front ends in GCC have testsuites. Currently only the C language testsuites are documented here; FIXME: document the others.

6.4.1 Idioms Used in Testsuite Code

In general C testcases have a trailing '-n.c', starting with '-1.c', in case other testcases with similar names are added later. If the test is a test of some well-defined feature, it

should have a name referring to that feature such as 'feature-1.c'. If it does not test a well-defined feature but just happens to exercise a bug somewhere in the compiler, and a bug report has been filed for this bug in the GCC bug database, 'prbug-number-1.c' is the appropriate form of name. Otherwise (for miscellaneous bugs not filed in the GCC bug database), and previously more generally, test cases are named after the date on which they were added. This allows people to tell at a glance whether a test failure is because of a recently found bug that has not yet been fixed, or whether it may be a regression, but does not give any other information about the bug or where discussion of it may be found. Some other language testsuites follow similar conventions.

In the 'gcc.dg' testsuite, it is often necessary to test that an error is indeed a hard error and not just a warning—for example, where it is a constraint violation in the C standard, which must become an error with '-pedantic-errors'. The following idiom, where the first line shown is line line of the file and the line that generates the error, is used for this:

```
/* { dg-bogus "warning" "warning in place of error" } */
/* { dg-error "regexp" "message" { target *-*-* } line } */
```

It may be necessary to check that an expression is an integer constant expression and has a certain value. To check that E has value V, an idiom similar to the following is used:

```
char x[((E) == (V) ? 1 : -1)];
```

In 'gcc.dg' tests, __typeof__ is sometimes used to make assertions about the types of expressions. See, for example, 'gcc.dg/c99-condexpr-1.c'. The more subtle uses depend on the exact rules for the types of conditional expressions in the C standard; see, for example, 'gcc.dg/c99-intconst-1.c'.

It is useful to be able to test that optimizations are being made properly. This cannot be done in all cases, but it can be done where the optimization will lead to code being optimized away (for example, where flow analysis or alias analysis should show that certain code cannot be called) or to functions not being called because they have been expanded as built-in functions. Such tests go in 'gcc.c-torture/execute'. Where code should be optimized away, a call to a nonexistent function such as link_failure () may be inserted; a definition

```
#ifndef __OPTIMIZE__
void
link_failure (void)
{
   abort ();
}
#endif
```

will also be needed so that linking still succeeds when the test is run without optimization. When all calls to a built-in function should have been optimized and no calls to the non-built-in version of the function should remain, that function may be defined as static to call abort () (although redeclaring a function as static may not work on all targets).

All testcases must be portable. Target-specific testcases must have appropriate code to avoid causing failures on unsupported systems; unfortunately, the mechanisms for this differ by directory.

FIXME: discuss non-C testsuites here.

6.4.2 Directives used within DejaGnu tests

Test directives appear within comments in a test source file and begin with dg-. Some of these are defined within DegaGnu and others are local to the GCC testsuite.

The order in which test directives appear in a test can be important: directives local to GCC sometimes override information used by the DejaGnu directives, which know nothing about the GCC directives, so the DejaGnu directives must precede GCC directives.

Several test directives include selectors which are usually preceded by the keyword target or xfail. A selector is one or more target triplets, possibly including wildcard characters, or else a single effective-target keyword. Depending on the context, the selector specifies whether a test is skipped and reported as unsupported or is expected to fail. Use '*-*-*' to match any target.

Effective-target keywords are defined in 'target-supports.exp' in the GCC testsuite or, in the case of unusual effective targets that are used only for a limited number of tests, in '.exp' files in the same directory as the tests. There is no mechanism to combine or negate effective-target keywords.

{ dg-do do-what-keyword [{ target/xfail selector }] }

do-what-keyword specifies how the test is compiled and whether it is executed. It is one of:

preprocess

Compile with '-E' to run only the preprocessor.

assemble Compile with '-S' to produce an assembly code file.

compile Compile with '-c' to produce a relocatable object file.

link Compile, assemble, and link to produce an executable file.

run Produce and run an executable file, which is expected to return an exit code of 0.

The default is compile. That can be overridden for a set of tests by redefining dg-do-what-default within the .exp file for those tests.

If the directive includes the optional '{ target selector }' then the test is skipped unless the target system is included in the list of target triplets or matches the effective-target keyword.

If the directive includes the optional '{ xfail selector }' and the selector is met then the test is expected to fail. For dg-do run, execution is expected to fail but compilation is expected to pass.

{ dg-options options [{ target selector }] }

This DejaGnu directive provides a list of compiler options, to be used if the target system matches *selector*, that replace the default options used for this set of tests.

{ dg-skip-if comment { selector } { include-opts } { exclude-opts } }

Skip the test if the test system is included in *selector* and if each of the options in *include-opts* is in the set of options with which the test would be compiled and if none of the options in *exclude-opts* is in the set of options with which the test would be compiled.

Use "*" for an empty include-opts list and "", for an empty exclude-opts list.

{ dg-xfail-if comment { selector } { include-opts } { exclude-opts } }

Expect the test to fail if the conditions (which are the same as for dg-skip-if) are met.

{ dg-require-support args }

Skip the test if the target does not provide the required support; see 'gcc-dg.exp' in the GCC testsuite for the actual directives. These directives must appear after any dg-do directive in the test. They require at least one argument, which can be an empty string if the specific procedure does not examine the argument.

{ dg-require-effective-target keyword }

Skip the test if the test target, including current multilib flags, is not covered by the effective-target keyword. This directive must appear after any dg-do directive in the test.

{ dg-error regexp [comment [{ target/xfail selector } [line] }]] }

This DejaGnu directive appears on a source line that is expected to get an error message, or else specifies the source line associated with the message. If there is no message for that line or if the text of that message is not matched by regexp then the check fails and comment is included in the FAIL message. The check does not look for the string '"error" unless it is part of regexp.

{ dg-warning regexp [comment [{ target/xfail selector } [line] }]] }

This DejaGnu directive appears on a source line that is expected to get a warning message, or else specifies the source line associated with the message. If there is no message for that line or if the text of that message is not matched by regexp then the check fails and comment is included in the FAIL message. The check does not look for the string "warning" unless it is part of regexp.

{ dg-bogus regexp [comment [{ target/xfail selector } [line] }]] }

This DejaGnu directive appears on a source line that should not get a message matching regexp, or else specifies the source line associated with the bogus message. It is usually used with 'xfail' to indicate that the message is a known problem for a particular set of targets.

{ dg-excess-errors comment [{ target/xfail selector }] }

This DejaGnu directive indicates that the test is expected to fail due to compiler messages that are not handled by 'dg-error', 'dg-warning' or 'dg-bogus'.

{ dg-output regexp [{ target/xfail selector }] }

This DejaGnu directive compares regexp to the combined output that the test executable writes to 'stdout' and 'stderr'.

{ dg-prune-output regexp }

Prune messages matching regexp from test output.

{ dg-additional-files "filelist" }

Specify additional files, other than source files, that must be copied to the system where the compiler runs.

{ dg-additional-sources "filelist" }

Specify additional source files to appear in the compile line following the main test file.

{ dg-final { local-directive } }

This DejaGnu directive is placed within a comment anywhere in the source file and is processed after the test has been compiled and run. Multiple 'dg-final' commands are processed in the order in which they appear in the source file.

The GCC testsuite defines the following directives to be used within dg-final.

scan-file filename regexp [{ target/xfail selector }]

Passes if regexp matches text in filename.

scan-file-not filename regexp [{ target/xfail selector }]

Passes if regexp does not match text in filename.

scan-hidden symbol [{ target/xfail selector }]

Passes if symbol is defined as a hidden symbol in the test's assembly output.

scan-not-hidden symbol [{ target/xfail selector }]

Passes if *symbol* is not defined as a hidden symbol in the test's assembly output.

scan-assembler-times regex num [{ target/xfail selector }]

Passes if regex is matched exactly num times in the test's assembler output.

scan-assembler regex [{ target/xfail selector }]

Passes if regex matches text in the test's assembler output.

scan-assembler-not regex [{ target/xfail selector }]

Passes if regex does not match text in the test's assembler output.

scan-assembler-dem regex [{ target/xfail selector }]

Passes if regex matches text in the test's demangled assembler output.

scan-assembler-dem-not regex [{ target/xfail selector }]

Passes if regex does not match text in the test's demangled assembler output.

scan-tree-dump-times regex num suffix [{ target/xfail selector }]

Passes if regex is found exactly num times in the dump file with suffix suffix.

scan-tree-dump regex suffix [{ target/xfail selector }]

Passes if regex matches text in the dump file with suffix suffix.

scan-tree-dump-not regex suffix [{ target/xfail selector }]

Passes if regex does not match text in the dump file with suffix suffix.

scan-tree-dump-dem regex suffix [{ target/xfail selector }]

Passes if regex matches demangled text in the dump file with suffix suffix.

scan-tree-dump-dem-not regex suffix [{ target/xfail selector }]

Passes if regex does not match demangled text in the dump file with suffix suffix.

run-gcov sourcefile

Check line counts in gcov tests.

run-gcov [branches] [calls] { opts sourcefile }

Check branch and/or call counts, in addition to line counts, in gcov tests.

6.4.3 Ada Language Testsuites

The Ada testsuite includes executable tests from the ACATS 2.5 testsuite, publicly available at http://www.adaic.org/compilers/acats/2.5

These tests are integrated in the GCC testsuite in the 'gcc/testsuite/ada/acats' directory, and enabled automatically when running make check, assuming the Ada language has been enabled when configuring GCC.

You can also run the Ada testsuite independently, using make check-ada, or run a subset of the tests by specifying which chapter to run, e.g.:

```
$ make check-ada CHAPTERS="c3 c9"
```

The tests are organized by directory, each directory corresponding to a chapter of the Ada Reference Manual. So for example, c9 corresponds to chapter 9, which deals with tasking features of the language.

There is also an extra chapter called 'gcc' containing a template for creating new executable tests.

The tests are run using two sh scripts: 'run_acats' and 'run_all.sh'. To run the tests using a simulator or a cross target, see the small customization section at the top of 'run_all.sh'.

These tests are run using the build tree: they can be run without doing a make install.

6.4.4 C Language Testsuites

GCC contains the following C language testsuites, in the 'gcc/testsuite' directory:

'gcc.dg' This contains tests of particular features of the C compiler, using the more modern 'dg' harness. Correctness tests for various compiler features should go here if possible.

Magic comments determine whether the file is preprocessed, compiled, linked or run. In these tests, error and warning message texts are compared against expected texts or regular expressions given in comments. These tests are run with the options '-ansi -pedantic' unless other options are given in the test. Except as noted below they are not run with multiple optimization options.

'gcc.dg/compat'

This subdirectory contains tests for binary compatibility using 'compat.exp', which in turn uses the language-independent support (see Section 6.4.8 [Support for testing binary compatibility], page 42).

'gcc.dg/cpp'

This subdirectory contains tests of the preprocessor.

'gcc.dg/debug'

This subdirectory contains tests for debug formats. Tests in this subdirectory are run for each debug format that the compiler supports.

'gcc.dg/format'

This subdirectory contains tests of the '-Wformat' format checking. Tests in this directory are run with and without '-DWIDE'.

'gcc.dg/noncompile'

This subdirectory contains tests of code that should not compile and does not need any special compilation options. They are run with multiple optimization options, since sometimes invalid code crashes the compiler with optimization.

'gcc.dg/special'

FIXME: describe this.

'gcc.c-torture'

This contains particular code fragments which have historically broken easily. These tests are run with multiple optimization options, so tests for features which only break at some optimization levels belong here. This also contains tests to check that certain optimizations occur. It might be worthwhile to separate the correctness tests cleanly from the code quality tests, but it hasn't been done yet.

'gcc.c-torture/compat'

FIXME: describe this.

This directory should probably not be used for new tests.

'gcc.c-torture/compile'

This testsuite contains test cases that should compile, but do not need to link or run. These test cases are compiled with several different combinations of optimization options. All warnings are disabled for these test cases, so this directory is not suitable if you wish to test for the presence or absence of compiler warnings. While special options can be set, and tests disabled on specific platforms, by the use of '.x' files, mostly these test cases should not contain platform dependencies. FIXME: discuss how defines such as NO_LABEL_VALUES and STACK_SIZE are used.

'gcc.c-torture/execute'

This testsuite contains test cases that should compile, link and run; otherwise the same comments as for 'gcc.c-torture/compile' apply.

'gcc.c-torture/execute/ieee'

This contains tests which are specific to IEEE floating point.

'gcc.c-torture/unsorted'

FIXME: describe this.

This directory should probably not be used for new tests.

'gcc.c-torture/misc-tests'

This directory contains C tests that require special handling. Some of these tests have individual expect files, and others share special-purpose expect files:

'bprob*.c'

Test '-fbranch-probabilities' using 'bprob.exp', which in turn uses the generic, language-independent framework (see Section 6.4.7 [Support for testing profile-directed optimizations], page 41).

'dg-*.c' Test the testsuite itself using 'dg-test.exp'.

'gcov*.c' Test gcov output using 'gcov.exp', which in turn uses the language-independent support (see Section 6.4.6 [Support for testing gcov], page 40).

```
'i386-pf-*.c'

Test i386-specific support for data prefetch using 'i386-prefetch.exp'.
```

FIXME: merge in 'testsuite/README.gcc' and discuss the format of test cases and magic comments more.

6.4.5 The Java library testsuites.

Runtime tests are executed via 'make check' in the 'target/libjava/testsuite' directory in the build tree. Additional runtime tests can be checked into this testsuite.

Regression testing of the core packages in libgcj is also covered by the Mauve testsuite. The Mauve Project develops tests for the Java Class Libraries. These tests are run as part of libgcj testing by placing the Mauve tree within the libjava testsuite sources at 'libjava/testsuite/libjava.mauve/mauve', or by specifying the location of that tree when invoking 'make', as in 'make MAUVEDIR="/mauve check'.

To detect regressions, a mechanism in 'mauve.exp' compares the failures for a test run against the list of expected failures in 'libjava/testsuite/libjava.mauve/xfails' from the source hierarchy. Update this file when adding new failing tests to Mauve, or when fixing bugs in libgcj that had caused Mauve test failures.

The Jacks project provides a testsuite for Java compilers that can be used to test changes that affect the GCJ front end. This testsuite is run as part of Java testing by placing the Jacks tree within the the libjava testsuite sources at 'libjava/testsuite/libjava.jacks/jacks'.

We encourage developers to contribute test cases to Mauve and Jacks.

6.4.6 Support for testing gcov

Language-independent support for testing gcov, and for checking that branch profiling produces expected values, is provided by the expect file 'gcov.exp'. gcov tests also rely on procedures in 'gcc.dg.exp' to compile and run the test program. A typical gcov test contains the following DejaGnu commands within comments:

```
{ dg-options "-fprofile-arcs -ftest-coverage" }
{ dg-do run { target native } }
{ dg-final { run-gcov sourcefile } }
```

Checks of gcov output can include line counts, branch percentages, and call return percentages. All of these checks are requested via commands that appear in comments in the test's source file. Commands to check line counts are processed by default. Commands to check branch percentages and call return percentages are processed if the run-gcov command has arguments branches or calls, respectively. For example, the following specifies checking both, as well as passing '-b' to gcov:

```
{ dg-final { run-gcov branches calls { -b sourcefile } } }
```

A line count command appears within a comment on the source line that is expected to get the specified count and has the form count(cnt). A test should only check line counts for lines that will get the same count for any architecture.

Commands to check branch percentages (branch) and call return percentages (returns) are very similar to each other. A beginning command appears on or before the first of a range of lines that will report the percentage, and the ending command follows that range of lines. The beginning command can include a list of percentages, all of which are expected to be found within the range. A range is terminated by the next command of the same kind. A command branch(end) or returns(end) marks the end of a range without starting a new one. For example:

For a call return percentage, the value specified is the percentage of calls reported to return. For a branch percentage, the value is either the expected percentage or 100 minus that value, since the direction of a branch can differ depending on the target or the optimization level.

Not all branches and calls need to be checked. A test should not check for branches that might be optimized away or replaced with predicated instructions. Don't check for calls inserted by the compiler or ones that might be inlined or optimized away.

A single test can check for combinations of line counts, branch percentages, and call return percentages. The command to check a line count must appear on the line that will report that count, but commands to check branch percentages and call return percentages can bracket the lines that report them.

6.4.7 Support for testing profile-directed optimizations

The file 'profopt.exp' provides language-independent support for checking correct execution of a test built with profile-directed optimization. This testing requires that a test program be built and executed twice. The first time it is compiled to generate profile data, and the second time it is compiled to use the data that was generated during the first execution. The second execution is to verify that the test produces the expected results.

To check that the optimization actually generated better code, a test can be built and run a third time with normal optimizations to verify that the performance is better with the profile-directed optimizations. 'profopt.exp' has the beginnings of this kind of support.

'profopt.exp' provides generic support for profile-directed optimizations. Each set of tests that uses it provides information about a specific optimization:

```
tool tool being tested, e.g., gcc
```

```
profile_option
```

options used to generate profile data

feedback_option

options used to optimize using that profile data

prof_ext suffix of profile data files

PROFOPT_OPTIONS

list of options with which to run each test, similar to the lists for torture tests

6.4.8 Support for testing binary compatibility

The file 'compat.exp' provides language-independent support for binary compatibility testing. It supports testing interoperability of two compilers that follow the same ABI, or of multiple sets of compiler options that should not affect binary compatibility. It is intended to be used for testsuites that complement ABI testsuites.

A test supported by this framework has three parts, each in a separate source file: a main program and two pieces that interact with each other to split up the functionality being tested.

```
'testname_main.suffix'
```

Contains the main program, which calls a function in file 'testname_x.suffix'.

'testname_x.suffix'

Contains at least one call to a function in 'testname_y.suffix'.

'testname_v.suffix'

Shares data with, or gets arguments from, 'testname_x.suffix'.

Within each test, the main program and one functional piece are compiled by the GCC under test. The other piece can be compiled by an alternate compiler. If no alternate compiler is specified, then all three source files are all compiled by the GCC under test. You can specify pairs of sets of compiler options. The first element of such a pair specifies options used with the GCC under test, and the second element of the pair specifies options used with the alternate compiler. Each test is compiled with each pair of options.

'compat.exp' defines default pairs of compiler options. These can be overridden by defining the environment variable COMPAT_OPTIONS as:

```
COMPAT_OPTIONS="[list [list {tst1} {alt1}]
...[list {tstn} {altn}]]"
```

where tsti and alti are lists of options, with tsti used by the compiler under test and alti used by the alternate compiler. For example, with [list [list {-g-00} {-03}] [list {-fpic} {-fPIC -02}]], the test is first built with '-g -00' by the compiler under test and with '-03' by the alternate compiler. The test is built a second time using '-fpic' by the compiler under test and '-fPIC -02' by the alternate compiler.

An alternate compiler is specified by defining an environment variable to be the full pathname of an installed compiler; for C define ALT_CC_UNDER_TEST, and for C++ define ALT_CXX_UNDER_TEST. These will be written to the 'site.exp' file used by DejaGnu. The default is to build each test with the compiler under test using the first of each pair of compiler options from COMPAT_OPTIONS. When ALT_CC_UNDER_TEST or ALT_CXX_UNDER_TEST is same, each test is built using the compiler under test but with combinations of the options from COMPAT_OPTIONS.

To run only the C++ compatibility suite using the compiler under test and another version of GCC using specific compiler options, do the following from 'objdir/gcc':

```
rm site.exp
make -k \
   ALT_CXX_UNDER_TEST=${alt_prefix}/bin/g++ \
   COMPAT_OPTIONS="lists as shown above" \
   check-c++ \
   RUNTESTFLAGS="compat.exp"
```

A test that fails when the source files are compiled with different compilers, but passes when the files are compiled with the same compiler, demonstrates incompatibility of the generated code or runtime support. A test that fails for the alternate compiler but passes for the compiler under test probably tests for a bug that was fixed in the compiler under test but is present in the alternate compiler.

The binary compatibility tests support a small number of test framework commands that appear within comments in a test file.

dg-require-*

These commands can be used in 'testname_main.suffix' to skip the test if specific support is not available on the target.

dg-options

The specified options are used for compiling this particular source file, appended to the options from COMPAT_OPTIONS. When this command appears in 'testname_main.suffix' the options are also used to link the test program.

dg-xfail-if

This command can be used in a secondary source file to specify that compilation is expected to fail for particular options on particular targets.

7 Passes and Files of the Compiler

This chapter is dedicated to giving an overview of the optimization and code generation passes of the compiler. In the process, it describes some of the language front end interface, though this description is no where near complete.

7.1 Parsing pass

The language front end is invoked only once, via lang_hooks.parse_file, to parse the entire input. The language front end may use any intermediate language representation deemed appropriate. The C front end uses GENERIC trees (CROSSREF), plus a double handful of language specific tree codes defined in 'c-common.def'. The Fortran front end uses a completely different private representation.

At some point the front end must translate the representation used in the front end to a representation understood by the language-independent portions of the compiler. Current practice takes one of two forms. The C front end manually invokes the gimplifier (CROSS-REF) on each function, and uses the gimplifier callbacks to convert the language-specific tree nodes directly to GIMPLE (CROSSREF) before passing the function off to be compiled. The Fortran front end converts from a private representation to GENERIC, which is later lowered to GIMPLE when the function is compiled. Which route to choose probably depends on how well GENERIC (plus extensions) can be made to match up with the source language and necessary parsing data structures.

BUG: Gimplification must occur before nested function lowering, and nested function lowering must be done by the front end before passing the data off to cgraph.

TODO: Cgraph should control nested function lowering. It would only be invoked when it is certain that the outer-most function is used.

TODO: Cgraph needs a gimplify_function callback. It should be invoked when (1) it is certain that the function is used, (2) warning flags specified by the user require some amount of compilation in order to honor, (3) the language indicates that semantic analysis is not complete until gimplification occurs. Hum... this sounds overly complicated. Perhaps we should just have the front end gimplify always; in most cases it's only one function call.

The front end needs to pass all function definitions and top level declarations off to the middle-end so that they can be compiled and emitted to the object file. For a simple procedural language, it is usually most convenient to do this as each top level declaration or definition is seen. There is also a distinction to be made between generating functional code and generating complete debug information. The only thing that is absolutely required for functional code is that function and data definitions be passed to the middle-end. For complete debug information, function, data and type declarations should all be passed as well

In any case, the front end needs each complete top-level function or data declaration, and each data definition should be passed to rest_of_decl_compilation. Each complete type definition should be passed to rest_of_type_compilation. Each function definition should be passed to cgraph_finalize_function.

TODO: I know rest_of_compilation currently has all sorts of rtl-generation semantics. I plan to move all code generation bits (both tree and rtl) to compile_function. Should we hide cgraph from the front ends and move back to rest_of_compilation as the official

interface? Possibly we should rename all three interfaces such that the names match in some meaningful way and that is more descriptive than "rest_of".

The middle-end will, at its option, emit the function and data definitions immediately or queue them for later processing.

7.2 Gimplification pass

Gimplification is a whimsical term for the process of converting the intermediate representation of a function into the GIMPLE language (CROSSREF). The term stuck, and so words like "gimplification", "gimplify", "gimplifier" and the like are sprinkled throughout this section of code.

While a front end may certainly choose to generate GIMPLE directly if it chooses, this can be a moderately complex process unless the intermediate language used by the front end is already fairly simple. Usually it is easier to generate GENERIC trees plus extensions and let the language-independent gimplifier do most of the work.

The main entry point to this pass is gimplify_function_tree located in 'gimplify.c'. From here we process the entire function gimplifying each statement in turn. The main workhorse for this pass is gimplify_expr. Approximately everything passes through here at least once, and it is from here that we invoke the lang_hooks.gimplify_expr callback.

The callback should examine the expression in question and return GS_UNHANDLED if the expression is not a language specific construct that requires attention. Otherwise it should alter the expression in some way to such that forward progress is made toward producing valid GIMPLE. If the callback is certain that the transformation is complete and the expression is valid GIMPLE, it should return GS_ALL_DONE. Otherwise it should return GS_OK, which will cause the expression to be processed again. If the callback encounters an error during the transformation (because the front end is relying on the gimplification process to finish semantic checks), it should return GS_ERROR.

7.3 Pass manager

The pass manager is located in 'passes.c', 'tree-optimize.c' and 'tree-pass.h'. Its job is to run all of the individual passes in the correct order, and take care of standard bookkeeping that applies to every pass.

The theory of operation is that each pass defines a structure that represents everything we need to know about that pass—when it should be run, how it should be run, what intermediate language form or on-the-side data structures it needs. We register the pass to be run in some particular order, and the pass manager arranges for everything to happen in the correct order.

The actuality doesn't completely live up to the theory at present. Command-line switches and timevar_id_t enumerations must still be defined elsewhere. The pass manager validates constraints but does not attempt to (re-)generate data structures or lower intermediate language form based on the requirements of the next pass. Nevertheless, what is present is useful, and a far sight better than nothing at all.

TODO: describe the global variables set up by the pass manager, and a brief description of how a new pass should use it. I need to look at what info rtl passes use first...

7.4 Tree-SSA passes

The following briefly describes the tree optimization passes that are run after gimplification and what source files they are located in.

• Remove useless statements

This pass is an extremely simple sweep across the gimple code in which we identify obviously dead code and remove it. Here we do things like simplify if statements with constant conditions, remove exception handling constructs surrounding code that obviously cannot throw, remove lexical bindings that contain no variables, and other assorted simplistic cleanups. The idea is to get rid of the obvious stuff quickly rather than wait until later when it's more work to get rid of it. This pass is located in 'tree-cfg.c' and described by pass_remove_useless_stmts.

• Mudflap declaration registration

If mudflap (see section "-fmudflap -fmudflapth -fmudflapir" in *Using the GNU Compiler Collection (GCC)*) is enabled, we generate code to register some variable declarations with the mudflap runtime. Specifically, the runtime tracks the lifetimes of those variable declarations that have their addresses taken, or whose bounds are unknown at compile time (extern). This pass generates new exception handling constructs (try/finally), and so must run before those are lowered. In addition, the pass enqueues declarations of static variables whose lifetimes extend to the entire program. The pass is located in 'tree-mudflap.c' and is described by pass_mudflap_1.

• Lower control flow

This pass flattens if statements (COND_EXPR) and and moves lexical bindings (BIND_EXPR) out of line. After this pass, all if statements will have exactly two goto statements in its then and else arms. Lexical binding information for each statement will be found in TREE_BLOCK rather than being inferred from its position under a BIND_EXPR. This pass is found in 'gimple-low.c' and is described by pass_lower_cf.

• Lower exception handling control flow

This pass decomposes high-level exception handling constructs (TRY_FINALLY_EXPR and TRY_CATCH_EXPR) into a form that explicitly represents the control flow involved. After this pass, lookup_stmt_eh_region will return a non-negative number for any statement that may have EH control flow semantics; examine tree_can_throw_internal or tree_can_throw_external for exact semantics. Exact control flow may be extracted from foreach_reachable_handler. The EH region nesting tree is defined in 'except.h' and built in 'except.c'. The lowering pass itself is in 'tree-eh.c' and is described by pass_lower_eh.

• Build the control flow graph

This pass decomposes a function into basic blocks and creates all of the edges that connect them. It is located in 'tree-cfg.c' and is described by pass_build_cfg.

• Find all referenced variables

This pass walks the entire function and collects an array of all variables referenced in the function, referenced_vars. The index at which a variable is found in the array is used as a UID for the variable within this function. This data is needed by the SSA rewriting routines. The pass is located in 'tree-dfa.c' and is described by pass_referenced_vars.

• Enter static single assignment form

This pass rewrites the function such that it is in SSA form. After this pass, all is_gimple_reg variables will be referenced by SSA_NAME, and all occurrences of other variables will be annotated with VDEFS and VUSES; phi nodes will have been inserted as necessary for each basic block. This pass is located in 'tree-ssa.c' and is described by pass_build_ssa.

• Warn for uninitialized variables

This pass scans the function for uses of SSA_NAMEs that are fed by default definition. For non-parameter variables, such uses are uninitialized. The pass is run twice, before and after optimization. In the first pass we only warn for uses that are positively uninitialized; in the second pass we warn for uses that are possibly uninitialized. The pass is located in 'tree-ssa.c' and is defined by pass_early_warn_uninitialized and pass_late_warn_uninitialized.

• Dead code elimination

This pass scans the function for statements without side effects whose result is unused. It does not do memory life analysis, so any value that is stored in memory is considered used. The pass is run multiple times throughout the optimization process. It is located in 'tree-ssa-dce.c' and is described by pass_dce.

• Dominator optimizations

This pass performs trivial dominator-based copy and constant propagation, expression simplification, and jump threading. It is run multiple times throughout the optimization process. It it located in 'tree-ssa-dom.c' and is described by pass_dominator.

• Redundant phi elimination

This pass removes phi nodes for which all of the arguments are the same value, excluding feedback. Such degenerate forms are typically created by removing unreachable code. The pass is run multiple times throughout the optimization process. It is located in 'tree-ssa.c' and is described by pass_redundant_phi.o

• Forward propagation of single-use variables

This pass attempts to remove redundant computation by substituting variables that are used once into the expression that uses them and seeing if the result can be simplified. It is located in 'tree-ssa-forwprop.c' and is described by pass_forwprop.

• Copy Renaming

This pass attempts to change the name of compiler temporaries involved in copy operations such that SSA->normal can coalesce the copy away. When compiler temporaries are copies of user variables, it also renames the compiler temporary to the user variable resulting in better use of user symbols. It is located in 'tree-ssa-copyrename.c' and is described by pass_copyrename.

• PHI node optimizations

This pass recognizes forms of phi inputs that can be represented as conditional expressions and rewrites them into straight line code. It is located in 'tree-ssa-phiopt.c' and is described by pass_phiopt.

• May-alias optimization

This pass performs a flow sensitive SSA-based points-to analysis. The resulting mayalias, must-alias, and escape analysis information is used to promote variables from

in-memory addressable objects to non-aliased variables that can be renamed into SSA form. We also update the VDEF/VUSE memory tags for non-renamable aggregates so that we get fewer false kills. The pass is located in 'tree-ssa-alias.c' and is described by pass_may_alias.

• Profiling

This pass rewrites the function in order to collect runtime block and value profiling data. Such data may be fed back into the compiler on a subsequent run so as to allow optimization based on expected execution frequencies. The pass is located in 'predict.c' and is described by pass_profile.

• Lower complex arithmetic

This pass rewrites complex arithmetic operations into their component scalar arithmetic operations. The pass is located in 'tree-complex.c' and is described by pass_lower_complex.

• Scalar replacement of aggregates

This pass rewrites suitable non-aliased local aggregate variables into a set of scalar variables. The resulting scalar variables are rewritten into SSA form, which allows subsequent optimization passes to do a significantly better job with them. The pass is located in 'tree-sra.c' and is described by pass_sra.

• Dead store elimination

This pass eliminates stores to memory that are subsequently overwritten by another store, without any intervening loads. The pass is located in 'tree-ssa-dse.c' and is described by pass_dse.

• Tail recursion elimination

This pass transforms tail recursion into a loop. It is located in 'tree-tailcall.c' and is described by pass_tail_recursion.

• Partial redundancy elimination

This pass eliminates partially redundant computations, as well as performing load motion. The pass is located in 'tree-ssa-pre.c' and is described by pass_pre.

• Loop optimization

The main driver of the pass is placed in 'tree-ssa-loop.c' and described by pass_loop.

The optimizations performed by this pass are:

Loop invariant motion. This pass moves only invariants that would be hard to handle on rtl level (function calls, operations that expand to nontrivial sequences of insns). With '-funswitch-loops' it also moves operands of conditions that are invariant out of the loop, so that we can use just trivial invariantness analysis in loop unswitching. The pass also includes store motion. The pass is implemented in 'tree-ssa-loop-im.c'.

Canonical induction variable creation. This pass creates a simple counter for number of iterations of the loop and replaces the exit condition of the loop using it, in case when a complicated analysis is necessary to determine the number of iterations. Later optimizations then may determine the number easily. The pass is implemented in 'tree-ssa-loop-ivcanon.c'.

Induction variable optimizations. This pass performs standard induction variable optimizations, including strength reduction, induction variable merging and induction variable elimination. The pass is implemented in 'tree-ssa-loop-ivopts.c'.

Loop unswitching. This pass moves the conditional jumps that are invariant out of the loops. To achieve this, a duplicate of the loop is created for each possible outcome of conditional jump(s). The pass is implemented in 'tree-ssa-loop-unswitch.c'. This pass should eventually replace the rtl-level loop unswitching in 'loop-unswitch.c', but currently the rtl-level pass is not completely redundant yet due to deficiencies in tree level alias analysis.

The optimizations also use various utility functions contained in 'tree-ssa-loop-manip.c', 'cfgloop.c', 'cfgloopanal.c' and 'cfgloopmanip.c'.

• Tree level if-conversion for vectorizer

This pass applies if-conversion to simple loops to help vectorizer. We identify if convertable loops, if-convert statements and merge basic blocks in one big block. The idea is to present loop in such form so that vectorizer can have one to one mapping between statements and available vector operations. This patch re-introduces COND_EXPR at GIMPLE level. This pass is located in 'tree-if-conv.c'.

• Conditional constant propagation

This pass relaxes a lattice of values in order to identify those that must be constant even in the presence of conditional branches. The pass is located in 'tree-ssa-ccp.c' and is described by pass_ccp.

• Folding builtin functions

This pass simplifies builtin functions, as applicable, with constant arguments or with inferrable string lengths. It is located in 'tree-ssa-ccp.c' and is described by pass_fold_builtins.

• Split critical edges

This pass identifies critical edges and inserts empty basic blocks such that the edge is no longer critical. The pass is located in 'tree-cfg.c' and is described by pass_split_crit_edges.

• Partial redundancy elimination

This pass answers the question "given a hypothetical temporary variable, what expressions could we eliminate?" It is located in 'tree-ssa-pre.c' and is described by pass_pre.

• Control dependence dead code elimination

This pass is a stronger form of dead code elimination that can eliminate unnecessary control flow statements. It is located in 'tree-ssa-dce.c' and is described by pass_cd dce.

• Tail call elimination

This pass identifies function calls that may be rewritten into jumps. No code transformation is actually applied here, but the data and control flow problem is solved. The code transformation requires target support, and so is delayed until RTL. In the meantime CALL_EXPR_TAILCALL is set indicating the possibility. The pass is located in 'tree-tailcall.c' and is described by pass_tail_calls. The RTL transformation is handled by fixup_tail_calls in 'calls.c'.

• Warn for function return without value

For non-void functions, this pass locates return statements that do not specify a value and issues a warning. Such a statement may have been injected by falling off the end of the function. This pass is run last so that we have as much time as possible to prove that the statement is not reachable. It is located in 'tree-cfg.c' and is described by pass_warn_function_return.

• Mudflap statement annotation

If mudflap is enabled, we rewrite some memory accesses with code to validate that the memory access is correct. In particular, expressions involving pointer dereferences (INDIRECT_REF, ARRAY_REF, etc.) are replaced by code that checks the selected address range against the mudflap runtime's database of valid regions. This check includes an inline lookup into a direct-mapped cache, based on shift/mask operations of the pointer value, with a fallback function call into the runtime. The pass is located in 'tree-mudflap.c' and is described by pass_mudflap_2.

• Leave static single assignment form

This pass rewrites the function such that it is in normal form. At the same time, we eliminate as many single-use temporaries as possible, so the intermediate language is no longer GIMPLE, but GENERIC. The pass is located in 'tree-ssa.c' and is described by pass_del_ssa.

7.5 RTL passes

The following briefly describes the rtl generation and optimization passes that are run after tree optimization.

• RTL generation

The source files for RTL generation include 'stmt.c', 'calls.c', 'expr.c', 'explow.c', 'expmed.c', 'function.c', 'optabs.c' and 'emit-rtl.c'. Also, the file 'insn-emit.c', generated from the machine description by the program genemit, is used in this pass. The header file 'expr.h' is used for communication within this pass.

The header files 'insn-flags.h' and 'insn-codes.h', generated from the machine description by the programs genflags and gencodes, tell this pass which standard names are available for use and which patterns correspond to them.

• Generate exception handling landing pads

This pass generates the glue that handles communication between the exception handling library routines and the exception handlers within the function. Entry points in the function that are invoked by the exception handling library are called *landing pads*. The code for this pass is located within 'except.c'.

• Cleanup control flow graph

This pass removes unreachable code, simplifies jumps to next, jumps to jump, jumps across jumps, etc. The pass is run multiple times. For historical reasons, it is occasionally referred to as the "jump optimization pass". The bulk of the code for this pass is in 'cfgcleanup.c', and there are support routines in 'cfgrtl.c' and 'jump.c'.

• Common subexpression elimination

This pass removes redundant computation within basic blocks, and optimizes addressing modes based on cost. The pass is run twice. The source is located in 'cse.c'.

• Global common subexpression elimination.

This pass performs two different types of GCSE depending on whether you are optimizing for size or not (LCM based GCSE tends to increase code size for a gain in speed, while Morel-Renvoise based GCSE does not). When optimizing for size, GCSE is done using Morel-Renvoise Partial Redundancy Elimination, with the exception that it does not try to move invariants out of loops—that is left to the loop optimization pass. If MR PRE GCSE is done, code hoisting (aka unification) is also done, as well as load motion. If you are optimizing for speed, LCM (lazy code motion) based GCSE is done. LCM is based on the work of Knoop, Ruthing, and Steffen. LCM based GCSE also does loop invariant code motion. We also perform load and store motion when optimizing for speed. Regardless of which type of GCSE is used, the GCSE pass also performs global constant and copy propagation. The source file for this pass is 'gcse.c', and the LCM routines are in '1cm.c'.

• Loop optimization

This pass moves constant expressions out of loops, and optionally does strength-reduction as well. The pass is located in 'loop.c'. Loop dependency analysis routines are contained in 'dependence.c'. This pass is seriously out-of-date and is supposed to be replaced by a new one described below in near future.

A second loop optimization pass takes care of basic block level optimizations—unrolling, peeling and unswitching loops. The source files are 'cfgloopanal.c' and 'cfgloopmanip.c' containing generic loop analysis and manipulation code, 'loop-init.c' with initialization and finalization code, 'loop-unswitch.c' for loop unswitching and 'loop-unroll.c' for loop unrolling and peeling. It also contains a separate loop invariant motion pass implemented in 'loop-invariant.c'.

• Jump bypassing

This pass is an aggressive form of GCSE that transforms the control flow graph of a function by propagating constants into conditional branch instructions. The source file for this pass is 'gcse.c'.

• If conversion

This pass attempts to replace conditional branches and surrounding assignments with arithmetic, boolean value producing comparison instructions, and conditional move instructions. In the very last invocation after reload, it will generate predicated instructions when supported by the target. The pass is located in 'ifcvt.c'.

• Web construction

This pass splits independent uses of each pseudo-register. This can improve effect of the other transformation, such as CSE or register allocation. Its source files are 'web.c'.

• Life analysis

This pass computes which pseudo-registers are live at each point in the program, and makes the first instruction that uses a value point at the instruction that computed the value. It then deletes computations whose results are never used, and combines memory references with add or subtract instructions to make autoincrement or autodecrement addressing. The pass is located in 'flow.c'.

• Instruction combination

This pass attempts to combine groups of two or three instructions that are related by data flow into single instructions. It combines the RTL expressions for the instructions by substitution, simplifies the result using algebra, and then attempts to match the result against the machine description. The pass is located in 'combine.c'.

• Register movement

This pass looks for cases where matching constraints would force an instruction to need a reload, and this reload would be a register-to-register move. It then attempts to change the registers used by the instruction to avoid the move instruction. The pass is located in 'regmove.c'.

• Optimize mode switching

This pass looks for instructions that require the processor to be in a specific "mode" and minimizes the number of mode changes required to satisfy all users. What these modes are, and what they apply to are completely target-specific. The source is located in 'lcm.c'.

• Modulo scheduling

This pass looks at innermost loops and reorders their instructions by overlapping different iterations. Modulo scheduling is performed immediately before instruction scheduling. The pass is located in ('modulo-sched.c').

• Instruction scheduling

This pass looks for instructions whose output will not be available by the time that it is used in subsequent instructions. Memory loads and floating point instructions often have this behavior on RISC machines. It re-orders instructions within a basic block to try to separate the definition and use of items that otherwise would cause pipeline stalls. This pass is performed twice, before and after register allocation. The pass is located in 'haifa-sched.c', 'sched-deps.c', 'sched-ebb.c', 'sched-rgn.c' and 'sched-vis.c'.

• Register allocation

These passes make sure that all occurrences of pseudo registers are eliminated, either by allocating them to a hard register, replacing them by an equivalent expression (e.g. a constant) or by placing them on the stack. This is done in several subpasses:

- Register class preferencing. The RTL code is scanned to find out which register class is best for each pseudo register. The source file is 'regclass.c'.
- Local register allocation. This pass allocates hard registers to pseudo registers that are used only within one basic block. Because the basic block is linear, it can use fast and powerful techniques to do a decent job. The source is located in 'local-alloc.c'.
- Global register allocation. This pass allocates hard registers for the remaining pseudo registers (those whose life spans are not contained in one basic block). The pass is located in 'global.c'.
- Reloading. This pass renumbers pseudo registers with the hardware registers numbers they were allocated. Pseudo registers that did not get hard registers are replaced with stack slots. Then it finds instructions that are invalid because a value has failed to end up in a register, or has ended up in a register of the wrong kind. It fixes up these instructions by reloading the problematical values temporarily into registers. Additional instructions are generated to do the copying.

The reload pass also optionally eliminates the frame pointer and inserts instructions to save and restore call-clobbered registers around calls.

Source files are 'reload.c' and 'reload1.c', plus the header 'reload.h' used for communication between them.

• Basic block reordering

This pass implements profile guided code positioning. If profile information is not available, various types of static analysis are performed to make the predictions normally coming from the profile feedback (IE execution frequency, branch probability, etc). It is implemented in the file 'bb-reorder.c', and the various prediction routines are in 'predict.c'.

• Variable tracking

This pass computes where the variables are stored at each position in code and generates notes describing the variable locations to RTL code. The location lists are then generated according to these notes to debug information if the debugging information format supports location lists.

• Delayed branch scheduling

This optional pass attempts to find instructions that can go into the delay slots of other instructions, usually jumps and calls. The source file name is 'reorg.c'.

• Branch shortening

On many RISC machines, branch instructions have a limited range. Thus, longer sequences of instructions must be used for long branches. In this pass, the compiler figures out what how far each instruction will be from each other instruction, and therefore whether the usual instructions, or the longer sequences, must be used for each branch.

• Register-to-stack conversion

Conversion from usage of some hard registers to usage of a register stack may be done at this point. Currently, this is supported only for the floating-point registers of the Intel 80387 coprocessor. The source file name is 'reg-stack.c'.

• Final

This pass outputs the assembler code for the function. The source files are 'final.c' plus 'insn-output.c'; the latter is generated automatically from the machine description by the tool 'genoutput'. The header file 'conditions.h' is used for communication between these files. If mudflap is enabled, the queue of deferred declarations and any addressed constants (e.g., string literals) is processed by mudflap_finish_file into a synthetic constructor function containing calls into the mudflap runtime.

• Debugging information output

This is run after final because it must output the stack slot offsets for pseudo registers that did not get hard registers. Source files are 'dbxout.c' for DBX symbol table format, 'sdbout.c' for SDB symbol table format, 'dwarfout.c' for DWARF symbol table format, files 'dwarf2out.c' and 'dwarf2asm.c' for DWARF2 symbol table format, and 'vmsdbgout.c' for VMS debug symbol table format.

8 Trees: The intermediate representation used by the C and C++ front ends

This chapter documents the internal representation used by GCC to represent C and C++ source programs. When presented with a C or C++ source program, GCC parses the program, performs semantic analysis (including the generation of error messages), and then produces the internal representation described here. This representation contains a complete representation for the entire translation unit provided as input to the front end. This representation is then typically processed by a code-generator in order to produce machine code, but could also be used in the creation of source browsers, intelligent editors, automatic documentation generators, interpreters, and any other programs needing the ability to process C or C++ code.

This chapter explains the internal representation. In particular, it documents the internal representation for C and C++ source constructs, and the macros, functions, and variables that can be used to access these constructs. The C++ representation is largely a superset of the representation used in the C front end. There is only one construct used in C that does not appear in the C++ front end and that is the GNU "nested function" extension. Many of the macros documented here do not apply in C because the corresponding language constructs do not appear in C.

If you are developing a "back end", be it is a code-generator or some other tool, that uses this representation, you may occasionally find that you need to ask questions not easily answered by the functions and macros available here. If that situation occurs, it is quite likely that GCC already supports the functionality you desire, but that the interface is simply not documented here. In that case, you should ask the GCC maintainers (via mail to gcc@gcc.gnu.org) about documenting the functionality you require. Similarly, if you find yourself writing functions that do not deal directly with your back end, but instead might be useful to other people using the GCC front end, you should submit your patches for inclusion in GCC.

8.1 Deficiencies

There are many places in which this document is incomplet and incorrekt. It is, as of yet, only *preliminary* documentation.

8.2 Overview

The central data structure used by the internal representation is the tree. These nodes, while all of the C type tree, are of many varieties. A tree is a pointer type, but the object to which it points may be of a variety of types. From this point forward, we will refer to trees in ordinary type, rather than in this font, except when talking about the actual C type tree.

You can tell what kind of node a particular tree is by using the TREE_CODE macro. Many, many macros take trees as input and return trees as output. However, most macros require a certain kind of tree node as input. In other words, there is a type-system for trees, but it is not reflected in the C type-system.

For safety, it is useful to configure GCC with '--enable-checking'. Although this results in a significant performance penalty (since all tree types are checked at run-time), and is

therefore inappropriate in a release version, it is extremely helpful during the development process.

Many macros behave as predicates. Many, although not all, of these predicates end in '_P'. Do not rely on the result type of these macros being of any particular type. You may, however, rely on the fact that the type can be compared to 0, so that statements like

are legal. Macros that return int values now may be changed to return tree values, or other pointers in the future. Even those that continue to return int may return multiple nonzero codes where previously they returned only zero and one. Therefore, you should not write code like

```
if (TEST_P (t) == 1)
```

as this code is not guaranteed to work correctly in the future.

You should not take the address of values returned by the macros or functions described here. In particular, no guarantee is given that the values are lyalues.

In general, the names of macros are all in uppercase, while the names of functions are entirely in lowercase. There are rare exceptions to this rule. You should assume that any macro or function whose name is made up entirely of uppercase letters may evaluate its arguments more than once. You may assume that a macro or function whose name is made up entirely of lowercase letters will evaluate its arguments only once.

The error_mark_node is a special tree. Its tree code is ERROR_MARK, but since there is only ever one node with that code, the usual practice is to compare the tree against error_mark_node. (This test is just a test for pointer equality.) If an error has occurred during front-end processing the flag errorcount will be set. If the front end has encountered code it cannot handle, it will issue a message to the user and set sorrycount. When these flags are set, any macro or function which normally returns a tree of a particular kind may instead return the error_mark_node. Thus, if you intend to do any processing of erroneous code, you must be prepared to deal with the error_mark_node.

Occasionally, a particular tree slot (like an operand to an expression, or a particular field in a declaration) will be referred to as "reserved for the back end". These slots are used to store RTL when the tree is converted to RTL for use by the GCC back end. However, if that process is not taking place (e.g., if the front end is being hooked up to an intelligent editor), then those slots may be used by the back end presently in use.

If you encounter situations that do not match this documentation, such as tree nodes of types not mentioned here, or macros documented to return entities of a particular kind that instead return entities of some different kind, you have found a bug, either in the front end or in the documentation. Please report these bugs as you would any other bug.

8.2.1 Trees

This section is not here yet.

8.2.2 Identifiers

An IDENTIFIER_NODE represents a slightly more general concept that the standard C or C++ concept of identifier. In particular, an IDENTIFIER_NODE may contain a '\$', or other extraordinary characters.

There are never two distinct IDENTIFIER_NODEs representing the same identifier. Therefore, you may use pointer equality to compare IDENTIFIER_NODEs, rather than using a routine like strcmp.

You can use the following macros to access identifiers:

IDENTIFIER_POINTER

The string represented by the identifier, represented as a char*. This string is always NUL-terminated, and contains no embedded NUL characters.

IDENTIFIER_LENGTH

The length of the string returned by IDENTIFIER_POINTER, not including the trailing NUL. This value of IDENTIFIER_LENGTH (x) is always the same as strlen (IDENTIFIER_POINTER (x)).

IDENTIFIER_OPNAME_P

This predicate holds if the identifier represents the name of an overloaded operator. In this case, you should not depend on the contents of either the IDENTIFIER_POINTER or the IDENTIFIER_LENGTH.

IDENTIFIER_TYPENAME_P

This predicate holds if the identifier represents the name of a user-defined conversion operator. In this case, the TREE_TYPE of the IDENTIFIER_NODE holds the type to which the conversion operator converts.

8.2.3 Containers

Two common container data structures can be represented directly with tree nodes. A TREE_LIST is a singly linked list containing two trees per node. These are the TREE_PURPOSE and TREE_VALUE of each node. (Often, the TREE_PURPOSE contains some kind of tag, or additional information, while the TREE_VALUE contains the majority of the payload. In other cases, the TREE_PURPOSE is simply NULL_TREE, while in still others both the TREE_PURPOSE and TREE_VALUE are of equal stature.) Given one TREE_LIST node, the next node is found by following the TREE_CHAIN. If the TREE_CHAIN is NULL_TREE, then you have reached the end of the list.

A TREE_VEC is a simple vector. The TREE_VEC_LENGTH is an integer (not a tree) giving the number of nodes in the vector. The nodes themselves are accessed using the TREE_VEC_ELT macro, which takes two arguments. The first is the TREE_VEC in question; the second is an integer indicating which element in the vector is desired. The elements are indexed from zero.

8.3 Types

All types have corresponding tree nodes. However, you should not assume that there is exactly one tree node corresponding to each type. There are often several nodes each of which correspond to the same type.

For the most part, different kinds of types have different tree codes. (For example, pointer types use a POINTER_TYPE code while arrays use an ARRAY_TYPE code.) However, pointers to member functions use the RECORD_TYPE code. Therefore, when writing a switch statement that depends on the code associated with a particular type, you should take care to handle pointers to member functions under the RECORD_TYPE case label.

In C++, an array type is not qualified; rather the type of the array elements is qualified. This situation is reflected in the intermediate representation. The macros described here will always examine the qualification of the underlying element type when applied to an array type. (If the element type is itself an array, then the recursion continues until a non-array type is found, and the qualification of this type is examined.) So, for example, CP_TYPE_CONST_P will hold of the type const int ()[7], denoting an array of seven ints.

The following functions and macros deal with cv-qualification of types:

CP_TYPE_QUALS

This macro returns the set of type qualifiers applied to this type. This value is TYPE_UNQUALIFIED if no qualifiers have been applied. The TYPE_QUAL_CONST bit is set if the type is const-qualified. The TYPE_QUAL_VOLATILE bit is set if the type is volatile-qualified. The TYPE_QUAL_RESTRICT bit is set if the type is restrict-qualified.

CP_TYPE_CONST_P

This macro holds if the type is const-qualified.

CP_TYPE_VOLATILE_P

This macro holds if the type is volatile-qualified.

CP_TYPE_RESTRICT_P

This macro holds if the type is restrict-qualified.

CP TYPE CONST NON VOLATILE P

This predicate holds for a type that is const-qualified, but not volatile-qualified; other cv-qualifiers are ignored as well: only the const-ness is tested.

TYPE_MAIN_VARIANT

This macro returns the unqualified version of a type. It may be applied to an unqualified type, but it is not always the identity function in that case.

A few other macros and functions are usable with all types:

TYPE_SIZE

The number of bits required to represent the type, represented as an INTEGER_CST. For an incomplete type, TYPE_SIZE will be NULL_TREE.

TYPE_ALIGN

The alignment of the type, in bits, represented as an int.

TYPE NAME

This macro returns a declaration (in the form of a TYPE_DECL) for the type. (Note this macro does *not* return a IDENTIFIER_NODE, as you might expect, given its name!) You can look at the DECL_NAME of the TYPE_DECL to obtain the actual name of the type. The TYPE_NAME will be NULL_TREE for a type that is not a built-in type, the result of a typedef, or a named class type.

CP_INTEGRAL_TYPE

This predicate holds if the type is an integral type. Notice that in C++, enumerations are *not* integral types.

ARITHMETIC_TYPE_P

This predicate holds if the type is an integral type (in the C++ sense) or a floating point type.

CLASS_TYPE_P

This predicate holds for a class-type.

TYPE_BUILT_IN

This predicate holds for a built-in type.

TYPE_PTRMEM_P

This predicate holds if the type is a pointer to data member.

TYPE_PTR_P

This predicate holds if the type is a pointer type, and the pointee is not a data member.

TYPE_PTRFN_P

This predicate holds for a pointer to function type.

TYPE PTROB P

This predicate holds for a pointer to object type. Note however that it does not hold for the generic pointer to object type void *. You may use TYPE_PTROBV_P to test for a pointer to object type as well as void *.

same_type_p

This predicate takes two types as input, and holds if they are the same type. For example, if one type is a typedef for the other, or both are typedefs for the same type. This predicate also holds if the two trees given as input are simply copies of one another; i.e., there is no difference between them at the source level, but, for whatever reason, a duplicate has been made in the representation. You should never use == (pointer equality) to compare types; always use same_type_p instead.

Detailed below are the various kinds of types, and the macros that can be used to access them. Although other kinds of types are used elsewhere in G++, the types described here are the only ones that you will encounter while examining the intermediate representation.

VOID_TYPE

Used to represent the void type.

INTEGER_TYPE

Used to represent the various integral types, including char, short, int, long, and long long. This code is not used for enumeration types, nor for the bool type. Note that GCC's CHAR_TYPE node is not used to represent char. The TYPE_PRECISION is the number of bits used in the representation, represented as an unsigned int. (Note that in the general case this is not the same value as TYPE_SIZE; suppose that there were a 24-bit integer type, but that alignment requirements for the ABI required 32-bit alignment. Then, TYPE_SIZE would be an INTEGER_CST for 32, while TYPE_PRECISION would be 24.) The integer type is unsigned if TYPE_UNSIGNED holds; otherwise, it is signed.

The TYPE_MIN_VALUE is an INTEGER_CST for the smallest integer that may be represented by this type. Similarly, the TYPE_MAX_VALUE is an INTEGER_CST for the largest integer that may be represented by this type.

REAL_TYPE

Used to represent the float, double, and long double types. The number of bits in the floating-point representation is given by TYPE_PRECISION, as in the INTEGER_TYPE case.

COMPLEX_TYPE

Used to represent GCC built-in __complex__ data types. The TREE_TYPE is the type of the real and imaginary parts.

ENUMERAL TYPE

Used to represent an enumeration type. The TYPE_PRECISION gives (as an int), the number of bits used to represent the type. If there are no negative enumeration constants, TYPE_UNSIGNED will hold. The minimum and maximum enumeration constants may be obtained with TYPE_MIN_VALUE and TYPE_MAX_VALUE, respectively; each of these macros returns an INTEGER_CST.

The actual enumeration constants themselves may be obtained by looking at the TYPE_VALUES. This macro will return a TREE_LIST, containing the constants. The TREE_PURPOSE of each node will be an IDENTIFIER_NODE giving the name of the constant; the TREE_VALUE will be an INTEGER_CST giving the value assigned to that constant. These constants will appear in the order in which they were declared. The TREE_TYPE of each of these constants will be the type of enumeration type itself.

BOOLEAN_TYPE

Used to represent the bool type.

POINTER_TYPE

Used to represent pointer types, and pointer to data member types. The TREE_TYPE gives the type to which this type points. If the type is a pointer to data member type, then TYPE_PTRMEM_P will hold. For a pointer to data member type of the form 'T X::*', TYPE_PTRMEM_CLASS_TYPE will be the type X, while TYPE_PTRMEM_POINTED_TO_TYPE will be the type T.

REFERENCE TYPE

Used to represent reference types. The TREE_TYPE gives the type to which this type refers.

FUNCTION_TYPE

Used to represent the type of non-member functions and of static member functions. The TREE_TYPE gives the return type of the function. The TYPE_ARG_TYPES are a TREE_LIST of the argument types. The TREE_VALUE of each node in this list is the type of the corresponding argument; the TREE_PURPOSE is an expression for the default argument value, if any. If the last node in the list is void_list_node (a TREE_LIST node whose TREE_VALUE is the void_type_node), then functions of this type do not take variable arguments. Otherwise, they do take a variable number of arguments.

Note that in C (but not in C++) a function declared like void f() is an unprototyped function taking a variable number of arguments; the TYPE_ARG_TYPES of such a function will be NULL.

METHOD_TYPE

Used to represent the type of a non-static member function. Like a FUNCTION_TYPE, the return type is given by the TREE_TYPE. The type of *this, i.e., the class of which functions of this type are a member, is given by the TYPE_METHOD_BASETYPE. The TYPE_ARG_TYPES is the parameter list, as for a FUNCTION_TYPE, and includes the this argument.

ARRAY_TYPE

Used to represent array types. The TREE_TYPE gives the type of the elements in the array. If the array-bound is present in the type, the TYPE_DOMAIN is an INTEGER_TYPE whose TYPE_MIN_VALUE and TYPE_MAX_VALUE will be the lower and upper bounds of the array, respectively. The TYPE_MIN_VALUE will always be an INTEGER_CST for zero, while the TYPE_MAX_VALUE will be one less than the number of elements in the array, i.e., the highest value which may be used to index an element in the array.

RECORD TYPE

Used to represent struct and class types, as well as pointers to member functions and similar constructs in other languages. TYPE_FIELDS contains the items contained in this type, each of which can be a FIELD_DECL, VAR_DECL, CONST_DECL, or TYPE_DECL. You may not make any assumptions about the ordering of the fields in the type or whether one or more of them overlap. If TYPE_PTRMEMFUNC_P holds, then this type is a pointer-to-member type. In that case, the TYPE_PTRMEMFUNC_FN_TYPE is a POINTER_TYPE pointing to a METHOD_TYPE. The METHOD_TYPE is the type of a function pointed to by the pointer-to-member function. If TYPE_PTRMEMFUNC_P does not hold, this type is a class type. For more information, see see Section 8.4.2 [Classes], page 63.

UNION_TYPE

Used to represent union types. Similar to RECORD_TYPE except that all FIELD_DECL nodes in TYPE_FIELD start at bit position zero.

QUAL_UNION_TYPE

Used to represent part of a variant record in Ada. Similar to UNION_TYPE except that each FIELD_DECL has a DECL_QUALIFIER field, which contains a boolean expression that indicates whether the field is present in the object. The type will only have one field, so each field's DECL_QUALIFIER is only evaluated if none of the expressions in the previous fields in TYPE_FIELDS are nonzero. Normally these expressions will reference a field in the outer object using a PLACEHOLDER_EXPR.

UNKNOWN_TYPE

This node is used to represent a type the knowledge of which is insufficient for a sound processing.

OFFSET_TYPE

This node is used to represent a pointer-to-data member. For a data member X::m the TYPE_OFFSET_BASETYPE is X and the TREE_TYPE is the type of m.

TYPENAME_TYPE

Used to represent a construct of the form typename T::A. The TYPE_CONTEXT is T; the TYPE_NAME is an IDENTIFIER_NODE for A. If the type is specified via a template-id, then TYPENAME_TYPE_FULLNAME yields a TEMPLATE_ID_EXPR. The TREE_TYPE is non-NULL if the node is implicitly generated in support for the implicit typename extension; in which case the TREE_TYPE is a type node for the base-class.

TYPEOF_TYPE

Used to represent the __typeof__ extension. The TYPE_FIELDS is the expression the type of which is being represented.

There are variables whose values represent some of the basic types. These include:

void_type_node

A node for void.

integer_type_node

A node for int.

unsigned_type_node.

A node for unsigned int.

char_type_node.

A node for char.

It may sometimes be useful to compare one of these variables with a type in hand, using same_type_p.

8.4 Scopes

The root of the entire intermediate representation is the variable global_namespace. This is the namespace specified with :: in C++ source code. All other namespaces, types, variables, functions, and so forth can be found starting with this namespace.

Besides namespaces, the other high-level scoping construct in C++ is the class. (Throughout this manual the term *class* is used to mean the types referred to in the ANSI/ISO C++ Standard as classes; these include types defined with the class, struct, and union keywords.)

8.4.1 Namespaces

A namespace is represented by a NAMESPACE_DECL node.

However, except for the fact that it is distinguished as the root of the representation, the global namespace is no different from any other namespace. Thus, in what follows, we describe namespaces generally, rather than the global namespace in particular.

The following macros and functions can be used on a NAMESPACE_DECL:

DECL_NAME

This macro is used to obtain the IDENTIFIER_NODE corresponding to the unqualified name of the name of the namespace (see Section 8.2.2 [Identifiers], page 56). The name of the global namespace is '::', even though in C++ the global namespace is unnamed. However, you should use comparison with global_namespace, rather than DECL_NAME to determine whether or not a namespace is the global one. An unnamed namespace will have a DECL_NAME equal to anonymous_namespace_name. Within a single translation unit, all unnamed namespaces will have the same name.

DECL CONTEXT

This macro returns the enclosing namespace. The DECL_CONTEXT for the global_namespace is NULL_TREE.

DECL_NAMESPACE_ALIAS

If this declaration is for a namespace alias, then DECL_NAMESPACE_ALIAS is the namespace for which this one is an alias.

Do not attempt to use cp_namespace_decls for a namespace which is an alias. Instead, follow DECL_NAMESPACE_ALIAS links until you reach an ordinary, non-alias, namespace, and call cp_namespace_decls there.

DECL_NAMESPACE_STD_P

This predicate holds if the namespace is the special ::std namespace.

${\tt cp_namespace_decls}$

This function will return the declarations contained in the namespace, including types, overloaded functions, other namespaces, and so forth. If there are no declarations, this function will return NULL_TREE. The declarations are connected through their TREE_CHAIN fields.

Although most entries on this list will be declarations, TREE_LIST nodes may also appear. In this case, the TREE_VALUE will be an OVERLOAD. The value of the TREE_PURPOSE is unspecified; back ends should ignore this value. As with the other kinds of declarations returned by cp_namespace_decls, the TREE_CHAIN will point to the next declaration in this list.

For more information on the kinds of declarations that can occur on this list, See Section 8.5 [Declarations], page 65. Some declarations will not appear on this list. In particular, no FIELD_DECL, LABEL_DECL, or PARM_DECL nodes will appear here.

This function cannot be used with namespaces that have DECL_NAMESPACE_ALIAS set.

8.4.2 Classes

A class type is represented by either a RECORD_TYPE or a UNION_TYPE. A class declared with the union tag is represented by a UNION_TYPE, while classes declared with either the struct or the class tag are represented by RECORD_TYPEs. You can use the CLASSTYPE_DECLARED_CLASS macro to discern whether or not a particular type is a class as opposed to a struct. This macro will be true only for classes declared with the class tag.

Almost all non-function members are available on the TYPE_FIELDS list. Given one member, the next can be found by following the TREE_CHAIN. You should not depend in any

way on the order in which fields appear on this list. All nodes on this list will be 'DECL' nodes. A FIELD_DECL is used to represent a non-static data member, a VAR_DECL is used to represent a static data member, and a TYPE_DECL is used to represent a type. Note that the CONST_DECL for an enumeration constant will appear on this list, if the enumeration type was declared in the class. (Of course, the TYPE_DECL for the enumeration type will appear here as well.) There are no entries for base classes on this list. In particular, there is no FIELD_DECL for the "base-class portion" of an object.

The TYPE_VFIELD is a compiler-generated field used to point to virtual function tables. It may or may not appear on the TYPE_FIELDS list. However, back ends should handle the TYPE_VFIELD just like all the entries on the TYPE_FIELDS list.

The function members are available on the TYPE_METHODS list. Again, subsequent members are found by following the TREE_CHAIN field. If a function is overloaded, each of the overloaded functions appears; no OVERLOAD nodes appear on the TYPE_METHODS list. Implicitly declared functions (including default constructors, copy constructors, assignment operators, and destructors) will appear on this list as well.

Every class has an associated binfo, which can be obtained with TYPE_BINFO. Binfos are used to represent base-classes. The binfo given by TYPE_BINFO is the degenerate case, whereby every class is considered to be its own base-class. The base binfos for a particular binfo are held in a vector, whose length is obtained with BINFO_N_BASE_BINFOS. The base binfos themselves are obtained with BINFO_BASE_BINFO and BINFO_BASE_ITERATE. To add a new binfo, use BINFO_BASE_APPEND. The vector of base binfos can be obtained with BINFO_BASE_BINFOS, but normally you do not need to use that. The class type associated with a binfo is given by BINFO_TYPE. It is not always the case that BINFO_TYPE (TYPE_BINFO (x)), because of typedefs and qualified types. Neither is it the case that TYPE_BINFO (BINFO_TYPE (y)) is the same binfo as y. The reason is that if y is a binfo representing a base-class B of a derived class D, then BINFO_TYPE (y) will be B, and TYPE_BINFO (BINFO_TYPE (y)) will be B as its own base-class, rather than as a base-class of D.

The access to a base type can be found with BINFO_BASE_ACCESS. This will produce access_public_node, access_private_node or access_protected_node. If bases are always public, BINFO_BASE_ACCESSES may be NULL.

BINFO_VIRTUAL_P is used to specify whether the binfo is inherited virtually or not. The other flags, BINFO_MARKED_P and BINFO_FLAG_1 to BINFO_FLAG_6 can be used for language specific use.

The following macros can be used on a tree node representing a class-type.

LOCAL_CLASS_P

This predicate holds if the class is local class i.e. declared inside a function body.

TYPE_POLYMORPHIC_P

This predicate holds if the class has at least one virtual function (declared or inherited).

TYPE_HAS_DEFAULT_CONSTRUCTOR

This predicate holds whenever its argument represents a class-type with default constructor.

CLASSTYPE_HAS_MUTABLE

TYPE_HAS_MUTABLE_P

These predicates hold for a class-type having a mutable data member.

CLASSTYPE_NON_POD_P

This predicate holds only for class-types that are not PODs.

TYPE_HAS_NEW_OPERATOR

This predicate holds for a class-type that defines operator new.

TYPE_HAS_ARRAY_NEW_OPERATOR

This predicate holds for a class-type for which operator new[] is defined.

TYPE_OVERLOADS_CALL_EXPR

This predicate holds for class-type for which the function call operator() is overloaded.

TYPE_OVERLOADS_ARRAY_REF

This predicate holds for a class-type that overloads operator []

TYPE_OVERLOADS_ARROW

This predicate holds for a class-type for which operator-> is overloaded.

8.5 Declarations

This section covers the various kinds of declarations that appear in the internal representation, except for declarations of functions (represented by FUNCTION_DECL nodes), which are described in Section 8.6 [Functions], page 67.

Some macros can be used with any kind of declaration. These include:

DECL NAME

This macro returns an IDENTIFIER_NODE giving the name of the entity.

TREE_TYPE

This macro returns the type of the entity declared.

TREE_FILENAME

This macro returns the name of the file in which the entity was declared, as a char*. For an entity declared implicitly by the compiler (like __builtin_ memcpy), this will be the string "<internal>".

TREE_LINENO

This macro returns the line number at which the entity was declared, as an int.

DECL_ARTIFICIAL

This predicate holds if the declaration was implicitly generated by the compiler. For example, this predicate will hold of an implicitly declared member function, or of the TYPE_DECL implicitly generated for a class type. Recall that in C++ code like:

```
struct S {};
is roughly equivalent to C code like:
      struct S {};
      typedef struct S S;
```

The implicitly generated typedef declaration is represented by a TYPE_DECL for which DECL_ARTIFICIAL holds.

DECL_NAMESPACE_SCOPE_P

This predicate holds if the entity was declared at a namespace scope.

DECL_CLASS_SCOPE_P

This predicate holds if the entity was declared at a class scope.

DECL_FUNCTION_SCOPE_P

This predicate holds if the entity was declared inside a function body.

The various kinds of declarations include:

LABEL_DECL

These nodes are used to represent labels in function bodies. For more information, see Section 8.6 [Functions], page 67. These nodes only appear in block scopes.

CONST_DECL

These nodes are used to represent enumeration constants. The value of the constant is given by DECL_INITIAL which will be an INTEGER_CST with the same type as the TREE_TYPE of the CONST_DECL, i.e., an ENUMERAL_TYPE.

RESULT_DECL

These nodes represent the value returned by a function. When a value is assigned to a RESULT_DECL, that indicates that the value should be returned, via bitwise copy, by the function. You can use DECL_SIZE and DECL_ALIGN on a RESULT_DECL, just as with a VAR_DECL.

TYPE_DECL

These nodes represent typedef declarations. The TREE_TYPE is the type declared to have the name given by DECL_NAME. In some cases, there is no associated name.

VAR_DECL These nodes represent variables with namespace or block scope, as well as static data members. The DECL_SIZE and DECL_ALIGN are analogous to TYPE_SIZE and TYPE_ALIGN. For a declaration, you should always use the DECL_SIZE and DECL_ALIGN rather than the TYPE_SIZE and TYPE_ALIGN given by the TREE_TYPE, since special attributes may have been applied to the variable to give it a particular size and alignment. You may use the predicates DECL_THIS_STATIC or DECL_THIS_EXTERN to test whether the storage class specifiers static or extern were used to declare a variable.

If this variable is initialized (but does not require a constructor), the DECL_INITIAL will be an expression for the initializer. The initializer should be evaluated, and a bitwise copy into the variable performed. If the DECL_INITIAL is the error_mark_node, there is an initializer, but it is given by an explicit statement later in the code; no bitwise copy is required.

GCC provides an extension that allows either automatic variables, or global variables, to be placed in particular registers. This extension is being used for

a particular VAR_DECL if DECL_REGISTER holds for the VAR_DECL, and if DECL_ASSEMBLER_NAME is not equal to DECL_NAME. In that case, DECL_ASSEMBLER_NAME is the name of the register into which the variable will be placed.

PARM_DECL

Used to represent a parameter to a function. Treat these nodes similarly to VAR_DECL nodes. These nodes only appear in the DECL_ARGUMENTS for a FUNCTION_DECL.

The DECL_ARG_TYPE for a PARM_DECL is the type that will actually be used when a value is passed to this function. It may be a wider type than the TREE_TYPE of the parameter; for example, the ordinary type might be short while the DECL_ARG_TYPE is int.

FIELD DECL

These nodes represent non-static data members. The DECL_SIZE and DECL_ALIGN behave as for VAR_DECL nodes. The DECL_FIELD_BITPOS gives the first bit used for this field, as an INTEGER_CST. These values are indexed from zero, where zero indicates the first bit in the object.

If DECL_C_BIT_FIELD holds, this field is a bit-field.

NAMESPACE_DECL

See Section 8.4.1 [Namespaces], page 62.

TEMPLATE_DECL

These nodes are used to represent class, function, and variable (static data member) templates. The DECL_TEMPLATE_SPECIALIZATIONS are a TREE_LIST. The TREE_VALUE of each node in the list is a TEMPLATE_DECLs or FUNCTION_DECLs representing specializations (including instantiations) of this template. Back ends can safely ignore TEMPLATE_DECLs, but should examine FUNCTION_DECL nodes on the specializations list just as they would ordinary FUNCTION_DECL nodes.

For a class template, the DECL_TEMPLATE_INSTANTIATIONS list contains the instantiations. The TREE_VALUE of each node is an instantiation of the class. The DECL_TEMPLATE_SPECIALIZATIONS contains partial specializations of the class.

USING_DECL

Back ends can safely ignore these nodes.

8.6 Functions

A function is represented by a FUNCTION_DECL node. A set of overloaded functions is sometimes represented by a OVERLOAD node.

An OVERLOAD node is not a declaration, so none of the 'DECL_' macros should be used on an OVERLOAD. An OVERLOAD node is similar to a TREE_LIST. Use OVL_CURRENT to get the function associated with an OVERLOAD node; use OVL_NEXT to get the next OVERLOAD node in the list of overloaded functions. The macros OVL_CURRENT and OVL_NEXT are actually polymorphic; you can use them to work with FUNCTION_DECL nodes as well as with overloads. In the case of a FUNCTION_DECL, OVL_CURRENT will always return the function itself, and OVL_NEXT will always be NULL_TREE.

To determine the scope of a function, you can use the DECL_CONTEXT macro. This macro will return the class (either a RECORD_TYPE or a UNION_TYPE) or namespace (a NAMESPACE_DECL) of which the function is a member. For a virtual function, this macro returns the class in which the function was actually defined, not the base class in which the virtual declaration occurred.

If a friend function is defined in a class scope, the DECL_FRIEND_CONTEXT macro can be used to determine the class in which it was defined. For example, in

```
class C { friend void f() {} };
```

the DECL_CONTEXT for f will be the global_namespace, but the DECL_FRIEND_CONTEXT will be the RECORD TYPE for C.

In C, the DECL_CONTEXT for a function maybe another function. This representation indicates that the GNU nested function extension is in use. For details on the semantics of nested functions, see the GCC Manual. The nested function can refer to local variables in its containing function. Such references are not explicitly marked in the tree structure; back ends must look at the DECL_CONTEXT for the referenced VAR_DECL. If the DECL_CONTEXT for the referenced VAR_DECL is not the same as the function currently being processed, and neither DECL_EXTERNAL nor DECL_STATIC hold, then the reference is to a local variable in a containing function, and the back end must take appropriate action.

8.6.1 Function Basics

The following macros and functions can be used on a FUNCTION_DECL:

DECL_MAIN_P

This predicate holds for a function that is the program entry point ::code.

DECL_NAME

This macro returns the unqualified name of the function, as an IDENTIFIER_NODE. For an instantiation of a function template, the DECL_NAME is the unqualified name of the template, not something like f<int>. The value of DECL_NAME is undefined when used on a constructor, destructor, overloaded operator, or type-conversion operator, or any function that is implicitly generated by the compiler. See below for macros that can be used to distinguish these cases.

DECL_ASSEMBLER_NAME

This macro returns the mangled name of the function, also an IDENTIFIER_NODE. This name does not contain leading underscores on systems that prefix all identifiers with underscores. The mangled name is computed in the same way on all platforms; if special processing is required to deal with the object file format used on a particular platform, it is the responsibility of the back end to perform those modifications. (Of course, the back end should not modify DECL_ASSEMBLER_NAME itself.)

Using DECL_ASSEMBLER_NAME will cause additional memory to be allocated (for the mangled name of the entity) so it should be used only when emitting assembly code. It should not be used within the optimizers to determine whether or not two declarations are the same, even though some of the existing optimizers do use it in that way. These uses will be removed over time.

DECL_EXTERNAL

This predicate holds if the function is undefined.

TREE_PUBLIC

This predicate holds if the function has external linkage.

DECL LOCAL FUNCTION P

This predicate holds if the function was declared at block scope, even though it has a global scope.

DECL_ANTICIPATED

This predicate holds if the function is a built-in function but its prototype is not yet explicitly declared.

DECL_EXTERN_C_FUNCTION_P

This predicate holds if the function is declared as an 'extern "C"' function.

DECL LINKONCE P

This macro holds if multiple copies of this function may be emitted in various translation units. It is the responsibility of the linker to merge the various copies. Template instantiations are the most common example of functions for which DECL_LINKONCE_P holds; G++ instantiates needed templates in all translation units which require them, and then relies on the linker to remove duplicate instantiations.

FIXME: This macro is not yet implemented.

DECL_FUNCTION_MEMBER_P

This macro holds if the function is a member of a class, rather than a member of a namespace.

DECL_STATIC_FUNCTION_P

This predicate holds if the function a static member function.

DECL_NONSTATIC_MEMBER_FUNCTION_P

This macro holds for a non-static member function.

DECL_CONST_MEMFUNC_P

This predicate holds for a const-member function.

DECL_VOLATILE_MEMFUNC_P

This predicate holds for a volatile-member function.

DECL_CONSTRUCTOR_P

This macro holds if the function is a constructor.

DECL NONCONVERTING P

This predicate holds if the constructor is a non-converting constructor.

DECL_COMPLETE_CONSTRUCTOR_P

This predicate holds for a function which is a constructor for an object of a complete type.

DECL BASE CONSTRUCTOR P

This predicate holds for a function which is a constructor for a base class subobject.

DECL_COPY_CONSTRUCTOR_P

This predicate holds for a function which is a copy-constructor.

DECL_DESTRUCTOR_P

This macro holds if the function is a destructor.

DECL_COMPLETE_DESTRUCTOR_P

This predicate holds if the function is the destructor for an object a complete type.

DECL_OVERLOADED_OPERATOR_P

This macro holds if the function is an overloaded operator.

DECL_CONV_FN_P

This macro holds if the function is a type-conversion operator.

DECL_GLOBAL_CTOR_P

This predicate holds if the function is a file-scope initialization function.

DECL_GLOBAL_DTOR_P

This predicate holds if the function is a file-scope finalization function.

DECL_THUNK_P

This predicate holds if the function is a thunk.

These functions represent stub code that adjusts the this pointer and then jumps to another function. When the jumped-to function returns, control is transferred directly to the caller, without returning to the thunk. The first parameter to the thunk is always the this pointer; the thunk should add THUNK_DELTA to this value. (The THUNK_DELTA is an int, not an INTEGER_CST.)

Then, if THUNK_VCALL_OFFSET (an INTEGER_CST) is nonzero the adjusted this pointer must be adjusted again. The complete calculation is given by the following pseudo-code:

```
this += THUNK_DELTA
if (THUNK_VCALL_OFFSET)
  this += (*((ptrdiff_t **) this))[THUNK_VCALL_OFFSET]
```

Finally, the thunk should jump to the location given by DECL_INITIAL; this will always be an expression for the address of a function.

DECL NON THUNK FUNCTION P

This predicate holds if the function is *not* a thunk function.

GLOBAL_INIT_PRIORITY

If either DECL_GLOBAL_CTOR_P or DECL_GLOBAL_DTOR_P holds, then this gives the initialization priority for the function. The linker will arrange that all functions for which DECL_GLOBAL_CTOR_P holds are run in increasing order of priority before main is called. When the program exits, all functions for which DECL_GLOBAL_DTOR_P holds are run in the reverse order.

DECL_ARTIFICIAL

This macro holds if the function was implicitly generated by the compiler, rather than explicitly declared. In addition to implicitly generated class member functions, this macro holds for the special functions created to implement static initialization and destruction, to compute run-time type information, and so forth.

DECL_ARGUMENTS

This macro returns the PARM_DECL for the first argument to the function. Subsequent PARM_DECL nodes can be obtained by following the TREE_CHAIN links.

DECL_RESULT

This macro returns the RESULT_DECL for the function.

TREE_TYPE

This macro returns the FUNCTION_TYPE or METHOD_TYPE for the function.

TYPE RAISES EXCEPTIONS

This macro returns the list of exceptions that a (member-)function can raise. The returned list, if non NULL, is comprised of nodes whose TREE_VALUE represents a type.

TYPE_NOTHROW_P

This predicate holds when the exception-specification of its arguments if of the form '()'.

DECL_ARRAY_DELETE_OPERATOR_P

This predicate holds if the function an overloaded operator delete [].

8.6.2 Function Bodies

A function that has a definition in the current translation unit will have a non-NULL DECL_INITIAL. However, back ends should not make use of the particular value given by DECL_INITIAL.

The DECL_SAVED_TREE macro will give the complete body of the function.

8.6.2.1 Statements

There are tree nodes corresponding to all of the source-level statement constructs, used within the C and C++ frontends. These are enumerated here, together with a list of the various macros that can be used to obtain information about them. There are a few macros that can be used with all statements:

STMT_IS_FULL_EXPR_P

In C++, statements normally constitute "full expressions"; temporaries created during a statement are destroyed when the statement is complete. However, G++ sometimes represents expressions by statements; these statements will not have STMT_IS_FULL_EXPR_P set. Temporaries created during such statements should be destroyed when the innermost enclosing statement with STMT_IS_FULL_EXPR_P set is exited.

Here is the list of the various statement nodes, and the macros used to access them. This documentation describes the use of these nodes in non-template functions (including instantiations of template functions). In template functions, the same nodes are used, but sometimes in slightly different ways.

Many of the statements have substatements. For example, a while loop will have a body, which is itself a statement. If the substatement is NULL_TREE, it is considered equivalent to a statement consisting of a single;, i.e., an expression statement in which the expression has been omitted. A substatement may in fact be a list of statements, connected via their TREE_CHAINS. So, you should always process the statement tree by looping over substatements, like this:

```
void process_stmt (stmt)
    tree stmt;
{
    while (stmt)
      {
        switch (TREE_CODE (stmt))
        {
            case IF_STMT:
            process_stmt (THEN_CLAUSE (stmt));
            /* More processing here. */
            break;
            ...
        }
        stmt = TREE_CHAIN (stmt);
    }
}
```

In other words, while the **then** clause of an **if** statement in C++ can be only one statement (although that one statement may be a compound statement), the intermediate representation will sometimes use several statements chained together.

ASM_EXPR

Used to represent an inline assembly statement. For an inline assembly statement like:

```
asm ("mov x, y");
```

The ASM_STRING macro will return a STRING_CST node for "mov x, y". If the original statement made use of the extended-assembly syntax, then ASM_OUTPUTS, ASM_INPUTS, and ASM_CLOBBERS will be the outputs, inputs, and clobbers for the statement, represented as STRING_CST nodes. The extended-assembly syntax looks like:

```
asm ("fsinx %1,%0" : "=f" (result) : "f" (angle));
```

The first string is the ASM_STRING, containing the instruction template. The next two strings are the output and inputs, respectively; this statement has no clobbers. As this example indicates, "plain" assembly statements are merely a special case of extended assembly statements; they have no cv-qualifiers, outputs, inputs, or clobbers. All of the strings will be NUL-terminated, and will contain no embedded NUL-characters.

If the assembly statement is declared volatile, or if the statement was not an extended assembly statement, and is therefore implicitly volatile, then the predicate ASM_VOLATILE_P will hold of the ASM_EXPR.

BREAK_STMT

Used to represent a break statement. There are no additional fields.

CASE_LABEL_EXPR

Use to represent a case label, range of case labels, or a default label. If CASE_LOW is NULL_TREE, then this is a default label. Otherwise, if CASE_HIGH is NULL_TREE, then this is an ordinary case label. In this case, CASE_LOW is an expression giving the value of the label. Both CASE_LOW and CASE_HIGH are INTEGER_CST nodes. These values will have the same type as the condition expression in the switch statement.

Otherwise, if both CASE_LOW and CASE_HIGH are defined, the statement is a range of case labels. Such statements originate with the extension that allows users to write things of the form:

The first value will be CASE_LOW, while the second will be CASE_HIGH.

CLEANUP_STMT

Used to represent an action that should take place upon exit from the enclosing scope. Typically, these actions are calls to destructors for local objects, but back ends cannot rely on this fact. If these nodes are in fact representing such destructors, CLEANUP_DECL will be the VAR_DECL destroyed. Otherwise, CLEANUP_DECL will be NULL_TREE. In any case, the CLEANUP_EXPR is the expression to execute. The cleanups executed on exit from a scope should be run in the reverse order of the order in which the associated CLEANUP_STMTs were encountered.

CONTINUE_STMT

Used to represent a continue statement. There are no additional fields.

CTOR_STMT

Used to mark the beginning (if CTOR_BEGIN_P holds) or end (if CTOR_END_P holds of the main body of a constructor. See also SUBOBJECT for more information on how to use these nodes.

DECL_STMT

Used to represent a local declaration. The DECL_STMT_DECL macro can be used to obtain the entity declared. This declaration may be a LABEL_DECL, indicating that the label declared is a local label. (As an extension, GCC allows the declaration of labels with scope.) In C, this declaration may be a FUNCTION_DECL, indicating the use of the GCC nested function extension. For more information, see Section 8.6 [Functions], page 67.

DO_STMT

Used to represent a do loop. The body of the loop is given by DO_BODY while the termination condition for the loop is given by DO_COND. The condition for a do-statement is always an expression.

EMPTY_CLASS_EXPR

Used to represent a temporary object of a class with no data whose address is never taken. (All such objects are interchangeable.) The TREE_TYPE represents the type of the object.

EXPR_STMT

Used to represent an expression statement. Use EXPR_STMT_EXPR to obtain the expression.

FOR_STMT

Used to represent a for statement. The FOR_INIT_STMT is the initialization statement for the loop. The FOR_COND is the termination condition. The FOR_EXPR is the expression executed right before the FOR_COND on each loop iteration; often, this expression increments a counter. The body of the loop is given by

FOR_BODY. Note that FOR_INIT_STMT and FOR_BODY return statements, while FOR_COND and FOR_EXPR return expressions.

GOTO_EXPR

Used to represent a goto statement. The GOTO_DESTINATION will usually be a LABEL_DECL. However, if the "computed goto" extension has been used, the GOTO_DESTINATION will be an arbitrary expression indicating the destination. This expression will always have pointer type.

HANDLER

Used to represent a C++ catch block. The HANDLER_TYPE is the type of exception that will be caught by this handler; it is equal (by pointer equality) to NULL if this handler is for all types. HANDLER_PARMS is the DECL_STMT for the catch parameter, and HANDLER_BODY is the code for the block itself.

IF_STMT

Used to represent an if statement. The IF_COND is the expression.

If the condition is a TREE_LIST, then the TREE_PURPOSE is a statement (usually a DECL_STMT). Each time the condition is evaluated, the statement should be executed. Then, the TREE_VALUE should be used as the conditional expression itself. This representation is used to handle C++ code like this:

if (int
$$i = 7$$
) ...

where there is a new local variable (or variables) declared within the condition. The THEN_CLAUSE represents the statement given by the then condition, while the ELSE_CLAUSE represents the statement given by the else condition.

LABEL_EXPR

Used to represent a label. The LABEL_DECL declared by this statement can be obtained with the LABEL_EXPR_LABEL macro. The IDENTIFIER_NODE giving the name of the label can be obtained from the LABEL_DECL with DECL_NAME.

RETURN_INIT

If the function uses the G++ "named return value" extension, meaning that the function has been defined like:

```
S f(int) return s {...}
```

then there will be a RETURN_INIT. There is never a named returned value for a constructor. The first argument to the RETURN_INIT is the name of the object returned; the second argument is the initializer for the object. The object is initialized when the RETURN_INIT is encountered. The object referred to is the actual object returned; this extension is a manual way of doing the "return-value optimization". Therefore, the object must actually be constructed in the place where the object will be returned.

RETURN_STMT

Used to represent a return statement. The RETURN_EXPR is the expression returned; it will be NULL_TREE if the statement was just

return;

SUBOBJECT

In a constructor, these nodes are used to mark the point at which a subobject of this is fully constructed. If, after this point, an exception is thrown before a

CTOR_STMT with CTOR_END_P set is encountered, the SUBOBJECT_CLEANUP must be executed. The cleanups must be executed in the reverse order in which they appear.

SWITCH_STMT

Used to represent a switch statement. The SWITCH_COND is the expression on which the switch is occurring. See the documentation for an IF_STMT for more information on the representation used for the condition. The SWITCH_BODY is the body of the switch statement. The SWITCH_TYPE is the original type of switch expression as given in the source, before any compiler conversions.

TRY_BLOCK

Used to represent a **try** block. The body of the try block is given by TRY_STMTS. Each of the catch blocks is a HANDLER node. The first handler is given by TRY_HANDLERS. Subsequent handlers are obtained by following the TREE_CHAIN link from one handler to the next. The body of the handler is given by HANDLER_BODY.

If CLEANUP_P holds of the TRY_BLOCK, then the TRY_HANDLERS will not be a HANDLER node. Instead, it will be an expression that should be executed if an exception is thrown in the try block. It must rethrow the exception after executing that code. And, if an exception is thrown while the expression is executing, terminate must be called.

USING_STMT

Used to represent a using directive. The namespace is given by USING_STMT_NAMESPACE, which will be a NAMESPACE_DECL. This node is needed inside template functions, to implement using directives during instantiation.

WHILE_STMT

Used to represent a while loop. The WHILE_COND is the termination condition for the loop. See the documentation for an IF_STMT for more information on the representation used for the condition.

The WHILE_BODY is the body of the loop.

8.7 Attributes in trees

Attributes, as specified using the <code>__attribute__</code> keyword, are represented internally as a <code>TREE_LIST</code>. The <code>TREE_PURPOSE</code> is the name of the attribute, as an <code>IDENTIFIER_NODE</code>. The <code>TREE_VALUE</code> is a <code>TREE_LIST</code> of the arguments of the attribute, if any, or <code>NULL_TREE</code> if there are no arguments; the arguments are stored as the <code>TREE_VALUE</code> of successive entries in the list, and may be identifiers or expressions. The <code>TREE_CHAIN</code> of the attribute is the next attribute in a list of attributes applying to the same declaration or type, or <code>NULL_TREE</code> if there are no further attributes in the list.

Attributes may be attached to declarations and to types; these attributes may be accessed with the following macros. All attributes are stored in this way, and many also cause other changes to the declaration or type or to other internal compiler data structures.

tree DECL_ATTRIBUTES (tree dec1)

[Tree Macro]

This macro returns the attributes on the declaration decl.

```
tree TYPE_ATTRIBUTES (tree type)
```

[Tree Macro]

This macro returns the attributes on the type type.

8.8 Expressions

The internal representation for expressions is for the most part quite straightforward. However, there are a few facts that one must bear in mind. In particular, the expression "tree" is actually a directed acyclic graph. (For example there may be many references to the integer constant zero throughout the source program; many of these will be represented by the same expression node.) You should not rely on certain kinds of node being shared, nor should rely on certain kinds of nodes being unshared.

The following macros can be used with all expression nodes:

TREE_TYPE

Returns the type of the expression. This value may not be precisely the same type that would be given the expression in the original program.

In what follows, some nodes that one might expect to always have type bool are documented to have either integral or boolean type. At some point in the future, the C front end may also make use of this same intermediate representation, and at this point these nodes will certainly have integral type. The previous sentence is not meant to imply that the C++ front end does not or will not give these nodes integral type.

Below, we list the various kinds of expression nodes. Except where noted otherwise, the operands to an expression are accessed using the TREE_OPERAND macro. For example, to access the first operand to a binary plus expression expr, use:

```
TREE_OPERAND (expr, 0)
```

As this example indicates, the operands are zero-indexed.

The table below begins with constants, moves on to unary expressions, then proceeds to binary expressions, and concludes with various other kinds of expressions:

INTEGER_CST

These nodes represent integer constants. Note that the type of these constants is obtained with TREE_TYPE; they are not always of type int. In particular, char constants are represented with INTEGER_CST nodes. The value of the integer constant e is given by

```
((TREE_INT_CST_HIGH (e) << HOST_BITS_PER_WIDE_INT)
+ TREE_INST_CST_LOW (e))</pre>
```

HOST_BITS_PER_WIDE_INT is at least thirty-two on all platforms. Both TREE_INT_CST_HIGH and TREE_INT_CST_LOW return a HOST_WIDE_INT. The value of an INTEGER_CST is interpreted as a signed or unsigned quantity depending on the type of the constant. In general, the expression given above will overflow, so it should not be used to calculate the value of the constant.

The variable integer_zero_node is an integer constant with value zero. Similarly, integer_one_node is an integer constant with value one. The size_zero_node and size_one_node variables are analogous, but have type size_t rather than int.

The function tree_int_cst_lt is a predicate which holds if its first argument is less than its second. Both constants are assumed to have the same signedness (i.e., either both should be signed or both should be unsigned.) The full

width of the constant is used when doing the comparison; the usual rules about promotions and conversions are ignored. Similarly, tree_int_cst_equal holds if the two constants are equal. The tree_int_cst_sgn function returns the sign of a constant. The value is 1, 0, or -1 according on whether the constant is greater than, equal to, or less than zero. Again, the signedness of the constant's type is taken into account; an unsigned constant is never less than zero, no matter what its bit-pattern.

REAL_CST

FIXME: Talk about how to obtain representations of this constant, do comparisons, and so forth.

COMPLEX_CST

These nodes are used to represent complex number constants, that is a __complex_ whose parts are constant nodes. The TREE_REALPART and TREE_IMAGPART return the real and the imaginary parts respectively.

VECTOR_CST

These nodes are used to represent vector constants, whose parts are constant nodes. Each individual constant node is either an integer or a double constant node. The first operand is a TREE_LIST of the constant nodes and is accessed through TREE_VECTOR_CST_ELTS.

STRING_CST

These nodes represent string-constants. The TREE_STRING_LENGTH returns the length of the string, as an int. The TREE_STRING_POINTER is a char* containing the string itself. The string may not be NUL-terminated, and it may contain embedded NUL characters. Therefore, the TREE_STRING_LENGTH includes the trailing NUL if it is present.

For wide string constants, the TREE_STRING_LENGTH is the number of bytes in the string, and the TREE_STRING_POINTER points to an array of the bytes of the string, as represented on the target system (that is, as integers in the target endianness). Wide and non-wide string constants are distinguished only by the TREE_TYPE of the STRING_CST.

FIXME: The formats of string constants are not well-defined when the target system bytes are not the same width as host system bytes.

PTRMEM_CST

These nodes are used to represent pointer-to-member constants. The PTRMEM_CST_CLASS is the class type (either a RECORD_TYPE or UNION_TYPE within which the pointer points), and the PTRMEM_CST_MEMBER is the declaration for the pointed to object. Note that the DECL_CONTEXT for the PTRMEM_CST_MEMBER is in general different from the PTRMEM_CST_CLASS. For example, given:

```
struct B { int i; };
struct D : public B {};
int D::*dp = &D::i;
```

The PTRMEM_CST_CLASS for &D::i is D, even though the DECL_CONTEXT for the PTRMEM_CST_MEMBER is B, since B::i is a member of B, not D.

VAR_DECL

These nodes represent variables, including static data members. For more information, see Section 8.5 [Declarations], page 65.

NEGATE_EXPR

These nodes represent unary negation of the single operand, for both integer and floating-point types. The type of negation can be determined by looking at the type of the expression.

The behavior of this operation on signed arithmetic overflow is controlled by the flag_wrapv and flag_trapv variables.

ABS_EXPR These nodes represent the absolute value of the single operand, for both integer and floating-point types. This is typically used to implement the abs, labs and llabs builtins for integer types, and the fabs, fabsf and fabsl builtins for floating point types. The type of abs operation can be determined by looking at the type of the expression.

This node is not used for complex types. To represent the modulus or complex abs of a complex value, use the BUILT_IN_CABS, BUILT_IN_CABSF or BUILT_IN_CABSL builtins, as used to implement the C99 cabs, cabsf and cabsl built-in functions.

BIT_NOT_EXPR

These nodes represent bitwise complement, and will always have integral type. The only operand is the value to be complemented.

TRUTH_NOT_EXPR

These nodes represent logical negation, and will always have integral (or boolean) type. The operand is the value being negated. The type of the operand and that of the result are always of BOOLEAN_TYPE or INTEGER_TYPE.

PREDECREMENT_EXPR PREINCREMENT_EXPR POSTDECREMENT_EXPR POSTINCREMENT_EXPR

These nodes represent increment and decrement expressions. The value of the single operand is computed, and the operand incremented or decremented. In the case of PREDECREMENT_EXPR and PREINCREMENT_EXPR, the value of the expression is the value resulting after the increment or decrement; in the case of POSTDECREMENT_EXPR and POSTINCREMENT_EXPR is the value before the increment or decrement occurs. The type of the operand, like that of the result, will be either integral, boolean, or floating-point.

ADDR_EXPR

These nodes are used to represent the address of an object. (These expressions will always have pointer or reference type.) The operand may be another expression, or it may be a declaration.

As an extension, GCC allows users to take the address of a label. In this case, the operand of the ADDR_EXPR will be a LABEL_DECL. The type of such an expression is void*.

If the object addressed is not an lvalue, a temporary is created, and the address of the temporary is used.

INDIRECT_REF

These nodes are used to represent the object pointed to by a pointer. The operand is the pointer being dereferenced; it will always have pointer or reference type.

FIX_TRUNC_EXPR

These nodes represent conversion of a floating-point value to an integer. The single operand will have a floating-point type, while the the complete expression will have an integral (or boolean) type. The operand is rounded towards zero.

FLOAT_EXPR

These nodes represent conversion of an integral (or boolean) value to a floating-point value. The single operand will have integral type, while the complete expression will have a floating-point type.

FIXME: How is the operand supposed to be rounded? Is this dependent on '-mieee'?

COMPLEX_EXPR

These nodes are used to represent complex numbers constructed from two expressions of the same (integer or real) type. The first operand is the real part and the second operand is the imaginary part.

CONJ_EXPR

These nodes represent the conjugate of their operand.

REALPART_EXPR

IMAGPART EXPR

These nodes represent respectively the real and the imaginary parts of complex numbers (their sole argument).

NON_LVALUE_EXPR

These nodes indicate that their one and only operand is not an lvalue. A back end can treat these identically to the single operand.

NOP_EXPR These nodes are used to represent conversions that do not require any codegeneration. For example, conversion of a char* to an int* does not require any code be generated; such a conversion is represented by a NOP_EXPR. The single operand is the expression to be converted. The conversion from a pointer to a reference is also represented with a NOP_EXPR.

CONVERT_EXPR

These nodes are similar to NOP_EXPRs, but are used in those situations where code may need to be generated. For example, if an <code>int*</code> is converted to an <code>int</code> code may need to be generated on some platforms. These nodes are never used for C++-specific conversions, like conversions between pointers to different classes in an inheritance hierarchy. Any adjustments that need to be made in such cases are always indicated explicitly. Similarly, a user-defined conversion is never represented by a <code>CONVERT_EXPR</code>; instead, the function calls are made explicit.

THROW_EXPR

These nodes represent throw expressions. The single operand is an expression for the code that should be executed to throw the exception. However, there

is one implicit action not represented in that expression; namely the call to __throw. This function takes no arguments. If setjmp/longjmp exceptions are used, the function __sjthrow is called instead. The normal GCC back end uses the function emit_throw to generate this code; you can examine this function to see what needs to be done.

LSHIFT_EXPR RSHIFT_EXPR

These nodes represent left and right shifts, respectively. The first operand is the value to shift; it will always be of integral type. The second operand is an expression for the number of bits by which to shift. Right shift should be treated as arithmetic, i.e., the high-order bits should be zero-filled when the expression has unsigned type and filled with the sign bit when the expression has signed type. Note that the result is undefined if the second operand is larger than or equal to the first operand's type size.

BIT_IOR_EXPR BIT_XOR_EXPR BIT_AND_EXPR

These nodes represent bitwise inclusive or, bitwise exclusive or, and bitwise and, respectively. Both operands will always have integral type.

TRUTH_ANDIF_EXPR
TRUTH_ORIF_EXPR

These nodes represent logical and and logical or, respectively. These operators are not strict; i.e., the second operand is evaluated only if the value of the expression is not determined by evaluation of the first operand. The type of the operands and that of the result are always of BOOLEAN_TYPE or INTEGER_TYPE.

TRUTH_AND_EXPR
TRUTH_OR_EXPR
TRUTH XOR EXPR

These nodes represent logical and, logical or, and logical exclusive or. They are strict; both arguments are always evaluated. There are no corresponding operators in C or C++, but the front end will sometimes generate these expressions anyhow, if it can tell that strictness does not matter. The type of the operands and that of the result are always of BOOLEAN_TYPE or INTEGER_TYPE.

PLUS_EXPR MINUS_EXPR MULT_EXPR

These nodes represent various binary arithmetic operations. Respectively, these operations are addition, subtraction (of the second operand from the first) and multiplication. Their operands may have either integral or floating type, but there will never be case in which one operand is of floating type and the other is of integral type.

The behavior of these operations on signed arithmetic overflow is controlled by the flag_wrapv and flag_trapv variables.

RDIV_EXPR

This node represents a floating point division operation.

TRUNC_DIV_EXPR FLOOR_DIV_EXPR CEIL_DIV_EXPR ROUND_DIV_EXPR

These nodes represent integer division operations that return an integer result. TRUNC_DIV_EXPR rounds towards zero, FLOOR_DIV_EXPR rounds towards negative infinity, CEIL_DIV_EXPR rounds towards positive infinity and ROUND_DIV_EXPR rounds to the closest integer. Integer division in C and C++ is truncating, i.e. TRUNC_DIV_EXPR.

The behavior of these operations on signed arithmetic overflow, when dividing the minimum signed integer by minus one, is controlled by the flag_wrapv and flag_trapv variables.

TRUNC_MOD_EXPR FLOOR_MOD_EXPR CEIL_MOD_EXPR ROUND_MOD_EXPR

These nodes represent the integer remainder or modulus operation. The integer modulus of two operands a and b is defined as a - (a/b)*b where the division calculated using the corresponding division operator. Hence for TRUNC_MOD_EXPR this definition assumes division using truncation towards zero, i.e. TRUNC_DIV_EXPR. Integer remainder in C and C++ uses truncating division, i.e. TRUNC_MOD_EXPR.

EXACT_DIV_EXPR

The EXACT_DIV_EXPR code is used to represent integer divisions where the numerator is known to be an exact multiple of the denominator. This allows the backend to choose between the faster of TRUNC_DIV_EXPR, CEIL_DIV_EXPR and FLOOR_DIV_EXPR for the current target.

ARRAY_REF

These nodes represent array accesses. The first operand is the array; the second is the index. To calculate the address of the memory accessed, you must scale the index by the size of the type of the array elements. The type of these expressions must be the type of a component of the array. The third and fourth operands are used after gimplification to represent the lower bound and component size but should not be used directly; call array_ref_low_bound and array_ref_element_size instead.

ARRAY_RANGE_REF

These nodes represent access to a range (or "slice") of an array. The operands are the same as that for ARRAY_REF and have the same meanings. The type of these expressions must be an array whose component type is the same as that of the first operand. The range of that array type determines the amount of data these expressions access.

LT_EXPR LE_EXPR GT_EXPR GE_EXPR EQ_EXPR

NE_EXPR

These nodes represent the less than, less than or equal to, greater than, greater than or equal to, equal, and not equal comparison operators. The first and second operand with either be both of integral type or both of floating type. The result type of these expressions will always be of integral or boolean type. These operations return the result type's zero value for false, and the result type's one value for true.

For floating point comparisons, if we honor IEEE NaNs and either operand is NaN, then NE_EXPR always returns true and the remaining operators always return false. On some targets, comparisons against an IEEE NaN, other than equality and inequality, may generate a floating point exception.

ORDERED_EXPR UNORDERED EXPR

These nodes represent non-trapping ordered and unordered comparison operators. These operations take two floating point operands and determine whether they are ordered or unordered relative to each other. If either operand is an IEEE NaN, their comparison is defined to be unordered, otherwise the comparison is defined to be ordered. The result type of these expressions will always be of integral or boolean type. These operations return the result type's zero value for false, and the result type's one value for true.

UNLT_EXPR UNLE_EXPR UNGT_EXPR UNGE_EXPR UNEQ_EXPR LTGT_EXPR

These nodes represent the unordered comparison operators. These operations take two floating point operands and determine whether the operands are unordered or are less than, less than or equal to, greater than, greater than or equal to, or equal respectively. For example, UNLT_EXPR returns true if either operand is an IEEE NaN or the first operand is less than the second. With the possible exception of LTGT_EXPR, all of these operations are guaranteed not to generate a floating point exception. The result type of these expressions will always be of integral or boolean type. These operations return the result type's zero value for false, and the result type's one value for true.

MODIFY EXPR

These nodes represent assignment. The left-hand side is the first operand; the right-hand side is the second operand. The left-hand side will be a VAR_DECL, INDIRECT_REF, COMPONENT_REF, or other lvalue.

These nodes are used to represent not only assignment with '=' but also compound assignments (like '+='), by reduction to '=' assignment. In other words, the representation for 'i += 3' looks just like that for 'i = i + 3'.

INIT_EXPR

These nodes are just like MODIFY_EXPR, but are used only when a variable is initialized, rather than assigned to subsequently.

COMPONENT REF

These nodes represent non-static data member accesses. The first operand is the object (rather than a pointer to it); the second operand is the FIELD_DECL for the data member. The third operand represents the byte offset of the field, but should not be used directly; call component_ref_field_offset instead.

COMPOUND_EXPR

These nodes represent comma-expressions. The first operand is an expression whose value is computed and thrown away prior to the evaluation of the second operand. The value of the entire expression is the value of the second operand.

COND EXPR

These nodes represent ?: expressions. The first operand is of boolean or integral type. If it evaluates to a nonzero value, the second operand should be evaluated, and returned as the value of the expression. Otherwise, the third operand is evaluated, and returned as the value of the expression.

The second operand must have the same type as the entire expression, unless it unconditionally throws an exception or calls a noreturn function, in which case it should have void type. The same constraints apply to the third operand. This allows array bounds checks to be represented conveniently as $(i \ge 0 \&\& i < 10)$? i : abort().

As a GNU extension, the C language front-ends allow the second operand of the ?: operator may be omitted in the source. For example, x ? : 3 is equivalent to x ? x : 3, assuming that x is an expression without side-effects. In the tree representation, however, the second operand is always present, possibly protected by SAVE_EXPR if the first argument does cause side-effects.

CALL_EXPR

These nodes are used to represent calls to functions, including non-static member functions. The first operand is a pointer to the function to call; it is always an expression whose type is a POINTER_TYPE. The second argument is a TREE_LIST. The arguments to the call appear left-to-right in the list. The TREE_VALUE of each list node contains the expression corresponding to that argument. (The value of TREE_PURPOSE for these nodes is unspecified, and should be ignored.) For non-static member functions, there will be an operand corresponding to the this pointer. There will always be expressions corresponding to all of the arguments, even if the function is declared with default arguments and some arguments are not explicitly provided at the call sites.

STMT_EXPR

These nodes are used to represent GCC's statement-expression extension. The statement-expression extension allows code like this:

```
int f() { return ({ int j; j = 3; j + 7; }); }
```

In other words, an sequence of statements may occur where a single expression would normally appear. The STMT_EXPR node represents such an expression. The STMT_EXPR_STMT gives the statement contained in the expression. The value of the expression is the value of the last sub-statement in the body. More precisely, the value is the value computed by the last statement nested inside BIND_EXPR, TRY_FINALLY_EXPR, or TRY_CATCH_EXPR. For example, in:

```
({3;})
```

the value is 3 while in:

$$(\{ if (x) \{ 3; \} \})$$

there is no value. If the STMT_EXPR does not yield a value, it's type will be void.

BIND_EXPR

These nodes represent local blocks. The first operand is a list of variables, connected via their TREE_CHAIN field. These will never require cleanups. The scope of these variables is just the body of the BIND_EXPR. The body of the BIND_EXPR is the second operand.

LOOP_EXPR

These nodes represent "infinite" loops. The LOOP_EXPR_BODY represents the body of the loop. It should be executed forever, unless an EXIT_EXPR is encountered.

EXIT_EXPR

These nodes represent conditional exits from the nearest enclosing LOOP_EXPR. The single operand is the condition; if it is nonzero, then the loop should be exited. An EXIT_EXPR will only appear within a LOOP_EXPR.

CLEANUP_POINT_EXPR

These nodes represent full-expressions. The single operand is an expression to evaluate. Any destructor calls engendered by the creation of temporaries during the evaluation of that expression should be performed immediately after the expression is evaluated.

CONSTRUCTOR

These nodes represent the brace-enclosed initializers for a structure or array. The first operand is reserved for use by the back end. The second operand is a TREE_LIST. If the TREE_TYPE of the CONSTRUCTOR is a RECORD_TYPE or UNION_TYPE, then the TREE_PURPOSE of each node in the TREE_LIST will be a FIELD_DECL and the TREE_VALUE of each node will be the expression used to initialize that field.

If the TREE_TYPE of the CONSTRUCTOR is an ARRAY_TYPE, then the TREE_PURPOSE of each element in the TREE_LIST will be an INTEGER_CST or a RANGE_EXPR of two INTEGER_CSTs. A single INTEGER_CST indicates which element of the array (indexed from zero) is being assigned to. A RANGE_EXPR indicates an inclusive range of elements to initialize. In both cases the TREE_VALUE is the corresponding initializer. It is re-evaluated for each element of a RANGE_EXPR. If the TREE_PURPOSE is NULL_TREE, then the initializer is for the next available array element.

In the front end, you should not depend on the fields appearing in any particular order. However, in the middle end, fields must appear in declaration order. You should not assume that all fields will be represented. Unrepresented fields will be set to zero.

COMPOUND_LITERAL_EXPR

These nodes represent ISO C99 compound literals. The COMPOUND_LITERAL_EXPR_DECL_STMT is a DECL_STMT containing an anonymous VAR_DECL for the unnamed object represented by the compound literal; the DECL_INITIAL of that VAR_DECL is a CONSTRUCTOR representing the brace-enclosed list of initializers in the compound literal. That anonymous VAR_DECL can also be accessed directly by the COMPOUND_LITERAL_EXPR_DECL macro.

SAVE_EXPR

A SAVE_EXPR represents an expression (possibly involving side-effects) that is used more than once. The side-effects should occur only the first time the expression is evaluated. Subsequent uses should just reuse the computed value. The first operand to the SAVE_EXPR is the expression to evaluate. The side-effects should be executed where the SAVE_EXPR is first encountered in a depth-first preorder traversal of the expression tree.

TARGET_EXPR

A TARGET_EXPR represents a temporary object. The first operand is a VAR_DECL for the temporary variable. The second operand is the initializer for the temporary. The initializer is evaluated and, if non-void, copied (bitwise) into the temporary. If the initializer is void, that means that it will perform the initialization itself.

Often, a TARGET_EXPR occurs on the right-hand side of an assignment, or as the second operand to a comma-expression which is itself the right-hand side of an assignment, etc. In this case, we say that the TARGET_EXPR is "normal"; otherwise, we say it is "orphaned". For a normal TARGET_EXPR the temporary variable should be treated as an alias for the left-hand side of the assignment, rather than as a new temporary variable.

The third operand to the TARGET_EXPR, if present, is a cleanup-expression (i.e., destructor call) for the temporary. If this expression is orphaned, then this expression must be executed when the statement containing this expression is complete. These cleanups must always be executed in the order opposite to that in which they were encountered. Note that if a temporary is created on one branch of a conditional operator (i.e., in the second or third operand to a COND_EXPR), the cleanup must be run only if that branch is actually executed. See STMT_IS_FULL_EXPR_P for more information about running these cleanups.

AGGR INIT EXPR

An AGGR_INIT_EXPR represents the initialization as the return value of a function call, or as the result of a constructor. An AGGR_INIT_EXPR will only appear as a full-expression, or as the second operand of a TARGET_EXPR. The first operand to the AGGR_INIT_EXPR is the address of a function to call, just as in a CALL_EXPR. The second operand are the arguments to pass that function, as a TREE_LIST, again in a manner similar to that of a CALL_EXPR.

If AGGR_INIT_VIA_CTOR_P holds of the AGGR_INIT_EXPR, then the initialization is via a constructor call. The address of the third operand of the AGGR_INIT_EXPR, which is always a VAR_DECL, is taken, and this value replaces the first argument in the argument list.

In either case, the expression is void.

VA_ARG_EXPR

This node is used to implement support for the C/C++ variable argument-list mechanism. It represents expressions like va_arg (ap, type). Its TREE_TYPE yields the tree representation for type and its sole argument yields the representation for ap.

9 Analysis and Optimization of GIMPLE Trees

GCC uses three main intermediate languages to represent the program during compilation: GENERIC, GIMPLE and RTL. GENERIC is a language-independent representation generated by each front end. It is used to serve as an interface between the parser and optimizer. GENERIC is a common representation that is able to represent programs written in all the languages supported by GCC.

GIMPLE and RTL are used to optimize the program. GIMPLE is used for target and language independent optimizations (e.g., inlining, constant propagation, tail call elimination, redundancy elimination, etc). Much like GENERIC, GIMPLE is a language independent, tree based representation. However, it differs from GENERIC in that the GIMPLE grammar is more restrictive: expressions contain no more than 3 operands (except function calls), it has no control flow structures and expressions with side-effects are only allowed on the right hand side of assignments. See the chapter describing GENERIC and GIMPLE for more details.

This chapter describes the data structures and functions used in the GIMPLE optimizers (also known as "tree optimizers" or "middle end"). In particular, it focuses on all the macros, data structures, functions and programming constructs needed to implement optimization passes for GIMPLE.

9.1 GENERIC

The purpose of GENERIC is simply to provide a language-independent way of representing an entire function in trees. To this end, it was necessary to add a few new tree codes to the back end, but most everything was already there. If you can express it with the codes in gcc/tree.def, it's GENERIC.

Early on, there was a great deal of debate about how to think about statements in a tree IL. In GENERIC, a statement is defined as any expression whose value, if any, is ignored. A statement will always have TREE_SIDE_EFFECTS set (or it will be discarded), but a non-statement expression may also have side effects. A CALL_EXPR, for instance.

It would be possible for some local optimizations to work on the GENERIC form of a function; indeed, the adapted tree inliner works fine on GENERIC, but the current compiler performs inlining after lowering to GIMPLE (a restricted form described in the next section). Indeed, currently the frontends perform this lowering before handing off to tree_rest_of_compilation, but this seems inelegant.

If necessary, a front end can use some language-dependent tree codes in its GENERIC representation, so long as it provides a hook for converting them to GIMPLE and doesn't expect them to work with any (hypothetical) optimizers that run before the conversion to GIMPLE. The intermediate representation used while parsing C and C++ looks very little like GENERIC, but the C and C++ gimplifier hooks are perfectly happy to take it as input and spit out GIMPLE.

9.2 GIMPLE

GIMPLE is a simplified subset of GENERIC for use in optimization. The particular subset chosen (and the name) was heavily influenced by the

SIMPLE IL used by the McCAT compiler project at McGill University (http://www-acaps.cs.mcgill.ca/info/McCAT/McCAT.html), though we have made some different choices. For one thing, SIMPLE doesn't support goto; a production compiler can't afford that kind of restriction.

GIMPLE retains much of the structure of the parse trees: lexical scopes are represented as containers, rather than markers. However, expressions are broken down into a 3-address form, using temporary variables to hold intermediate values. Also, control structures are lowered to gotos.

In GIMPLE no container node is ever used for its value; if a COND_EXPR or BIND_EXPR has a value, it is stored into a temporary within the controlled blocks, and that temporary is used in place of the container.

The compiler pass which lowers GENERIC to GIMPLE is referred to as the 'gimplifier'. The gimplifier works recursively, replacing complex statements with sequences of simple statements.

9.2.1 Interfaces

The tree representation of a function is stored in DECL_SAVED_TREE. It is lowered to GIM-PLE by a call to gimplify_function_tree.

If a front end wants to include language-specific tree codes in the tree representation which it provides to the back end, it must provide a definition of LANG_HOOKS_GIMPLIFY_EXPR which knows how to convert the front end trees to GIMPLE. Usually such a hook will involve much of the same code for expanding front end trees to RTL. This function can return fully lowered GIMPLE, or it can return GENERIC trees and let the main gimplifier lower them the rest of the way; this is often simpler.

The C and C++ front ends currently convert directly from front end trees to GIMPLE, and hand that off to the back end rather than first converting to GENERIC. Their gimplifier hooks know about all the _STMT nodes and how to convert them to GENERIC forms. There was some work done on a genericization pass which would run first, but the existence of STMT_EXPR meant that in order to convert all of the C statements into GENERIC equivalents would involve walking the entire tree anyway, so it was simpler to lower all the way. This might change in the future if someone writes an optimization pass which would work better with higher-level trees, but currently the optimizers all expect GIMPLE.

A front end which wants to use the tree optimizers (and already has some sort of whole-function tree representation) only needs to provide a definition of LANG_HOOKS_GIMPLIFY_EXPR, call gimplify_function_tree to lower to GIMPLE, and then hand off to tree_rest_of_compilation to compile and output the function.

You can tell the compiler to dump a C-like representation of the GIMPLE form with the flag '-fdump-tree-gimple'.

9.2.2 Temporaries

When gimplification encounters a subexpression which is too complex, it creates a new temporary variable to hold the value of the subexpression, and adds a new statement to initialize it before the current statement. These special temporaries are known as 'expression temporaries', and are allocated using get_formal_tmp_var. The compiler tries to always

evaluate identical expressions into the same temporary, to simplify elimination of redundant calculations.

We can only use expression temporaries when we know that it will not be reevaluated before its value is used, and that it will not be otherwise modified¹. Other temporaries can be allocated using get_initialized_tmp_var or create_tmp_var.

Currently, an expression like a=b+5 is not reduced any further. We tried converting it to something like

```
T1 = b + 5;
a = T1;
```

but this bloated the representation for minimal benefit. However, a variable which must live in memory cannot appear in an expression; its value is explicitly loaded into a temporary first. Similarly, storing the value of an expression to a memory variable goes through a temporary.

9.2.3 Expressions

In general, expressions in GIMPLE consist of an operation and the appropriate number of simple operands; these operands must either be a GIMPLE rvalue (is_gimple_val), i.e. a constant or a register variable. More complex operands are factored out into temporaries, so that

```
a = b + c + d
becomes

T1 = b + c;
a = T1 + d;
```

The same rule holds for arguments to a CALL_EXPR.

The target of an assignment is usually a variable, but can also be an INDIRECT_REF or a compound lvalue as described below.

9.2.3.1 Compound Expressions

The left-hand side of a C comma expression is simply moved into a separate statement.

9.2.3.2 Compound Lyalues

Currently compound lvalues involving array and structure field references are not broken down; an expression like a.b[2] = 42 is not reduced any further (though complex array subscripts are). This restriction is a workaround for limitations in later optimizers; if we were to convert this to

```
T1 = &a.b;

T1[2] = 42;
```

alias analysis would not remember that the reference to T1[2] came by way of a.b, so it would think that the assignment could alias another member of a; this broke struct-alias-1.c. Future optimizer improvements may make this limitation unnecessary.

9.2.3.3 Conditional Expressions

A C?: expression is converted into an if statement with each branch assigning to the same temporary. So,

¹ These restrictions are derived from those in Morgan 4.8.

```
a = b ? c : d;
becomes
  if (b)
    T1 = c;
  else
    T1 = d;
  a = T1:
```

Tree level if-conversion pass re-introduces ?: expression, if appropriate. It is used to vectorize loops with conditions using vector conditional operations.

Note that in GIMPLE, if statements are also represented using COND_EXPR, as described below.

9.2.3.4 Logical Operators

Except when they appear in the condition operand of a COND_EXPR, logical 'and' and 'or' operators are simplified as follows: a = b && c becomes

```
T1 = (bool)b;
if (T1)
T1 = (bool)c;
a = T1:
```

Note that T1 in this example cannot be an expression temporary, because it has two different assignments.

9.2.4 Statements

Most statements will be assignment statements, represented by MODIFY_EXPR. A CALL_EXPR whose value is ignored can also be a statement. No other C expressions can appear at statement level; a reference to a volatile object is converted into a MODIFY_EXPR. In GIMPLE form, type of MODIFY_EXPR is not meaningful. Instead, use type of LHS or RHS.

There are also several varieties of complex statements.

9.2.4.1 Blocks

Block scopes and the variables they declare in GENERIC and GIMPLE are expressed using the BIND_EXPR code, which in previous versions of GCC was primarily used for the C statement-expression extension.

Variables in a block are collected into BIND_EXPR_VARS in declaration order. Any runtime initialization is moved out of DECL_INITIAL and into a statement in the controlled block. When gimplifying from C or C++, this initialization replaces the DECL_STMT.

Variable-length arrays (VLAs) complicate this process, as their size often refers to variables initialized earlier in the block. To handle this, we currently split the block at that point, and move the VLA into a new, inner BIND_EXPR. This strategy may change in the future.

DECL_SAVED_TREE for a GIMPLE function will always be a BIND_EXPR which contains declarations for the temporary variables used in the function.

A C++ program will usually contain more BIND_EXPRs than there are syntactic blocks in the source code, since several C++ constructs have implicit scopes associated with them. On the other hand, although the C++ front end uses pseudo-scopes to handle cleanups for objects with destructors, these don't translate into the GIMPLE form; multiple declarations at the same level use the same BIND_EXPR.

9.2.4.2 Statement Sequences

Multiple statements at the same nesting level are collected into a STATEMENT_LIST. Statement lists are modified and traversed using the interface in 'tree-iterator.h'.

9.2.4.3 Empty Statements

Whenever possible, statements with no effect are discarded. But if they are nested within another construct which cannot be discarded for some reason, they are instead replaced with an empty statement, generated by build_empty_stmt. Initially, all empty statements were shared, after the pattern of the Java front end, but this caused a lot of trouble in practice.

An empty statement is represented as (void)0.

9.2.4.4 Loops

At one time loops were expressed in GIMPLE using LOOP_EXPR, but now they are lowered to explicit gotos.

9.2.4.5 Selection Statements

A simple selection statement, such as the C if statement, is expressed in GIMPLE using a void COND_EXPR. If only one branch is used, the other is filled with an empty statement.

Normally, the condition expression is reduced to a simple comparison. If it is a shortcut (&& or ||) expression, however, we try to break up the if into multiple ifs so that the implied shortcut is taken directly, much like the transformation done by do_jump in the RTL expander.

A SWITCH_EXPR in GIMPLE contains the condition and a TREE_VEC of CASE_LABEL_EXPRS describing the case values and corresponding LABEL_DECLs to jump to. The body of the switch is moved after the SWITCH EXPR.

9.2.4.6 Jumps

Other jumps are expressed by either GOTO_EXPR or RETURN_EXPR.

The operand of a GOTO_EXPR must be either a label or a variable containing the address to jump to.

The operand of a RETURN_EXPR is either NULL_TREE or a MODIFY_EXPR which sets the return value. It would be nice to move the MODIFY_EXPR into a separate statement, but the special return semantics in expand_return make that difficult. It may still happen in the future, perhaps by moving most of that logic into expand_assignment.

9.2.4.7 Cleanups

Destructors for local C++ objects and similar dynamic cleanups are represented in GIMPLE by a TRY_FINALLY_EXPR. When the controlled block exits, the cleanup is run.

TRY_FINALLY_EXPR complicates the flow graph, since the cleanup needs to appear on every edge out of the controlled block; this reduces the freedom to move code across these edges. Therefore, the EH lowering pass which runs before most of the optimization passes eliminates these expressions by explicitly adding the cleanup to each edge.

9.2.4.8 Exception Handling

Other exception handling constructs are represented using TRY_CATCH_EXPR. The handler operand of a TRY_CATCH_EXPR can be a normal statement to be executed if the controlled block throws an exception, or it can have one of two special forms:

- 1. A CATCH_EXPR executes its handler if the thrown exception matches one of the allowed types. Multiple handlers can be expressed by a sequence of CATCH_EXPR statements.
- 2. An EH_FILTER_EXPR executes its handler if the thrown exception does not match one of the allowed types.

Currently throwing an exception is not directly represented in GIMPLE, since it is implemented by calling a function. At some point in the future we will want to add some way to express that the call will throw an exception of a known type.

Just before running the optimizers, the compiler lowers the high-level EH constructs above into a set of 'goto's, magic labels, and EH regions. Continuing to unwind at the end of a cleanup is represented with a RESX_EXPR.

9.2.5 GIMPLE Example

```
struct A { A(); ~A(); };
    int i;
    int g();
    void f()
      A a;
      int j = (--i, i?0:1);
      for (int x = 42; x > 0; --x)
          i += g()*4 + 32;
    }
becomes
    void f()
    {
      int i.0;
      int T.1;
      int iftmp.2;
      int T.3;
      int T.4;
      int T.5;
      int T.6;
      {
        struct A a;
        int j;
        __comp_ctor (&a);
        try
            i.0 = i;
            T.1 = i.0 - 1;
            i = T.1;
            i.0 = i;
```

```
if (i.0 == 0)
          iftmp.2 = 1;
          iftmp.2 = 0;
        j = iftmp.2;
          int x;
          x = 42;
          goto test;
          loop:;
          T.3 = g();
          T.4 = T.3 * 4;
          i.0 = i;
          T.5 = T.4 + i.0;
          T.6 = T.5 + 32;
          i = T.6;
          x = x - 1;
          test:;
          if (x > 0)
           goto loop;
          else
            goto break_;
          break_:;
     }
   finally
        __comp_dtor (&a);
 }
}
```

9.2.6 Rough GIMPLE Grammar

```
function
            : FUNCTION_DECL
                    DECL_SAVED_TREE -> compound-stmt
compound-stmt: STATEMENT_LIST
                    members -> stmt
            : block
stmt
            if-stmt
            switch-stmt
            goto-stmt
            return-stmt
            resx-stmt
            label-stmt
            | try-stmt
            | modify-stmt
            | call-stmt
block
            : BIND_EXPR
                    BIND_EXPR_VARS -> chain of DECLs
                    BIND_EXPR_BLOCK -> BLOCK
                    BIND_EXPR_BODY -> compound-stmt
```

if-stmt : COND_EXPR

op0 -> condition
op1 -> compound-stmt
op2 -> compound-stmt

switch-stmt : SWITCH_EXPR

op0 -> val op1 -> NULL

op2 -> TREE_VEC of CASE_LABEL_EXPRs

The CASE_LABEL_EXPRs are sorted by CASE_LOW,

and default is last.

goto-stmt : GOTO_EXPR

opO -> LABEL_DECL | val

return-stmt : RETURN_EXPR

op0 -> return-value

return-value : NULL

| RESULT_DECL | MODIFY_EXPR

opO -> RESULT_DECL

 $op1 \rightarrow lhs$

resx-stmt : RESX_EXPR

label-stmt : LABEL_EXPR

opO -> LABEL_DECL

try-stmt : TRY_CATCH_EXPR

op0 -> compound-stmt
op1 -> handler

TRY_FINALLY_EXPR

op0 -> compound-stmt
op1 -> compound-stmt

 $\verb| handler : catch-seq| \\$

| EH_FILTER_EXPR | compound-stmt

catch-seq : STATEMENT_LIST

members -> CATCH_EXPR

modify-stmt : MODIFY_EXPR

op0 -> lhs op1 -> rhs

call-stmt : CALL_EXPR

op0 -> val | OBJ_TYPE_REF
op1 -> call-arg-list

call-arg-list: TREE_LIST

members -> 1hs | CONST

addr-expr-arg: ID

compref

addressable : addr-expr-arg

```
indirectref
with-size-arg: addressable
             call-stmt
indirectref : INDIRECT_REF
                    op0 -> val
lhs
             : addressable
             bitfieldref
             WITH_SIZE_EXPR
                    op0 -> with-size-arg
                     op1 -> val
min-lval
            : ID
             indirectref
bitfieldref : BIT_FIELD_REF
                    op0 -> inner-compref
                     op1 -> CONST
                     op2 -> var
compref
             : inner-compref
             REALPART_EXPR
                    op0 -> inner-compref
             IMAGPART_EXPR
                     op0 -> inner-compref
inner-compref: min-lval
             COMPONENT_REF
                     op0 -> inner-compref
                     op1 -> FIELD_DECL
                     op2 -> val
             ARRAY_REF
                     op0 -> inner-compref
                     op1 \rightarrow val
                     op2 -> val
                     op3 -> val
             ARRAY_RANGE_REF
                     op0 -> inner-compref
                     op1 -> val
                     op2 -> val
                     op3 -> val
             | VIEW_CONVERT_EXPR
                     op0 -> inner-compref
condition
             : val
             RELOP
                     op0 \rightarrow val
                     op1 \rightarrow val
val
             : ID
             CONST
rhs
             : lhs
             CONST
             call-stmt
             ADDR_EXPR
```

9.3 Annotations

The optimizers need to associate attributes with statements and variables during the optimization process. For instance, we need to know what basic block does a statement belong to or whether a variable has aliases. All these attributes are stored in data structures called annotations which are then linked to the field ann in struct tree_common.

Presently, we define annotations for statements (stmt_ann_t), variables (var_ann_t) and SSA names (ssa_name_ann_t). Annotations are defined and documented in 'tree-flow.h'.

9.4 Statement Operands

Almost every GIMPLE statement will contain a reference to a variable or memory location. Since statements come in different shapes and sizes, their operands are going to be located at various spots inside the statement's tree. To facilitate access to the statement's operands, they are organized into arrays associated inside each statement's annotation. Each element in an operand array is a pointer to a VAR_DECL, PARM_DECL or SSA_NAME tree node. This provides a very convenient way of examining and replacing operands.

Data flow analysis and optimization is done on all tree nodes representing variables. Any node for which SSA_VAR_P returns nonzero is considered when scanning statement operands. However, not all SSA_VAR_P variables are processed in the same way. For the purposes of optimization, we need to distinguish between references to local scalar variables and references to globals, statics, structures, arrays, aliased variables, etc. The reason is simple, the compiler can gather complete data flow information for a local scalar. On the other hand, a global variable may be modified by a function call, it may not be possible to keep track of all the elements of an array or the fields of a structure, etc.

The operand scanner gathers two kinds of operands: real and virtual. An operand for which is_gimple_reg returns true is considered real, otherwise it is a virtual operand. We also distinguish between uses and definitions. An operand is used if its value is loaded by the statement (e.g., the operand at the RHS of an assignment). If the statement assigns a new value to the operand, the operand is considered a definition (e.g., the operand at the LHS of an assignment).

Virtual and real operands also have very different data flow properties. Real operands are unambiguous references to the full object that they represent. For instance, given

```
{
   int a, b;
   a = b
}
```

Since a and b are non-aliased locals, the statement a = b will have one real definition and one real use because variable b is completely modified with the contents of variable a. Real definition are also known as killing definitions. Similarly, the use of a reads all its bits.

In contrast, virtual operands are used with variables that can have a partial or ambiguous reference. This includes structures, arrays, globals, and aliased variables. In these cases, we have two types of definitions. For globals, structures, and arrays, we can determine from a statement whether a variable of these types has a killing definition. If the variable does, then the statement is marked as having a must definition of that variable. However, if a statement is only defining a part of the variable (i.e. a field in a structure), or if we know that a statement might define the variable but we cannot say for sure, then we mark that statement as having a may definition. For instance, given

```
{
  int a, b, *p;
  if (...)
    p = &a;
  else
    p = &b;
  *p = 5;
  return *p;
}
```

The assignment *p = 5 may be a definition of a or b. If we cannot determine statically where p is pointing to at the time of the store operation, we create virtual definitions to mark that statement as a potential definition site for a and b. Memory loads are similarly marked with virtual use operands. Virtual operands are shown in tree dumps right before the statement that contains them. To request a tree dump with virtual operands, use the '-vops' option to '-fdump-tree':

```
{
  int a, b, *p;

  if (...)
    p = &a;
  else
    p = &b;
  # a = V_MAY_DEF <a>
  # b = V_MAY_DEF <b>
  *p = 5;

# VUSE <a>
  # VUSE <b>
  return *p;
}
```

Notice that V_MAY_DEF operands have two copies of the referenced variable. This indicates that this is not a killing definition of that variable. In this case we refer to it as a may definition or aliased store. The presence of the second copy of the variable in the V_MAY_DEF operand will become important when the function is converted into SSA form. This will be used to link all the non-killing definitions to prevent optimizations from making incorrect assumptions about them.

Operands are collected by 'tree-ssa-operands.c'. They are stored inside each statement's annotation and can be accessed with DEF_OPS, USE_OPS, V_MAY_DEF_OPS, V_MUST_DEF_OPS and VUSE_OPS. The following are all the accessor macros available to access USE

operands. To access all the other operand arrays, just change the name accordingly. Note that this interface to the operands is deprecated, and is slated for removal in a future version of gcc. The preferred interface is the operand iterator interface. Unless you need to discover the number of operands of a given type on a statement, you are strongly urged not to use this interface.

USE_OPS (ann) [Macro]

Returns the array of operands used by the statement with annotation ann.

STMT_USE_OPS (stmt) [Macro]

Alternate version of USE_OPS that takes the statement stmt as input.

NUM_USES (ops) [Macro]

Return the number of USE operands in array ops.

USE_OP_PTR (ops, i) [Macro]

Return a pointer to the *i*th operand in array ops.

 $USE_OP (ops, i)$ [Macro]

Return the *i*th operand in array ops.

The following function shows how to print all the operands of a given statement:

```
void
print_ops (tree stmt)
{
  vuse_optype vuses;
  v_may_def_optype v_may_defs;
  v_must_def_optype v_must_defs;
 def_optype defs;
 use_optype uses;
  stmt_ann_t ann;
  size_t i;
  get_stmt_operands (stmt);
 ann = stmt_ann (stmt);
 defs = DEF_OPS (ann);
 for (i = 0; i < NUM_DEFS (defs); i++)</pre>
   print_generic_expr (stderr, DEF_OP (defs, i), 0);
 uses = USE_OPS (ann);
 for (i = 0; i < NUM_USES (uses); i++)
    print_generic_expr (stderr, USE_OP (uses, i), 0);
  v_may_defs = V_MAY_DEF_OPS (ann);
  for (i = 0; i < NUM_V_MAY_DEFS (v_may_defs); i++)</pre>
      print_generic_expr (stderr, V_MAY_DEF_OP (v_may_defs, i), 0);
     print_generic_expr (stderr, V_MAY_DEF_RESULT (v_may_defs, i), 0);
  v_must_defs = V_MUST_DEF_OPS (ann);
  for (i = 0; i < NUM_V_MUST_DEFS (v_must_defs); i++)</pre>
    print_generic_expr (stderr, V_MUST_DEF_OP (v_must_defs, i), 0);
```

```
vuses = VUSE_OPS (ann);
for (i = 0; i < NUM_VUSES (vuses); i++)
   print_generic_expr (stderr, VUSE_OP (vuses, i), 0);
}</pre>
```

To collect the operands, you first need to call get_stmt_operands. Since that is a potentially expensive operation, statements are only scanned if they have been marked modified by a call to modify_stmt. So, if your pass replaces operands in a statement, make sure to call modify_stmt.

9.4.1 Operand Iterators

There is an alternative to iterating over the operands in a statement. It is especially useful when you wish to perform the same operation on more than one type of operand. The previous example could be rewritten as follows:

```
print_ops (tree stmt)
{
    ssa_op_iter;
    tree var;

    get_stmt_operands (stmt);
    FOR_EACH_SSA_TREE_OPERAND (var, stmt, iter, SSA_OP_ALL_OPERANDS)
        print_generic_expr (stderr, var, 0);
}
```

1. Determine whether you are need to see the operand pointers, or just the trees, and choose the appropriate macro:

```
Need Macro:
----
use_operand_p FOR_EACH_SSA_USE_OPERAND
def_operand_p FOR_EACH_SSA_TREE_OPERAND
tree FOR_EACH_SSA_TREE_OPERAND
```

- 2. You need to declare a variable of the type you are interested in, and an ssa_op_iter structure which serves as the loop controlling variable.
- 3. Determine which operands you wish to use, and specify the flags of those you are interested in. They are documented in 'tree-ssa-operands.h':

```
#define SSA_OP_USE
                                0x01
                                        /* Real USE operands. */
#define SSA_OP_DEF
                                0x02
                                        /* Real DEF operands. */
#define SSA_OP_VUSE
                                0x04
                                        /* VUSE operands. */
#define SSA_OP_VMAYUSE
                                80x0
                                        /* USE portion of V_MAY_DEFS.
#define SSA_OP_VMAYDEF
                                        /* DEF portion of V_MAY_DEFS.
                                0x10
#define SSA_OP_VMUSTDEF
                                0x20
                                        /* V_MUST_DEF definitions. */
/* These are commonly grouped operand flags. */
#define SSA_OP_VIRTUAL_USES
                                (SSA_OP_VUSE | SSA_OP_VMAYUSE)
#define SSA_OP_VIRTUAL_DEFS
                                (SSA_OP_VMAYDEF | SSA_OP_VMUSTDEF)
#define SSA_OP_ALL_USES
                                (SSA_OP_VIRTUAL_USES | SSA_OP_USE)
#define SSA_OP_ALL_DEFS
                                (SSA_OP_VIRTUAL_DEFS | SSA_OP_DEF)
#define SSA_OP_ALL_OPERANDS
                                (SSA_OP_ALL_USES | SSA_OP_ALL_DEFS)
```

So if you want to look at the use pointers for all the USE and VUSE operands, you would do something like:

```
use_operand_p use_p;
ssa_op_iter iter;
```

```
FOR_EACH_SSA_USE_OPERAND (use_p, stmt, iter, (SSA_OP_USE | SSA_OP_VUSE))
{
   process_use_ptr (use_p);
}
```

The _TREE_ macro is basically the same as the USE and DEF macros, only with the use or def dereferenced via USE_FROM_PTR (use_p) and DEF_FROM_PTR (def_p). Since we aren't using operand pointers, use and defs flags can be mixed.

V_MAY_DEFs are broken into two flags, one for the DEF portion (SSA_OP_VMAYDEF) and one for the USE portion (SSA_OP_VMAYUSE). If all you want to look at are the V_MAY_DEFs together, there is a fourth iterator macro for this, which returns both a def_operand_p and a use_operand_p for each V_MAY_DEF in the statement. Note that you don't need any flags for this one.

```
use_operand_p use_p;
def_operand_p def_p;
ssa_op_iter iter;

FOR_EACH_SSA_MAYDEF_OPERAND (def_p, use_p, stmt, iter)
   {
      my_code;
   }
```

V_MUST_DEFs are broken into two flags, one for the DEF portion (SSA_OP_VMUSTDEF) and one for the kill portion (SSA_OP_VMUSTDEFKILL). If all you want to look at are the V_MUST_DEFs together, there is a fourth iterator macro for this, which returns both a def_operand_p and a use_operand_p for each V_MUST_DEF in the statement. Note that you don't need any flags for this one.

```
use_operand_p kill_p;
def_operand_p def_p;
ssa_op_iter iter;

FOR_EACH_SSA_MUSTDEF_OPERAND (def_p, kill_p, stmt, iter)
   {
      my_code;
}
```

There are many examples in the code as well, as well as the documentation in 'tree-ssa-operands.h'.

9.5 Static Single Assignment

Most of the tree optimizers rely on the data flow information provided by the Static Single Assignment (SSA) form. We implement the SSA form as described in R. Cytron, J. Ferrante, B. Rosen, M. Wegman, and K. Zadeck. Efficiently Computing Static Single Assignment Form and the Control Dependence Graph. ACM Transactions on Programming Languages and Systems, 13(4):451-490, October 1991.

The SSA form is based on the premise that program variables are assigned in exactly one location in the program. Multiple assignments to the same variable create new versions of that variable. Naturally, actual programs are seldom in SSA form initially because variables tend to be assigned multiple times. The compiler modifies the program representation so that every time a variable is assigned in the code, a new version of the variable is created. Different versions of the same variable are distinguished by subscripting the variable name with its version number. Variables used in the right-hand side of expressions are renamed so that their version number matches that of the most recent assignment.

We represent variable versions using SSA_NAME nodes. The renaming process in 'tree-ssa.c' wraps every real and virtual operand with an SSA_NAME node which contains the version number and the statement that created the SSA_NAME. Only definitions and virtual definitions may create new SSA_NAME nodes.

Sometimes, flow of control makes it impossible to determine what is the most recent version of a variable. In these cases, the compiler inserts an artificial definition for that variable called *PHI function* or *PHI node*. This new definition merges all the incoming versions of the variable to create a new name for it. For instance,

```
if (...)
  a_1 = 5;
else if (...)
  a_2 = 2;
else
  a_3 = 13;
# a_4 = PHI <a_1, a_2, a_3>
return a_4;
```

Since it is not possible to determine which of the three branches will be taken at runtime, we don't know which of a_1, a_2 or a_3 to use at the return statement. So, the SSA renamer creates a new version a_4 which is assigned the result of "merging" a_1, a_2 and a_3. Hence, PHI nodes mean "one of these operands. I don't know which".

The following macros can be used to examine PHI nodes

```
PHI_RESULT (phi)
```

[Macro]

Returns the SSA_NAME created by PHI node phi (i.e., phi's LHS).

PHI_NUM_ARGS (phi)

Macro

Returns the number of arguments in *phi*. This number is exactly the number of incoming edges to the basic block holding *phi*.

PHI_ARG_ELT (phi, i)

[Macro]

Returns a tuple representing the *i*th argument of *phi*. Each element of this tuple contains an SSA_NAME var and the incoming edge through which var flows.

PHI_ARG_EDGE (phi, i)

[Macro]

Returns the incoming edge for the ith argument of phi.

PHI_ARG_DEF (phi, i)

[Macro]

Returns the SSA_NAME for the ith argument of phi.

9.5.1 Preserving the SSA form

Some optimization passes make changes to the function that invalidate the SSA property. This can happen when a pass has added new variables or changed the program so that variables that were previously aliased aren't anymore.

Whenever something like this happens, the affected variables must be renamed into SSA form again. To do this, you should mark the new variables in the global bitmap vars_to_rename. Once your pass has finished, the pass manager will invoke the SSA renamer to put the program into SSA once more.

9.5.2 Examining SSA_NAME nodes

The following macros can be used to examine SSA_NAME nodes

$SSA_NAME_DEF_STMT (var)$

[Macro]

Returns the statement s that creates the SSA_NAME var. If s is an empty statement (i.e., IS_EMPTY_STMT (s) returns true), it means that the first reference to this variable is a USE or a VUSE.

SSA_NAME_VERSION (var)

[Macro]

Returns the version number of the SSA_NAME object var.

9.5.3 Walking use-def chains

void walk_use_def_chains (var, fn, data)

[Tree SSA function]

Walks use-def chains starting at the SSA_NAME node var. Calls function fn at each reaching definition found. Function FN takes three arguments: var, its defining statement (def_stmt) and a generic pointer to whatever state information that fn may want to maintain (data). Function fn is able to stop the walk by returning true, otherwise in order to continue the walk, fn should return false.

Note, that if *def_stmt* is a PHI node, the semantics are slightly different. For each argument *arg* of the PHI node, this function will:

- 1. Walk the use-def chains for arg.
- 2. Call FN (arg, phi, data).

Note how the first argument to fn is no longer the original variable var, but the PHI argument currently being examined. If fn wants to get at var, it should call PHI_RESULT (phi).

9.5.4 Walking the dominator tree

void walk_dominator_tree (walk_data, bb)

[Tree SSA function]

This function walks the dominator tree for the current CFG calling a set of callback functions defined in *struct dom_walk_data* in 'domwalk.h'. The call back functions you need to define give you hooks to execute custom code at various points during traversal:

1. Once to initialize any local data needed while processing bb and its children. This local data is pushed into an internal stack which is automatically pushed and popped as the walker traverses the dominator tree.

- 2. Once before traversing all the statements in the bb.
- 3. Once for every statement inside bb.
- 4. Once after traversing all the statements and before recursing into bb's dominator children.
- 5. It then recurses into all the dominator children of bb.
- 6. After recursing into all the dominator children of bb it can, optionally, traverse every statement in bb again (i.e., repeating steps 2 and 3).
- 7. Once after walking the statements in bb and bb's dominator children. At this stage, the block local data stack is popped.

9.6 Alias analysis

Alias analysis proceeds in 3 main phases:

1. Points-to and escape analysis.

This phase walks the use-def chains in the SSA web looking for three things:

- Assignments of the form P_i = &VAR
- Assignments of the form P_i = malloc()
- Pointers and ADDR_EXPR that escape the current function.

The concept of 'escaping' is the same one used in the Java world. When a pointer or an ADDR_EXPR escapes, it means that it has been exposed outside of the current function. So, assignment to global variables, function arguments and returning a pointer are all escape sites.

This is where we are currently limited. Since not everything is renamed into SSA, we lose track of escape properties when a pointer is stashed inside a field in a structure, for instance. In those cases, we are assuming that the pointer does escape.

We use escape analysis to determine whether a variable is call-clobbered. Simply put, if an ADDR_EXPR escapes, then the variable is call-clobbered. If a pointer P_i escapes, then all the variables pointed-to by P_i (and its memory tag) also escape.

2. Compute flow-sensitive aliases

We have two classes of memory tags. Memory tags associated with the pointed-to data type of the pointers in the program. These tags are called "type memory tag" (TMT). The other class are those associated with SSA_NAMEs, called "name memory tag" (NMT). The basic idea is that when adding operands for an INDIRECT_REF *P_i, we will first check whether P_i has a name tag, if it does we use it, because that will have more precise aliasing information. Otherwise, we use the standard type tag.

In this phase, we go through all the pointers we found in points-to analysis and create alias sets for the name memory tags associated with each pointer P_i. If P_i escapes, we mark call-clobbered the variables it points to and its tag.

3. Compute flow-insensitive aliases

This pass will compare the alias set of every type memory tag and every addressable variable found in the program. Given a type memory tag TMT and an addressable variable V. If the alias sets of TMT and V conflict (as computed by may_alias_p), then V is marked as an alias tag and added to the alias set of TMT.

For instance, consider the following function:

```
foo (int i)
{
   int *p, *q, a, b;
   if (i > 10)
      p = &a;
   else
      q = &b;

   *p = 3;
   *q = 5;
   a = b + 2;
   return *p;
}
```

After aliasing analysis has finished, the type memory tag for pointer p will have two aliases, namely variables a and b. Every time pointer p is dereferenced, we want to mark the operation as a potential reference to a and b.

```
foo (int i)
{
 int *p, a, b;
  if (i_2 > 10)
   p_4 = &a;
   p_6 = b;
  p_1 = PHI < p_4(1), p_6(2);
  \# a_7 = V_MAY_DEF < a_3>;
  # b_8 = V_MAY_DEF < b_5>;
  *p_1 = 3;
  \# a_9 = V_MAY_DEF < a_7 >
  # VUSE <b_8>
  a_9 = b_8 + 2;
  # VUSE <a_9>;
 # VUSE <b_8>;
  return *p_1;
```

In certain cases, the list of may aliases for a pointer may grow too large. This may cause an explosion in the number of virtual operands inserted in the code. Resulting in increased memory consumption and compilation time.

When the number of virtual operands needed to represent aliased loads and stores grows too large (configurable with '--param max-aliased-vops'), alias sets are grouped to avoid severe compile-time slow downs and memory consumption. The alias grouping heuristic proceeds as follows:

- 1. Sort the list of pointers in decreasing number of contributed virtual operands.
- 2. Take the first pointer from the list and reverse the role of the memory tag and its aliases. Usually, whenever an aliased variable Vi is found to alias with a memory tag T, we add Vi to the may-aliases set for T. Meaning that after alias analysis, we will have:

```
may-aliases(T) = { V1, V2, V3, ..., Vn }
```

This means that every statement that references T, will get n virtual operands for each of the Vi tags. But, when alias grouping is enabled, we make T an alias tag and add it to the alias set of all the Vi variables:

```
may-aliases(V1) = { T }
may-aliases(V2) = { T }
...
may-aliases(Vn) = { T }
```

This has two effects: (a) statements referencing T will only get a single virtual operand, and, (b) all the variables Vi will now appear to alias each other. So, we lose alias precision to improve compile time. But, in theory, a program with such a high level of aliasing should not be very optimizable in the first place.

3. Since variables may be in the alias set of more than one memory tag, the grouping done in step (2) needs to be extended to all the memory tags that have a non-empty intersection with the may-aliases set of tag T. For instance, if we originally had these may-aliases sets:

```
may-aliases(T) = { V1, V2, V3 } may-aliases(R) = { V2, V4 }
```

In step (2) we would have reverted the aliases for T as:

```
may-aliases(V1) = { T }
may-aliases(V2) = { T }
may-aliases(V3) = { T }
```

But note that now V2 is no longer aliased with R. We could add R to may-aliases (V2), but we are in the process of grouping aliases to reduce virtual operands so what we do is add V4 to the grouping to obtain:

4. If the total number of virtual operands due to aliasing is still above the threshold set by max-alias-vops, go back to (2).

10 RTL Representation

Most of the work of the compiler is done on an intermediate representation called register transfer language. In this language, the instructions to be output are described, pretty much one by one, in an algebraic form that describes what the instruction does.

RTL is inspired by Lisp lists. It has both an internal form, made up of structures that point at other structures, and a textual form that is used in the machine description and in printed debugging dumps. The textual form uses nested parentheses to indicate the pointers in the internal form.

10.1 RTL Object Types

RTL uses five kinds of objects: expressions, integers, wide integers, strings and vectors. Expressions are the most important ones. An RTL expression ("RTX", for short) is a C structure, but it is usually referred to with a pointer; a type that is given the typedef name rtx.

An integer is simply an int; their written form uses decimal digits. A wide integer is an integral object whose type is HOST_WIDE_INT; their written form uses decimal digits.

A string is a sequence of characters. In core it is represented as a char * in usual C fashion, and it is written in C syntax as well. However, strings in RTL may never be null. If you write an empty string in a machine description, it is represented in core as a null pointer rather than as a pointer to a null character. In certain contexts, these null pointers instead of strings are valid. Within RTL code, strings are most commonly found inside symbol_ref expressions, but they appear in other contexts in the RTL expressions that make up machine descriptions.

In a machine description, strings are normally written with double quotes, as you would in C. However, strings in machine descriptions may extend over many lines, which is invalid C, and adjacent string constants are not concatenated as they are in C. Any string constant may be surrounded with a single set of parentheses. Sometimes this makes the machine description easier to read.

There is also a special syntax for strings, which can be useful when C code is embedded in a machine description. Wherever a string can appear, it is also valid to write a C-style brace block. The entire brace block, including the outermost pair of braces, is considered to be the string constant. Double quote characters inside the braces are not special. Therefore, if you write string constants in the C code, you need not escape each quote character with a backslash.

A vector contains an arbitrary number of pointers to expressions. The number of elements in the vector is explicitly present in the vector. The written form of a vector consists of square brackets ('[...]') surrounding the elements, in sequence and with whitespace separating them. Vectors of length zero are not created; null pointers are used instead.

Expressions are classified by expression codes (also called RTX codes). The expression code is a name defined in 'rtl.def', which is also (in uppercase) a C enumeration constant. The possible expression codes and their meanings are machine-independent. The code of an RTX can be extracted with the macro GET_CODE (x) and altered with PUT_CODE (x, newcode).

The expression code determines how many operands the expression contains, and what kinds of objects they are. In RTL, unlike Lisp, you cannot tell by looking at an operand what kind of object it is. Instead, you must know from its context—from the expression code of the containing expression. For example, in an expression of code subreg, the first operand is to be regarded as an expression and the second operand as an integer. In an expression of code plus, there are two operands, both of which are to be regarded as expressions. In a symbol_ref expression, there is one operand, which is to be regarded as a string.

Expressions are written as parentheses containing the name of the expression type, its flags and machine mode if any, and then the operands of the expression (separated by spaces).

Expression code names in the 'md' file are written in lowercase, but when they appear in C code they are written in uppercase. In this manual, they are shown as follows: const int.

In a few contexts a null pointer is valid where an expression is normally wanted. The written form of this is (nil).

10.2 RTL Classes and Formats

The various expression codes are divided into several *classes*, which are represented by single characters. You can determine the class of an RTX code with the macro GET_RTX_CLASS (code). Currently, 'rtx.def' defines these classes:

RTX_OBJ An RTX code that represents an actual object, such as a register (REG) or a memory location (MEM, SYMBOL_REF). LO_SUM) is also included; instead, SUBREG and STRICT_LOW_PART are not in this class, but in class x.

RTX CONST OBJ

An RTX code that represents a constant object. HIGH is also included in this class.

RTX_COMPARE

An RTX code for a non-symmetric comparison, such as GEU or LT.

RTX COMM COMPARE

An RTX code for a symmetric (commutative) comparison, such as EQ or ORDERED.

RTX_UNARY

An RTX code for a unary arithmetic operation, such as NEG, NOT, or ABS. This category also includes value extension (sign or zero) and conversions between integer and floating point.

RTX COMM ARITH

An RTX code for a commutative binary operation, such as PLUS or AND. NE and EQ are comparisons, so they have class <.

RTX_BIN_ARITH

An RTX code for a non-commutative binary operation, such as MINUS, DIV, or ASHIFTRT.

RTX_BITFIELD_OPS

An RTX code for a bit-field operation. Currently only ZERO_EXTRACT and SIGN_EXTRACT. These have three inputs and are lvalues (so they can be used for insertion as well). See Section 10.11 [Bit-Fields], page 133.

RTX_TERNARY

An RTX code for other three input operations. Currently only IF_THEN_ELSE and VEC_MERGE.

RTX_INSN An RTX code for an entire instruction: INSN, JUMP_INSN, and CALL_INSN. See Section 10.18 [Insns], page 142.

RTX_MATCH

An RTX code for something that matches in insns, such as MATCH_DUP. These only occur in machine descriptions.

RTX_AUTOINC

An RTX code for an auto-increment addressing mode, such as POST_INC.

RTX_EXTRA

All other RTX codes. This category includes the remaining codes used only in machine descriptions (DEFINE_*, etc.). It also includes all the codes describing side effects (SET, USE, CLOBBER, etc.) and the non-insns that may appear on an insn chain, such as NOTE, BARRIER, and CODE_LABEL. SUBREG is also part of this class.

For each expression code, 'rtl.def' specifies the number of contained objects and their kinds using a sequence of characters called the *format* of the expression code. For example, the format of subreg is 'ei'.

These are the most commonly used format characters:

- e An expression (actually a pointer to an expression).
- i An integer.
- w A wide integer.
- s A string.
- E A vector of expressions.

A few other format characters are used occasionally:

- u 'u' is equivalent to 'e' except that it is printed differently in debugging dumps. It is used for pointers to insns.
- n 'n' is equivalent to 'i' except that it is printed differently in debugging dumps. It is used for the line number or code number of a **note** insn.
- S 'S' indicates a string which is optional. In the RTL objects in core, 'S' is equivalent to 's', but when the object is read, from an 'md' file, the string value of this operand may be omitted. An omitted string is taken to be the null string.

- V 'V' indicates a vector which is optional. In the RTL objects in core, 'V' is equivalent to 'E', but when the object is read from an 'md' file, the vector value of this operand may be omitted. An omitted vector is effectively the same as a vector of no elements.
- B 'B' indicates a pointer to basic block structure.
- O '0' means a slot whose contents do not fit any normal category. '0' slots are not printed at all in dumps, and are often used in special ways by small parts of the compiler.

There are macros to get the number of operands and the format of an expression code:

GET_RTX_LENGTH (code)

Number of operands of an RTX of code code.

GET_RTX_FORMAT (code)

The format of an RTX of code code, as a C string.

Some classes of RTX codes always have the same format. For example, it is safe to assume that all comparison operations have format ee.

1 All codes of this class have format e.

< c

2 All codes of these classes have format ee.

b

- 3 All codes of these classes have format eee.
- i All codes of this class have formats that begin with iuueiee. See Section 10.18 [Insns], page 142. Note that not all RTL objects linked onto an insn chain are of class i.

o m

You can make no assumptions about the format of these codes.

10.3 Access to Operands

Operands of expressions are accessed using the macros XEXP, XINT, XWINT and XSTR. Each of these macros takes two arguments: an expression-pointer (RTX) and an operand number (counting from zero). Thus,

```
XEXP (x, 2)
```

accesses operand 2 of expression x, as an expression.

```
XINT (x, 2)
```

accesses the same operand as an integer. XSTR, used in the same fashion, would access it as a string.

Any operand can be accessed as an integer, as an expression or as a string. You must choose the correct method of access for the kind of value actually stored in the operand. You would do this based on the expression code of the containing expression. That is also how you would know how many operands there are.

For example, if x is a subreg expression, you know that it has two operands which can be correctly accessed as XEXP (x, 0) and XINT (x, 1). If you did XINT (x, 0), you would get the address of the expression operand but cast as an integer; that might occasionally be useful, but it would be cleaner to write (int) XEXP (x, 0). XEXP (x, 1) would also compile without error, and would return the second, integer operand cast as an expression pointer, which would probably result in a crash when accessed. Nothing stops you from writing XEXP (x, 28) either, but this will access memory past the end of the expression with unpredictable results.

Access to operands which are vectors is more complicated. You can use the macro XVEC to get the vector-pointer itself, or the macros XVECEXP and XVECLEN to access the elements and length of a vector.

XVEC (exp, idx)

Access the vector-pointer which is operand number idx in exp.

XVECLEN (exp, idx)

Access the length (number of elements) in the vector which is in operand number idx in exp. This value is an int.

XVECEXP (exp, idx, eltnum)

Access element number eltnum in the vector which is in operand number idx in exp. This value is an RTX.

It is up to you to make sure that *eltnum* is not negative and is less than XVECLEN (exp, idx).

All the macros defined in this section expand into lvalues and therefore can be used to assign the operands, lengths and vector elements as well as to access them.

10.4 Access to Special Operands

Some RTL nodes have special annotations associated with them.

MEM

MEM_ALIAS_SET (x)

If 0, x is not in any alias set, and may alias anything. Otherwise, x can only alias MEMs in a conflicting alias set. This value is set in a language-dependent manner in the front-end, and should not be altered in the back-end. In some front-ends, these numbers may correspond in some way to types, or other language-level entities, but they need not, and the back-end makes no such assumptions. These set numbers are tested with alias_sets_conflict_p.

$MEM_EXPR(x)$

If this register is known to hold the value of some user-level declaration, this is that tree node. It may also be a COMPONENT_REF, in which case this is some field reference, and TREE_OPERAND (x, 0) contains the declaration, or another COMPONENT_REF, or null if there is no compile-time object associated with the reference.

$MEM_OFFSET(x)$

The offset from the start of MEM_EXPR as a CONST_INT rtx.

$MEM_SIZE(x)$

The size in bytes of the memory reference as a CONST_INT rtx. This is mostly relevant for BLKmode references as otherwise the size is implied by the mode.

$MEM_ALIGN(x)$

The known alignment in bits of the memory reference.

REG

ORIGINAL_REGNO (x)

This field holds the number the register "originally" had; for a pseudo register turned into a hard reg this will hold the old pseudo register number.

REG EXPR (x)

If this register is known to hold the value of some user-level declaration, this is that tree node.

REG_OFFSET (x)

If this register is known to hold the value of some user-level declaration, this is the offset into that logical storage.

SYMBOL_REF

SYMBOL_REF_DECL (x)

If the $symbol_ref x$ was created for a VAR_DECL or a $FUNCTION_DECL$, that tree is recorded here. If this value is null, then x was created by back end code generation routines, and there is no associated front end symbol table entry.

SYMBOL_REF_DECL may also point to a tree of class 'c', that is, some sort of constant. In this case, the symbol_ref is an entry in the per-file constant pool; again, there is no associated front end symbol table entry.

SYMBOL_REF_FLAGS (x)

In a symbol_ref, this is used to communicate various predicates about the symbol. Some of these are common enough to be computed by common code, some are specific to the target. The common bits are:

SYMBOL_FLAG_FUNCTION

Set if the symbol refers to a function.

SYMBOL_FLAG_LOCAL

Set if the symbol is local to this "module". See TARGET_BINDS_LOCAL_P.

SYMBOL FLAG EXTERNAL

Set if this symbol is not defined in this translation unit. Note that this is not the inverse of SYMBOL_FLAG_LOCAL.

SYMBOL_FLAG_SMALL

Set if the symbol is located in the small data section. See TARGET_IN_SMALL_DATA_P.

SYMBOL_REF_TLS_MODEL (x)

This is a multi-bit field accessor that returns the tls_model to be used for a thread-local storage symbol. It returns zero for non-thread-local symbols.

Bits beginning with SYMBOL_FLAG_MACH_DEP are available for the target's use.

10.5 Flags in an RTL Expression

RTL expressions contain several flags (one-bit bit-fields) that are used in certain types of expression. Most often they are accessed with the following macros, which expand into lvalues.

CONSTANT_POOL_ADDRESS_P(x)

Nonzero in a symbol_ref if it refers to part of the current function's constant pool. For most targets these addresses are in a .rodata section entirely separate from the function, but for some targets the addresses are close to the beginning of the function. In either case GCC assumes these addresses can be addressed directly, perhaps with the help of base registers. Stored in the unchanging field and printed as '/u'.

CONST_OR_PURE_CALL_P (x)

In a call_insn, note, or an expr_list for notes, indicates that the insn represents a call to a const or pure function. Stored in the unchanging field and printed as '/u'.

INSN_ANNULLED_BRANCH_P (x)

In a jump_insn, call_insn, or insn indicates that the branch is an annulling one. See the discussion under sequence below. Stored in the unchanging field and printed as '/u'.

$INSN_DELETED_P(x)$

In an insn, call_insn, jump_insn, code_label, barrier, or note, nonzero if the insn has been deleted. Stored in the volatil field and printed as '/v'.

INSN_FROM_TARGET_P (x)

In an insn or jump_insn or call_insn in a delay slot of a branch, indicates that the insn is from the target of the branch. If the branch insn has INSN_ANNULLED_BRANCH_P set, this insn will only be executed if the branch is taken. For annulled branches with INSN_FROM_TARGET_P clear, the insn will be executed only if the branch is not taken. When INSN_ANNULLED_BRANCH_P is not set, this insn will always be executed. Stored in the in_struct field and printed as '/s'.

LABEL OUTSIDE LOOP P(x)

In label_ref expressions, nonzero if this is a reference to a label that is outside the innermost loop containing the reference to the label. Stored in the in_struct field and printed as '/s'.

LABEL_PRESERVE_P (x)

In a code_label or note, indicates that the label is referenced by code or data not visible to the RTL of a given function. Labels referenced by a non-local goto will have this bit set. Stored in the in_struct field and printed as '/s'.

LABEL_REF_NONLOCAL_P (x)

In label_ref and reg_label expressions, nonzero if this is a reference to a non-local label. Stored in the volatil field and printed as '/v'.

$MEM_IN_STRUCT_P(x)$

In mem expressions, nonzero for reference to an entire structure, union or array, or to a component of one. Zero for references to a scalar variable or through a pointer to a scalar. If both this flag and MEM_SCALAR_P are clear, then we don't know whether this mem is in a structure or not. Both flags should never be simultaneously set. Stored in the in_struct field and printed as '/s'.

MEM_KEEP_ALIAS_SET_P (x)

In mem expressions, 1 if we should keep the alias set for this mem unchanged when we access a component. Set to 1, for example, when we are already in a non-addressable component of an aggregate. Stored in the jump field and printed as '/j'.

MEM_SCALAR_P (x)

In mem expressions, nonzero for reference to a scalar known not to be a member of a structure, union, or array. Zero for such references and for indirections through pointers, even pointers pointing to scalar types. If both this flag and MEM_IN_STRUCT_P are clear, then we don't know whether this mem is in a structure or not. Both flags should never be simultaneously set. Stored in the frame_related field and printed as '/f'.

MEM_VOLATILE_P (x)

In mem, asm_operands, and asm_input expressions, nonzero for volatile memory references. Stored in the volatil field and printed as '/v'.

MEM_NOTRAP_P (x)

In mem, nonzero for memory references that will not trap. Stored in the call field and printed as '/c'.

REG FUNCTION VALUE P (x)

Nonzero in a reg if it is the place in which this function's value is going to be returned. (This happens only in a hard register.) Stored in the integrated field and printed as '/i'.

$REG_POINTER(x)$

Nonzero in a reg if the register holds a pointer. Stored in the frame_related field and printed as '/f'.

$REG_USERVAR_P(x)$

In a reg, nonzero if it corresponds to a variable present in the user's source code. Zero for temporaries generated internally by the compiler. Stored in the volatil field and printed as '/v'.

The same hard register may be used also for collecting the values of functions called by this one, but REG_FUNCTION_VALUE_P is zero in this kind of use.

RTX_FRAME_RELATED_P (x)

Nonzero in an insn, call_insn, jump_insn, barrier, or set which is part of a function prologue and sets the stack pointer, sets the frame pointer, or saves a register. This flag should also be set on an instruction that sets up a temporary register to use in place of the frame pointer. Stored in the frame_related field and printed as '/f'.

In particular, on RISC targets where there are limits on the sizes of immediate constants, it is sometimes impossible to reach the register save area directly from the stack pointer. In that case, a temporary register is used that is near enough to the register save area, and the Canonical Frame Address, i.e., DWARF2's logical frame pointer, register must (temporarily) be changed to be this temporary register. So, the instruction that sets this temporary register must be marked as RTX_FRAME_RELATED_P.

If the marked instruction is overly complex (defined in terms of what dwarf2out_frame_debug_expr can handle), you will also have to create a REG_FRAME_RELATED_EXPR note and attach it to the instruction. This note should contain a simple expression of the computation performed by this instruction, i.e., one that dwarf2out_frame_debug_expr can handle.

This flag is required for exception handling support on targets with RTL prologues.

code_label, insn_list, const, or note if it resulted from an in-line function call. Stored in the integrated field and printed as '/i'.

$MEM_READONLY_P(x)$

Nonzero in a mem, if the memory is statically allocated and read-only.

Read-only in this context means never modified during the lifetime of the program, not necessarily in ROM or in write-disabled pages. A common example of the later is a shared library's global offset table. This table is initialized by the runtime loader, so the memory is technically writable, but after control is transferred from the runtime loader to the application, this memory will never be subsequently modified.

Stored in the unchanging field and printed as '/u'.

$SCHED_GROUP_P(x)$

During instruction scheduling, in an insn, call_insn or jump_insn, indicates that the previous insn must be scheduled together with this insn. This is used to ensure that certain groups of instructions will not be split up by the instruction scheduling pass, for example, use insns before a call_insn may not be separated from the call_insn. Stored in the in_struct field and printed as '/s'.

$SET_IS_RETURN_P(x)$

For a set, nonzero if it is for a return. Stored in the jump field and printed as '/j'.

$SIBLING_CALL_P(x)$

For a call_insn, nonzero if the insn is a sibling call. Stored in the jump field and printed as '/j'.

STRING_POOL_ADDRESS_P (x)

For a symbol_ref expression, nonzero if it addresses this function's string constant pool. Stored in the frame_related field and printed as '/f'.

SUBREG_PROMOTED_UNSIGNED_P (x)

Returns a value greater then zero for a subreg that has SUBREG_PROMOTED_VAR_P nonzero if the object being referenced is kept zero-extended, zero if it is kept sign-extended, and less then zero if it is extended some other way via the ptr_extend instruction. Stored in the unchanging field and volatil field, printed as '/u' and '/v'. This macro may only be used to get the value it may not be used to change the value. Use SUBREG_PROMOTED_UNSIGNED_SET to change the value.

SUBREG_PROMOTED_UNSIGNED_SET (x)

Set the unchanging and volatil fields in a subreg to reflect zero, sign, or other extension. If volatil is zero, then unchanging as nonzero means zero extension and as zero means sign extension. If volatil is nonzero then some other type of extension was done via the ptr_extend instruction.

SUBREG_PROMOTED_VAR_P (x)

Nonzero in a subreg if it was made when accessing an object that was promoted to a wider mode in accord with the PROMOTED_MODE machine description macro (see Section 13.5 [Storage Layout], page 260). In this case, the mode of the subreg is the declared mode of the object and the mode of SUBREG_REG is the mode of the register that holds the object. Promoted variables are always either sign- or zero-extended to the wider mode on every assignment. Stored in the in_struct field and printed as '/s'.

SYMBOL_REF_USED (x)

In a symbol_ref, indicates that x has been used. This is normally only used to ensure that x is only declared external once. Stored in the used field.

SYMBOL_REF_WEAK (x)

In a $symbol_ref$, indicates that x has been declared weak. Stored in the integrated field and printed as '/i'.

SYMBOL REF FLAG (x)

In a symbol_ref, this is used as a flag for machine-specific purposes. Stored in the volatil field and printed as '/v'.

Most uses of SYMBOL_REF_FLAG are historic and may be subsumed by SYMBOL_REF_FLAGS. Certainly use of SYMBOL_REF_FLAGS is mandatory if the target requires more than one bit of storage.

These are the fields to which the above macros refer:

call In a mem, 1 means that the memory reference will not trap.

In an RTL dump, this flag is represented as '/c'.

frame related

In an insn or set expression, 1 means that it is part of a function prologue and sets the stack pointer, sets the frame pointer, saves a register, or sets up a temporary register to use in place of the frame pointer.

In reg expressions, 1 means that the register holds a pointer.

In symbol_ref expressions, 1 means that the reference addresses this function's string constant pool.

In mem expressions, 1 means that the reference is to a scalar.

In an RTL dump, this flag is represented as '/f'.

in_struct

In mem expressions, it is 1 if the memory datum referred to is all or part of a structure or array; 0 if it is (or might be) a scalar variable. A reference through a C pointer has 0 because the pointer might point to a scalar variable. This information allows the compiler to determine something about possible cases of aliasing.

In reg expressions, it is 1 if the register has its entire life contained within the test expression of some loop.

In subreg expressions, 1 means that the subreg is accessing an object that has had its mode promoted from a wider mode.

In label_ref expressions, 1 means that the referenced label is outside the innermost loop containing the insn in which the label_ref was found.

In code_label expressions, it is 1 if the label may never be deleted. This is used for labels which are the target of non-local gotos. Such a label that would have been deleted is replaced with a note of type NOTE_INSN_DELETED_LABEL.

In an insn during dead-code elimination, 1 means that the insn is dead code.

In an insn or jump_insn during reorg for an insn in the delay slot of a branch, 1 means that this insn is from the target of the branch.

In an insn during instruction scheduling, 1 means that this insn must be scheduled as part of a group together with the previous insn.

In an RTL dump, this flag is represented as '/s'.

integrated

In an insn, insn_list, or const, 1 means the RTL was produced by procedure integration.

In reg expressions, 1 means the register contains the value to be returned by the current function. On machines that pass parameters in registers, the same register number may be used for parameters as well, but this flag is not set on such uses.

In symbol_ref expressions, 1 means the referenced symbol is weak.

In an RTL dump, this flag is represented as '/i'.

jump In a mem expression, 1 means we should keep the alias set for this mem unchanged when we access a component.

In a set, 1 means it is for a return.

In a call_insn, 1 means it is a sibling call.

In an RTL dump, this flag is represented as '/j'.

unchanging

In reg and mem expressions, 1 means that the value of the expression never changes.

In subreg expressions, it is 1 if the subreg references an unsigned object whose mode has been promoted to a wider mode.

In an insn or jump_insn in the delay slot of a branch instruction, 1 means an annulling branch should be used.

In a symbol_ref expression, 1 means that this symbol addresses something in the per-function constant pool.

In a call_insn, note, or an expr_list of notes, 1 means that this instruction is a call to a const or pure function.

In an RTL dump, this flag is represented as '/u'.

This flag is used directly (without an access macro) at the end of RTL generation for a function, to count the number of times an expression appears in insns. Expressions that appear more than once are copied, according to the rules for shared structure (see Section 10.20 [Sharing], page 152).

For a reg, it is used directly (without an access macro) by the leaf register renumbering code to ensure that each register is only renumbered once.

In a symbol_ref, it indicates that an external declaration for the symbol has already been written.

volatil In a mem, asm_operands, or asm_input expression, it is 1 if the memory reference is volatile. Volatile memory references may not be deleted, reordered or combined

In a symbol_ref expression, it is used for machine-specific purposes.

In a reg expression, it is 1 if the value is a user-level variable. 0 indicates an internal compiler temporary.

In an insn, 1 means the insn has been deleted.

In label_ref and reg_label expressions, 1 means a reference to a non-local

In an RTL dump, this flag is represented as '/v'.

10.6 Machine Modes

A machine mode describes a size of data object and the representation used for it. In the C code, machine modes are represented by an enumeration type, enum machine_mode, defined in 'machmode.def'. Each RTL expression has room for a machine mode and so do certain kinds of tree expressions (declarations and types, to be precise).

In debugging dumps and machine descriptions, the machine mode of an RTL expression is written after the expression code with a colon to separate them. The letters 'mode' which appear at the end of each machine mode name are omitted. For example, (reg:SI 38) is a reg expression with machine mode SImode. If the mode is VOIDmode, it is not written at all.

Here is a table of machine modes. The term "byte" below refers to an object of BITS_PER_UNIT bits (see Section 13.5 [Storage Layout], page 260).

BImode "Bit" mode represents a single bit, for predicate registers.

QImode "Quarter-Integer" mode represents a single byte treated as an integer.

HImode "Half-Integer" mode represents a two-byte integer.

PSImode "Partial Single Integer" mode represents an integer which occupies four bytes but which doesn't really use all four. On some machines, this is the right mode to use for pointers.

SImode "Single Integer" mode represents a four-byte integer.

PDImode "Partial Double Integer" mode represents an integer which occupies eight bytes but which doesn't really use all eight. On some machines, this is the right mode to use for certain pointers.

DImode "Double Integer" mode represents an eight-byte integer.

TImode "Tetra Integer" (?) mode represents a sixteen-byte integer.

Olmode "Octa Integer" (?) mode represents a thirty-two-byte integer.

QFmode "Quarter-Floating" mode represents a quarter-precision (single byte) floating point number.

HFmode "Half-Floating" mode represents a half-precision (two byte) floating point number.

TQFmode "Three-Quarter-Floating" (?) mode represents a three-quarter-precision (three byte) floating point number.

"Single Floating" mode represents a four byte floating point number. In the common case, of a processor with IEEE arithmetic and 8-bit bytes, this is a single-precision IEEE floating point number; it can also be used for double-precision (on processors with 16-bit bytes) and single-precision VAX and IBM types.

DFmode "Double Floating" mode represents an eight byte floating point number. In the common case, of a processor with IEEE arithmetic and 8-bit bytes, this is a double-precision IEEE floating point number.

XFmode "Extended Floating" mode represents an IEEE extended floating point number. This mode only has 80 meaningful bits (ten bytes). Some processors require such numbers to be padded to twelve bytes, others to sixteen; this mode is used for either.

TFmode "Tetra Floating" mode represents a sixteen byte floating point number all 128 of whose bits are meaningful. One common use is the IEEE quad-precision format.

"Condition Code" mode represents the value of a condition code, which is a machine-specific set of bits used to represent the result of a comparison operation. Other machine-specific modes may also be used for the condition code. These modes are not used on machines that use cc0 (see see Section 13.15 [Condition Code], page 320).

BLKmode "Block" mode represents values that are aggregates to which none of the other modes apply. In RTL, only memory references can have this mode, and only if they appear in string-move or vector instructions. On machines which have no such instructions, BLKmode will not appear in RTL.

VOIDmode Void mode means the absence of a mode or an unspecified mode. For example, RTL expressions of code const_int have mode VOIDmode because they can be taken to have whatever mode the context requires. In debugging dumps of RTL, VOIDmode is expressed by the absence of any mode.

QCmode, HCmode, SCmode, DCmode, XCmode, TCmode

These modes stand for a complex number represented as a pair of floating point values. The floating point values are in QFmode, HFmode, SFmode, DFmode, XFmode, and TFmode, respectively.

CQImode, CHImode, CSImode, CDImode, CTImode, COImode

These modes stand for a complex number represented as a pair of integer values. The integer values are in QImode, HImode, SImode, DImode, TImode, and OImode, respectively.

The machine description defines Pmode as a C macro which expands into the machine mode used for addresses. Normally this is the mode whose size is BITS_PER_WORD, SImode on 32-bit machines.

The only modes which a machine description *must* support are QImode, and the modes corresponding to BITS_PER_WORD, FLOAT_TYPE_SIZE and DOUBLE_TYPE_SIZE. The compiler will attempt to use DImode for 8-byte structures and unions, but this can be prevented by overriding the definition of MAX_FIXED_MODE_SIZE. Alternatively, you can have the compiler use TImode for 16-byte structures and unions. Likewise, you can arrange for the C type short int to avoid using HImode.

Very few explicit references to machine modes remain in the compiler and these few references will soon be removed. Instead, the machine modes are divided into mode classes. These are represented by the enumeration type enum mode_class defined in 'machmode.h'. The possible mode classes are:

MODE_INT Integer modes. By default these are BImode, QImode, HImode, SImode, DImode, TImode, and OImode.

MODE_PARTIAL_INT

The "partial integer" modes, PQImode, PHImode, PSImode and PDImode.

MODE_FLOAT

Floating point modes. By default these are QFmode, HFmode, TQFmode, SFmode, DFmode, XFmode and TFmode.

MODE_COMPLEX_INT

Complex integer modes. (These are not currently implemented).

MODE_COMPLEX_FLOAT

Complex floating point modes. By default these are QCmode, HCmode, SCmode, DCmode, XCmode, and TCmode.

MODE_FUNCTION

Algol or Pascal function variables including a static chain. (These are not currently implemented).

MODE_CC Modes representing condition code values. These are CCmode plus any modes listed in the EXTRA_CC_MODES macro. See Section 12.12 [Jump Patterns], page 213, also see Section 13.15 [Condition Code], page 320.

MODE_RANDOM

This is a catchall mode class for modes which don't fit into the above classes. Currently VOIDmode and BLKmode are in MODE_RANDOM.

Here are some C macros that relate to machine modes:

GET MODE (x)

Returns the machine mode of the RTX x.

PUT_MODE (x, newmode)

Alters the machine mode of the RTX x to be newmode.

NUM_MACHINE_MODES

Stands for the number of machine modes available on the target machine. This is one greater than the largest numeric value of any machine mode.

GET MODE NAME (m)

Returns the name of mode m as a string.

GET_MODE_CLASS (m)

Returns the mode class of mode m.

GET_MODE_WIDER_MODE (m)

Returns the next wider natural mode. For example, the expression GET_MODE_WIDER_MODE (QImode) returns HImode.

GET_MODE_SIZE (m)

Returns the size in bytes of a datum of mode m.

GET_MODE_BITSIZE (m)

Returns the size in bits of a datum of mode m.

GET MODE MASK (m)

Returns a bitmask containing 1 for all bits in a word that fit within mode m. This macro can only be used for modes whose bitsize is less than or equal to ${\tt HOST_BITS_PER_INT}$.

GET_MODE_ALIGNMENT (m)

Return the required alignment, in bits, for an object of mode m.

GET_MODE_UNIT_SIZE (m)

Returns the size in bytes of the subunits of a datum of mode m. This is the same as $\mathtt{GET_MODE_SIZE}$ except in the case of complex modes. For them, the unit size is the size of the real or imaginary part.

GET_MODE_NUNITS (m)

Returns the number of units contained in a mode, i.e., GET_MODE_SIZE divided by GET_MODE_UNIT_SIZE.

GET_CLASS_NARROWEST_MODE (c)

Returns the narrowest mode in mode class c.

The global variables byte_mode and word_mode contain modes whose classes are MODE_INT and whose bitsizes are either BITS_PER_UNIT or BITS_PER_WORD, respectively. On 32-bit machines, these are QImode and SImode, respectively.

10.7 Constant Expression Types

The simplest RTL expressions are those that represent constant values.

(const_int i)

This type of expression represents the integer value *i. i* is customarily accessed with the macro INTVAL as in INTVAL (exp), which is equivalent to XWINT (exp, 0).

Constants generated for modes with fewer bits than HOST_WIDE_INT must be sign extended to full width (e.g., with gen_int_mode).

There is only one expression object for the integer value zero; it is the value of the variable const0_rtx. Likewise, the only expression for integer value one is found in const1_rtx, the only expression for integer value two is found in const2_rtx, and the only expression for integer value negative one is found in constm1_rtx. Any attempt to create an expression of code const_int and value zero, one, two or negative one will return const0_rtx, const1_rtx, const2_rtx or constm1_rtx as appropriate.

Similarly, there is only one object for the integer whose value is STORE_FLAG_VALUE. It is found in const_true_rtx. If STORE_FLAG_VALUE is one, const_true_rtx and const1_rtx will point to the same object. If STORE_FLAG_VALUE is -1, const_true_rtx and constm1_rtx will point to the same object.

(const_double:m addr i0 i1 ...)

Represents either a floating-point constant of mode m or an integer constant too large to fit into HOST_BITS_PER_WIDE_INT bits but small enough to fit within twice that number of bits (GCC does not provide a mechanism to represent even larger constants). In the latter case, m will be VOIDmode.

$(const_vector:m [x0 x1 ...])$

Represents a vector constant. The square brackets stand for the vector containing the constant elements. $x\theta$, x1 and so on are the const_int or const_double elements.

The number of units in a const_vector is obtained with the macro CONST_VECTOR_NUNITS as in CONST_VECTOR_NUNITS (v).

Individual elements in a vector constant are accessed with the macro CONST_VECTOR_ELT as in CONST_VECTOR_ELT (v, n) where v is the vector constant and n is the element desired.

addr is used to contain the mem expression that corresponds to the location in memory that at which the constant can be found. If it has not been allocated a memory location, but is on the chain of all const_double expressions in this compilation (maintained using an undisplayed field), addr contains const0_rtx. If it is not on the chain, addr contains cc0_rtx. addr is customarily

accessed with the macro CONST_DOUBLE_MEM and the chain field via CONST_DOUBLE_CHAIN.

If m is VOIDmode, the bits of the value are stored in i0 and i1. i0 is customarily accessed with the macro CONST_DOUBLE_LOW and i1 with CONST_DOUBLE_HIGH.

If the constant is floating point (regardless of its precision), then the number of integers used to store the value depends on the size of REAL_VALUE_TYPE (see Section 13.22 [Floating Point], page 365). The integers represent a floating point number, but not precisely in the target machine's or host machine's floating point format. To convert them to the precise bit pattern used by the target machine, use the macro REAL_VALUE_TO_TARGET_DOUBLE and friends (see Section 13.20.2 [Data Output], page 337).

The macro CONSTO_RTX (mode) refers to an expression with value 0 in mode mode. If mode mode is of mode class MODE_INT, it returns constO_rtx. If mode mode is of mode class MODE_FLOAT, it returns a CONST_DOUBLE expression in mode mode. Otherwise, it returns a CONST_VECTOR expression in mode mode. Similarly, the macro CONST1_RTX (mode) refers to an expression with value 1 in mode mode and similarly for CONST2_RTX. The CONST1_RTX and CONST2_RTX macros are undefined for vector modes.

(const_string str)

Represents a constant string with value *str*. Currently this is used only for insn attributes (see Section 12.19 [Insn Attributes], page 228) since constant strings in C are placed in memory.

(symbol_ref:mode symbol)

Represents the value of an assembler label for data. *symbol* is a string that describes the name of the assembler label. If it starts with a '*', the label is the rest of *symbol* not including the '*'. Otherwise, the label is *symbol*, usually prefixed with '_'.

The symbol_ref contains a mode, which is usually Pmode. Usually that is the only mode for which a symbol is directly valid.

(label_ref label)

Represents the value of an assembler label for code. It contains one operand, an expression, which must be a code_label or a note of type NOTE_INSN_DELETED_LABEL that appears in the instruction sequence to identify the place where the label should go.

The reason for using a distinct expression type for code label references is so that jump optimization can distinguish them.

(const:m exp)

Represents a constant that is the result of an assembly-time arithmetic computation. The operand, exp, is an expression that contains only constants (const_int, symbol_ref and label_ref expressions) combined with plus and minus. However, not all combinations are valid, since the assembler cannot do arbitrary arithmetic on relocatable symbols.

m should be Pmode.

(high:m exp)

Represents the high-order bits of exp, usually a symbol_ref. The number of bits is machine-dependent and is normally the number of bits specified in an instruction that initializes the high order bits of a register. It is used with lo_sum to represent the typical two-instruction sequence used in RISC machines to reference a global memory location.

m should be Pmode.

10.8 Registers and Memory

Here are the RTL expression types for describing access to machine registers and to main memory.

(reg:m n)

For small values of the integer n (those that are less than FIRST_PSEUDO_REGISTER), this stands for a reference to machine register number n: a hard register. For larger values of n, it stands for a temporary value or pseudo register. The compiler's strategy is to generate code assuming an unlimited number of such pseudo registers, and later convert them into hard registers or into memory references.

m is the machine mode of the reference. It is necessary because machines can generally refer to each register in more than one mode. For example, a register may contain a full word but there may be instructions to refer to it as a half word or as a single byte, as well as instructions to refer to it as a floating point number of various precisions.

Even for a register that the machine can access in only one mode, the mode must always be specified.

The symbol FIRST_PSEUDO_REGISTER is defined by the machine description, since the number of hard registers on the machine is an invariant characteristic of the machine. Note, however, that not all of the machine registers must be general registers. All the machine registers that can be used for storage of data are given hard register numbers, even those that can be used only in certain instructions or can hold only certain types of data.

A hard register may be accessed in various modes throughout one function, but each pseudo register is given a natural mode and is accessed only in that mode. When it is necessary to describe an access to a pseudo register using a nonnatural mode, a subreg expression is used.

A reg expression with a machine mode that specifies more than one word of data may actually stand for several consecutive registers. If in addition the register number specifies a hardware register, then it actually represents several consecutive hardware registers starting with the specified one.

Each pseudo register number used in a function's RTL code is represented by a unique reg expression.

Some pseudo register numbers, those within the range of FIRST_VIRTUAL_REGISTER to LAST_VIRTUAL_REGISTER only appear during the RTL generation phase and are eliminated before the optimization phases. These represent locations in the stack frame that cannot be determined until RTL generation for

the function has been completed. The following virtual register numbers are defined:

VIRTUAL INCOMING ARGS REGNUM

This points to the first word of the incoming arguments passed on the stack. Normally these arguments are placed there by the caller, but the callee may have pushed some arguments that were previously passed in registers.

When RTL generation is complete, this virtual register is replaced by the sum of the register given by ARG_POINTER_REGNUM and the value of FIRST_PARM_OFFSET.

VIRTUAL_STACK_VARS_REGNUM

If FRAME_GROWS_DOWNWARD is defined, this points to immediately above the first variable on the stack. Otherwise, it points to the first variable on the stack.

VIRTUAL_STACK_VARS_REGNUM is replaced with the sum of the register given by FRAME_POINTER_REGNUM and the value STARTING_FRAME_OFFSET.

VIRTUAL_STACK_DYNAMIC_REGNUM

This points to the location of dynamically allocated memory on the stack immediately after the stack pointer has been adjusted by the amount of memory desired.

This virtual register is replaced by the sum of the register given by STACK_POINTER_REGNUM and the value STACK_DYNAMIC_OFFSET.

VIRTUAL_OUTGOING_ARGS_REGNUM

This points to the location in the stack at which outgoing arguments should be written when the stack is pre-pushed (arguments pushed using push insns should always use STACK_POINTER_REGNUM).

This virtual register is replaced by the sum of the register given by STACK_POINTER_REGNUM and the value STACK_POINTER_OFFSET.

(subreg:m reg bytenum)

subreg expressions are used to refer to a register in a machine mode other than its natural one, or to refer to one register of a multi-part reg that actually refers to several registers.

Each pseudo-register has a natural mode. If it is necessary to operate on it in a different mode—for example, to perform a fullword move instruction on a pseudo-register that contains a single byte—the pseudo-register must be enclosed in a subreg. In such a case, bytenum is zero.

Usually m is at least as narrow as the mode of reg, in which case it is restricting consideration to only the bits of reg that are in m.

Sometimes m is wider than the mode of reg. These subreg expressions are often called paradoxical. They are used in cases where we want to refer to an object in a wider mode but do not care what value the additional bits have. The reload pass ensures that paradoxical references are only made to hard registers.

The other use of subreg is to extract the individual registers of a multi-register value. Machine modes such as DImode and TImode can indicate values longer than a word, values which usually require two or more consecutive registers. To access one of the registers, use a subreg with mode SImode and a bytenum offset that says which register.

Storing in a non-paradoxical subreg has undefined results for bits belonging to the same word as the subreg. This laxity makes it easier to generate efficient code for such instructions. To represent an instruction that preserves all the bits outside of those in the subreg, use strict_low_part around the subreg.

The compilation parameter WORDS_BIG_ENDIAN, if set to 1, says that byte number zero is part of the most significant word; otherwise, it is part of the least significant word.

The compilation parameter BYTES_BIG_ENDIAN, if set to 1, says that byte number zero is the most significant byte within a word; otherwise, it is the least significant byte within a word.

On a few targets, FLOAT_WORDS_BIG_ENDIAN disagrees with WORDS_BIG_ENDIAN. However, most parts of the compiler treat floating point values as if they had the same endianness as integer values. This works because they handle them solely as a collection of integer values, with no particular numerical value. Only real.c and the runtime libraries care about FLOAT_WORDS_BIG_ENDIAN.

Between the combiner pass and the reload pass, it is possible to have a paradoxical subreg which contains a mem instead of a reg as its first operand. After the reload pass, it is also possible to have a non-paradoxical subreg which contains a mem; this usually occurs when the mem is a stack slot which replaced a pseudo register.

Note that it is not valid to access a DFmode value in SFmode using a subreg. On some machines the most significant part of a DFmode value does not have the same format as a single-precision floating value.

It is also not valid to access a single word of a multi-word value in a hard register when less registers can hold the value than would be expected from its size. For example, some 32-bit machines have floating-point registers that can hold an entire DFmode value. If register 10 were such a register (subreg:SI (reg:DF 10) 4) would be invalid because there is no way to convert that reference to a single machine register. The reload pass prevents subreg expressions such as these from being formed.

The first operand of a subreg expression is customarily accessed with the SUBREG_REG macro and the second operand is customarily accessed with the SUBREG_BYTE macro.

(scratch:m)

This represents a scratch register that will be required for the execution of a single instruction and not used subsequently. It is converted into a reg by either the local register allocator or the reload pass.

scratch is usually present inside a clobber operation (see Section 10.15 [Side Effects], page 135).

- (cc0) This refers to the machine's condition code register. It has no operands and may not have a machine mode. There are two ways to use it:
 - To stand for a complete set of condition code flags. This is best on most machines, where each comparison sets the entire series of flags.
 - With this technique, (cc0) may be validly used in only two contexts: as the destination of an assignment (in test and compare instructions) and in comparison operators comparing against zero (const_int with value zero; that is to say, const0_rtx).
 - To stand for a single flag that is the result of a single condition. This is useful on machines that have only a single flag bit, and in which comparison instructions must specify the condition to test.

With this technique, (cc0) may be validly used in only two contexts: as the destination of an assignment (in test and compare instructions) where the source is a comparison operator, and as the first operand of if_then_else (in a conditional branch).

There is only one expression object of code cc0; it is the value of the variable cc0_rtx. Any attempt to create an expression of code cc0 will return cc0_rtx.

Instructions can set the condition code implicitly. On many machines, nearly all instructions set the condition code based on the value that they compute or store. It is not necessary to record these actions explicitly in the RTL because the machine description includes a prescription for recognizing the instructions that do so (by means of the macro NOTICE_UPDATE_CC). See Section 13.15 [Condition Code], page 320. Only instructions whose sole purpose is to set the condition code, and instructions that use the condition code, need mention (cc0).

On some machines, the condition code register is given a register number and a reg is used instead of (cc0). This is usually the preferable approach if only a small subset of instructions modify the condition code. Other machines store condition codes in general registers; in such cases a pseudo register should be used.

Some machines, such as the SPARC and RS/6000, have two sets of arithmetic instructions, one that sets and one that does not set the condition code. This is best handled by normally generating the instruction that does not set the condition code, and making a pattern that both performs the arithmetic and sets the condition code register (which would not be (cc0) in this case). For examples, search for 'addcc' and 'andcc' in 'sparc.md'.

(pc) This represents the machine's program counter. It has no operands and may not have a machine mode. (pc) may be validly used only in certain specific contexts in jump instructions.

There is only one expression object of code pc; it is the value of the variable pc_rtx. Any attempt to create an expression of code pc will return pc_rtx.

All instructions that do not jump alter the program counter implicitly by incrementing it, but there is no need to mention this in the RTL.

(mem: m addr alias)

This RTX represents a reference to main memory at an address represented by the expression addr. m specifies how large a unit of memory is accessed. alias specifies an alias set for the reference. In general two items are in different alias sets if they cannot reference the same memory address.

The construct (mem: BLK (scratch)) is considered to alias all other memories. Thus it may be used as a memory barrier in epilogue stack deallocation patterns.

(addressof:m reg)

This RTX represents a request for the address of register reg. Its mode is always Pmode. If there are any addressof expressions left in the function after CSE, reg is forced into the stack and the addressof expression is replaced with a plus expression for the address of its stack slot.

10.9 RTL Expressions for Arithmetic

Unless otherwise specified, all the operands of arithmetic expressions must be valid for mode m. An operand is valid for mode m if it has mode m, or if it is a const_int or const_double and m is a mode of class MODE_INT.

For commutative binary operations, constants should be placed in the second operand.

```
(plus:m x y)
(ss_plus:m x y)
(us_plus:m x y)
```

These three expressions all represent the sum of the values represented by x and y carried out in machine mode m. They differ in their behavior on overflow of integer modes. plus wraps round modulo the width of m; ss_plus saturates at the maximum signed value representable in m; us_plus saturates at the maximum unsigned value.

```
(lo_sum: m \times y)
```

This expression represents the sum of x and the low-order bits of y. It is used with high (see Section 10.7 [Constants], page 122) to represent the typical two-instruction sequence used in RISC machines to reference a global memory location.

The number of low order bits is machine-dependent but is normally the number of bits in a Pmode item minus the number of bits set by high.

m should be Pmode.

```
(minus:m x y)
(ss_minus:m x y)
(us_minus:m x y)
```

These three expressions represent the result of subtracting y from x, carried out in mode M. Behavior on overflow is the same as for the three variants of plus (see above).

```
(compare: m x y)
```

Represents the result of subtracting y from x for purposes of comparison. The result is computed without overflow, as if with infinite precision.

Of course, machines can't really subtract with infinite precision. However, they can pretend to do so when only the sign of the result will be used, which is the case when the result is stored in the condition code. And that is the *only* way this kind of expression may validly be used: as a value to be stored in the condition codes, either (cc0) or a register. See Section 10.10 [Comparisons], page 131.

The mode m is not related to the modes of x and y, but instead is the mode of the condition code value. If (cc0) is used, it is VOIDmode. Otherwise it is some mode in class MODE_CC, often CCmode. See Section 13.15 [Condition Code], page 320. If m is VOIDmode or CCmode, the operation returns sufficient information (in an unspecified format) so that any comparison operator can be applied to the result of the COMPARE operation. For other modes in class MODE_CC, the operation only returns a subset of this information.

Normally, x and y must have the same mode. Otherwise, compare is valid only if the mode of x is in class MODE_INT and y is a const_int or const_double with mode VOIDmode. The mode of x determines what mode the comparison is to be done in; thus it must not be VOIDmode.

If one of the operands is a constant, it should be placed in the second operand and the comparison code adjusted as appropriate.

A compare specifying two VOIDmode constants is not valid since there is no way to know in what mode the comparison is to be performed; the comparison must either be folded during the compilation or the first operand must be loaded into a register while its mode is still known.

(neg: m x)

Represents the negation (subtraction from zero) of the value represented by x, carried out in mode m.

(mult:m x y)

Represents the signed product of the values represented by x and y carried out in machine mode m.

Some machines support a multiplication that generates a product wider than the operands. Write the pattern for this as

```
(mult:m (sign_extend:m x) (sign_extend:m y))
```

where m is wider than the modes of x and y, which need not be the same.

For unsigned widening multiplication, use the same idiom, but with zero_extend instead of sign_extend.

$(div: m \times v)$

Represents the quotient in signed division of x by y, carried out in machine mode m. If m is a floating point mode, it represents the exact quotient; otherwise, the integerized quotient.

Some machines have division instructions in which the operands and quotient widths are not all the same; you should represent such instructions using truncate and sign_extend as in,

```
(truncate:m1 (div:m2 x (sign_extend:m2 y)))
```

```
(udiv: m \times y)
```

Like div but represents unsigned division.

$(mod: m \times y)$

 $(umod: m \times y)$

Like div and udiv but represent the remainder instead of the quotient.

$(smin: m \times y)$

(smax:m x y)

Represents the smaller (for smin) or larger (for smax) of x and y, interpreted as signed values in mode m. When used with floating point, if both operands are zeros, or if either operand is NaN, then it is unspecified which of the two operands is returned as the result.

$(umin: m \times y)$

(umax: m x y)

Like smin and smax, but the values are interpreted as unsigned integers.

(not: m x)

Represents the bitwise complement of the value represented by x, carried out in mode m, which must be a fixed-point machine mode.

$(and: m \times y)$

Represents the bitwise logical-and of the values represented by x and y, carried out in machine mode m, which must be a fixed-point machine mode.

$(ior: m \times y)$

Represents the bitwise inclusive-or of the values represented by x and y, carried out in machine mode m, which must be a fixed-point mode.

$(xor: m \times y)$

Represents the bitwise exclusive-or of the values represented by x and y, carried out in machine mode m, which must be a fixed-point mode.

$(ashift: m \times c)$

Represents the result of arithmetically shifting x left by c places. x have mode m, a fixed-point machine mode. c be a fixed-point mode or be a constant with mode VOIDmode; which mode is determined by the mode called for in the machine description entry for the left-shift instruction. For example, on the VAX, the mode of c is QImode regardless of m.

$(lshiftrt: m \times c)$

(ashiftrt: m x c)

Like ashift but for right shift. Unlike the case for left shift, these two operations are distinct.

$(rotate: m \times c)$

 $(rotatert: m \times c)$

Similar but represent left and right rotate. If c is a constant, use rotate.

(abs:mx)

Represents the absolute value of x, computed in mode m.

(sqrt:mx)

Represents the square root of x, computed in mode m. Most often m will be a floating point mode.

(ffs:mx)

Represents one plus the index of the least significant 1-bit in x, represented as an integer of mode m. (The value is zero if x is zero.) The mode of x need not be m; depending on the target machine, various mode combinations may be valid.

(clz:mx)

Represents the number of leading 0-bits in x, represented as an integer of mode m, starting at the most significant bit position. If x is zero, the value is determined by CLZ_DEFINED_VALUE_AT_ZERO. Note that this is one of the few expressions that is not invariant under widening. The mode of x will usually be an integer mode.

(ctz:mx)

Represents the number of trailing 0-bits in x, represented as an integer of mode m, starting at the least significant bit position. If x is zero, the value is determined by CTZ_DEFINED_VALUE_AT_ZERO. Except for this case, ctz(x) is equivalent to ffs(x) - 1. The mode of x will usually be an integer mode.

(popcount: m x)

Represents the number of 1-bits in x, represented as an integer of mode m. The mode of x will usually be an integer mode.

(parity:mx)

Represents the number of 1-bits modulo 2 in x, represented as an integer of mode m. The mode of x will usually be an integer mode.

10.10 Comparison Operations

Comparison operators test a relation on two operands and are considered to represent a machine-dependent nonzero value described by, but not necessarily equal to, STORE_FLAG_VALUE (see Section 13.28 [Misc], page 371) if the relation holds, or zero if it does not, for comparison operators whose results have a 'MODE_INT' mode, FLOAT_STORE_FLAG_VALUE (see Section 13.28 [Misc], page 371) if the relation holds, or zero if it does not, for comparison operators that return floating-point values, and a vector of either VECTOR_STORE_FLAG_VALUE (see Section 13.28 [Misc], page 371) if the relation holds, or of zeros if it does not, for comparison operators that return vector results. The mode of the comparison operation is independent of the mode of the data being compared. If the comparison operation is being tested (e.g., the first operand of an if_then_else), the mode must be VOIDmode.

There are two ways that comparison operations may be used. The comparison operators may be used to compare the condition codes (cc0) against zero, as in (eq (cc0) (const_int 0)). Such a construct actually refers to the result of the preceding instruction in which the condition codes were set. The instruction setting the condition code must be adjacent to the instruction using the condition code; only note insns may separate them.

Alternatively, a comparison operation may directly compare two data objects. The mode of the comparison is determined by the operands; they must both be valid for a common

machine mode. A comparison with both operands constant would be invalid as the machine mode could not be deduced from it, but such a comparison should never exist in RTL due to constant folding.

In the example above, if (cc0) were last set to (compare x y), the comparison operation is identical to (eq x y). Usually only one style of comparisons is supported on a particular machine, but the combine pass will try to merge the operations to produce the eq shown in case it exists in the context of the particular insn involved.

Inequality comparisons come in two flavors, signed and unsigned. Thus, there are distinct expression codes \mathtt{gt} and \mathtt{gtu} for signed and unsigned greater-than. These can produce different results for the same pair of integer values: for example, 1 is signed greater-than -1 but not unsigned greater-than, because -1 when regarded as unsigned is actually $\mathtt{0xffffffff}$ which is greater than 1.

The signed comparisons are also used for floating point values. Floating point comparisons are distinguished by the machine modes of the operands.

```
(eq:m \times y)
            STORE_FLAG_VALUE if the values represented by x and y are equal, otherwise 0.
(ne:m \times y)
            STORE_FLAG_VALUE if the values represented by x and y are not equal, otherwise
(gt:m \times y)
            STORE_FLAG_VALUE if the x is greater than y. If they are fixed-point, the com-
            parison is done in a signed sense.
(gtu: m \times v)
            Like gt but does unsigned comparison, on fixed-point numbers only.
(1t:m \times y)
(ltu: m \times y)
            Like gt and gtu but test for "less than".
(ge: m \times y)
(geu: m \times y)
            Like gt and gtu but test for "greater than or equal".
(le:m \times y)
(leu: m \times y)
            Like gt and gtu but test for "less than or equal".
(if_then_else cond then else)
            This is not a comparison operation but is listed here because it is always used in
```

This is not a comparison operation but is listed here because it is always used in conjunction with a comparison operation. To be precise, *cond* is a comparison expression. This expression represents a choice, according to *cond*, between the value represented by *then* and the one represented by *else*.

On most machines, if_then_else expressions are valid only to express conditional jumps.

(cond [test1 value1 test2 value2 ...] default)

Similar to if_then_else, but more general. Each of test1, test2, ... is performed in turn. The result of this expression is the value corresponding to the first nonzero test, or default if none of the tests are nonzero expressions.

This is currently not valid for instruction patterns and is supported only for insn attributes. See Section 12.19 [Insn Attributes], page 228.

10.11 Bit-Fields

Special expression codes exist to represent bit-field instructions.

(sign_extract:m loc size pos)

This represents a reference to a sign-extended bit-field contained or starting in loc (a memory or register reference). The bit-field is size bits wide and starts at bit pos. The compilation option BITS_BIG_ENDIAN says which end of the memory unit pos counts from.

If loc is in memory, its mode must be a single-byte integer mode. If loc is in a register, the mode to use is specified by the operand of the insv or extv pattern (see Section 12.9 [Standard Names], page 195) and is usually a full-word integer mode, which is the default if none is specified.

The mode of *pos* is machine-specific and is also specified in the **insv** or **extv** pattern.

The mode m is the same as the mode that would be used for loc if it were a register.

A sign_extract can not appear as an Ivalue, or part thereof, in RTL.

(zero_extract:m loc size pos)

Like sign_extract but refers to an unsigned or zero-extended bit-field. The same sequence of bits are extracted, but they are filled to an entire word with zeros instead of by sign-extension.

Unlike sign_extract, this type of expressions can be lvalues in RTL; they may appear on the left side of an assignment, indicating insertion of a value into the specified bit-field.

10.12 Vector Operations

All normal RTL expressions can be used with vector modes; they are interpreted as operating on each part of the vector independently. Additionally, there are a few new expressions to describe specific vector operations.

(vec_merge:m vec1 vec2 items)

This describes a merge operation between two vectors. The result is a vector of mode m; its elements are selected from either vec1 or vec2. Which elements are selected is described by items, which is a bit mask represented by a $const_int$; a zero bit indicates the corresponding element in the result vector is taken from vec2 while a set bit indicates it is taken from vec1.

(vec_select:m vec1 selection)

This describes an operation that selects parts of a vector. *vec1* is the source vector, *selection* is a parallel that contains a const_int for each of the sub-

parts of the result vector, giving the number of the source subpart that should be stored into it.

(vec_concat:m vec1 vec2)

Describes a vector concat operation. The result is a concatenation of the vectors vec1 and vec2; its length is the sum of the lengths of the two inputs.

(vec_duplicate:m vec)

This operation converts a small vector into a larger one by duplicating the input values. The output vector mode must have the same submodes as the input vector mode, and the number of output parts must be an integer multiple of the number of input parts.

10.13 Conversions

All conversions between machine modes must be represented by explicit conversion operations. For example, an expression which is the sum of a byte and a full word cannot be written as (plus:SI (reg:QI 34) (reg:SI 80)) because the plus operation requires two operands of the same machine mode. Therefore, the byte-sized operand is enclosed in a conversion operation, as in

```
(plus:SI (sign_extend:SI (reg:QI 34)) (reg:SI 80))
```

The conversion operation is not a mere placeholder, because there may be more than one way of converting from a given starting mode to the desired final mode. The conversion operation code says how to do it.

For all conversion operations, x must not be VOIDmode because the mode in which to do the conversion would not be known. The conversion must either be done at compile-time or x must be placed into a register.

$(sign_extend: m x)$

Represents the result of sign-extending the value x to machine mode m. m must be a fixed-point mode and x a fixed-point value of a mode narrower than m.

(zero_extend: m x)

Represents the result of zero-extending the value x to machine mode m. m must be a fixed-point mode and x a fixed-point value of a mode narrower than m.

(float_extend:m x)

Represents the result of extending the value x to machine mode m. m must be a floating point mode and x a floating point value of a mode narrower than m.

(truncate: m x)

Represents the result of truncating the value x to machine mode m. m must be a fixed-point mode and x a fixed-point value of a mode wider than m.

(ss_truncate:m x)

Represents the result of truncating the value x to machine mode m, using signed saturation in the case of overflow. Both m and the mode of x must be fixed-point modes.

(us_truncate:m x)

Represents the result of truncating the value x to machine mode m, using unsigned saturation in the case of overflow. Both m and the mode of x must be fixed-point modes.

(float_truncate: m x)

Represents the result of truncating the value x to machine mode m. m must be a floating point mode and x a floating point value of a mode wider than m.

(float: m x)

Represents the result of converting fixed point value x, regarded as signed, to floating point mode m.

(unsigned_float:m x)

Represents the result of converting fixed point value x, regarded as unsigned, to floating point mode m.

(fix: m x)

When m is a fixed point mode, represents the result of converting floating point value x to mode m, regarded as signed. How rounding is done is not specified, so this operation may be used validly in compiling C code only for integer-valued operands.

(unsigned_fix:m x)

Represents the result of converting floating point value x to fixed point mode m, regarded as unsigned. How rounding is done is not specified.

(fix: mx)

When m is a floating point mode, represents the result of converting floating point value x (valid for mode m) to an integer, still represented in floating point mode m, by rounding towards zero.

10.14 Declarations

Declaration expression codes do not represent arithmetic operations but rather state assertions about their operands.

(strict_low_part (subreg:m (reg:n r) 0))

This expression code is used in only one context: as the destination operand of a set expression. In addition, the operand of this expression must be a non-paradoxical subreg expression.

The presence of $strict_low_part$ says that the part of the register which is meaningful in mode n, but is not part of mode m, is not to be altered. Normally, an assignment to such a subreg is allowed to have undefined effects on the rest of the register when m is less than a word.

10.15 Side Effect Expressions

The expression codes described so far represent values, not actions. But machine instructions never produce values; they are meaningful only for their side effects on the state of the machine. Special expression codes are used to represent side effects.

The body of an instruction is always one of these side effect codes; the codes described above, which represent values, appear only as the operands of these.

(set lval x)

Represents the action of storing the value of x into the place represented by *lval. lval* must be an expression representing a place that can be stored in: reg (or subreg, strict_low_part or zero_extract), mem, pc, parallel, or cc0.

If *lval* is a reg, subreg or mem, it has a machine mode; then x must be valid for that mode.

If *lval* is a **reg** whose machine mode is less than the full width of the register, then it means that the part of the register specified by the machine mode is given the specified value and the rest of the register receives an undefined value. Likewise, if *lval* is a **subreg** whose machine mode is narrower than the mode of the register, the rest of the register can be changed in an undefined way.

If *lval* is a strict_low_part of a subreg, then the part of the register specified by the machine mode of the subreg is given the value x and the rest of the register is not changed.

If *lval* is a zero_extract, then the referenced part of the bit-field (a memory or register reference) specified by the zero_extract is given the value x and the rest of the bit-field is not changed. Note that sign_extract can not appear in *lval*.

If lval is (cc0), it has no machine mode, and x may be either a compare expression or a value that may have any mode. The latter case represents a "test" instruction. The expression (set (cc0) (reg:m n)) is equivalent to (set (cc0) (compare (reg:m n) (const_int 0))). Use the former expression to save space during the compilation.

If *lval* is a parallel, it is used to represent the case of a function returning a structure in multiple registers. Each element of the parallel is an expr_list whose first operand is a reg and whose second operand is a const_int representing the offset (in bytes) into the structure at which the data in that register corresponds. The first element may be null to indicate that the structure is also passed partly in memory.

If lval is (pc), we have a jump instruction, and the possibilities for x are very limited. It may be a label_ref expression (unconditional jump). It may be an if_then_else (conditional jump), in which case either the second or the third operand must be (pc) (for the case which does not jump) and the other of the two must be a label_ref (for the case which does jump). x may also be a mem or (plus:SI (pc) y), where y may be a reg or a mem; these unusual patterns are used to represent jumps through branch tables.

If lval is neither (cc0) nor (pc), the mode of lval must not be VOIDmode and the mode of x must be valid for the mode of lval.

lval is customarily accessed with the SET_DEST macro and x with the SET_SRC macro.

(return) As the sole expression in a pattern, represents a return from the current function, on machines where this can be done with one instruction, such as VAXen.

On machines where a multi-instruction "epilogue" must be executed in order to return from the function, returning is done by jumping to a label which precedes the epilogue, and the **return** expression code is never used.

Inside an if_then_else expression, represents the value to be placed in pc to return to the caller.

Note that an insn pattern of (return) is logically equivalent to (set (pc) (return)), but the latter form is never used.

(call function nargs)

Represents a function call. *function* is a mem expression whose address is the address of the function to be called. *nargs* is an expression which can be used for two purposes: on some machines it represents the number of bytes of stack argument; on others, it represents the number of argument registers.

Each machine has a standard machine mode which function must have. The machine description defines macro FUNCTION_MODE to expand into the requisite mode name. The purpose of this mode is to specify what kind of addressing is allowed, on machines where the allowed kinds of addressing depend on the machine mode being addressed.

(clobber x)

Represents the storing or possible storing of an unpredictable, undescribed value into x, which must be a reg, scratch, parallel or mem expression.

One place this is used is in string instructions that store standard values into particular hard registers. It may not be worth the trouble to describe the values that are stored, but it is essential to inform the compiler that the registers will be altered, lest it attempt to keep data in them across the string instruction.

If x is (mem:BLK (const_int 0)) or (mem:BLK (scratch)), it means that all memory locations must be presumed clobbered. If x is a parallel, it has the same meaning as a parallel in a set expression.

Note that the machine description classifies certain hard registers as "call-clobbered". All function call instructions are assumed by default to clobber these registers, so there is no need to use clobber expressions to indicate this fact. Also, each function call is assumed to have the potential to alter any memory location, unless the function is declared const.

If the last group of expressions in a parallel are each a clobber expression whose arguments are reg or match_scratch (see Section 12.4 [RTL Template], page 167) expressions, the combiner phase can add the appropriate clobber expressions to an insn it has constructed when doing so will cause a pattern to be matched.

This feature can be used, for example, on a machine that whose multiply and add instructions don't use an MQ register but which has an add-accumulate instruction that does clobber the MQ register. Similarly, a combined instruction might require a temporary register while the constituent instructions might not.

When a clobber expression for a register appears inside a parallel with other side effects, the register allocator guarantees that the register is unoccupied both before and after that insn. However, the reload phase may allocate a

register used for one of the inputs unless the '&' constraint is specified for the selected alternative (see Section 12.8.4 [Modifiers], page 183). You can clobber either a specific hard register, a pseudo register, or a scratch expression; in the latter two cases, GCC will allocate a hard register that is available there for use as a temporary.

For instructions that require a temporary register, you should use scratch instead of a pseudo-register because this will allow the combiner phase to add the clobber when required. You do this by coding (clobber (match_scratch ...)). If you do clobber a pseudo register, use one which appears nowhere else—generate a new one each time. Otherwise, you may confuse CSE.

There is one other known use for clobbering a pseudo register in a parallel: when one of the input operands of the insn is also clobbered by the insn. In this case, using the same pseudo register in the clobber and elsewhere in the insn produces the expected results.

(use x) Represents the use of the value of x. It indicates that the value in x at this point in the program is needed, even though it may not be apparent why this is so. Therefore, the compiler will not attempt to delete previous instructions whose only effect is to store a value in x. x must be a reg expression.

In some situations, it may be tempting to add a use of a register in a parallel to describe a situation where the value of a special register will modify the behavior of the instruction. An hypothetical example might be a pattern for an addition that can either wrap around or use saturating addition depending on the value of a special control register:

This will not work, several of the optimizers only look at expressions locally; it is very likely that if you have multiple insns with identical inputs to the unspec, they will be optimized away even if register 1 changes in between.

This means that use can *only* be used to describe that the register is live. You should think twice before adding use statements, more often you will want to use unspec instead. The use RTX is most commonly useful to describe that a fixed register is implicitly used in an insn. It is also safe to use in patterns where the compiler knows for other reasons that the result of the whole pattern is variable, such as 'movmemm' or 'call' patterns.

During the reload phase, an insn that has a use as pattern can carry a reg_equal note. These use insns will be deleted before the reload phase exits.

During the delayed branch scheduling phase, x may be an insn. This indicates that x previously was located at this place in the code and its data dependencies need to be taken into account. These use insns will be deleted before the delayed branch scheduling phase exits.

```
(parallel [x0 x1 \dots])
```

Represents several side effects performed in parallel. The square brackets stand for a vector; the operand of parallel is a vector of expressions. x0, x1 and so

on are individual side effect expressions—expressions of code set, call, return, clobber or use.

"In parallel" means that first all the values used in the individual side-effects are computed, and second all the actual side-effects are performed. For example,

says unambiguously that the values of hard register 1 and the memory location addressed by it are interchanged. In both places where (reg:SI 1) appears as a memory address it refers to the value in register 1 before the execution of the insn.

It follows that it is *incorrect* to use parallel and expect the result of one set to be available for the next one. For example, people sometimes attempt to represent a jump-if-zero instruction this way:

But this is incorrect, because it says that the jump condition depends on the condition code value *before* this instruction, not on the new value that is set by this instruction.

Peephole optimization, which takes place together with final assembly code output, can produce insns whose patterns consist of a parallel whose elements are the operands needed to output the resulting assembler code—often reg, mem or constant expressions. This would not be well-formed RTL at any other stage in compilation, but it is ok then because no further optimization remains to be done. However, the definition of the macro NOTICE_UPDATE_CC, if any, must deal with such insns if you define any peephole optimizations.

(cond_exec [cond expr])

Represents a conditionally executed expression. The *expr* is executed only if the *cond* is nonzero. The *cond* expression must not have side-effects, but the *expr* may very well have side-effects.

(sequence [insns ...])

Represents a sequence of insns. Each of the *insns* that appears in the vector is suitable for appearing in the chain of insns, so it must be an <code>insn</code>, <code>jump_insn</code>, <code>call_insn</code>, <code>code_label</code>, <code>barrier</code> or <code>note</code>.

A sequence RTX is never placed in an actual insn during RTL generation. It represents the sequence of insns that result from a define_expand before those insns are passed to emit_insn to insert them in the chain of insns. When actually inserted, the individual sub-insns are separated out and the sequence is forgotten.

After delay-slot scheduling is completed, an insn and all the insns that reside in its delay slots are grouped together into a **sequence**. The insn requiring the delay slot is the first insn in the vector; subsequent insns are to be placed in the delay slot.

INSN_ANNULLED_BRANCH_P is set on an insn in a delay slot to indicate that a branch insn should be used that will conditionally annul the effect of the insns in the delay slots. In such a case, INSN_FROM_TARGET_P indicates that the insn is from the target of the branch and should be executed only if the branch is taken; otherwise the insn should be executed only if the branch is not taken. See Section 12.19.7 [Delay Slots], page 235.

These expression codes appear in place of a side effect, as the body of an insn, though strictly speaking they do not always describe side effects as such:

(asm_input s)

Represents literal assembler code as described by the string s.

```
(unspec [operands ...] index)
(unspec_volatile [operands ...] index)
```

Represents a machine-specific operation on *operands*. *index* selects between multiple machine-specific operations. unspec_volatile is used for volatile operations and operations that may trap; unspec is used for other operations.

These codes may appear inside a pattern of an insn, inside a parallel, or inside an expression.

```
(addr_vec:m [1r0 1r1 ...])
```

Represents a table of jump addresses. The vector elements $lr\theta$, etc., are label_ref expressions. The mode m specifies how much space is given to each address; normally m would be Pmode.

```
(addr_diff_vec:m base [lr0 lr1 ...] min max flags)
```

Represents a table of jump addresses expressed as offsets from base. The vector elements lr0, etc., are label_ref expressions and so is base. The mode m specifies how much space is given to each address-difference. min and max are set up by branch shortening and hold a label with a minimum and a maximum address, respectively. flags indicates the relative position of base, min and max to the containing insn and of min and max to base. See rtl.def for details.

(prefetch:m addr rw locality)

Represents prefetch of memory at address addr. Operand rw is 1 if the prefetch is for data to be written, 0 otherwise; targets that do not support write prefetches should treat this as a normal prefetch. Operand locality specifies the amount of temporal locality; 0 if there is none or 1, 2, or 3 for increasing levels of temporal locality; targets that do not support locality hints should ignore this.

This insn is used to minimize cache-miss latency by moving data into a cache before it is accessed. It should use only non-faulting data prefetch instructions.

10.16 Embedded Side-Effects on Addresses

Six special side-effect expression codes appear as memory addresses.

```
(pre_dec:m x)
```

Represents the side effect of decrementing x by a standard amount and represents also the value that x has after being decremented. x must be a reg or

mem, but most machines allow only a reg. m must be the machine mode for pointers on the machine in use. The amount x is decremented by is the length in bytes of the machine mode of the containing memory reference of which this expression serves as the address. Here is an example of its use:

```
(mem:DF (pre_dec:SI (reg:SI 39)))
```

This says to decrement pseudo register 39 by the length of a DFmode value and use the result to address a DFmode value.

(pre_inc:m x)

Similar, but specifies incrementing x instead of decrementing it.

(post_dec:m x)

Represents the same side effect as pre_dec but a different value. The value represented here is the value x has before being decremented.

(post_inc:mx)

Similar, but specifies incrementing x instead of decrementing it.

```
(post_modify:m x y)
```

Represents the side effect of setting x to y and represents x before x is modified. x must be a reg or mem, but most machines allow only a reg. m must be the machine mode for pointers on the machine in use.

The expression y must be one of three forms:

```
(plus: m \times z), (minus: m \times z), or (plus: m \times i),
```

where z is an index register and i is a constant.

Here is an example of its use:

This says to modify pseudo register 42 by adding the contents of pseudo register 48 to it, after the use of what ever 42 points to.

```
(pre_modify:m x expr)
```

Similar except side effects happen before the use.

These embedded side effect expressions must be used with care. Instruction patterns may not use them. Until the 'flow' pass of the compiler, they may occur only to represent pushes onto the stack. The 'flow' pass finds cases where registers are incremented or decremented in one instruction and used as an address shortly before or after; these cases are then transformed to use pre- or post-increment or -decrement.

If a register used as the operand of these expressions is used in another address in an insn, the original value of the register is used. Uses of the register outside of an address are not permitted within the same insn as a use in an embedded side effect expression because such insns behave differently on different machines and hence must be treated as ambiguous and disallowed.

An instruction that can be represented with an embedded side effect could also be represented using parallel containing an additional set to describe how the address register is altered. This is not done because machines that allow these operations at all typically allow them wherever a memory address is called for. Describing them as additional parallel stores would require doubling the number of entries in the machine description.

10.17 Assembler Instructions as Expressions

The RTX code asm_operands represents a value produced by a user-specified assembler instruction. It is used to represent an asm statement with arguments. An asm statement with a single output operand, like this:

```
asm ("foo \frac{1}{2},\frac{2}{0}": "=a" (outputvar): "g" (x + y), "di" (*z));
```

is represented using a single asm_operands RTX which represents the value that is stored in outputvar:

Here the operands of the asm_operands RTX are the assembler template string, the output-operand's constraint, the index-number of the output operand among the output operands specified, a vector of input operand RTX's, and a vector of input-operand modes and constraints. The mode m1 is the mode of the sum $\mathbf{x}+\mathbf{y}$; m2 is that of $\mathbf{*z}$.

When an asm statement has multiple output values, its insn has several such set RTX's inside of a parallel. Each set contains a asm_operands; all of these share the same assembler template and vectors, but each contains the constraint for the respective output operand. They are also distinguished by the output-operand index number, which is 0, 1, . . . for successive output operands.

10.18 Insns

The RTL representation of the code for a function is a doubly-linked chain of objects called *insns*. Insns are expressions with special codes that are used for no other purpose. Some insns are actual instructions; others represent dispatch tables for switch statements; others represent labels to jump to or various sorts of declarative information.

In addition to its own specific data, each insn must have a unique id-number that distinguishes it from all other insns in the current function (after delayed branch scheduling, copies of an insn with the same id-number may be present in multiple places in a function, but these copies will always be identical and will only appear inside a sequence), and chain pointers to the preceding and following insns. These three fields occupy the same position in every insn, independent of the expression code of the insn. They could be accessed with XEXP and XINT, but instead three special macros are always used:

```
INSN_UID (i)
```

Accesses the unique id of insn i.

```
PREV_INSN (i)
```

Accesses the chain pointer to the insn preceding i. If i is the first insn, this is a null pointer.

```
NEXT_INSN (i)
```

Accesses the chain pointer to the insn following i. If i is the last insn, this is a null pointer.

The first insn in the chain is obtained by calling get_insns; the last insn is the result of calling get_last_insn. Within the chain delimited by these insns, the NEXT_INSN and PREV_INSN pointers must always correspond: if insn is not the first insn,

After delay slot scheduling, some of the insns in the chain might be sequence expressions, which contain a vector of insns. The value of NEXT_INSN in all but the last of these insns is the next insn in the vector; the value of NEXT_INSN of the last insn in the vector is the same as the value of NEXT_INSN for the sequence in which it is contained. Similar rules apply for PREV_INSN.

This means that the above invariants are not necessarily true for insns inside sequence expressions. Specifically, if *insn* is the first insn in a sequence, NEXT_INSN (PREV_INSN (*insn*)) is the insn containing the sequence expression, as is the value of PREV_INSN (NEXT_INSN (*insn*)) if *insn* is the last insn in the sequence expression. You can use these expressions to find the containing sequence expression.

Every insn has one of the following six expression codes:

insn

The expression code insn is used for instructions that do not jump and do not do function calls. sequence expressions are always contained in insns with code insn even if one of those insns should jump or do function calls.

Insps with code insp have four additional fields beyond the three mandatory ones listed above. These four are described in a table below.

jump_insn

The expression code jump_insn is used for instructions that may jump (or, more generally, may contain label_ref expressions). If there is an instruction to return from the current function, it is recorded as a jump_insn.

jump_insn insns have the same extra fields as insn insns, accessed in the same way and in addition contain a field JUMP_LABEL which is defined once jump optimization has completed.

For simple conditional and unconditional jumps, this field contains the <code>code_label</code> to which this insn will (possibly conditionally) branch. In a more complex jump, <code>JUMP_LABEL</code> records one of the labels that the insn refers to; the only way to find the others is to scan the entire body of the insn. In an <code>addr_vec</code>, <code>JUMP_LABEL</code> is <code>NULL_RTX</code>.

Return insns count as jumps, but since they do not refer to any labels, their JUMP_LABEL is NULL_RTX.

call_insn

The expression code call_insn is used for instructions that may do function calls. It is important to distinguish these instructions because they imply that certain registers and memory locations may be altered unpredictably.

call_insn insns have the same extra fields as insn insns, accessed in the same way and in addition contain a field CALL_INSN_FUNCTION_USAGE, which contains a list (chain of expr_list expressions) containing use and clobber expressions that denote hard registers and MEMs used or clobbered by the called function.

A MEM generally points to a stack slots in which arguments passed to the libcall by reference (see Section 13.10.7 [Register Arguments], page 297) are

stored. If the argument is caller-copied (see Section 13.10.7 [Register Arguments], page 297), the stack slot will be mentioned in CLOBBER and USE entries; if it's callee-copied, only a USE will appear, and the MEM may point to addresses that are not stack slots. These MEMs are used only in libcalls, because, unlike regular function calls, CONST_CALLs (which libcalls generally are, see Section 10.5 [Flags], page 113) aren't assumed to read and write all memory, so flow would consider the stores dead and remove them. Note that, since a libcall must never return values in memory (see Section 13.10.9 [Aggregate Return], page 303), there will never be a CLOBBER for a memory address holding a return value.

CLOBBERed registers in this list augment registers specified in CALL_USED_REGISTERS (see Section 13.8.1 [Register Basics], page 272).

code_label

A code_label insn represents a label that a jump insn can jump to. It contains two special fields of data in addition to the three standard ones. CODE_LABEL_NUMBER is used to hold the *label number*, a number that identifies this label uniquely among all the labels in the compilation (not just in the current function). Ultimately, the label is represented in the assembler output as an assembler label, usually of the form 'Ln' where n is the label number.

When a code_label appears in an RTL expression, it normally appears within a label_ref which represents the address of the label, as a number.

Besides as a code_label, a label can also be represented as a note of type NOTE_INSN_DELETED_LABEL.

The field LABEL_NUSES is only defined once the jump optimization phase is completed. It contains the number of times this label is referenced in the current function.

The field LABEL_KIND differentiates four different types of labels: LABEL_NORMAL, LABEL_STATIC_ENTRY, LABEL_GLOBAL_ENTRY, and LABEL_WEAK_ENTRY. The only labels that do not have type LABEL_NORMAL are alternate entry points to the current function. These may be static (visible only in the containing translation unit), global (exposed to all translation units), or weak (global, but can be overridden by another symbol with the same name).

Much of the compiler treats all four kinds of label identically. Some of it needs to know whether or not a label is an alternate entry point; for this purpose, the macro LABEL_ALT_ENTRY_P is provided. It is equivalent to testing whether 'LABEL_KIND (label) == LABEL_NORMAL'. The only place that cares about the distinction between static, global, and weak alternate entry points, besides the front-end code that creates them, is the function output_alternate_entry_point, in 'final.c'.

To set the kind of a label, use the SET_LABEL_KIND macro.

barrier

Barriers are placed in the instruction stream when control cannot flow past them. They are placed after unconditional jump instructions to indicate that the jumps are unconditional and after calls to volatile functions, which do not return (e.g., exit). They contain no information beyond the three standard fields. note

note insns are used to represent additional debugging and declarative information. They contain two nonstandard fields, an integer which is accessed with the macro NOTE_LINE_NUMBER and a string accessed with NOTE_SOURCE_FILE.

If NOTE_LINE_NUMBER is positive, the note represents the position of a source line and NOTE_SOURCE_FILE is the source file name that the line came from. These notes control generation of line number data in the assembler output.

Otherwise, NOTE_LINE_NUMBER is not really a line number but a code with one of the following values (and NOTE_SOURCE_FILE must contain a null pointer):

NOTE_INSN_DELETED

Such a note is completely ignorable. Some passes of the compiler delete insns by altering them into notes of this kind.

NOTE_INSN_DELETED_LABEL

This marks what used to be a code_label, but was not used for other purposes than taking its address and was transformed to mark that no code jumps to it.

NOTE_INSN_BLOCK_BEG

NOTE_INSN_BLOCK_END

These types of notes indicate the position of the beginning and end of a level of scoping of variable names. They control the output of debugging information.

NOTE INSN EH REGION BEG

NOTE_INSN_EH_REGION_END

These types of notes indicate the position of the beginning and end of a level of scoping for exception handling. NOTE_BLOCK_NUMBER identifies which CODE_LABEL or note of type NOTE_INSN_DELETED_LABEL is associated with the given region.

NOTE_INSN_LOOP_BEG

NOTE_INSN_LOOP_END

These types of notes indicate the position of the beginning and end of a while or for loop. They enable the loop optimizer to find loops quickly.

NOTE_INSN_LOOP_CONT

Appears at the place in a loop that continue statements jump to.

NOTE INSN LOOP VTOP

This note indicates the place in a loop where the exit test begins for those loops in which the exit test has been duplicated. This position becomes another virtual start of the loop when considering loop invariants.

NOTE_INSN_FUNCTION_END

Appears at the start of the function body, after the function prologue.

NOTE_INSN_FUNCTION_END

Appears near the end of the function body, just before the label that **return** statements jump to (on machine where a single instruction does not suffice for returning). This note may be deleted by jump optimization.

NOTE_INSN_SETJMP

Appears following each call to set imp or a related function.

These codes are printed symbolically when they appear in debugging dumps.

The machine mode of an insn is normally VOIDmode, but some phases use the mode for various purposes.

The common subexpression elimination pass sets the mode of an insn to QImode when it is the first insn in a block that has already been processed.

The second Haifa scheduling pass, for targets that can multiple issue, sets the mode of an insn to TImode when it is believed that the instruction begins an issue group. That is, when the instruction cannot issue simultaneously with the previous. This may be relied on by later passes, in particular machine-dependent reorg.

Here is a table of the extra fields of insn, jump_insn and call_insn insns:

PATTERN (i)

An expression for the side effect performed by this insn. This must be one of the following codes: set, call, use, clobber, return, asm_input, asm_output, addr_vec, addr_diff_vec, trap_if, unspec, unspec_volatile, parallel, cond_exec, or sequence. If it is a parallel, each element of the parallel must be one these codes, except that parallel expressions cannot be nested and addr_vec and addr_diff_vec are not permitted inside a parallel expression.

INSN_CODE (i)

An integer that says which pattern in the machine description matches this insn, or -1 if the matching has not yet been attempted.

Such matching is never attempted and this field remains -1 on an insn whose pattern consists of a single use, clobber, asm_input, addr_vec or addr_diff_vec expression.

Matching is also never attempted on insns that result from an asm statement. These contain at least one asm_operands expression. The function asm_noperands returns a non-negative value for such insns.

In the debugging output, this field is printed as a number followed by a symbolic representation that locates the pattern in the 'md' file as some small positive or negative offset from a named pattern.

LOG LINKS (i)

A list (chain of insn_list expressions) giving information about dependencies between instructions within a basic block. Neither a jump nor a label may come between the related insns.

REG_NOTES (i)

A list (chain of expr_list and insn_list expressions) giving miscellaneous information about the insn. It is often information pertaining to the registers used in this insn.

The LOG_LINKS field of an insn is a chain of insn_list expressions. Each of these has two operands: the first is an insn, and the second is another insn_list expression (the next one in the chain). The last insn_list in the chain has a null pointer as second operand. The significant thing about the chain is which insns appear in it (as first operands of insn_list expressions). Their order is not significant.

This list is originally set up by the flow analysis pass; it is a null pointer until then. Flow only adds links for those data dependencies which can be used for instruction combination. For each insn, the flow analysis pass adds a link to insns which store into registers values that are used for the first time in this insn. The instruction scheduling pass adds extra links so that every dependence will be represented. Links represent data dependencies, antidependencies and output dependencies; the machine mode of the link distinguishes these three types: antidependencies have mode REG_DEP_ANTI, output dependencies have mode REG_DEP_OUTPUT, and data dependencies have mode VOIDmode.

The REG_NOTES field of an insn is a chain similar to the LOG_LINKS field but it includes expr_list expressions in addition to insn_list expressions. There are several kinds of register notes, which are distinguished by the machine mode, which in a register note is really understood as being an enum reg_note. The first operand op of the note is data whose meaning depends on the kind of note.

The macro REG_NOTE_KIND (x) returns the kind of register note. Its counterpart, the macro PUT_REG_NOTE_KIND (x, newkind) sets the register note type of x to be newkind.

Register notes are of three classes: They may say something about an input to an insn, they may say something about an output of an insn, or they may create a linkage between two insns. There are also a set of values that are only used in LOG_LINKS.

These register notes annotate inputs to an insn:

REG_DEAD The value in op dies in this insn; that is to say, altering the value immediately after this insn would not affect the future behavior of the program.

It does not follow that the register op has no useful value after this insn since op is not necessarily modified by this insn. Rather, no subsequent instruction uses the contents of op.

REG UNUSED

The register op being set by this inso will not be used in a subsequent inso. This differs from a REG_DEAD note, which indicates that the value in an input will not be used subsequently. These two notes are independent; both may be present for the same register.

REG_INC The register op is incremented (or decremented; at this level there is no distinction) by an embedded side effect inside this insn. This means it appears in a post_inc, pre_inc, post_dec or pre_dec expression.

REG_NONNEG

The register op is known to have a nonnegative value when this insn is reached. This is used so that decrement and branch until zero instructions, such as the m68k dbra, can be matched.

The REG_NONNEG note is added to insns only if the machine description has a 'decrement_and_branch_until_zero' pattern.

REG_NO_CONFLICT

This inso does not cause a conflict between op and the item being set by this inso even though it might appear that it does. In other words, if the destination register and op could otherwise be assigned the same register, this inso does not prevent that assignment.

Insns with this note are usually part of a block that begins with a clobber insn specifying a multi-word pseudo register (which will be the output of the block), a group of insns that each set one word of the value and have the REG_NO_CONFLICT note attached, and a final insn that copies the output to itself with an attached REG_EQUAL note giving the expression being computed. This block is encapsulated with REG_LIBCALL and REG_RETVAL notes on the first and last insns, respectively.

REG_LABEL

This insn uses op, a code_label or a note of type NOTE_INSN_DELETED_LABEL, but is not a jump_insn, or it is a jump_insn that required the label to be held in a register. The presence of this note allows jump optimization to be aware that op is, in fact, being used, and flow optimization to build an accurate flow graph.

REG_CROSSING_JUMP

This insn is an branching instruction (either an unconditional jump or an indirect jump) which crosses between hot and cold sections, which could potentially be very far apart in the executable. The presence of this note indicates to other optimizations that this this branching instruction should not be "collapsed" into a simpler branching construct. It is used when the optimization to partition basic blocks into hot and cold sections is turned on.

The following notes describe attributes of outputs of an insn:

REG_EQUIV REG_EQUAL

This note is only valid on an insn that sets only one register and indicates that that register will be equal to op at run time; the scope of this equivalence differs between the two types of notes. The value which the insn explicitly copies into the register may look different from op, but they will be equal at run time. If the output of the single set is a strict_low_part expression, the note refers to the register that is contained in SUBREG_REG of the subreg expression.

For REG_EQUIV, the register is equivalent to op throughout the entire function, and could validly be replaced in all its occurrences by op. ("Validly" here refers to the data flow of the program; simple replacement may make some insns

invalid.) For example, when a constant is loaded into a register that is never assigned any other value, this kind of note is used.

When a parameter is copied into a pseudo-register at entry to a function, a note of this kind records that the register is equivalent to the stack slot where the parameter was passed. Although in this case the register may be set by other insns, it is still valid to replace the register by the stack slot throughout the function.

A REG_EQUIV note is also used on an instruction which copies a register parameter into a pseudo-register at entry to a function, if there is a stack slot where that parameter could be stored. Although other insns may set the pseudo-register, it is valid for the compiler to replace the pseudo-register by stack slot throughout the function, provided the compiler ensures that the stack slot is properly initialized by making the replacement in the initial copy instruction as well. This is used on machines for which the calling convention allocates stack space for register parameters. See REG_PARM_STACK_SPACE in Section 13.10.6 [Stack Arguments], page 295.

In the case of REG_EQUAL, the register that is set by this insn will be equal to op at run time at the end of this insn but not necessarily elsewhere in the function. In this case, op is typically an arithmetic expression. For example, when a sequence of insns such as a library call is used to perform an arithmetic operation, this kind of note is attached to the insn that produces or copies the final value.

These two notes are used in different ways by the compiler passes. REG_EQUAL is used by passes prior to register allocation (such as common subexpression elimination and loop optimization) to tell them how to think of that value. REG_EQUIV notes are used by register allocation to indicate that there is an available substitute expression (either a constant or a mem expression for the location of a parameter on the stack) that may be used in place of a register if insufficient registers are available.

Except for stack homes for parameters, which are indicated by a REG_EQUIV note and are not useful to the early optimization passes and pseudo registers that are equivalent to a memory location throughout their entire life, which is not detected until later in the compilation, all equivalences are initially indicated by an attached REG_EQUAL note. In the early stages of register allocation, a REG_EQUAL note is changed into a REG_EQUIV note if op is a constant and the insn represents the only set of its destination register.

Thus, compiler passes prior to register allocation need only check for REG_EQUAL notes and passes subsequent to register allocation need only check for REG_EQUIV notes.

These notes describe linkages between insns. They occur in pairs: one insn has one of a pair of notes that points to a second insn, which has the inverse note pointing back to the first insn.

REG_RETVAL

This insn copies the value of a multi-insn sequence (for example, a library call), and op is the first insn of the sequence (for a library call, the first insn that was generated to set up the arguments for the library call).

Loop optimization uses this note to treat such a sequence as a single operation for code motion purposes and flow analysis uses this note to delete such sequences whose results are dead.

A REG_EQUAL note will also usually be attached to this inso to provide the expression being computed by the sequence.

These notes will be deleted after reload, since they are no longer accurate or useful.

REG_LIBCALL

This is the inverse of REG_RETVAL: it is placed on the first insn of a multi-insn sequence, and it points to the last one.

These notes are deleted after reload, since they are no longer useful or accurate.

REG CC SETTER

REG_CC_USER

On machines that use cc0, the insns which set and use cc0 set and use cc0 are adjacent. However, when branch delay slot filling is done, this may no longer be true. In this case a REG_CC_USER note will be placed on the insn setting cc0 to point to the insn using cc0 and a REG_CC_SETTER note will be placed on the insn using cc0 to point to the insn setting cc0.

These values are only used in the LOG_LINKS field, and indicate the type of dependency that each link represents. Links which indicate a data dependence (a read after write dependence) do not use any code, they simply have mode VOIDmode, and are printed without any descriptive text.

REG_DEP_ANTI

This indicates an anti dependence (a write after read dependence).

REG_DEP_OUTPUT

This indicates an output dependence (a write after write dependence).

These notes describe information gathered from gcov profile data. They are stored in the REG_NOTES field of an insn as an expr_list.

REG_BR_PROB

This is used to specify the ratio of branches to non-branches of a branch insn according to the profile data. The value is stored as a value between 0 and REG_BR_PROB_BASE; larger values indicate a higher probability that the branch will be taken.

REG BR PRED

These notes are found in JUMP insns after delayed branch scheduling has taken place. They indicate both the direction and the likelihood of the JUMP. The format is a bitmask of ATTR_FLAG_* values.

REG_FRAME_RELATED_EXPR

This is used on an RTX_FRAME_RELATED_P inso wherein the attached expression is used in place of the actual inso pattern. This is done in cases where the pattern is either complex or misleading.

For convenience, the machine mode in an insn_list or expr_list is printed using these symbolic codes in debugging dumps.

The only difference between the expression codes <code>insn_list</code> and <code>expr_list</code> is that the first operand of an <code>insn_list</code> is assumed to be an insn and is printed in debugging dumps as the insn's unique id; the first operand of an <code>expr_list</code> is printed in the ordinary way as an expression.

10.19 RTL Representation of Function-Call Insns

Insure that call subroutines have the RTL expression code call_insure. These insure must satisfy special rules, and their bodies must use a special RTL expression code, call.

A call expression has two operands, as follows:

```
(call (mem:fm addr) nbytes)
```

Here nbytes is an operand that represents the number of bytes of argument data being passed to the subroutine, fm is a machine mode (which must equal as the definition of the FUNCTION_MODE macro in the machine description) and addr represents the address of the subroutine.

For a subroutine that returns no value, the call expression as shown above is the entire body of the insn, except that the insn might also contain use or clobber expressions.

For a subroutine that returns a value whose mode is not BLKmode, the value is returned in a hard register. If this register's number is r, then the body of the call inso looks like this:

```
(set (reg:m r)
          (call (mem:fm addr) nbytes))
```

This RTL expression makes it clear (to the optimizer passes) that the appropriate register receives a useful value in this insn.

When a subroutine returns a BLKmode value, it is handled by passing to the subroutine the address of a place to store the value. So the call insn itself does not "return" any value, and it has the same RTL form as a call that returns nothing.

On some machines, the call instruction itself clobbers some register, for example to contain the return address. call_insn insns on these machines should have a body which is a parallel that contains both the call expression and clobber expressions that indicate which registers are destroyed. Similarly, if the call instruction requires some register other than the stack pointer that is not explicitly mentioned it its RTL, a use subexpression should mention that register.

Functions that are called are assumed to modify all registers listed in the configuration macro CALL_USED_REGISTERS (see Section 13.8.1 [Register Basics], page 272) and, with the exception of const functions and library calls, to modify all of memory.

Insure containing just use expressions directly precede the call_insu insure to indicate which registers contain inputs to the function. Similarly, if registers other than those in CALL_USED_REGISTERS are clobbered by the called function, insure containing a single clobber follow immediately after the call to indicate which registers.

10.20 Structure Sharing Assumptions

The compiler assumes that certain kinds of RTL expressions are unique; there do not exist two distinct objects representing the same value. In other cases, it makes an opposite assumption: that no RTL expression object of a certain kind appears in more than one place in the containing structure.

These assumptions refer to a single function; except for the RTL objects that describe global variables and external functions, and a few standard objects such as small integer constants, no RTL objects are common to two functions.

- Each pseudo-register has only a single **reg** object to represent it, and therefore only a single machine mode.
- For any symbolic label, there is only one symbol_ref object referring to it.
- All const_int expressions with equal values are shared.
- There is only one pc expression.
- There is only one cc0 expression.
- There is only one const_double expression with value 0 for each floating point mode. Likewise for values 1 and 2.
- There is only one const_vector expression with value 0 for each vector mode, be it an integer or a double constant vector.
- No label_ref or scratch appears in more than one place in the RTL structure; in other words, it is safe to do a tree-walk of all the insns in the function and assume that each time a label_ref or scratch is seen it is distinct from all others that are seen.
- Only one mem object is normally created for each static variable or stack slot, so these objects are frequently shared in all the places they appear. However, separate but equal objects for these variables are occasionally made.
- When a single asm statement has multiple output operands, a distinct asm_operands expression is made for each output operand. However, these all share the vector which contains the sequence of input operands. This sharing is used later on to test whether two asm_operands expressions come from the same statement, so all optimizations must carefully preserve the sharing if they copy the vector at all.
- No RTL object appears in more than one place in the RTL structure except as described above. Many passes of the compiler rely on this by assuming that they can modify RTL objects in place without unwanted side-effects on other insns.
- During initial RTL generation, shared structure is freely introduced. After all the RTL for a function has been generated, all shared structure is copied by unshare_all_rtl in 'emit-rtl.c', after which the above rules are guaranteed to be followed.
- During the combiner pass, shared structure within an insn can exist temporarily. However, the shared structure is copied before the combiner is finished with the insn. This is done by calling copy_rtx_if_shared, which is a subroutine of unshare_all_rtl.

10.21 Reading RTL

To read an RTL object from a file, call read_rtx. It takes one argument, a stdio stream, and returns a single RTL object. This routine is defined in 'read-rtl.c'. It is not available

in the compiler itself, only the various programs that generate the compiler back end from the machine description.

People frequently have the idea of using RTL stored as text in a file as an interface between a language front end and the bulk of GCC. This idea is not feasible.

GCC was designed to use RTL internally only. Correct RTL for a given program is very dependent on the particular target machine. And the RTL does not contain all the information about the program.

The proper way to interface GCC to a new language front end is with the "tree" data structure, described in the files 'tree.h' and 'tree.def'. The documentation for this structure (see Chapter 8 [Trees], page 55) is incomplete.

11 Control Flow Graph

A control flow graph (CFG) is a data structure built on top of the intermediate code representation (the RTL or tree instruction stream) abstracting the control flow behavior of a function that is being compiled. The CFG is a directed graph where the vertices represent basic blocks and edges represent possible transfer of control flow from one basic block to another. The data structures used to represent the control flow graph are defined in 'basic-block.h'.

11.1 Basic Blocks

A basic block is a straight-line sequence of code with only one entry point and only one exit. In GCC, basic blocks are represented using the basic_block data type.

Two pointer members of the basic_block structure are the pointers next_bb and prev_bb. These are used to keep doubly linked chain of basic blocks in the same order as the underlying instruction stream. The chain of basic blocks is updated transparently by the provided API for manipulating the CFG. The macro FOR_EACH_BB can be used to visit all the basic blocks in lexicographical order. Dominator traversals are also possible using walk_dominator_tree. Given two basic blocks A and B, block A dominates block B if A is always executed before B.

The BASIC_BLOCK array contains all basic blocks in an unspecified order. Each basic_block structure has a field that holds a unique integer identifier index that is the index of the block in the BASIC_BLOCK array. The total number of basic blocks in the function is n_basic_blocks. Both the basic block indices and the total number of basic blocks may vary during the compilation process, as passes reorder, create, duplicate, and destroy basic blocks. The index for any block should never be greater than last_basic_block.

Special basic blocks represent possible entry and exit points of a function. These blocks are called ENTRY_BLOCK_PTR and EXIT_BLOCK_PTR. These blocks do not contain any code, and are not elements of the BASIC_BLOCK array. Therefore they have been assigned unique, negative index numbers.

Each basic_block also contains pointers to the first instruction (the head) and the last instruction (the tail) or end of the instruction stream contained in a basic block. In fact, since the basic_block data type is used to represent blocks in both major intermediate representations of GCC (tree and RTL), there are pointers to the head and end of a basic block for both representations.

For RTL, these pointers are rtx head, end. In the RTL function representation, the head pointer always points either to a NOTE_INSN_BASIC_BLOCK or to a CODE_LABEL, if present. In the RTL representation of a function, the instruction stream contains not only the "real" instructions, but also notes. Any function that moves or duplicates the basic blocks needs to take care of updating of these notes. Many of these notes expect that the instruction stream consists of linear regions, making such updates difficult. The NOTE_INSN_BASIC_BLOCK note is the only kind of note that may appear in the instruction stream contained in a basic block. The instruction stream of a basic block always follows a NOTE_INSN_BASIC_BLOCK, but zero or more CODE_LABEL nodes can precede the block note. A basic block ends by control flow instruction or last instruction before following CODE_LABEL or NOTE_INSN_BASIC_BLOCK. A CODE_LABEL cannot appear in the instruction stream of a basic block.

In addition to notes, the jump table vectors are also represented as "pseudo-instructions" inside the insn stream. These vectors never appear in the basic block and should always be placed just after the table jump instructions referencing them. After removing the table-jump it is often difficult to eliminate the code computing the address and referencing the vector, so cleaning up these vectors is postponed until after liveness analysis. Thus the jump table vectors may appear in the insn stream unreferenced and without any purpose. Before any edge is made fall-thru, the existence of such construct in the way needs to be checked by calling can_fallthru function.

For the tree representation, the head and end of the basic block are being pointed to by the stmt_list field, but this special tree should never be referenced directly. Instead, at the tree level abstract containers and iterators are used to access statements and expressions in basic blocks. These iterators are called block statement iterators (BSIs). Grep for `bsi in the various 'tree-*' files. The following snippet will pretty-print all the statements of the program in the GIMPLE representation.

```
FOR_EACH_BB (bb)
{
    block_stmt_iterator si;

    for (si = bsi_start (bb); !bsi_end_p (si); bsi_next (&si))
        {
            tree stmt = bsi_stmt (si);
            print_generic_stmt (stderr, stmt, 0);
        }
}
```

11.2 Edges

Edges represent possible control flow transfers from the end of some basic block A to the head of another basic block B. We say that A is a predecessor of B, and B is a successor of A. Edges are represented in GCC with the edge data type. Each edge acts as a link between two basic blocks: the src member of an edge points to the predecessor basic block of the dest basic block. The members preds and succs of the basic_block data type point to type-safe vectors of edges to the predecessors and successors of the block.

When walking the edges in an edge vector, edge iterators should be used. Edge iterators are constructed using the edge_iterator data structure and several methods are available to operate on them:

- ei_start This function initializes an edge_iterator that points to the first edge in a vector of edges.
- ei_last This function initializes an edge_iterator that points to the last edge in a vector of edges.
- ei_end_p This predicate is true if an edge_iterator represents the last edge in an edge vector.

ei_one_before_end_p

This predicate is true if an edge_iterator represents the second last edge in an edge vector.

ei_next This function takes a pointer to an edge_iterator and makes it point to the next edge in the sequence.

ei_prev This function takes a pointer to an edge_iterator and makes it point to the previous edge in the sequence.

ei_edge This function returns the edge currently pointed to by an edge_iterator.

ei_safe_safe

This function returns the edge currently pointed to by an edge_iterator, but returns NULL if the iterator is pointing at the end of the sequence. This function has been provided for existing code makes the assumption that a NULL edge indicates the end of the sequence.

The convenience macro FOR_EACH_EDGE can be used to visit all of the edges in a sequence of predecessor or successor edges. It must not be used when an element might be removed during the traversal, otherwise elements will be missed. Here is an example of how to use the macro:

There are various reasons why control flow may transfer from one block to another. One possibility is that some instruction, for example a CODE_LABEL, in a linearized instruction stream just always starts a new basic block. In this case a fall-thru edge links the basic block to the first following basic block. But there are several other reasons why edges may be created. The flags field of the edge data type is used to store information about the type of edge we are dealing with. Each edge is of one of the following types:

jump No type flags are set for edges corresponding to jump instructions. These edges are used for unconditional or conditional jumps and in RTL also for table jumps. They are the easiest to manipulate as they may be freely redirected when the flow graph is not in SSA form.

Fall-thru edges are present in case where the basic block may continue execution to the following one without branching. These edges have the EDGE_FALLTHRU flag set. Unlike other types of edges, these edges must come into the basic block immediately following in the instruction stream. The function force_nonfallthru is available to insert an unconditional jump in the case that redirection is needed. Note that this may require creation of a new basic block.

exception handling

Exception handling edges represent possible control transfers from a trapping instruction to an exception handler. The definition of "trapping" varies. In C++, only function calls can throw, but for Java, exceptions like division by zero or segmentation fault are defined and thus each instruction possibly throwing this kind of exception needs to be handled as control flow instruction. Exception edges have the EDGE_ABNORMAL and EDGE_EH flags set.

When updating the instruction stream it is easy to change possibly trapping instruction to non-trapping, by simply removing the exception edge. The opposite conversion is difficult, but should not happen anyway. The edges can be eliminated via purge_dead_edges call.

In the RTL representation, the destination of an exception edge is specified by REG_EH_REGION note attached to the insn. In case of a trapping call the EDGE_ABNORMAL_CALL flag is set too. In the tree representation, this extra flag is not set.

In the RTL representation, the predicate may_trap_p may be used to check whether instruction still may trap or not. For the tree representation, the tree_could_trap_p predicate is available, but this predicate only checks for possible memory traps, as in dereferencing an invalid pointer location.

sibling calls

Sibling calls or tail calls terminate the function in a non-standard way and thus an edge to the exit must be present. EDGE_SIBCALL and EDGE_ABNORMAL are set in such case. These edges only exist in the RTL representation.

computed jumps

Computed jumps contain edges to all labels in the function referenced from the code. All those edges have EDGE_ABNORMAL flag set. The edges used to represent computed jumps often cause compile time performance problems, since functions consisting of many taken labels and many computed jumps may have very dense flow graphs, so these edges need to be handled with special care. During the earlier stages of the compilation process, GCC tries to avoid such dense flow graphs by factoring computed jumps. For example, given the following series of jumps,

```
goto *x;
[ ... ]
goto *x;
[ ... ]
goto *x;
[ ... ]
```

factoring the computed jumps results in the following code sequence which has a much simpler flow graph:

```
goto y;
[ ... ]
goto y;
[ ... ]
goto y;
[ ... ]
y:
goto *x;
```

However, the classic problem with this transformation is that it has a runtime cost in there resulting code: An extra jump. Therefore, the computed jumps are un-factored in the later passes of the compiler. Be aware of that when

you work on passes in that area. There have been numerous examples already where the compile time for code with unfactored computed jumps caused some serious headaches.

nonlocal goto handlers

GCC allows nested functions to return into caller using a goto to a label passed to as an argument to the callee. The labels passed to nested functions contain special code to cleanup after function call. Such sections of code are referred to as "nonlocal goto receivers". If a function contains such nonlocal goto receivers, an edge from the call to the label is created with the EDGE_ABNORMAL and EDGE_ABNORMAL_CALL flags set.

function entry points

By definition, execution of function starts at basic block 0, so there is always an edge from the ENTRY_BLOCK_PTR to basic block 0. There is no tree representation for alternate entry points at this moment. In RTL, alternate entry points are specified by CODE_LABEL with LABEL_ALTERNATE_NAME defined. This feature is currently used for multiple entry point prologues and is limited to post-reload passes only. This can be used by back-ends to emit alternate prologues for functions called from different contexts. In future full support for multiple entry functions defined by Fortran 90 needs to be implemented.

function exits

In the pre-reload representation a function terminates after the last instruction in the insn chain and no explicit return instructions are used. This corresponds to the fall-thru edge into exit block. After reload, optimal RTL epilogues are used that use explicit (conditional) return instructions that are represented by edges with no flags set.

11.3 Profile information

In many cases a compiler must make a choice whether to trade speed in one part of code for speed in another, or to trade code size for code speed. In such cases it is useful to know information about how often some given block will be executed. That is the purpose for maintaining profile within the flow graph. GCC can handle profile information obtained through profile feedback, but it can also estimate branch probabilities based on statics and heuristics.

The feedback based profile is produced by compiling the program with instrumentation, executing it on a train run and reading the numbers of executions of basic blocks and edges back to the compiler while re-compiling the program to produce the final executable. This method provides very accurate information about where a program spends most of its time on the train run. Whether it matches the average run of course depends on the choice of train data set, but several studies have shown that the behavior of a program usually changes just marginally over different data sets.

When profile feedback is not available, the compiler may be asked to attempt to predict the behavior of each branch in the program using a set of heuristics (see 'predict.def' for details) and compute estimated frequencies of each basic block by propagating the probabilities over the graph.

Each basic_block contains two integer fields to represent profile information: frequency and count. The frequency is an estimation how often is basic block executed within a function. It is represented as an integer scaled in the range from 0 to BB_FREQ_BASE. The most frequently executed basic block in function is initially set to BB_FREQ_BASE and the rest of frequencies are scaled accordingly. During optimization, the frequency of the most frequent basic block can both decrease (for instance by loop unrolling) or grow (for instance by cross-jumping optimization), so scaling sometimes has to be performed multiple times.

The count contains hard-counted numbers of execution measured during training runs and is nonzero only when profile feedback is available. This value is represented as the host's widest integer (typically a 64 bit integer) of the special type gcov_type.

Most optimization passes can use only the frequency information of a basic block, but a few passes may want to know hard execution counts. The frequencies should always match the counts after scaling, however during updating of the profile information numerical error may accumulate into quite large errors.

Each edge also contains a branch probability field: an integer in the range from 0 to REG_BR_PROB_BASE. It represents probability of passing control from the end of the src basic block to the dest basic block, i.e. the probability that control will flow along this edge. The EDGE_FREQUENCY macro is available to compute how frequently a given edge is taken. There is a count field for each edge as well, representing same information as for a basic block.

The basic block frequencies are not represented in the instruction stream, but in the RTL representation the edge frequencies are represented for conditional jumps (via the REG_BR_PROB macro) since they are used when instructions are output to the assembly file and the flow graph is no longer maintained.

The probability that control flow arrives via a given edge to its destination basic block is called *reverse probability* and is not directly represented, but it may be easily computed from frequencies of basic blocks.

Updating profile information is a delicate task that can unfortunately not be easily integrated with the CFG manipulation API. Many of the functions and hooks to modify the CFG, such as redirect_edge_and_branch, do not have enough information to easily update the profile, so updating it is in the majority of cases left up to the caller. It is difficult to uncover bugs in the profile updating code, because they manifest themselves only by producing worse code, and checking profile consistency is not possible because of numeric error accumulation. Hence special attention needs to be given to this issue in each pass that modifies the CFG.

It is important to point out that REG_BR_PROB_BASE and BB_FREQ_BASE are both set low enough to be possible to compute second power of any frequency or probability in the flow graph, it is not possible to even square the count field, as modern CPUs are fast enough to execute \$2^32\$ operations quickly.

11.4 Maintaining the CFG

An important task of each compiler pass is to keep both the control flow graph and all profile information up-to-date. Reconstruction of the control flow graph after each pass is not an option, since it may be very expensive and lost profile information cannot be reconstructed at all.

GCC has two major intermediate representations, and both use the basic_block and edge data types to represent control flow. Both representations share as much of the CFG maintenance code as possible. For each representation, a set of hooks is defined so that each representation can provide its own implementation of CFG manipulation routines when necessary. These hooks are defined in 'cfghooks.h'. There are hooks for almost all common CFG manipulations, including block splitting and merging, edge redirection and creating and deleting basic blocks. These hooks should provide everything you need to maintain and manipulate the CFG in both the RTL and tree representation.

At the moment, the basic block boundaries are maintained transparently when modifying instructions, so there rarely is a need to move them manually (such as in case someone wants to output instruction outside basic block explicitly). Often the CFG may be better viewed as integral part of instruction chain, than structure built on the top of it. However, in principle the control flow graph for the tree representation is not an integral part of the representation, in that a function tree may be expanded without first building a flow graph for the tree representation at all. This happens when compiling without any tree optimization enabled. When the tree optimizations are enabled and the instruction stream is rewritten in SSA form, the CFG is very tightly coupled with the instruction stream. In particular, statement insertion and removal has to be done with care. In fact, the whole tree representation can not be easily used or maintained without proper maintenance of the CFG simultaneously.

In the RTL representation, each instruction has a BLOCK_FOR_INSN value that represents pointer to the basic block that contains the instruction. In the tree representation, the function bb_for_stmt returns a pointer to the basic block containing the queried statement.

When changes need to be applied to a function in its tree representation, block statement iterators should be used. These iterators provide an integrated abstraction of the flow graph and the instruction stream. Block statement iterators iterators are constructed using the block_stmt_iterator data structure and several modifier are available, including the following:

bsi_start

This function initializes a block_stmt_iterator that points to the first non-empty statement in a basic block.

bsi_last This function initializes a block_stmt_iterator that points to the last statement in a basic block.

bsi_end_p

This predicate is true if a block_stmt_iterator represents the end of a basic block.

bsi_next This function takes a block_stmt_iterator and makes it point to its successor.

bsi_prev This function takes a block_stmt_iterator and makes it point to its predecessor.

bsi_insert_after

This function inserts a statement after the block_stmt_iterator passed in. The final parameter determines whether the statement iterator is updated to point to the newly inserted statement, or left pointing to the original statement.

bsi_insert_before

This function inserts a statement before the block_stmt_iterator passed in. The final parameter determines whether the statement iterator is updated to point to the newly inserted statement, or left pointing to the original statement.

bsi_remove

This function removes the block_stmt_iterator passed in and rechains the remaining statements in a basic block, if any.

In the RTL representation, the macros BB_HEAD and BB_END may be used to get the head and end rtx of a basic block. No abstract iterators are defined for traversing the insn chain, but you can just use NEXT_INSN and PREV_INSN instead. See See Section 10.18 [Insns], page 142.

Usually a code manipulating pass simplifies the instruction stream and the flow of control, possibly eliminating some edges. This may for example happen when a conditional jump is replaced with an unconditional jump, but also when simplifying possibly trapping instruction to non-trapping while compiling Java. Updating of edges is not transparent and each optimization pass is required to do so manually. However only few cases occur in practice. The pass may call purge_dead_edges on a given basic block to remove superfluous edges, if any.

Another common scenario is redirection of branch instructions, but this is best modeled as redirection of edges in the control flow graph and thus use of redirect_edge_and_branch is preferred over more low level functions, such as redirect_jump that operate on RTL chain only. The CFG hooks defined in 'cfghooks.h' should provide the complete API required for manipulating and maintaining the CFG.

It is also possible that a pass has to insert control flow instruction into the middle of a basic block, thus creating an entry point in the middle of the basic block, which is impossible by definition: The block must be split to make sure it only has one entry point, i.e. the head of the basic block. In the RTL representation, the find_sub_basic_blocks may be used to split existing basic block and add necessary edges. The CFG hook split_block may be used when an instruction in the middle of a basic block has to become the target of a jump or branch instruction.

For a global optimizer, a common operation is to split edges in the flow graph and insert instructions on them. In the RTL representation, this can be easily done using the <code>insert_insn_on_edge</code> function that emits an instruction "on the edge", caching it for a later <code>commit_edge_insertions</code> call that will take care of moving the inserted instructions off the edge into the instruction stream contained in a basic block. This includes the creation of new basic blocks where needed. In the <code>tree</code> representation, the equivalent functions are <code>bsi_insert_on_edge</code> which inserts a block statement iterator on an edge, and <code>bsi_commit_edge_inserts</code> which flushes the instruction to actual instruction stream.

While debugging the optimization pass, an verify_flow_info function may be useful to find bugs in the control flow graph updating code.

Note that at present, the representation of control flow in the tree representation is discarded before expanding to RTL. Long term the CFG should be maintained and "expanded" to the RTL representation along with the function tree itself.

11.5 Liveness information

Liveness information is useful to determine whether some register is "live" at given point of program, i.e. that it contains a value that may be used at a later point in the program. This information is used, for instance, during register allocation, as the pseudo registers only need to be assigned to a unique hard register or to a stack slot if they are live. The hard registers and stack slots may be freely reused for other values when a register is dead.

The liveness information is stored partly in the RTL instruction stream and partly in the flow graph. Local information is stored in the instruction stream: Each instruction may contain REG_DEAD notes representing that the value of a given register is no longer needed, or REG_UNUSED notes representing that the value computed by the instruction is never used. The second is useful for instructions computing multiple values at once.

Global liveness information is stored in the control flow graph. Each basic block contains two bitmaps, global_live_at_start and global_live_at_end representing liveness of each register at the entry and exit of the basic block. The file flow.c contains functions to compute liveness of each register at any given place in the instruction stream using this information.

Liveness is expensive to compute and thus it is desirable to keep it up to date during code modifying passes. This can be easily accomplished using the flags field of a basic block. Functions modifying the instruction stream automatically set the BB_DIRTY flag of a modifies basic block, so the pass may simply useclear_bb_flags before doing any modifications and then ask the data flow module to have liveness updated via the update_life_info_in_dirty_blocks function.

This scheme works reliably as long as no control flow graph transformations are done. The task of updating liveness after control flow graph changes is more difficult as normal iterative data flow analysis may produce invalid results or get into an infinite cycle when the initial solution is not below the desired one. Only simple transformations, like splitting basic blocks or inserting on edges, are safe, as functions to implement them already know how to update liveness information locally.

12 Machine Descriptions

A machine description has two parts: a file of instruction patterns ('.md' file) and a C header file of macro definitions.

The '.md' file for a target machine contains a pattern for each instruction that the target machine supports (or at least each instruction that is worth telling the compiler about). It may also contain comments. A semicolon causes the rest of the line to be a comment, unless the semicolon is inside a quoted string.

See the next chapter for information on the C header file.

12.1 Overview of How the Machine Description is Used

There are three main conversions that happen in the compiler:

- 1. The front end reads the source code and builds a parse tree.
- 2. The parse tree is used to generate an RTL insn list based on named instruction patterns.
- 3. The insn list is matched against the RTL templates to produce assembler code.

For the generate pass, only the names of the insns matter, from either a named define_insn or a define_expand. The compiler will choose the pattern with the right name and apply the operands according to the documentation later in this chapter, without regard for the RTL template or operand constraints. Note that the names the compiler looks for are hard-coded in the compiler—it will ignore unnamed patterns and patterns with names it doesn't know about, but if you don't provide a named pattern it needs, it will abort.

If a define_insn is used, the template given is inserted into the insn list. If a define_expand is used, one of three things happens, based on the condition logic. The condition logic may manually create new insns for the insn list, say via emit_insn(), and invoke DONE. For certain named patterns, it may invoke FAIL to tell the compiler to use an alternate way of performing that task. If it invokes neither DONE nor FAIL, the template given in the pattern is inserted, as if the define_expand were a define_insn.

Once the insn list is generated, various optimization passes convert, replace, and rearrange the insns in the insn list. This is where the define_split and define_peephole patterns get used, for example.

Finally, the insn list's RTL is matched up with the RTL templates in the define_insn patterns, and those patterns are used to emit the final assembly code. For this purpose, each named define_insn acts like it's unnamed, since the names are ignored.

12.2 Everything about Instruction Patterns

Each instruction pattern contains an incomplete RTL expression, with pieces to be filled in later, operand constraints that restrict how the pieces can be filled in, and an output pattern or C code to generate the assembler output, all wrapped up in a define_insn expression.

A define_insn is an RTL expression containing four or five operands:

1. An optional name. The presence of a name indicate that this instruction pattern can perform a certain standard job for the RTL-generation pass of the compiler. This pass knows certain names and will use the instruction patterns with those names, if the names are defined in the machine description.

The absence of a name is indicated by writing an empty string where the name should go. Nameless instruction patterns are never used for generating RTL code, but they may permit several simpler insns to be combined later on.

Names that are not thus known and used in RTL-generation have no effect; they are equivalent to no name at all.

For the purpose of debugging the compiler, you may also specify a name beginning with the '*' character. Such a name is used only for identifying the instruction in RTL dumps; it is entirely equivalent to having a nameless pattern for all other purposes.

2. The RTL template (see Section 12.4 [RTL Template], page 167) is a vector of incomplete RTL expressions which show what the instruction should look like. It is incomplete because it may contain match_operand, match_operator, and match_dup expressions that stand for operands of the instruction.

If the vector has only one element, that element is the template for the instruction pattern. If the vector has multiple elements, then the instruction pattern is a parallel expression containing the elements described.

3. A condition. This is a string which contains a C expression that is the final test to decide whether an insn body matches this pattern.

For a named pattern, the condition (if present) may not depend on the data in the insn being matched, but only the target-machine-type flags. The compiler needs to test these conditions during initialization in order to learn exactly which named instructions are available in a particular run.

For nameless patterns, the condition is applied only when matching an individual insn, and only after the insn has matched the pattern's recognition template. The insn's operands may be found in the vector operands. For an insn where the condition has once matched, it can't be used to control register allocation, for example by excluding certain hard registers or hard register combinations.

4. The *output template*: a string that says how to output matching insns as assembler code. '%' in this string specifies where to substitute the value of an operand. See Section 12.5 [Output Template], page 170.

When simple substitution isn't general enough, you can specify a piece of C code to compute the output. See Section 12.6 [Output Statement], page 172.

5. Optionally, a vector containing the values of attributes for insns matching this pattern. See Section 12.19 [Insn Attributes], page 228.

12.3 Example of define_insn

Here is an actual example of an instruction pattern, for the 68000/68020.

This can also be written using braced strings:

This is an instruction that sets the condition codes based on the value of a general operand. It has no condition, so any insn whose RTL description has the form shown may be handled according to this pattern. The name 'tstsi' means "test a SImode value" and tells the RTL generation pass that, when it is necessary to test such a value, an insn to do so can be constructed using this pattern.

The output control string is a piece of C code which chooses which output template to return based on the kind of operand and the specific type of CPU for which code is being generated.

""rm" is an operand constraint. Its meaning is explained below.

12.4 RTL Template

The RTL template is used to define which insns match the particular pattern and how to find their operands. For named patterns, the RTL template also says how to construct an insn from specified operands.

Construction involves substituting specified operands into a copy of the template. Matching involves determining the values that serve as the operands in the insn being matched. Both of these activities are controlled by special expression types that direct matching and substitution of the operands.

(match_operand:m n predicate constraint)

This expression is a placeholder for operand number n of the insn. When constructing an insn, operand number n will be substituted at this point. When matching an insn, whatever appears at this position in the insn will be taken as operand number n; but it must satisfy predicate or this instruction pattern will not match at all.

Operand numbers must be chosen consecutively counting from zero in each instruction pattern. There may be only one match_operand expression in the pattern for each operand number. Usually operands are numbered in the order of appearance in match_operand expressions. In the case of a define_expand, any operand numbers used only in match_dup expressions have higher values than all other operand numbers.

predicate is a string that is the name of a function that accepts two arguments, an expression and a machine mode. See Section 12.7 [Predicates], page 173. During matching, the function will be called with the putative operand as the expression and m as the mode argument (if m is not specified, VOIDmode will be used, which normally causes predicate to accept any mode). If it returns zero, this instruction pattern fails to match. predicate may be an empty string; then

it means no test is to be done on the operand, so anything which occurs in this position is valid.

Most of the time, predicate will reject modes other than m—but not always. For example, the predicate address_operand uses m as the mode of memory ref that the address should be valid for. Many predicates accept const_int nodes even though their mode is VOIDmode.

constraint controls reloading and the choice of the best register class to use for a value, as explained later (see Section 12.8 [Constraints], page 177). If the constraint would be an empty string, it can be omitted.

People are often unclear on the difference between the constraint and the predicate. The predicate helps decide whether a given insumatches the pattern. The constraint plays no role in this decision; instead, it controls various decisions in the case of an insum which does match.

(match_scratch:m n constraint)

This expression is also a placeholder for operand number n and indicates that operand must be a scratch or reg expression.

When matching patterns, this is equivalent to

(match_operand:m n "scratch_operand" pred)

but, when generating RTL, it produces a (scratch:m) expression.

If the last few expressions in a parallel are clobber expressions whose operands are either a hard register or match_scratch, the combiner can add or delete them when necessary. See Section 10.15 [Side Effects], page 135.

(match_dup n)

This expression is also a placeholder for operand number n. It is used when the operand needs to appear more than once in the insn.

In construction, match_dup acts just like match_operand: the operand is substituted into the insn being constructed. But in matching, match_dup behaves differently. It assumes that operand number n has already been determined by a match_operand appearing earlier in the recognition template, and it matches only an identical-looking expression.

Note that match_dup should not be used to tell the compiler that a particular register is being used for two operands (example: add that adds one register to another; the second register is both an input operand and the output operand). Use a matching constraint (see Section 12.8.1 [Simple Constraints], page 177) for those. match_dup is for the cases where one operand is used in two places in the template, such as an instruction that computes both a quotient and a remainder, where the opcode takes two input operands but the RTL template has to refer to each of those twice; once for the quotient pattern and once for the remainder pattern.

(match_operator:m n predicate [operands...])

This pattern is a kind of placeholder for a variable RTL expression code.

When constructing an insn, it stands for an RTL expression whose expression code is taken from that of operand n, and whose operands are constructed from the patterns operands.

When matching an expression, it matches an expression if the function predicate returns nonzero on that expression and the patterns operands match the operands of the expression.

Suppose that the function commutative_operator is defined as follows, to match any expression whose operator is one of the commutative arithmetic operators of RTL and whose mode is *mode*:

Then the following pattern will match any RTL expression consisting of a commutative operator applied to two general operands:

```
(match_operator:SI 3 "commutative_operator"
  [(match_operand:SI 1 "general_operand" "g")
  (match_operand:SI 2 "general_operand" "g")])
```

Here the vector [operands...] contains two patterns because the expressions to be matched all contain two operands.

When this pattern does match, the two operands of the commutative operator are recorded as operands 1 and 2 of the insn. (This is done by the two instances of match_operand.) Operand 3 of the insn will be the entire commutative expression: use GET_CODE (operands[3]) to see which commutative operator was used.

The machine mode m of match_operator works like that of match_operand: it is passed as the second argument to the predicate function, and that function is solely responsible for deciding whether the expression to be matched "has" that mode.

When constructing an insn, argument 3 of the gen-function will specify the operation (i.e. the expression code) for the expression to be made. It should be an RTL expression, whose expression code is copied into a new expression whose operands are arguments 1 and 2 of the gen-function. The subexpressions of argument 3 are not used; only its expression code matters.

When match_operator is used in a pattern for matching an insn, it usually best if the operand number of the match_operator is higher than that of the actual operands of the insn. This improves register allocation because the register allocator often looks at operands 1 and 2 of insns to see if it can do register tying.

There is no way to specify constraints in match_operator. The operand of the insn which corresponds to the match_operator never has any constraints because it is never reloaded as a whole. However, if parts of its operands are matched by match_operand patterns, those parts may have constraints of their own.

```
(match_op_dup:m n [operands...])
```

Like match_dup, except that it applies to operators instead of operands. When constructing an insn, operand number n will be substituted at this point. But in matching, match_op_dup behaves differently. It assumes that operand number n has already been determined by a match_operator appearing earlier in the recognition template, and it matches only an identical-looking expression.

(match_parallel n predicate [subpat...])

This pattern is a placeholder for an insn that consists of a parallel expression with a variable number of elements. This expression should only appear at the top level of an insn pattern.

When constructing an insn, operand number n will be substituted at this point. When matching an insn, it matches if the body of the insn is a parallel expression with at least as many elements as the vector of subpat expressions in the match_parallel, if each subpat matches the corresponding element of the parallel, and the function predicate returns nonzero on the parallel that is the body of the insn. It is the responsibility of the predicate to validate elements of the parallel beyond those listed in the match_parallel.

A typical use of match_parallel is to match load and store multiple expressions, which can contain a variable number of elements in a parallel. For example,

This example comes from 'a29k.md'. The function load_multiple_operation is defined in 'a29k.c' and checks that subsequent elements in the parallel are the same as the set in the pattern, except that they are referencing subsequent registers and memory locations.

An insn that matches this pattern might look like:

```
(match_par_dup n [subpat...])
```

Like match_op_dup, but for match_parallel instead of match_operator.

12.5 Output Templates and Operand Substitution

The *output template* is a string which specifies how to output the assembler code for an instruction pattern. Most of the template is a fixed string which is output literally. The character '%' is used to specify where to substitute an operand; it can also be used to identify places where different variants of the assembler require different syntax.

In the simplest case, a "%" followed by a digit n says to output operand n at that point in the string.

"%" followed by a letter and a digit says to output an operand in an alternate fashion. Four letters have standard, built-in meanings described below. The machine description macro PRINT_OPERAND can define additional letters with nonstandard meanings.

"%cdigit' can be used to substitute an operand that is a constant value without the syntax that normally indicates an immediate operand.

'%ndigit' is like '%cdigit' except that the value of the constant is negated before printing.

"%adigit' can be used to substitute an operand as if it were a memory reference, with the actual operand treated as the address. This may be useful when outputting a "load address" instruction, because often the assembler syntax for such an instruction requires you to write the operand as if it were a memory reference.

'%ldigit' is used to substitute a label_ref into a jump instruction.

"%=" outputs a number which is unique to each instruction in the entire compilation. This is useful for making local labels to be referred to more than once in a single template that generates multiple assembler instructions.

'%' followed by a punctuation character specifies a substitution that does not use an operand. Only one case is standard: '%' outputs a '%' into the assembler code. Other nonstandard cases can be defined in the PRINT_OPERAND macro. You must also define which punctuation characters are valid with the PRINT_OPERAND_PUNCT_VALID_P macro.

The template may generate multiple assembler instructions. Write the text for the instructions, with '\;' between them.

When the RTL contains two operands which are required by constraint to match each other, the output template must refer only to the lower-numbered operand. Matching operands are not always identical, and the rest of the compiler arranges to put the proper RTL expression for printing into the lower-numbered operand.

One use of nonstandard letters or punctuation following '%' is to distinguish between different assembler languages for the same machine; for example, Motorola syntax versus MIT syntax for the 68000. Motorola syntax requires periods in most opcode names, while MIT syntax does not. For example, the opcode 'movel' in MIT syntax is 'move.1' in Motorola syntax. The same file of patterns is used for both kinds of output syntax, but the character sequence '%.' is used in each place where Motorola syntax wants a period. The PRINT_OPERAND macro for Motorola syntax defines the sequence to output a period; the macro for MIT syntax defines it to do nothing.

As a special case, a template consisting of the single character # instructs the compiler to first split the insn, and then output the resulting instructions separately. This helps eliminate redundancy in the output templates. If you have a define_insn that needs to emit multiple assembler instructions, and there is an matching define_split already

defined, then you can simply use # as the output template instead of writing an output template that emits the multiple assembler instructions.

If the macro ASSEMBLER_DIALECT is defined, you can use construct of the form '{option0|option1|option2}' in the templates. These describe multiple variants of assembler language syntax. See Section 13.20.7 [Instruction Output], page 351.

12.6 C Statements for Assembler Output

Often a single fixed template string cannot produce correct and efficient assembler code for all the cases that are recognized by a single instruction pattern. For example, the opcodes may depend on the kinds of operands; or some unfortunate combinations of operands may require extra machine instructions.

If the output control string starts with a '@', then it is actually a series of templates, each on a separate line. (Blank lines and leading spaces and tabs are ignored.) The templates correspond to the pattern's constraint alternatives (see Section 12.8.2 [Multi-Alternative], page 181). For example, if a target machine has a two-address add instruction 'addr' to add into a register and another 'addm' to add a register to memory, you might write this pattern:

If the output control string starts with a '*', then it is not an output template but rather a piece of C program that should compute a template. It should execute a **return** statement to return the template-string you want. Most such templates use C string literals, which require doublequote characters to delimit them. To include these doublequote characters in the string, prefix each one with '\'.

If the output control string is written as a brace block instead of a double-quoted string, it is automatically assumed to be C code. In that case, it is not necessary to put in a leading asterisk, or to escape the doublequotes surrounding C string literals.

The operands may be found in the array operands, whose C data type is rtx [].

It is very common to select different ways of generating assembler code based on whether an immediate operand is within a certain range. Be careful when doing this, because the result of INTVAL is an integer on the host machine. If the host machine has more bits in an int than the target machine has in the mode in which the constant will be used, then some of the bits you get from INTVAL will be superfluous. For proper results, you must carefully disregard the values of those bits.

It is possible to output an assembler instruction and then go on to output or compute more of them, using the subroutine output_asm_insn. This receives two arguments: a template-string and a vector of operands. The vector may be operands, or it may be another array of rtx that you declare locally and initialize yourself.

When an insn pattern has multiple alternatives in its constraints, often the appearance of the assembler code is determined mostly by which alternative was matched. When this

is so, the C code can test the variable which_alternative, which is the ordinal number of the alternative that was actually satisfied (0 for the first, 1 for the second alternative, etc.).

For example, suppose there are two opcodes for storing zero, 'clrreg' for registers and 'clrmem' for memory locations. Here is how a pattern could use which_alternative to choose between them:

The example above, where the assembler code to generate was *solely* determined by the alternative, could also have been specified as follows, having the output control string start with a '@':

12.7 Predicates

A predicate determines whether a match_operand or match_operator expression matches, and therefore whether the surrounding instruction pattern will be used for that combination of operands. GCC has a number of machine-independent predicates, and you can define machine-specific predicates as needed. By convention, predicates used with match_operand have names that end in '_operand', and those used with match_operator have names that end in '_operator'.

All predicates are Boolean functions (in the mathematical sense) of two arguments: the RTL expression that is being considered at that position in the instruction pattern, and the machine mode that the match_operand or match_operator specifies. In this section, the first argument is called op and the second argument mode. Predicates can be called from C as ordinary two-argument functions; this can be useful in output templates or other machine-specific code.

Operand predicates can allow operands that are not actually acceptable to the hard-ware, as long as the constraints give reload the ability to fix them up (see Section 12.8 [Constraints], page 177). However, GCC will usually generate better code if the predicates specify the requirements of the machine instructions as closely as possible. Reload cannot fix up operands that must be constants ("immediate operands"); you must use a predicate that allows only constants, or else enforce the requirement in the extra condition.

Most predicates handle their mode argument in a uniform manner. If mode is VOIDmode (unspecified), then op can have any mode. If mode is anything else, then op must have the same mode, unless op is a CONST_INT or integer CONST_DOUBLE. These RTL expressions always have VOIDmode, so it would be counterproductive to check that their mode matches.

Instead, predicates that accept CONST_INT and/or integer CONST_DOUBLE check that the value stored in the constant will fit in the requested mode.

Predicates with this behavior are called *normal*. **genrecog** can optimize the instruction recognizer based on knowledge of how normal predicates treat modes. It can also diagnose certain kinds of common errors in the use of normal predicates; for instance, it is almost always an error to use a normal predicate without specifying a mode.

Predicates that do something different with their mode argument are called special. The generic predicates address_operand and pmode_register_operand are special predicates. genrecog does not do any optimizations or diagnosis when special predicates are used.

12.7.1 Machine-Independent Predicates

These are the generic predicates available to all back ends. They are defined in 'recog.c'. The first category of predicates allow only constant, or *immediate*, operands.

immediate_operand

[Function]

This predicate allows any sort of constant that fits in *mode*. It is an appropriate choice for instructions that take operands that must be constant.

const_int_operand

[Function]

This predicate allows any CONST_INT expression that fits in *mode*. It is an appropriate choice for an immediate operand that does not allow a symbol or label.

const_double_operand

[Function]

This predicate accepts any CONST_DOUBLE expression that has exactly mode. If mode is VOIDmode, it will also accept CONST_INT. It is intended for immediate floating point constants.

The second category of predicates allow only some kind of machine register.

register_operand

[Function]

This predicate allows any REG or SUBREG expression that is valid for *mode*. It is often suitable for arithmetic instruction operands on a RISC machine.

pmode_register_operand

[Function]

This is a slight variant on register_operand which works around a limitation in the machine-description reader.

(match_operand n "pmode_register_operand" constraint)

means exactly what

```
(match_operand:P n "register_operand" constraint)
```

would mean, if the machine-description reader accepted ':P' mode suffixes. Unfortunately, it cannot, because Pmode is an alias for some other mode, and might vary with machine-specific options. See Section 13.28 [Misc], page 371.

scratch_operand

[Function]

This predicate allows hard registers and SCRATCH expressions, but not pseudo-registers. It is used internally by match_scratch; it should not be used directly.

The third category of predicates allow only some kind of memory reference.

memory_operand

[Function]

This predicate allows any valid reference to a quantity of mode *mode* in memory, as determined by the weak form of GO_IF_LEGITIMATE_ADDRESS (see Section 13.14 [Addressing Modes], page 315).

address_operand

[Function]

This predicate is a little unusual; it allows any operand that is a valid expression for the *address* of a quantity of mode *mode*, again determined by the weak form of GO_IF_LEGITIMATE_ADDRESS. To first order, if '(mem: mode (exp))' is acceptable to memory_operand, then exp is acceptable to address_operand. Note that exp does not necessarily have the mode *mode*.

indirect_operand

[Function]

This is a stricter form of memory_operand which allows only memory references with a general_operand as the address expression. New uses of this predicate are discouraged, because general_operand is very permissive, so it's hard to tell what an indirect_operand does or does not allow. If a target has different requirements for memory operands for different instructions, it is better to define target-specific predicates which enforce the hardware's requirements explicitly.

push_operand

[Function]

This predicate allows a memory reference suitable for pushing a value onto the stack. This will be a MEM which refers to stack_pointer_rtx, with a side-effect in its address expression (see Section 10.16 [Incdec], page 140); which one is determined by the STACK_PUSH_CODE macro (see Section 13.10.1 [Frame Layout], page 285).

pop_operand

[Function]

This predicate allows a memory reference suitable for popping a value off the stack. Again, this will be a MEM referring to stack_pointer_rtx, with a side-effect in its address expression. However, this time STACK_POP_CODE is expected.

The fourth category of predicates allow some combination of the above operands.

nonmemory_operand

[Function]

This predicate allows any immediate or register operand valid for mode.

nonimmediate_operand

[Function]

This predicate allows any register or memory operand valid for mode.

general_operand

[Function]

This predicate allows any immediate, register, or memory operand valid for mode.

Finally, there is one generic operator predicate.

comparison_operator

[Function]

This predicate matches any expression which performs an arithmetic comparison in *mode*; that is, COMPARISON_P is true for the expression code.

12.7.2 Defining Machine-Specific Predicates

Many machines have requirements for their operands that cannot be expressed precisely using the generic predicates. You can define additional predicates using define_predicate and define_special_predicate expressions. These expressions have three operands:

- The name of the predicate, as it will be referred to in match_operand or match_operator expressions.
- An RTL expression which evaluates to true if the predicate allows the operand op, false if it does not. This expression can only use the following RTL codes:

MATCH_OPERAND

When written inside a predicate expression, a MATCH_OPERAND expression evaluates to true if the predicate it names would allow op. The operand number and constraint are ignored. Due to limitations in genrecog, you can only refer to generic predicates and predicates that have already been defined.

MATCH_CODE

This expression has one operand, a string constant containing a commaseparated list of RTX code names (in lower case). It evaluates to true if op has any of the listed codes.

MATCH_TEST

This expression has one operand, a string constant containing a C expression. The predicate's arguments, op and mode, are available with those names in the C expression. The MATCH_TEST evaluates to true if the C expression evaluates to a nonzero value. MATCH_TEST expressions must not have side effects.

AND
IOR
NOT
IF_THEN_ELSE

The basic 'MATCH_' expressions can be combined using these logical operators, which have the semantics of the C operators '&&', '||', '!', and '?:' respectively.

• An optional block of C code, which should execute 'return true' if the predicate is found to match and 'return false' if it does not. It must not have any side effects. The predicate arguments, op and mode, are available with those names.

If a code block is present in a predicate definition, then the RTL expression must evaluate to true and the code block must execute 'return true' for the predicate to allow the operand. The RTL expression is evaluated first; do not re-check anything in the code block that was checked in the RTL expression.

The program genrecog scans define_predicate and define_special_predicate expressions to determine which RTX codes are possibly allowed. You should always make this explicit in the RTL predicate expression, using MATCH_OPERAND and MATCH_CODE.

Here is an example of a simple predicate definition, from the IA64 machine description:

Predicates written with define_predicate automatically include a test that *mode* is VOIDmode, or *op* has the same mode as *mode*, or *op* is a CONST_INT or CONST_DOUBLE. They do *not* check specifically for integer CONST_DOUBLE, nor do they test that the value of either kind of constant fits in the requested mode. This is because target-specific predicates that take constants usually have to do more stringent value checks anyway. If you need the exact same treatment of CONST_INT or CONST_DOUBLE that the generic predicates provide, use a MATCH_OPERAND subexpression to call const_int_operand, const_double_operand, or immediate_operand.

Predicates written with define_special_predicate do not get any automatic mode checks, and are treated as having special mode handling by genrecog.

The program genpreds is responsible for generating code to test predicates. It also writes a header file containing function declarations for all machine-specific predicates. It is not necessary to declare these predicates in 'cpu-protos.h'.

12.8 Operand Constraints

Each match_operand in an instruction pattern can specify constraints for the operands allowed. The constraints allow you to fine-tune matching within the set of operands allowed by the predicate.

Constraints can say whether an operand may be in a register, and which kinds of register; whether the operand can be a memory reference, and which kinds of address; whether the operand may be an immediate constant, and which possible values it may have. Constraints can also require two operands to match.

12.8.1 Simple Constraints

The simplest kind of constraint is a string full of letters, each of which describes one kind of operand that is permitted. Here are the letters that are allowed:

whitespace

Whitespace characters are ignored and can be inserted at any position except the first. This enables each alternative for different operands to be visually aligned in the machine description even if they have different number of constraints and modifiers.

- 'm' A memory operand is allowed, with any kind of address that the machine supports in general.
- 'o' A memory operand is allowed, but only if the address is offsettable. This means that adding a small integer (actually, the width in bytes of the operand, as determined by its machine mode) may be added to the address and the result is also a valid memory address.

For example, an address which is constant is offsettable; so is an address that is the sum of a register and a constant (as long as a slightly larger constant is also within the range of address-offsets supported by the machine); but an autoincrement or autodecrement address is not offsettable. More complicated indirect/indexed addresses may or may not be offsettable depending on the other addressing modes that the machine supports.

Note that in an output operand which can be matched by another operand, the constraint letter 'o' is valid only when accompanied by both '<' (if the target machine has predecrement addressing) and '>' (if the target machine has preincrement addressing).

- 'V' A memory operand that is not offsettable. In other words, anything that would fit the 'm' constraint but not the 'o' constraint.
- '<' A memory operand with autodecrement addressing (either predecrement or postdecrement) is allowed.
- '>' A memory operand with autoincrement addressing (either preincrement or postincrement) is allowed.
- 'r' A register operand is allowed provided that it is in a general register.
- 'i' An immediate integer operand (one with constant value) is allowed. This includes symbolic constants whose values will be known only at assembly time or later.
- 'n' An immediate integer operand with a known numeric value is allowed. Many systems cannot support assembly-time constants for operands less than a word wide. Constraints for these operands should use 'n' rather than 'i'.
- 'I', 'J', 'K', ... 'P'

Other letters in the range 'I' through 'P' may be defined in a machine-dependent fashion to permit immediate integer operands with explicit integer values in specified ranges. For example, on the 68000, 'I' is defined to stand for the range of values 1 to 8. This is the range permitted as a shift count in the shift instructions.

- 'E' An immediate floating operand (expression code const_double) is allowed, but only if the target floating point format is the same as that of the host machine (on which the compiler is running).
- 'F' An immediate floating operand (expression code const_double or const_vector) is allowed.
- 'G', 'H' 'G' and 'H' may be defined in a machine-dependent fashion to permit immediate floating operands in particular ranges of values.

's' An immediate integer operand whose value is not an explicit integer is allowed.

This might appear strange; if an insn allows a constant operand with a value

This might appear strange; if an insh allows a constant operand with a value not known at compile time, it certainly must allow any known value. So why use 's' instead of 'i'? Sometimes it allows better code to be generated.

For example, on the 68000 in a fullword instruction it is possible to use an immediate operand; but if the immediate value is between -128 and 127, better code results from loading the value into a register and using the register. This is because the load into the register can be done with a 'moveq' instruction. We arrange for this to happen by defining the letter 'K' to mean "any integer outside the range -128 to 127", and then specifying 'Ks' in the operand constraints.

- 'g' Any register, memory or immediate integer operand is allowed, except for registers that are not general registers.
- 'X' Any operand whatsoever is allowed, even if it does not satisfy general_operand. This is normally used in the constraint of a match_scratch when certain alternatives will not actually require a scratch register.
- '0', '1', '2', ... '9'

An operand that matches the specified operand number is allowed. If a digit is used together with letters within the same alternative, the digit should come last.

This number is allowed to be more than a single digit. If multiple digits are encountered consecutively, they are interpreted as a single decimal integer. There is scant chance for ambiguity, since to-date it has never been desirable that '10' be interpreted as matching either operand 1 or operand 0. Should this be desired, one can use multiple alternatives instead.

This is called a *matching constraint* and what it really means is that the assembler has only a single operand that fills two roles considered separate in the RTL insn. For example, an add insn has two input operands and one output operand in the RTL, but on most CISC machines an add instruction really has only two operands, one of them an input-output operand:

addl #35,r12

Matching constraints are used in these circumstances. More precisely, the two operands that match must include one input-only operand and one output-only operand. Moreover, the digit must be a smaller number than the number of the operand that uses it in the constraint.

For operands to match in a particular case usually means that they are identical-looking RTL expressions. But in a few special cases specific kinds of dissimilarity are allowed. For example, *x as an input operand will match *x++ as an output operand. For proper results in such cases, the output template should always use the output-operand's number when printing the operand.

'p' An operand that is a valid memory address is allowed. This is for "load address" and "push address" instructions.

'p' in the constraint must be accompanied by address_operand as the predicate in the match_operand. This predicate interprets the mode specified in the

match_operand as the mode of the memory reference for which the address would be valid.

other-letters

Other letters can be defined in machine-dependent fashion to stand for particular classes of registers or other arbitrary operand types. 'd', 'a' and 'f' are defined on the 68000/68020 to stand for data, address and floating point registers.

The machine description macro REG_CLASS_FROM_LETTER has first cut at the otherwise unused letters. If it evaluates to NO_REGS, then EXTRA_CONSTRAINT is evaluated.

A typical use for EXTRA_CONSTRAINT would be to distinguish certain types of memory references that affect other inso operands.

In order to have valid assembler code, each operand must satisfy its constraint. But a failure to do so does not prevent the pattern from applying to an insn. Instead, it directs the compiler to modify the code so that the constraint will be satisfied. Usually this is done by copying an operand into a register.

Contrast, therefore, the two instruction patterns that follow:

which has two operands, one of which must appear in two places, and

which has three operands, two of which are required by a constraint to be identical. If we are considering an insn of the form

the first pattern would not apply at all, because this inso does not contain two identical subexpressions in the right place. The pattern would say, "That does not look like an add instruction; try other patterns". The second pattern would say, "Yes, that's an add instruction, but there is something wrong with it". It would direct the reload pass of the compiler to generate additional insort to make the constraint true. The results might look like this:

```
(insn n2 prev n
  (set (reg:SI 3) (reg:SI 6))
   ...)
(insn n n2 next
  (set (reg:SI 3)
```

```
(plus:SI (reg:SI 3) (reg:SI 109)))
...)
```

It is up to you to make sure that each operand, in each pattern, has constraints that can handle any RTL expression that could be present for that operand. (When multiple alternatives are in use, each pattern must, for each possible combination of operand expressions, have at least one alternative which can handle that combination of operands.) The constraints don't need to allow any possible operand—when this is the case, they do not constrain—but they must at least point the way to reloading any possible operand so that it will fit.

• If the constraint accepts whatever operands the predicate permits, there is no problem: reloading is never necessary for this operand.

For example, an operand whose constraints permit everything except registers is safe provided its predicate rejects registers.

An operand whose predicate accepts only constant values is safe provided its constraints include the letter 'i'. If any possible constant value is accepted, then nothing less than 'i' will do; if the predicate is more selective, then the constraints may also be more selective.

- Any operand expression can be reloaded by copying it into a register. So if an operand's constraints allow some kind of register, it is certain to be safe. It need not permit all classes of registers; the compiler knows how to copy a register into another register of the proper class in order to make an instruction valid.
- A nonoffsettable memory reference can be reloaded by copying the address into a register. So if the constraint uses the letter 'o', all memory references are taken care of.
- A constant operand can be reloaded by allocating space in memory to hold it as preinitialized data. Then the memory reference can be used in place of the constant. So if the constraint uses the letters 'o' or 'm', constant operands are not a problem.
- If the constraint permits a constant and a pseudo register used in an insn was not allocated to a hard register and is equivalent to a constant, the register will be replaced with the constant. If the predicate does not permit a constant and the insn is rerecognized for some reason, the compiler will crash. Thus the predicate must always recognize any objects allowed by the constraint.

If the operand's predicate can recognize registers, but the constraint does not permit them, it can make the compiler crash. When this operand happens to be a register, the reload pass will be stymied, because it does not know how to copy a register temporarily into memory.

If the predicate accepts a unary operator, the constraint applies to the operand. For example, the MIPS processor at ISA level 3 supports an instruction which adds two registers in SImode to produce a DImode result, but only if the registers are correctly sign extended. This predicate for the input operands accepts a sign_extend of an SImode register. Write the constraint to indicate the type of register that is required for the operand of the sign_extend.

ļ

12.8.2 Multiple Alternative Constraints

Sometimes a single instruction has multiple alternative sets of possible operands. For example, on the 68000, a logical-or instruction can combine register or an immediate value into memory, or it can combine any kind of operand into a register; but it cannot combine one memory location into another.

These constraints are represented as multiple alternatives. An alternative can be described by a series of letters for each operand. The overall constraint for an operand is made from the letters for this operand from the first alternative, a comma, the letters for this operand from the second alternative, a comma, and so on until the last alternative. Here is how it is done for fullword logical-or on the 68000:

The first alternative has 'm' (memory) for operand 0, '0' for operand 1 (meaning it must match operand 0), and 'dKs' for operand 2. The second alternative has 'd' (data register) for operand 0, '0' for operand 1, and 'dmKs' for operand 2. The '=' and '%' in the constraints apply to all the alternatives; their meaning is explained in the next section (see Section 12.8.3 [Class Preferences], page 182).

If all the operands fit any one alternative, the instruction is valid. Otherwise, for each alternative, the compiler counts how many instructions must be added to copy the operands so that that alternative applies. The alternative requiring the least copying is chosen. If two alternatives need the same amount of copying, the one that comes first is chosen. These choices can be altered with the '?' and '!' characters:

- ? Disparage slightly the alternative that the '?' appears in, as a choice when no alternative applies exactly. The compiler regards this alternative as one unit more costly for each '?' that appears in it.
 - Disparage severely the alternative that the '!' appears in. This alternative can still be used if it fits without reloading, but if reloading is needed, some other alternative will be used.

When an insn pattern has multiple alternatives in its constraints, often the appearance of the assembler code is determined mostly by which alternative was matched. When this is so, the C code for writing the assembler code can use the variable which_alternative, which is the ordinal number of the alternative that was actually satisfied (0 for the first, 1 for the second alternative, etc.). See Section 12.6 [Output Statement], page 172.

12.8.3 Register Class Preferences

The operand constraints have another function: they enable the compiler to decide which kind of hardware register a pseudo register is best allocated to. The compiler examines the constraints that apply to the insns that use the pseudo register, looking for the machine-dependent letters such as 'd' and 'a' that specify classes of registers. The pseudo register is put in whichever class gets the most "votes". The constraint letters 'g' and 'r' also vote: they vote in favor of a general register. The machine description says which registers are considered general.

Of course, on some machines all registers are equivalent, and no register classes are defined. Then none of this complexity is relevant.

12.8.4 Constraint Modifier Characters

Here are constraint modifier characters.

- '=' Means that this operand is write-only for this instruction: the previous value is discarded and replaced by output data.
- '+' Means that this operand is both read and written by the instruction.

When the compiler fixes up the operands to satisfy the constraints, it needs to know which operands are inputs to the instruction and which are outputs from it. '=' identifies an output; '+' identifies an operand that is both input and output; all other operands are assumed to be input only.

If you specify '=' or '+' in a constraint, you put it in the first character of the constraint string.

'&' Means (in a particular alternative) that this operand is an earlyclobber operand, which is modified before the instruction is finished using the input operands. Therefore, this operand may not lie in a register that is used as an input operand or as part of any memory address.

'&' applies only to the alternative in which it is written. In constraints with multiple alternatives, sometimes one alternative requires '&' while others do not. See, for example, the 'movdf' insn of the 68000.

An input operand can be tied to an earlyclobber operand if its only use as an input occurs before the early result is written. Adding alternatives of this form often allows GCC to produce better code when only some of the inputs can be affected by the earlyclobber. See, for example, the 'mulsi3' insn of the ARM.

'&' does not obviate the need to write '='.

Declares the instruction to be commutative for this operand and the following operand. This means that the compiler may interchange the two operands if that is the cheapest way to make all operands fit the constraints. This is often used in patterns for addition instructions that really have only two operands: the result must go in one of the arguments. Here for example, is how the 68000 halfword-add instruction is defined:

GCC can only handle one commutative pair in an asm; if you use more, the compiler may fail. Note that you need not use the modifier if the two alternatives are strictly identical; this would only waste time in the reload pass.

- '#' Says that all following characters, up to the next comma, are to be ignored as a constraint. They are significant only for choosing register preferences.
- '*' Says that the following character should be ignored when choosing register preferences. '*' has no effect on the meaning of the constraint as a constraint, and no effect on reloading.

Here is an example: the 68000 has an instruction to sign-extend a halfword in a data register, and can also sign-extend a value by copying it into an address register. While either kind of register is acceptable, the constraints on an address-register destination are less strict, so it is best if register allocation makes an address register its goal. Therefore, '*' is used so that the 'd' constraint letter (for data register) is ignored when computing register preferences.

12.8.5 Constraints for Particular Machines

Whenever possible, you should use the general-purpose constraint letters in asm arguments, since they will convey meaning more readily to people reading your code. Failing that, use the constraint letters that usually have very similar meanings across architectures. The most commonly used constraints are 'm' and 'r' (for memory and general-purpose registers respectively; see Section 12.8.1 [Simple Constraints], page 177), and 'I', usually the letter indicating the most common immediate-constant format.

For each machine architecture, the 'config/machine/machine.h' file defines additional constraints. These constraints are used by the compiler itself for instruction generation, as well as for asm statements; therefore, some of the constraints are not particularly interesting for asm. The constraints are defined through these macros:

REG_CLASS_FROM_LETTER

Register class constraints (usually lowercase).

CONST_OK_FOR_LETTER_P

Immediate constant constraints, for non-floating point constants of word size or smaller precision (usually uppercase).

CONST_DOUBLE_OK_FOR_LETTER_P

Immediate constant constraints, for all floating point constants and for constants of greater than word size precision (usually uppercase).

EXTRA CONSTRAINT

Special cases of registers or memory. This macro is not required, and is only defined for some machines.

Inspecting these macro definitions in the compiler source for your machine is the best way to be certain you have the right constraints. However, here is a summary of the machine-dependent constraints available on some particular machines.

ARM family—'arm.h'

f	Floating-point register
W	VFP floating-point register
F	One of the floating-point constants 0.0, 0.5, 1.0, 2.0, 3.0, 4.0, 5.0 or 10.0
G	Floating-point constant that would satisfy the constraint 'F' if it were negated

	I	Integer that is valid as an immediate operand in a data processing instruction. That is, an integer in the range 0 to 255 rotated by a multiple of 2
	J	Integer in the range -4095 to 4095
	K	Integer that satisfies constraint 'I' when inverted (ones complement)
	L	Integer that satisfies constraint 'I' when negated (twos complement)
	M	Integer in the range 0 to 32
	Q	A memory reference where the exact address is in a single register ("m" is preferable for asm statements)
	R	An item in the constant pool
	S	A symbol in the text segment of the current file
Uv	A memory	reference suitable for VFP load/store insns (reg+constant offset)
Uy	A memory	reference suitable for iWMMXt load/store instructions.
Uq	A memory	reference suitable for for the ARMv4 ldrsb instruction.
$AVR\ famil$	y—'avr.h'	
	1	Registers from r0 to r15
	a	Registers from r16 to r23
	d	Registers from r16 to r31
	W	Registers from r24 to r31. These registers can be used in 'adiw' command
	е	Pointer register (r26-r31)
	b	Base pointer register (r28–r31)
	q	Stack pointer register (SPH:SPL)
	t	Temporary register r0
	x	Register pair X (r27:r26)
	у	Register pair Y (r29:r28)
	Z	Register pair Z (r31:r30)
	I	Constant greater than -1 , less than 64
	J	Constant greater than -64 , less than 1
	K	Constant integer 2
	L	Constant integer 0
	M	Constant that fits in 8 bits
	N	Constant integer -1

0	Constant integer 8, 16, or 24		
Р	Constant integer 1		
G	A floating point constant 0.0		
PowerPC and IBM RS	16000—'rs6000.h'		
b	Address base register		
f	Floating point register		
v	Vector register		
h	'MQ', 'CTR', or 'LINK' register		
q	'MQ' register		
С	'CTR' register		
1	'LINK' register		
x	'CR' register (condition register) number 0		
У	'CR' register (condition register)		
z	'FPMEM' stack memory for FPR-GPR transfers		
I	Signed 16-bit constant		
J	Unsigned 16-bit constant shifted left 16 bits (use 'L' instead for SImode constants)		
K	Unsigned 16-bit constant		
L	Signed 16-bit constant shifted left 16 bits		
M	Constant larger than 31		
N	Exact power of 2		
0	Zero		
P	Constant whose negation is a signed 16-bit constant		
G	Floating point constant that can be loaded into a register with one instruction per word		
Q	Memory operand that is an offset from a register ('m' is preferable for \mathtt{asm} statements)		
R	AIX TOC entry		
S	Constant suitable as a 64-bit mask operand		
T	Constant suitable as a 32-bit mask operand		
U	System V Release 4 small data area reference		
Intel 386—'i386.h'			
q	'a', b, c, or d register for the i386. For x86-64 it is equivalent to 'r' class (for 8-bit instructions that do not use upper halves).		

```
Q
                        'a', b, c, or d register (for 8-bit instructions, that do use upper
                        halves).
            R
                        Legacy register—equivalent to r class in i386 mode. (for non-8-bit
                        registers used together with 8-bit upper halves in a single instruc-
                        tion)
            Α
                        Specifies the 'a' or 'd' registers. This is primarily useful for 64-bit
                        integer values (when in 32-bit mode) intended to be returned with
                        the 'd' register holding the most significant bits and the 'a' register
                        holding the least significant bits.
                        Floating point register
            f
                        First (top of stack) floating point register
            t
                        Second floating point register
            u
                        'a' register
            а
                        'b' register
            b
                        'c' register
            С
            С
                        Specifies constant that can be easily constructed in SSE register
                        without loading it from memory.
                        'd' register
            d
            D
                        'di' register
            S
                        'si' register
                        'xmm' SSE register
            х
                        MMX register
            У
            Ι
                        Constant in range 0 to 31 (for 32-bit shifts)
            J
                        Constant in range 0 to 63 (for 64-bit shifts)
                        '0xff'
            K
            L
                        'Oxffff'
                        0, 1, 2, or 3 (shifts for lea instruction)
            М
            N
                        Constant in range 0 to 255 (for out instruction)
            Ζ
                        Constant in range 0 to Oxffffffff or symbolic reference known to
                        fit specified range. (for using immediates in zero extending 32-bit
                        to 64-bit x86-64 instructions)
                        Constant in range -2147483648 to 2147483647 or symbolic refer-
            е
                        ence known to fit specified range. (for using immediates in 64-bit
                        x86-64 instructions)
                        Standard 80387 floating point constant
            G
Intel\ IA-64—'ia64.h'
            a
                        General register r0 to r3 for addl instruction
```

	b	Branch register
	С	Predicate register ('c' as in "conditional")
	d	Application register residing in M-unit
	е	Application register residing in I-unit
	f	Floating-point register
	m	Memory operand. Remember that 'm' allows postincrement and postdecrement which require printing with '%Pn' on IA-64. Use 'S' to disallow postincrement and postdecrement.
	G	Floating-point constant 0.0 or 1.0
	I	14-bit signed integer constant
	J	22-bit signed integer constant
	K	8-bit signed integer constant for logical instructions
	L	8-bit adjusted signed integer constant for compare pseudo-ops
	M	6-bit unsigned integer constant for shift counts
	N	9-bit signed integer constant for load and store postincrements
	0	The constant zero
	P	0 or -1 for dep instruction
	Q	Non-volatile memory for floating-point loads and stores
	R	Integer constant in the range 1 to 4 for shladd instruction
	S	Memory operand except postincrement and postdecrement
FRV—'frv	.h'	
	a	Register in the class ACC_REGS (acc0 to acc7).
	b	Register in the class EVEN_ACC_REGS (acc0 to acc7).
	С	Register in the class CC_REGS (fcc0 to fcc3 and icc0 to icc3).
	d	Register in the class GPR_REGS (gr0 to gr63).
	е	Register in the class EVEN_REGS (gr0 to gr63). Odd registers are excluded not in the class but through the use of a machine mode larger than 4 bytes.
	f	Register in the class FPR_REGS (fr0 to fr63).
	h	Register in the class FEVEN_REGS (fr0 to fr63). Odd registers are excluded not in the class but through the use of a machine mode larger than 4 bytes.
	1	Register in the class LR_REG (the 1r register).
	q	Register in the class QUAD_REGS (gr2 to gr63). Register numbers not divisible by 4 are excluded not in the class but through the use of a machine mode larger than 8 bytes.

t

```
Register in the class FCC_REGS (fcc0 to fcc3).
            u
                        Register in the class ICR_REGS (cc4 to cc7).
            ٧
                        Register in the class FCR_REGS (cc0 to cc3).
            W
                        Register in the class QUAD_FPR_REGS (fro to fr63). Register num-
            x
                        bers not divisible by 4 are excluded not in the class but through
                        the use of a machine mode larger than 8 bytes.
                        Register in the class SPR_REGS (lcr and lr).
            z
            Α
                        Register in the class QUAD_ACC_REGS (acc0 to acc7).
                        Register in the class ACCG_REGS (accg0 to accg7).
            В
            С
                        Register in the class CR_REGS (cc0 to cc7).
                        Floating point constant zero
            G
            Ι
                        6-bit signed integer constant
            J
                        10-bit signed integer constant
            L
                        16-bit signed integer constant
            М
                        16-bit unsigned integer constant
            N
                        12-bit signed integer constant that is negative—i.e. in the range of
                         -2048 \text{ to } -1
            0
                        Constant zero
            Ρ
                        12-bit signed integer constant that is greater than zero—i.e. in the
                        range of 1 to 2047.
IP2K—'ip2k.h'
                        'DP' or 'IP' registers (general address)
            a
                        'IP' register
            f
                        'IPL' register
            j
                        'IPH' register
            k
                        'DP' register
            b
                        'DPH' register
            У
                        'DPL' register
            z
                        'SP' register
            q
                        'DP' or 'SP' registers (offsettable address)
            С
                        Non-pointer registers (not 'SP', 'DP', 'IP')
            d
                        Non-SP registers (everything except 'SP')
            u
                        Indirect through 'IP'—Avoid this except for QImode, since we can't
            R
                        access extra bytes
```

Register in the class ICC_REGS (icc0 to icc3).

S	Indirect through 'SP' or 'DP' with short displacement (0127)
T	Data-section immediate value
I	Integers from -255 to -1
J	Integers from 0 to 7—valid bit number in a register
K	Integers from 0 to 127—valid displacement for addressing mode
L	Integers from 1 to 127
М	Integer -1
N	Integer 1
0	Zero
P	Integers from 0 to 255
MIPS—'mips.h'	
d	General-purpose integer register
f	Floating-point register (if available)
h	'Hi' register
1	'Lo' register
x	'Hi' or 'Lo' register
у	General-purpose integer register
z	Floating-point status register
I	Signed 16-bit constant (for arithmetic instructions)
J	Zero
К	Zero-extended 16-bit constant (for logic instructions)
L	Constant with low 16 bits zero (can be loaded with lui)
М	32-bit constant which requires two instructions to load (a constant which is not 'I', 'K', or 'L')
N	Negative 16-bit constant
0	Exact power of two
P	Positive 16-bit constant
G	Floating point zero
Q	Memory reference that can be loaded with more than one instruction ('m' is preferable for asm statements)
R	Memory reference that can be loaded with one instruction ('m' is preferable for $asm\ statements$)
S	Memory reference in external OSF/rose PIC format ('m' is preferable for \mathtt{asm} statements)

Motorola 680x0—'m681	s.h ′
a	Address register
d	Data register
f	68881 floating-point register, if available
I	Integer in the range 1 to 8
J	16-bit signed number
K	Signed number whose magnitude is greater than 0x80
L	Integer in the range -8 to -1
М	Signed number whose magnitude is greater than 0x100
G	Floating point constant that is not a 68881 constant
Motorola 68HC11 & 6	8HC12 families—'m68hc11.h'
a	Register 'a'
b	Register 'b'
d	Register 'd'
q	An 8-bit register
t	Temporary soft registertmp
u	A soft registerd1 tod31
w	Stack pointer register
х	Register 'x'
У	Register 'y'
Z	Pseudo register 'z' (replaced by 'x' or 'y' at the end)
A	An address register: x, y or z
В	An address register: x or y
D	Register pair (x:d) to form a 32-bit value
L	Constants in the range -65536 to 65535
M	Constants whose 16-bit low part is zero
N	Constant integer 1 or -1
0	Constant integer 16
P	Constants in the range -8 to 2
SPARC—'sparc.h'	
f	Floating-point register on the SPARC-V8 architecture and lower floating-point register on the SPARC-V9 architecture.
е	Floating-point register. It is equivalent to 'f' on the SPARC-V8 architecture and contains both lower and upper floating-point registers on the SPARC-V9 architecture.

С

,	d	Lower floating-point register. It is only valid on the SPARC-V9 architecture when the Visual Instruction Set is available.
1	b	Floating-point register. It is only valid on the SPARC-V9 architecture when the Visual Instruction Set is available.
]	h	64-bit global or out register for the SPARC-V8+ architecture.
	I	Signed 13-bit constant
	J	Zero
1	K	32-bit constant with the low 12 bits clear (a constant that can be loaded with the sethi instruction)
:	L	A constant in the range supported by movcc instructions
1	M	A constant in the range supported by movrcc instructions
j	N	Same as 'K', except that it verifies that bits that are not in the lower 32-bit range are all zero. Must be used instead of 'K' for modes wider than SImode
l	0	The constant 4096
(G	Floating-point zero
]	Н	Signed 13-bit constant, sign-extended to 32 or 64 bits
I	Q	Floating-point constant whose integral representation can be moved into an integer register using a single sethi instruction
1	R	Floating-point constant whose integral representation can be moved into an integer register using a single mov instruction
:	S	Floating-point constant whose integral representation can be moved into an integer register using a high/lo_sum instruction sequence
	Т	Memory address aligned to an 8-byte boundary
1	U	Even register
1	W	Memory address for 'e' constraint registers
	Y	Vector zero
TMS320C3x	:/ <i>C4x</i> —'c4z	x.h'
;	a	Auxiliary (address) register (ar0-ar7)
1	b	Stack pointer register (sp)
	С	Standard (32-bit) precision integer register
:	f	Extended (40-bit) precision register (r0-r11)
]	k	Block count register (bk)
,	q	Extended (40-bit) precision low register (r0-r7)

Floating-point condition code register.

```
Extended (40-bit) precision register (r0-r1)
           t
                       Extended (40-bit) precision register (r2-r3)
           u
                       Repeat count register (rc)
           ٧
                       Index register (ir0-ir1)
           х
                       Status (condition code) register (st)
           у
                       Data page register (dp)
           z
           G
                       Floating-point zero
           Η
                       Immediate 16-bit floating-point constant
           Ι
                        Signed 16-bit constant
           J
                       Signed 8-bit constant
           K
                        Signed 5-bit constant
           L
                        Unsigned 16-bit constant
                        Unsigned 8-bit constant
           М
           N
                        Ones complement of unsigned 16-bit constant
                       High 16-bit constant (32-bit constant with 16 LSBs zero)
           0
                       Indirect memory reference with signed 8-bit or index register dis-
           Q
                       placement
           R
                       Indirect memory reference with unsigned 5-bit displacement
           S
                       Indirect memory reference with 1 bit or index register displacement
           Τ
                       Direct memory reference
           U
                        Symbolic address
S/390 and zSeries—'s390.h'
                        Address register (general purpose register except r0)
           a
                        Condition code register
           С
                       Data register (arbitrary general purpose register)
           d
           f
                       Floating-point register
           Ι
                        Unsigned 8-bit constant (0–255)
           J
                        Unsigned 12-bit constant (0-4095)
           K
                       Signed 16-bit constant (-32768-32767)
           L
                        Value appropriate as displacement.
                        (0..4095)
                                   for short displacement
                        (-524288..524287)
                                    for long displacement
```

M	Constant	integer	with a	value	of 0x7fffffff.	

N Multiple letter constraint followed by 4 parameter letters.

0..9: number of the part counting from most to least significant

H,Q: mode of the part

D,S,H: mode of the containing operand

O,F: value of the other parts (F—all bits set)

The constraint matches if the specified part of a constant has a value different from it's other parts.

Q Memory reference without index register and with short displacement.

R Memory reference with index register and short displacement.

Memory reference without index register but with long displacement.

T Memory reference with index register and long displacement.

U Pointer with short displacement.

W Pointer with long displacement.

Y Shift count operand.

Xstormy16—'stormy16.h'

a Register r0.

b Register r1.

c Register r2.

d Register r8.

e Registers r0 through r7.

t Registers r0 and r1.

y The carry register.

z Registers r8 and r9.

I A constant between 0 and 3 inclusive.

J A constant that has exactly one bit set.

K A constant that has exactly one bit clear.

L A constant between 0 and 255 inclusive.

M A constant between -255 and 0 inclusive.

N A constant between -3 and 0 inclusive.

O A constant between 1 and 4 inclusive.

P	A constant between -4 and -1 inclusive.		
Q	A memory reference that is a stack push.		
R	A memory reference that is a stack pop.		
S	A memory reference that refers to a constant address of known value.		
T	The register indicated by Rx (not implemented yet).		
U	A constant that is not between 2 and 15 inclusive.		
Z	The constant 0.		
Xtensa—'xtensa.h'			
a	General-purpose 32-bit register		
b	One-bit boolean register		
A	MAC16 40-bit accumulator register		
I	Signed 12-bit integer constant, for use in MOVI instructions		
J	Signed 8-bit integer constant, for use in ADDI instructions		
K	Integer constant valid for BccI instructions		
L	Unsigned constant valid for BccUI instructions		

12.9 Standard Pattern Names For Generation

Here is a table of the instruction names that are meaningful in the RTL generation pass of the compiler. Giving one of these names to an instruction pattern tells the RTL generation pass that it can use the pattern to accomplish a certain task.

'mo vm'

Here m stands for a two-letter machine mode name, in lowercase. This instruction pattern moves data with that machine mode from operand 1 to operand 0. For example, 'movsi' moves full-word data.

If operand 0 is a subreg with mode m of a register whose own mode is wider than m, the effect of this instruction is to store the specified value in the part of the register that corresponds to mode m. Bits outside of m, but which are within the same target word as the subreg are undefined. Bits which are outside the target word are left unchanged.

This class of patterns is special in several ways. First of all, each of these names up to and including full word size *must* be defined, because there is no other way to copy a datum from one place to another. If there are patterns accepting operands in larger modes, 'movm' must be defined for integer modes of those sizes.

Second, these patterns are not used solely in the RTL generation pass. Even the reload pass can generate move insns to copy values from stack slots into temporary registers. When it does so, one of the operands is a hard register and the other is an operand that can need to be reloaded into a register.

Therefore, when given such a pair of operands, the pattern must generate RTL which needs no reloading and needs no temporary registers—no registers other

than the operands. For example, if you support the pattern with a define_expand, then in such a case the define_expand mustn't call force_reg or any other such function which might generate new pseudo registers.

This requirement exists even for subword modes on a RISC machine where fetching those modes from memory normally requires several insns and some temporary registers.

During reload a memory reference with an invalid address may be passed as an operand. Such an address will be replaced with a valid address later in the reload pass. In this case, nothing may be done with the address except to use it as it stands. If it is copied, it will not be replaced with a valid address. No attempt should be made to make such an address into a valid address and no routine (such as change_address) that will do so may be called. Note that general_operand will fail when applied to such an address.

The global variable reload_in_progress (which must be explicitly declared if required) can be used to determine whether such special handling is required.

The variety of operands that have reloads depends on the rest of the machine description, but typically on a RISC machine these can only be pseudo registers that did not get hard registers, while on other machines explicit memory references will get optional reloads.

If a scratch register is required to move an object to or from memory, it can be allocated using gen_reg_rtx prior to life analysis.

If there are cases which need scratch registers during or after reload, you must define SECONDARY_INPUT_RELOAD_CLASS and/or SECONDARY_OUTPUT_RELOAD_CLASS to detect them, and provide patterns 'reload_inm' or 'reload_outm' to handle them. See Section 13.9 [Register Classes], page 277.

The global variable no_new_pseudos can be used to determine if it is unsafe to create new pseudo registers. If this variable is nonzero, then it is unsafe to call gen_reg_rtx to allocate a new pseudo.

The constraints on a 'movm' must permit moving any hard register to any other hard register provided that HARD_REGNO_MODE_OK permits mode m in both registers and REGISTER_MOVE_COST applied to their classes returns a value of 2.

It is obligatory to support floating point 'movm' instructions into and out of any registers that can hold fixed point values, because unions and structures (which have modes SImode or DImode) can be in those registers and they may have floating point members.

There may also be a need to support fixed point 'movm' instructions in and out of floating point registers. Unfortunately, I have forgotten why this was so, and I don't know whether it is still true. If HARD_REGNO_MODE_OK rejects fixed point values in floating point registers, then the constraints of the fixed point 'movm' instructions must be designed to avoid ever trying to reload into a floating point register.

'reload_inm'
'reload_outm'

Like 'movm', but used when a scratch register is required to move between operand 0 and operand 1. Operand 2 describes the scratch register. See the

discussion of the SECONDARY_RELOAD_CLASS macro in see Section 13.9 [Register Classes], page 277.

There are special restrictions on the form of the match_operands used in these patterns. First, only the predicate for the reload operand is examined, i.e., reload_in examines operand 1, but not the predicates for operand 0 or 2. Second, there may be only one alternative in the constraints. Third, only a single register class letter may be used for the constraint; subsequent constraint letters are ignored. As a special exception, an empty constraint string matches the ALL_REGS register class. This may relieve ports of the burden of defining an ALL_REGS constraint letter just for these patterns.

'movstrictm'

Like 'movm' except that if operand 0 is a subreg with mode m of a register whose natural mode is wider, the 'movstrictm' instruction is guaranteed not to alter any of the register except the part which belongs to mode m.

'movmisalignm'

This variant of a move pattern is designed to load or store a value from a memory address that is not naturally aligned for its mode. For a store, the memory will be in operand 0; for a load, the memory will be in operand 1. The other operand is guaranteed not to be a memory, so that it's easy to tell whether this is a load or store.

This pattern is used by the autovectorizer, and when expanding a MISALIGNED_INDIRECT_REF expression.

'load_multiple'

Load several consecutive memory locations into consecutive registers. Operand 0 is the first of the consecutive registers, operand 1 is the first memory location, and operand 2 is a constant: the number of consecutive registers.

Define this only if the target machine really has such an instruction; do not define this if the most efficient way of loading consecutive registers from memory is to do them one at a time.

On some machines, there are restrictions as to which consecutive registers can be stored into memory, such as particular starting or ending register numbers or only a range of valid counts. For those machines, use a define_expand (see Section 12.15 [Expander Definitions], page 217) and make the pattern fail if the restrictions are not met.

Write the generated insn as a parallel with elements being a set of one register from the appropriate memory location (you may also need use or clobber elements). Use a match_parallel (see Section 12.4 [RTL Template], page 167) to recognize the insn. See 'rs6000.md' for examples of the use of this insn pattern.

'store_multiple'

Similar to 'load_multiple', but store several consecutive registers into consecutive memory locations. Operand 0 is the first of the consecutive memory locations, operand 1 is the first register, and operand 2 is a constant: the number of consecutive registers.

'vec_setm'

Set given field in the vector value. Operand 0 is the vector to modify, operand 1 is new value of field and operand 2 specify the field index.

'vec_extractm'

Extract given field from the vector value. Operand 1 is the vector, operand 2 specify field index and operand 0 place to store value into.

'vec_initm'

Initialize the vector to given values. Operand 0 is the vector to initialize and operand 1 is parallel containing values for individual fields.

'pushm' Output a push instruction. Operand 0 is value to push. Used only when PUSH_ROUNDING is defined. For historical reason, this pattern may be missing and in such case an mov expander is used instead, with a MEM expression forming the push operation. The mov expander method is deprecated.

'addm3' Add operand 2 and operand 1, storing the result in operand 0. All operands must have mode m. This can be used even on two-address machines, by means of constraints requiring operands 1 and 0 to be the same location.

'subm3', 'mulm3'

'divm3', 'udivm3'

'modm3', 'umodm3'

'uminm3', 'umaxm3'

'andm3', 'iorm3', 'xorm3'

Similar, for other arithmetic operations.

'sminm3', 'smaxm3'

Signed minimum and maximum operations. When used with floating point, if both operands are zeros, or if either operand is NaN, then it is unspecified which of the two operands is returned as the result.

'mulhisi3'

Multiply operands 1 and 2, which have mode HImode, and store a SImode product in operand 0.

'mulqihi3', 'mulsidi3'

Similar widening-multiplication instructions of other widths.

'umulqihi3', 'umulhisi3', 'umulsidi3'

Similar widening-multiplication instructions that do unsigned multiplication.

'smulm3_highpart'

Perform a signed multiplication of operands 1 and 2, which have mode m, and store the most significant half of the product in operand 0. The least significant half of the product is discarded.

'umulm3_highpart'

Similar, but the multiplication is unsigned.

'divmodm4'

Signed division that produces both a quotient and a remainder. Operand 1 is divided by operand 2 to produce a quotient stored in operand 0 and a remainder stored in operand 3.

For machines with an instruction that produces both a quotient and a remainder, provide a pattern for 'divmodm4' but do not provide patterns for 'divm3' and 'modm3'. This allows optimization in the relatively common case when both the quotient and remainder are computed.

If an instruction that just produces a quotient or just a remainder exists and is more efficient than the instruction that produces both, write the output routine of 'divmodm4' to call find_reg_note and look for a REG_UNUSED note on the quotient or remainder and generate the appropriate instruction.

'udivmodm4'

Similar, but does unsigned division.

'ashlm3' Arithmetic-shift operand 1 left by a number of bits specified by operand 2, and store the result in operand 0. Here m is the mode of operand 0 and operand 1; operand 2's mode is specified by the instruction pattern, and the compiler will convert the operand to that mode before generating the instruction. The meaning of out-of-range shift counts can optionally be specified by TARGET_SHIFT_TRUNCATION_MASK, See [TARGET_SHIFT_TRUNCATION_MASK], page 374.

'ashrm3', 'lshrm3', 'rotlm3', 'rotrm3'

Other shift and rotate instructions, analogous to the ashlm3 instructions.

'negm2' Negate operand 1 and store the result in operand 0.

'absm2' Store the absolute value of operand 1 into operand 0.

'sqrtm2' Store the square root of operand 1 into operand 0.

The sqrt built-in function of C always uses the mode which corresponds to the C data type double and the sqrtf built-in function uses the mode which corresponds to the C data type float.

'cosm2' Store the cosine of operand 1 into operand 0.

The cos built-in function of C always uses the mode which corresponds to the C data type double and the cosf built-in function uses the mode which corresponds to the C data type float.

'sinm2' Store the sine of operand 1 into operand 0.

The sin built-in function of C always uses the mode which corresponds to the C data type double and the sinf built-in function uses the mode which corresponds to the C data type float.

'expm2' Store the exponential of operand 1 into operand 0.

The exp built-in function of C always uses the mode which corresponds to the C data type double and the expf built-in function uses the mode which corresponds to the C data type float.

'logm2' Store the natural logarithm of operand 1 into operand 0.

The log built-in function of C always uses the mode which corresponds to the C data type double and the logf built-in function uses the mode which corresponds to the C data type float.

'powm3' Store the value of operand 1 raised to the exponent operand 2 into operand 0.

The pow built-in function of C always uses the mode which corresponds to the C data type double and the powf built-in function uses the mode which corresponds to the C data type float.

'atan2m3' Store the arc tangent (inverse tangent) of operand 1 divided by operand 2 into operand 0, using the signs of both arguments to determine the quadrant of the result.

The atan2 built-in function of C always uses the mode which corresponds to the C data type double and the atan2f built-in function uses the mode which corresponds to the C data type float.

'floorm2' Store the largest integral value not greater than argument.

The floor built-in function of C always uses the mode which corresponds to the C data type double and the floorf built-in function uses the mode which corresponds to the C data type float.

'truncm2' Store the argument rounded to integer towards zero.

The trunc built-in function of C always uses the mode which corresponds to the C data type double and the truncf built-in function uses the mode which corresponds to the C data type float.

'roundm2' Store the argument rounded to integer away from zero.

The round built-in function of C always uses the mode which corresponds to the C data type double and the roundf built-in function uses the mode which corresponds to the C data type float.

'ceilm2' Store the argument rounded to integer away from zero.

The ceil built-in function of C always uses the mode which corresponds to the C data type double and the ceilf built-in function uses the mode which corresponds to the C data type float.

'nearbyintm2'

Store the argument rounded according to the default rounding mode

The nearbyint built-in function of C always uses the mode which corresponds to the C data type double and the nearbyintf built-in function uses the mode which corresponds to the C data type float.

'ffsm2' Store into operand 0 one plus the index of the least significant 1-bit of operand 1. If operand 1 is zero, store zero. m is the mode of operand 0; operand 1's mode is specified by the instruction pattern, and the compiler will convert the operand to that mode before generating the instruction.

The ffs built-in function of C always uses the mode which corresponds to the C data type int.

'clzm2' Store into operand 0 the number of leading 0-bits in x, starting at the most significant bit position. If x is 0, the result is undefined. m is the mode of operand 0; operand 1's mode is specified by the instruction pattern, and the compiler will convert the operand to that mode before generating the instruction.

'ctzm2' Store into operand 0 the number of trailing 0-bits in x, starting at the least significant bit position. If x is 0, the result is undefined. m is the mode of operand 0; operand 1's mode is specified by the instruction pattern, and the compiler will convert the operand to that mode before generating the instruction.

'popcountm2'

Store into operand 0 the number of 1-bits in x. m is the mode of operand 0; operand 1's mode is specified by the instruction pattern, and the compiler will convert the operand to that mode before generating the instruction.

'paritym2'

Store into operand 0 the parity of x, i.e. the number of 1-bits in x modulo 2. m is the mode of operand 0; operand 1's mode is specified by the instruction pattern, and the compiler will convert the operand to that mode before generating the instruction.

'one_cmplm2'

Store the bitwise-complement of operand 1 into operand 0.

'cmpm' Compare operand 0 and operand 1, and set the condition codes. The RTL pattern should look like this:

'tstm' Compare operand 0 against zero, and set the condition codes. The RTL pattern should look like this:

```
(set (cc0) (match_operand:m 0 ...))
```

'tstm' patterns should not be defined for machines that do not use (cc0). Doing so would confuse the optimizer since it would no longer be clear which set operations were comparisons. The 'cmpm' patterns should be used instead.

'movmemm' Block move instruction. The destination and source blocks of memory are the first two operands, and both are mem: BLKs with an address in mode Pmode.

The number of bytes to move is the third operand, in mode m. Usually, you specify word_mode for m. However, if you can generate better code knowing the range of valid lengths is smaller than those representable in a full word, you should provide a pattern with a mode corresponding to the range of values you can handle efficiently (e.g., QImode for values in the range 0–127; note we avoid numbers that appear negative) and also a pattern with word_mode.

The fourth operand is the known shared alignment of the source and destination, in the form of a const_int rtx. Thus, if the compiler knows that both source and destination are word-aligned, it may provide the value 4 for this operand.

Descriptions of multiple movmemm patterns can only be beneficial if the patterns for smaller modes have fewer restrictions on their first, second and fourth operands. Note that the mode m in movmemm does not impose any restriction on the mode of individually moved data units in the block.

These patterns need not give special consideration to the possibility that the source and destination strings might overlap.

'movstr' String copy instruction, with stpcpy semantics. Operand 0 is an output operand in mode Pmode. The addresses of the destination and source strings are operands 1 and 2, and both are mem: BLKs with addresses in mode Pmode. The execution of the expansion of this pattern should store in operand 0 the address in which the NUL terminator was stored in the destination string.

'clrmemm' Block clear instruction. The destination string is the first operand, given as a mem: BLK whose address is in mode Pmode. The number of bytes to clear is the second operand, in mode m. See 'movmemm' for a discussion of the choice of mode.

The third operand is the known alignment of the destination, in the form of a const_int rtx. Thus, if the compiler knows that the destination is word-aligned, it may provide the value 4 for this operand.

The use for multiple clrmemm is as for movmemm.

'cmpstrm' String compare instruction, with five operands. Operand 0 is the output; it has mode m. The remaining four operands are like the operands of 'movmemm'. The two memory blocks specified are compared byte by byte in lexicographic order starting at the beginning of each string. The instruction is not allowed to prefetch more than one byte at a time since either string may end in the first byte and reading past that may access an invalid page or segment and cause a fault. The effect of the instruction is to store a value in operand 0 whose sign indicates the result of the comparison.

'cmpmemm' Block compare instruction, with five operands like the operands of 'cmpstrm'. The two memory blocks specified are compared byte by byte in lexicographic order starting at the beginning of each block. Unlike 'cmpstrm' the instruction can prefetch any bytes in the two memory blocks. The effect of the instruction is to store a value in operand 0 whose sign indicates the result of the comparison.

'strlenm' Compute the length of a string, with three operands. Operand 0 is the result (of mode m), operand 1 is a mem referring to the first character of the string, operand 2 is the character to search for (normally zero), and operand 3 is a constant describing the known alignment of the beginning of the string.

'floatmn2'

Convert signed integer operand 1 (valid for fixed point mode m) to floating point mode n and store in operand 0 (which has mode n).

'floatunsmn2'

Convert unsigned integer operand 1 (valid for fixed point mode m) to floating point mode n and store in operand 0 (which has mode n).

'fixmn2' Convert operand 1 (valid for floating point mode m) to fixed point mode n as a signed number and store in operand 0 (which has mode n). This instruction's result is defined only when the value of operand 1 is an integer.

If the machine description defines this pattern, it also needs to define the ftrunc pattern.

'fixunsmn2'

Convert operand 1 (valid for floating point mode m) to fixed point mode n as an unsigned number and store in operand 0 (which has mode n). This instruction's result is defined only when the value of operand 1 is an integer.

'ftruncm2'

Convert operand 1 (valid for floating point mode m) to an integer value, still represented in floating point mode m, and store it in operand 0 (valid for floating point mode m).

'fix_truncmn2'

Like 'fixmn 2' but works for any floating point value of mode m by converting the value to an integer.

'fixuns_truncmn2'

Like 'fixunsmn2' but works for any floating point value of mode m by converting the value to an integer.

'truncmn 2'

Truncate operand 1 (valid for mode m) to mode n and store in operand 0 (which has mode n). Both modes must be fixed point or both floating point.

'extendmn 2'

Sign-extend operand 1 (valid for mode m) to mode n and store in operand 0 (which has mode n). Both modes must be fixed point or both floating point.

'zero_extendmn2'

Zero-extend operand 1 (valid for mode m) to mode n and store in operand 0 (which has mode n). Both modes must be fixed point.

'extv' Extract a bit-field from operand 1 (a register or memory operand), where operand 2 specifies the width in bits and operand 3 the starting bit, and store it in operand 0. Operand 0 must have mode word_mode. Operand 1 may have mode byte_mode or word_mode; often word_mode is allowed only for registers. Operands 2 and 3 must be valid for word_mode.

The RTL generation pass generates this instruction only with constants for operands 2 and 3.

The bit-field value is sign-extended to a full word integer before it is stored in operand 0.

'extzv' Like 'extv' except that the bit-field value is zero-extended.

'insv' Store operand 3 (which must be valid for word_mode) into a bit-field in operand 0, where operand 1 specifies the width in bits and operand 2 the starting bit. Operand 0 may have mode byte_mode or word_mode; often word_mode is allowed only for registers. Operands 1 and 2 must be valid for word_mode.

The RTL generation pass generates this instruction only with constants for operands 1 and 2.

'movmodecc'

Conditionally move operand 2 or operand 3 into operand 0 according to the comparison in operand 1. If the comparison is true, operand 2 is moved into operand 0, otherwise operand 3 is moved.

The mode of the operands being compared need not be the same as the operands being moved. Some machines, sparc64 for example, have instructions that conditionally move an integer value based on the floating point condition codes and vice versa.

If the machine does not have conditional move instructions, do not define these patterns.

'addmodecc'

Similar to 'movmodecc' but for conditional addition. Conditionally move operand 2 or (operands 2 + operand 3) into operand 0 according to the comparison in operand 1. If the comparison is true, operand 2 is moved into operand 0, otherwise (operand 2 + operand 3) is moved.

'scond'

Store zero or nonzero in the operand according to the condition codes. Value stored is nonzero iff the condition *cond* is true. *cond* is the name of a comparison operation expression code, such as eq. 1t or leu.

You specify the mode that the operand must have when you write the match_operand expression. The compiler automatically sees which mode you have used and supplies an operand of that mode.

The value stored for a true condition must have 1 as its low bit, or else must be negative. Otherwise the instruction is not suitable and you should omit it from the machine description. You describe to the compiler exactly which value is stored by defining the macro STORE_FLAG_VALUE (see Section 13.28 [Misc], page 371). If a description cannot be found that can be used for all the 'scond' patterns, you should omit those operations from the machine description.

These operations may fail, but should do so only in relatively uncommon cases; if they would fail for common cases involving integer comparisons, it is best to omit these patterns.

If these operations are omitted, the compiler will usually generate code that copies the constant one to the target and branches around an assignment of zero to the target. If this code is more efficient than the potential instructions used for the 'scond' pattern followed by those required to convert the result into a 1 or a zero in SImode, you should omit the 'scond' operations from the machine description.

'bcond'

Conditional branch instruction. Operand 0 is a label_ref that refers to the label to jump to. Jump if the condition codes meet condition cond.

Some machines do not follow the model assumed here where a comparison instruction is followed by a conditional branch instruction. In that case, the 'cmpm' (and 'tstm') patterns should simply store the operands away and generate all the required insns in a define_expand (see Section 12.15 [Expander Definitions], page 217) for the conditional branch operations. All calls to expand 'bcond' patterns are immediately preceded by calls to expand either a 'cmpm' pattern or a 'tstm' pattern.

Machines that use a pseudo register for the condition code value, or where the mode used for the comparison depends on the condition being tested, should also use the above mechanism. See Section 12.12 [Jump Patterns], page 213.

The above discussion also applies to the 'movmodecc' and 'scond' patterns.

'cbranchmode4'

Conditional branch instruction combined with a compare instruction. Operand 0 is a comparison operator. Operand 1 and operand 2 are the first and second operands of the comparison, respectively. Operand 3 is a label_ref that refers to the label to jump to.

'jump' A jump inside a function; an unconditional branch. Operand 0 is the label_ref of the label to jump to. This pattern name is mandatory on all machines.

'call' Subroutine call instruction returning no value. Operand 0 is the function to call; operand 1 is the number of bytes of arguments pushed as a const_int; operand 2 is the number of registers used as operands.

On most machines, operand 2 is not actually stored into the RTL pattern. It is supplied for the sake of some RISC machines which need to put this information into the assembler code; they can put it in the RTL instead of operand 1.

Operand 0 should be a mem RTX whose address is the address of the function. Note, however, that this address can be a symbol_ref expression even if it would not be a legitimate memory address on the target machine. If it is also not a valid argument for a call instruction, the pattern for this operation should be a define_expand (see Section 12.15 [Expander Definitions], page 217) that places the address into a register and uses that register in the call instruction.

'call value'

Subroutine call instruction returning a value. Operand 0 is the hard register in which the value is returned. There are three more operands, the same as the three operands of the 'call' instruction (but with numbers increased by one). Subroutines that return BLKmode objects use the 'call' insn.

'call_pop', 'call_value_pop'

Similar to 'call' and 'call_value', except used if defined and if RETURN_POPS_ARGS is nonzero. They should emit a parallel that contains both the function call and a set to indicate the adjustment made to the frame pointer.

For machines where RETURN_POPS_ARGS can be nonzero, the use of these patterns increases the number of functions for which the frame pointer can be eliminated, if desired.

'untyped_call'

Subroutine call instruction returning a value of any type. Operand 0 is the function to call; operand 1 is a memory location where the result of calling the function is to be stored; operand 2 is a parallel expression where each element is a set expression that indicates the saving of a function return value into the result block.

This instruction pattern should be defined to support __builtin_apply on machines where special instructions are needed to call a subroutine with arbitrary arguments or to save the value returned. This instruction pattern is required on machines that have multiple registers that can hold a return value (i.e. FUNCTION_VALUE_REGNO_P is true for more than one register).

'return'

Subroutine return instruction. This instruction pattern name should be defined only if a single instruction can do all the work of returning from a function.

Like the 'movm' patterns, this pattern is also used after the RTL generation phase. In this case it is to support machines where multiple instructions are usually needed to return from a function, but some class of functions only requires one instruction to implement a return. Normally, the applicable functions are those which do not need to save any registers or allocate stack space.

For such machines, the condition specified in this pattern should only be true when reload_completed is nonzero and the function's epilogue would only be a single instruction. For machines with register windows, the routine leaf_function_p may be used to determine if a register window push is required.

Machines that have conditional return instructions should define patterns such as

where *condition* would normally be the same condition specified on the named 'return' pattern.

'untyped_return'

Untyped subroutine return instruction. This instruction pattern should be defined to support __builtin_return on machines where special instructions are needed to return a value of any type.

Operand 0 is a memory location where the result of calling a function with __builtin_apply is stored; operand 1 is a parallel expression where each element is a set expression that indicates the restoring of a function return value from the result block.

'nop' No-op instruction. This instruction pattern name should always be defined to output a no-op in assembler code. (const_int 0) will do as an RTL pattern.

'indirect_jump'

An instruction to jump to an address which is operand zero. This pattern name is mandatory on all machines.

'casesi' Instruction to jump through a dispatch table, including bounds checking. This instruction takes five operands:

- 1. The index to dispatch on, which has mode SImode.
- 2. The lower bound for indices in the table, an integer constant.
- 3. The total range of indices in the table—the largest index minus the smallest one (both inclusive).
- 4. A label that precedes the table itself.
- 5. A label to jump to if the index has a value outside the bounds.

The table is a addr_vec or addr_diff_vec inside of a jump_insn. The number of elements in the table is one plus the difference between the upper bound and the lower bound.

'table jump'

Instruction to jump to a variable address. This is a low-level capability which can be used to implement a dispatch table when there is no 'casesi' pattern.

This pattern requires two operands: the address or offset, and a label which should immediately precede the jump table. If the macro CASE_VECTOR_PC_RELATIVE evaluates to a nonzero value then the first operand is an offset which counts from the address of the table; otherwise, it is an absolute address to jump to. In either case, the first operand has mode Pmode.

The 'table jump' insn is always the last insn before the jump table it uses. Its assembler code normally has no need to use the second operand, but you should incorporate it in the RTL pattern so that the jump optimizer will not delete the table as unreachable code.

'decrement and branch until zero'

Conditional branch instruction that decrements a register and jumps if the register is nonzero. Operand 0 is the register to decrement and test; operand 1 is the label to jump to if the register is nonzero. See Section 12.13 [Looping Patterns], page 214.

This optional instruction pattern is only used by the combiner, typically for loops reversed by the loop optimizer when strength reduction is enabled.

'doloop_end'

Conditional branch instruction that decrements a register and jumps if the register is nonzero. This instruction takes five operands: Operand 0 is the register to decrement and test; operand 1 is the number of loop iterations as a const_int or const0_rtx if this cannot be determined until run-time; operand 2 is the actual or estimated maximum number of iterations as a const_int; operand 3 is the number of enclosed loops as a const_int (an innermost loop has a value of 1); operand 4 is the label to jump to if the register is nonzero. See Section 12.13 [Looping Patterns], page 214.

This optional instruction pattern should be defined for machines with low-overhead looping instructions as the loop optimizer will try to modify suitable loops to utilize it. If nested low-overhead looping is not supported, use a define_expand (see Section 12.15 [Expander Definitions], page 217) and make the pattern fail if operand 3 is not const1_rtx. Similarly, if the actual or estimated maximum number of iterations is too large for this instruction, make it fail.

'doloop_begin'

Companion instruction to doloop_end required for machines that need to perform some initialization, such as loading special registers used by a low-overhead looping instruction. If initialization insns do not always need to be emitted, use a define_expand (see Section 12.15 [Expander Definitions], page 217) and make it fail.

'canonicalize_funcptr_for_compare'

Canonicalize the function pointer in operand 1 and store the result into operand 0.

Operand 0 is always a reg and has mode Pmode; operand 1 may be a reg, mem, symbol_ref, const_int, etc and also has mode Pmode.

Canonicalization of a function pointer usually involves computing the address of the function which would be called if the function pointer were used in an indirect call.

Only define this pattern if function pointers on the target machine can have different values but still call the same function when used in an indirect call.

```
'save_stack_block'
'save_stack_function'
'save_stack_nonlocal'
'restore_stack_block'
'restore_stack_function'
'restore_stack_nonlocal'
```

Most machines save and restore the stack pointer by copying it to or from an object of mode Pmode. Do not define these patterns on such machines.

Some machines require special handling for stack pointer saves and restores. On those machines, define the patterns corresponding to the non-standard cases by using a define_expand (see Section 12.15 [Expander Definitions], page 217) that produces the required insns. The three types of saves and restores are:

- 1. 'save_stack_block' saves the stack pointer at the start of a block that allocates a variable-sized object, and 'restore_stack_block' restores the stack pointer when the block is exited.
- 'save_stack_function' and 'restore_stack_function' do a similar job
 for the outermost block of a function and are used when the function allocates variable-sized objects or calls alloca. Only the epilogue uses the
 restored stack pointer, allowing a simpler save or restore sequence on some
 machines.
- 3. 'save_stack_nonlocal' is used in functions that contain labels branched to by nested functions. It saves the stack pointer in such a way that the inner function can use 'restore_stack_nonlocal' to restore the stack pointer. The compiler generates code to restore the frame and argument pointer registers, but some machines require saving and restoring additional data such as register window information or stack backchains. Place insns in these patterns to save and restore any such required data.

When saving the stack pointer, operand 0 is the save area and operand 1 is the stack pointer. The mode used to allocate the save area defaults to Pmode but you can override that choice by defining the STACK_SAVEAREA_MODE macro (see Section 13.5 [Storage Layout], page 260). You must specify an integral mode, or VOIDmode if no save area is needed for a particular type of save (either because no save is needed or because a machine-specific save area can be used). Operand 0 is the stack pointer and operand 1 is the save area for restore operations. If

'save_stack_block' is defined, operand 0 must not be VOIDmode since these saves can be arbitrarily nested.

A save area is a mem that is at a constant offset from virtual_stack_vars_rtx when the stack pointer is saved for use by nonlocal gotos and a reg in the other two cases.

'allocate_stack'

Subtract (or add if STACK_GROWS_DOWNWARD is undefined) operand 1 from the stack pointer to create space for dynamically allocated data.

Store the resultant pointer to this space into operand 0. If you are allocating space from the main stack, do this by emitting a move insn to copy virtual_stack_dynamic_rtx to operand 0. If you are allocating the space elsewhere, generate code to copy the location of the space to operand 0. In the latter case, you must ensure this space gets freed when the corresponding space on the main stack is free.

Do not define this pattern if all that must be done is the subtraction. Some machines require other operations such as stack probes or maintaining the back chain. Define this pattern to emit those operations in addition to updating the stack pointer.

'check stack'

If stack checking cannot be done on your system by probing the stack with a load or store instruction (see Section 13.10.3 [Stack Checking], page 290), define this pattern to perform the needed check and signaling an error if the stack has overflowed. The single operand is the location in the stack furthest from the current stack pointer that you need to validate. Normally, on machines where this pattern is needed, you would obtain the stack limit from a global or thread-specific variable or register.

'nonlocal_goto'

Emit code to generate a non-local goto, e.g., a jump from one function to a label in an outer function. This pattern has four arguments, each representing a value to be used in the jump. The first argument is to be loaded into the frame pointer, the second is the address to branch to (code to dispatch to the actual label), the third is the address of a location where the stack is saved, and the last is the address of the label, to be placed in the location for the incoming static chain.

On most machines you need not define this pattern, since GCC will already generate the correct code, which is to load the frame pointer and static chain, restore the stack (using the 'restore_stack_nonlocal' pattern, if defined), and jump indirectly to the dispatcher. You need only define this pattern if this code will not work on your machine.

'nonlocal_goto_receiver'

This pattern, if defined, contains code needed at the target of a nonlocal goto after the code already generated by GCC. You will not normally need to define this pattern. A typical reason why you might need this pattern is if some value, such as a pointer to a global table, must be restored when the frame pointer

is restored. Note that a nonlocal goto only occurs within a unit-of-translation, so a global table pointer that is shared by all functions of a given module need not be restored. There are no arguments.

'exception_receiver'

This pattern, if defined, contains code needed at the site of an exception handler that isn't needed at the site of a nonlocal goto. You will not normally need to define this pattern. A typical reason why you might need this pattern is if some value, such as a pointer to a global table, must be restored after control flow is branched to the handler of an exception. There are no arguments.

'builtin_setjmp_setup'

This pattern, if defined, contains additional code needed to initialize the jmp_buf. You will not normally need to define this pattern. A typical reason why you might need this pattern is if some value, such as a pointer to a global table, must be restored. Though it is preferred that the pointer value be recalculated if possible (given the address of a label for instance). The single argument is a pointer to the jmp_buf. Note that the buffer is five words long and that the first three are normally used by the generic mechanism.

'builtin_setjmp_receiver'

This pattern, if defined, contains code needed at the site of an built-in setjmp that isn't needed at the site of a nonlocal goto. You will not normally need to define this pattern. A typical reason why you might need this pattern is if some value, such as a pointer to a global table, must be restored. It takes one argument, which is the label to which builtin_longjmp transfered control; this pattern may be emitted at a small offset from that label.

'builtin_longjmp'

This pattern, if defined, performs the entire action of the longjmp. You will not normally need to define this pattern unless you also define builtin_setjmp_setup. The single argument is a pointer to the jmp_buf.

'eh_return'

This pattern, if defined, affects the way __builtin_eh_return, and thence the call frame exception handling library routines, are built. It is intended to handle non-trivial actions needed along the abnormal return path.

The address of the exception handler to which the function should return is passed as operand to this pattern. It will normally need to copied by the pattern to some special register or memory location. If the pattern needs to determine the location of the target call frame in order to do so, it may use EH_RETURN_STACKADJ_RTX, if defined; it will have already been assigned.

If this pattern is not defined, the default action will be to simply copy the return address to EH_RETURN_HANDLER_RTX. Either that macro or this pattern needs to be defined if call frame exception handling is to be used.

'prologue'

This pattern, if defined, emits RTL for entry to a function. The function entry is responsible for setting up the stack frame, initializing the frame pointer register, saving callee saved registers, etc.

Using a prologue pattern is generally preferred over defining TARGET_ASM_FUNCTION_PROLOGUE to emit assembly code for the prologue.

The prologue pattern is particularly useful for targets which perform instruction scheduling.

'epilogue'

This pattern emits RTL for exit from a function. The function exit is responsible for deallocating the stack frame, restoring callee saved registers and emitting the return instruction.

Using an epilogue pattern is generally preferred over defining TARGET_ASM_FUNCTION_EPILOGUE to emit assembly code for the epilogue.

The epilogue pattern is particularly useful for targets which perform instruction scheduling or which have delay slots for their return instruction.

'sibcall_epilogue'

This pattern, if defined, emits RTL for exit from a function without the final branch back to the calling function. This pattern will be emitted before any sibling call (aka tail call) sites.

The sibcall_epilogue pattern must not clobber any arguments used for parameter passing or any stack slots for arguments passed to the current function.

'trap' This pattern, if defined, signals an error, typically by causing some kind of signal to be raised. Among other places, it is used by the Java front end to signal 'invalid array index' exceptions.

'conditional_trap'

Conditional trap instruction. Operand 0 is a piece of RTL which performs a comparison. Operand 1 is the trap code, an integer.

A typical conditional_trap pattern looks like

'prefetch'

This pattern, if defined, emits code for a non-faulting data prefetch instruction. Operand 0 is the address of the memory to prefetch. Operand 1 is a constant 1 if the prefetch is preparing for a write to the memory address, or a constant 0 otherwise. Operand 2 is the expected degree of temporal locality of the data and is a value between 0 and 3, inclusive; 0 means that the data has no temporal locality, so it need not be left in the cache after the access; 3 means that the data has a high degree of temporal locality and should be left in all levels of cache possible; 1 and 2 mean, respectively, a low or moderate degree of temporal locality.

Targets that do not support write prefetches or locality hints can ignore the values of operands 1 and 2.

12.10 When the Order of Patterns Matters

Sometimes an insn can match more than one instruction pattern. Then the pattern that appears first in the machine description is the one used. Therefore, more specific patterns (patterns that will match fewer things) and faster instructions (those that will produce better code when they do match) should usually go first in the description.

In some cases the effect of ordering the patterns can be used to hide a pattern when it is not valid. For example, the 68000 has an instruction for converting a fullword to floating point and another for converting a byte to floating point. An instruction converting an integer to floating point could match either one. We put the pattern to convert the fullword first to make sure that one will be used rather than the other. (Otherwise a large integer might be generated as a single-byte immediate quantity, which would not work.) Instead of using this pattern ordering it would be possible to make the pattern for convert-a-byte smart enough to deal properly with any constant value.

12.11 Interdependence of Patterns

Every machine description must have a named pattern for each of the conditional branch names 'bcond'. The recognition template must always have the form

In addition, every machine description must have an anonymous pattern for each of the possible reverse-conditional branches. Their templates look like

They are necessary because jump optimization can turn direct-conditional branches into reverse-conditional branches.

It is often convenient to use the match_operator construct to reduce the number of patterns that must be specified for branches. For example,

In some cases machines support instructions identical except for the machine mode of one or more operands. For example, there may be "sign-extend halfword" and "sign-extend byte" instructions whose patterns are

```
(set (match_operand:SI 0 ...)
     (extend:SI (match_operand:HI 1 ...)))
(set (match_operand:SI 0 ...)
     (extend:SI (match_operand:QI 1 ...)))
```

Constant integers do not specify a machine mode, so an instruction to extend a constant value could match either pattern. The pattern it actually will match is the one that appears first in the file. For correct results, this must be the one for the widest possible mode (HImode, here). If the pattern matches the QImode instruction, the results will be incorrect if the constant value does not actually fit that mode.

Such instructions to extend constants are rarely generated because they are optimized away, but they do occasionally happen in nonoptimized compilations.

If a constraint in a pattern allows a constant, the reload pass may replace a register with a constant permitted by the constraint in some cases. Similarly for memory references. Because of this substitution, you should not provide separate patterns for increment and decrement instructions. Instead, they should be generated from the same pattern that supports register-register add insns by examining the operands and generating the appropriate machine instruction.

12.12 Defining Jump Instruction Patterns

For most machines, GCC assumes that the machine has a condition code. A comparison insn sets the condition code, recording the results of both signed and unsigned comparison of the given operands. A separate branch insn tests the condition code and branches or not according its value. The branch insns come in distinct signed and unsigned flavors. Many common machines, such as the VAX, the 68000 and the 32000, work this way.

Some machines have distinct signed and unsigned compare instructions, and only one set of conditional branch instructions. The easiest way to handle these machines is to treat them just like the others until the final stage where assembly code is written. At this time, when outputting code for the compare instruction, peek ahead at the following branch using next_ccO_user (insn). (The variable insn refers to the insn being output, in the output-writing code in an instruction pattern.) If the RTL says that is an unsigned branch, output an unsigned compare; otherwise output a signed compare. When the branch itself is output, you can treat signed and unsigned branches identically.

The reason you can do this is that GCC always generates a pair of consecutive RTL insns, possibly separated by **note** insns, one to set the condition code and one to test it, and keeps the pair inviolate until the end.

To go with this technique, you must define the machine-description macro NOTICE_UPDATE_CC to do CC_STATUS_INIT; in other words, no compare instruction is superfluous.

Some machines have compare-and-branch instructions and no condition code. A similar technique works for them. When it is time to "output" a compare instruction, record its operands in two static variables. When outputting the branch-on-condition-code instruction that follows, actually output a compare-and-branch instruction that uses the remembered operands.

It also works to define patterns for compare-and-branch instructions. In optimizing compilation, the pair of compare and branch instructions will be combined according to these patterns. But this does not happen if optimization is not requested. So you must use one of the solutions above in addition to any special patterns you define.

In many RISC machines, most instructions do not affect the condition code and there may not even be a separate condition code register. On these machines, the restriction

that the definition and use of the condition code be adjacent insns is not necessary and can prevent important optimizations. For example, on the IBM RS/6000, there is a delay for taken branches unless the condition code register is set three instructions earlier than the conditional branch. The instruction scheduler cannot perform this optimization if it is not permitted to separate the definition and use of the condition code register.

On these machines, do not use (cc0), but instead use a register to represent the condition code. If there is a specific condition code register in the machine, use a hard register. If the condition code or comparison result can be placed in any general register, or if there are multiple condition registers, use a pseudo register.

On some machines, the type of branch instruction generated may depend on the way the condition code was produced; for example, on the 68k and SPARC, setting the condition code directly from an add or subtract instruction does not clear the overflow bit the way that a test instruction does, so a different branch instruction must be used for some conditional branches. For machines that use (cc0), the set and use of the condition code must be adjacent (separated only by note insns) allowing flags in cc_status to be used. (See Section 13.15 [Condition Code], page 320.) Also, the comparison and branch insns can be located from each other by using the functions prev_cc0_setter and next_cc0_user.

However, this is not true on machines that do not use (cc0). On those machines, no assumptions can be made about the adjacency of the compare and branch insns and the above methods cannot be used. Instead, we use the machine mode of the condition code register to record different formats of the condition code register.

Registers used to store the condition code value should have a mode that is in class MODE_CC. Normally, it will be CCmode. If additional modes are required (as for the add example mentioned above in the SPARC), define the macro EXTRA_CC_MODES to list the additional modes required (see Section 13.15 [Condition Code], page 320). Also define SELECT_CC_MODE to choose a mode given an operand of a compare.

If it is known during RTL generation that a different mode will be required (for example, if the machine has separate compare instructions for signed and unsigned quantities, like most IBM processors), they can be specified at that time.

If the cases that require different modes would be made by instruction combination, the macro SELECT_CC_MODE determines which machine mode should be used for the comparison result. The patterns should be written using that mode. To support the case of the add on the SPARC discussed above, we have the pattern

The SELECT_CC_MODE macro on the SPARC returns CC_NOOVmode for comparisons whose argument is a plus.

12.13 Defining Looping Instruction Patterns

Some machines have special jump instructions that can be utilized to make loops more efficient. A common example is the 68000 'dbra' instruction which performs a decrement of a register and a branch if the result was greater than zero. Other machines, in particular digital signal processors (DSPs), have special block repeat instructions to provide low-overhead loop support. For example, the TI TMS320C3x/C4x DSPs have a block repeat instruction that loads special registers to mark the top and end of a loop and to count the number of loop iterations. This avoids the need for fetching and executing a 'dbra'-like instruction and avoids pipeline stalls associated with the jump.

GCC has three special named patterns to support low overhead looping. They are 'decrement_and_branch_until_zero', 'doloop_begin', and 'doloop_end'. The first pattern, 'decrement_and_branch_until_zero', is not emitted during RTL generation but may be emitted during the instruction combination phase. This requires the assistance of the loop optimizer, using information collected during strength reduction, to reverse a loop to count down to zero. Some targets also require the loop optimizer to add a REG_NONNEG note to indicate that the iteration count is always positive. This is needed if the target performs a signed loop termination test. For example, the 68000 uses a pattern similar to the following for its dbra instruction:

Note that since the insn is both a jump insn and has an output, it must deal with its own reloads, hence the 'm' constraints. Also note that since this insn is generated by the instruction combination phase combining two sequential insns together into an implicit parallel insn, the iteration counter needs to be biased by the same amount as the decrement operation, in this case -1. Note that the following similar pattern will not be matched by the combiner.

The other two special looping patterns, 'doloop_begin' and 'doloop_end', are emitted by the loop optimizer for certain well-behaved loops with a finite number of loop iterations using information collected during strength reduction.

The 'doloop_end' pattern describes the actual looping instruction (or the implicit looping operation) and the 'doloop_begin' pattern is an optional companion pattern that can be used for initialization needed for some low-overhead looping instructions.

Note that some machines require the actual looping instruction to be emitted at the top of the loop (e.g., the TMS320C3x/C4x DSPs). Emitting the true RTL for a looping instruction at the top of the loop can cause problems with flow analysis. So instead, a dummy doloop insn is emitted at the end of the loop. The machine dependent reorg pass checks for the presence of this doloop insn and then searches back to the top of the loop, where it inserts the true looping insn (provided there are no instructions in the loop which would cause problems). Any additional labels can be emitted at this point. In addition, if the desired special iteration counter register was not allocated, this machine dependent reorg pass could emit a traditional compare and jump instruction pair.

The essential difference between the 'decrement_and_branch_until_zero' and the 'doloop_end' patterns is that the loop optimizer allocates an additional pseudo register for the latter as an iteration counter. This pseudo register cannot be used within the loop (i.e., general induction variables cannot be derived from it), however, in many cases the loop induction variable may become redundant and removed by the flow pass.

12.14 Canonicalization of Instructions

There are often cases where multiple RTL expressions could represent an operation performed by a single machine instruction. This situation is most commonly encountered with logical, branch, and multiply-accumulate instructions. In such cases, the compiler attempts to convert these multiple RTL expressions into a single canonical form to reduce the number of insn patterns required.

In addition to algebraic simplifications, following canonicalizations are performed:

- For commutative and comparison operators, a constant is always made the second operand. If a machine only supports a constant as the second operand, only patterns that match a constant in the second operand need be supplied.
- For associative operators, a sequence of operators will always chain to the left; for instance, only the left operand of an integer plus can itself be a plus. and, ior, xor, plus, mult, smin, smax, umin, and umax are associative when applied to integers, and sometimes to floating-point.
- For these operators, if only one operand is a neg, not, mult, plus, or minus expression, it will be the first operand.
- In combinations of neg, mult, plus, and minus, the neg operations (if any) will be moved inside the operations as far as possible. For instance, (neg (mult A B)) is canonicalized as (mult (neg A) B), but (plus (mult (neg A) B) C) is canonicalized as (minus A (mult B C)).
- For the compare operator, a constant is always the second operand on machines where cc0 is used (see Section 12.12 [Jump Patterns], page 213). On other machines, there are rare cases where the compiler might want to construct a compare with a constant as the

first operand. However, these cases are not common enough for it to be worthwhile to provide a pattern matching a constant as the first operand unless the machine actually has such an instruction.

An operand of neg, not, mult, plus, or minus is made the first operand under the same conditions as above.

- (minus x (const_int n)) is converted to (plus x (const_int -n)).
- Within address computations (i.e., inside mem), a left shift is converted into the appropriate multiplication by a power of two.
- De Morgan's Law is used to move bitwise negation inside a bitwise logical-and or logical-or operation. If this results in only one operand being a **not** expression, it will be the first one.

A machine that has an instruction that performs a bitwise logical-and of one operand with the bitwise negation of the other should specify the pattern for that instruction as

In both cases, it is not necessary to include patterns for the many logically equivalent RTL expressions.

- The only possible RTL expressions involving both bitwise exclusive-or and bitwise negation are (xor: m x y) and (not: m (xor: m x y)).
- The sum of three items, one of which is a constant, will only appear in the form (plus:m (plus:m x y) constant)
- On machines that do not use cc0, (compare x (const_int 0)) will be converted to x.
- Equality comparisons of a group of bits (usually a single bit) with zero will be written using zero_extract rather than the equivalent and or sign_extract operations.

12.15 Defining RTL Sequences for Code Generation

On some target machines, some standard pattern names for RTL generation cannot be handled with single insn, but a sequence of RTL insns can represent them. For these target machines, you can write a define_expand to specify how to generate the sequence of RTL.

A define_expand is an RTL expression that looks almost like a define_insn; but, unlike the latter, a define_expand is used only for RTL generation and it can produce more than one RTL insn.

A define_expand RTX has four operands:

- The name. Each define_expand must have a name, since the only use for it is to refer to it by name.
- The RTL template. This is a vector of RTL expressions representing a sequence of separate instructions. Unlike define_insn, there is no implicit surrounding PARALLEL.
- The condition, a string containing a C expression. This expression is used to express how the availability of this pattern depends on subclasses of target machine, selected by command-line options when GCC is run. This is just like the condition of a define_insn that has a standard name. Therefore, the condition (if present) may not depend on the data in the insn being matched, but only the target-machine-type flags. The compiler needs to test these conditions during initialization in order to learn exactly which named instructions are available in a particular run.
- The preparation statements, a string containing zero or more C statements which are to be executed before RTL code is generated from the RTL template.
 - Usually these statements prepare temporary registers for use as internal operands in the RTL template, but they can also generate RTL insns directly by calling routines such as emit_insn, etc. Any such insns precede the ones that come from the RTL template.

Every RTL insn emitted by a define_expand must match some define_insn in the machine description. Otherwise, the compiler will crash when trying to generate code for the insn or trying to optimize it.

The RTL template, in addition to controlling generation of RTL insns, also describes the operands that need to be specified when this pattern is used. In particular, it gives a predicate for each operand.

A true operand, which needs to be specified in order to generate RTL from the pattern, should be described with a match_operand in its first occurrence in the RTL template. This enters information on the operand's predicate into the tables that record such things. GCC uses the information to preload the operand into a register if that is required for valid RTL code. If the operand is referred to more than once, subsequent references should use match_dup.

The RTL template may also refer to internal "operands" which are temporary registers or labels used only within the sequence made by the define_expand. Internal operands are substituted into the RTL template with match_dup, never with match_operand. The values of the internal operands are not passed in as arguments by the compiler when it requests use of this pattern. Instead, they are computed within the pattern, in the preparation statements. These statements compute the values and store them into the appropriate elements of operands so that match_dup can find them.

There are two special macros defined for use in the preparation statements: DONE and FAIL. Use them with a following semicolon, as a statement.

Use the DONE macro to end RTL generation for the pattern. The only RTL insns resulting from the pattern on this occasion will be those already emitted by explicit calls to emit_insn within the preparation statements; the RTL template will not be generated.

FAIL Make the pattern fail on this occasion. When a pattern fails, it means that the pattern was not truly available. The calling routines in the compiler will try other strategies for code generation using other patterns.

Failure is currently supported only for binary (addition, multiplication, shifting, etc.) and bit-field (extv, extzv, and insv) operations.

If the preparation falls through (invokes neither DONE nor FAIL), then the define_expand acts like a define_insn in that the RTL template is used to generate the insn.

The RTL template is not used for matching, only for generating the initial insn list. If the preparation statement always invokes DONE or FAIL, the RTL template may be reduced to a simple list of operands, such as this example:

```
(define_expand "addsi3"
      [(match_operand:SI 0 "register_operand" "")
       (match_operand:SI 1 "register_operand" "")
       (match_operand:SI 2 "register_operand" "")]
    {
     handle_add (operands[0], operands[1], operands[2]);
     DONE:
    }")
Here is an example, the definition of left-shift for the SPUR chip:
    (define_expand "ashlsi3"
      [(set (match_operand:SI 0 "register_operand" "")
            (ashift:SI
              (match_operand:SI 1 "register_operand" "")
              (match_operand:SI 2 "nonmemory_operand" "")))]
      11.11
      if (GET_CODE (operands[2]) != CONST_INT
          || (unsigned) INTVAL (operands[2]) > 3)
        FAIL;
    }")
```

This example uses define_expand so that it can generate an RTL insn for shifting when the shift-count is in the supported range of 0 to 3 but fail in other cases where machine insns aren't available. When it fails, the compiler tries another strategy using different patterns (such as, a library call).

If the compiler were able to handle nontrivial condition-strings in patterns with names, then it would be possible to use a define_insn in that case. Here is another case (zero-extension on the 68000) which makes more use of the power of define_expand:

Here two RTL insns are generated, one to clear the entire output operand and the other to copy the input operand into its low half. This sequence is incorrect if the input operand refers to [the old value of] the output operand, so the preparation statement makes sure this isn't so. The function make_safe_from copies the operands[1] into a temporary register if it refers to operands[0]. It does this by emitting another RTL insn.

Finally, a third example shows the use of an internal operand. Zero-extension on the SPUR chip is done by and-ing the result against a halfword mask. But this mask cannot be represented by a const_int because the constant value is too large to be legitimate on this machine. So it must be copied into a register with force_reg and then the register used in the and.

Note: If the define_expand is used to serve a standard binary or unary arithmetic operation or a bit-field operation, then the last insn it generates must not be a code_label, barrier or note. It must be an insn, jump_insn or call_insn. If you don't need a real insn at the end, emit an insn to copy the result of the operation into itself. Such an insn will generate no code, but it can avoid problems in the compiler.

12.16 Defining How to Split Instructions

There are two cases where you should specify how to split a pattern into multiple insns. On machines that have instructions requiring delay slots (see Section 12.19.7 [Delay Slots], page 235) or that have instructions whose output is not available for multiple cycles (see Section 12.19.8 [Processor pipeline description], page 236), the compiler phases that optimize these cases need to be able to move insns into one-instruction delay slots. However, some insns may generate more than one machine instruction. These insns cannot be placed into a delay slot.

Often you can rewrite the single insn as a list of individual insns, each corresponding to one machine instruction. The disadvantage of doing so is that it will cause the compilation to be slower and require more space. If the resulting insns are too complex, it may also suppress some optimizations. The compiler splits the insn if there is a reason to believe that it might improve instruction or delay slot scheduling.

The insn combiner phase also splits putative insns. If three insns are merged into one insn with a complex expression that cannot be matched by some define_insn pattern, the combiner phase attempts to split the complex pattern into two insns that are recognized. Usually it can break the complex pattern into two patterns by splitting out some subexpression. However, in some other cases, such as performing an addition of a large constant in two insns on a RISC machine, the way to split the addition into two insns is machine-dependent.

The define_split definition tells the compiler how to split a complex insn into several simpler insns. It looks like this:

```
(define_split
  [insn-pattern]
  "condition"
  [new-insn-pattern-1
   new-insn-pattern-2
   ...]
  "preparation-statements")
```

insn-pattern is a pattern that needs to be split and condition is the final condition to be tested, as in a define_insn. When an insn matching insn-pattern and satisfying condition is found, it is replaced in the insn list with the insns given by new-insn-pattern-1, new-insn-pattern-2, etc.

The preparation-statements are similar to those statements that are specified for define_expand (see Section 12.15 [Expander Definitions], page 217) and are executed before the new RTL is generated to prepare for the generated code or emit some insns whose pattern is not fixed. Unlike those in define_expand, however, these statements must not generate any new pseudo-registers. Once reload has completed, they also must not allocate any space in the stack frame.

Patterns are matched against insn-pattern in two different circumstances. If an insn needs to be split for delay slot scheduling or insn scheduling, the insn is already known to be valid, which means that it must have been matched by some define_insn and, if reload_completed is nonzero, is known to satisfy the constraints of that define_insn. In that case, the new insn patterns must also be insns that are matched by some define_insn and, if reload_completed is nonzero, must also satisfy the constraints of those definitions.

As an example of this usage of define_split, consider the following example from 'a29k.md', which splits a sign_extend from HImode to SImode into a pair of shift insns:

When the combiner phase tries to split an insn pattern, it is always the case that the pattern is not matched by any define_insn. The combiner pass first tries to split a single set expression and then the same set expression inside a parallel, but followed by a clobber of a pseudo-reg to use as a scratch register. In these cases, the combiner expects exactly two new insn patterns to be generated. It will verify that these patterns match some define_insn definitions, so you need not do this test in the define_split (of course, there is no point in writing a define_split that will never produce insns that match).

Here is an example of this use of define_split, taken from 'rs6000.md':

```
[(set (match_dup 0) (plus:SI (match_dup 1) (match_dup 3)))
    (set (match_dup 0) (plus:SI (match_dup 0) (match_dup 4)))]
"
{
    int low = INTVAL (operands[2]) & Oxffff;
    int high = (unsigned) INTVAL (operands[2]) >> 16;

    if (low & Ox8000)
        high++, low |= Oxffff0000;

    operands[3] = GEN_INT (high << 16);
    operands[4] = GEN_INT (low);
}")</pre>
```

Here the predicate non_add_cint_operand matches any const_int that is not a valid operand of a single add insn. The add with the smaller displacement is written so that it can be substituted into the address of a subsequent operation.

An example that uses a scratch register, from the same file, generates an equality comparison of a register and a large constant:

```
(define_split
  [(set (match_operand:CC 0 "cc_reg_operand" "")
        (compare:CC (match_operand:SI 1 "gen_reg_operand" "")
                    (match_operand:SI 2 "non_short_cint_operand" "")))
   (clobber (match_operand:SI 3 "gen_reg_operand" ""))]
  "find_single_use (operands[0], insn, 0)
   && (GET_CODE (*find_single_use (operands[0], insn, 0)) == EQ
       || GET_CODE (*find_single_use (operands[0], insn, 0)) == NE)"
  [(set (match_dup 3) (xor:SI (match_dup 1) (match_dup 4)))
   (set (match_dup 0) (compare:CC (match_dup 3) (match_dup 5)))]
{
  /* Get the constant we are comparing against, C, and see what it
    looks like sign-extended to 16 bits. Then see what constant
     could be XOR'ed with C to get the sign-extended value. */
  int c = INTVAL (operands[2]);
  int sextc = (c << 16) >> 16;
  int xorv = c ^ sextc;
 operands[4] = GEN_INT (xorv);
 operands[5] = GEN_INT (sextc);
```

To avoid confusion, don't write a single define_split that accepts some insns that match some define_insn as well as some insns that don't. Instead, write two separate define_split definitions, one for the insns that are valid and one for the insns that are not valid.

The splitter is allowed to split jump instructions into sequence of jumps or create new jumps in while splitting non-jump instructions. As the central flowgraph and branch prediction information needs to be updated, several restriction apply.

Splitting of jump instruction into sequence that over by another jump instruction is always valid, as compiler expect identical behavior of new jump. When new sequence contains multiple jump instructions or new labels, more assistance is needed. Splitter is required to create only unconditional jumps, or simple conditional jump instructions. Additionally it must attach a REG_BR_PROB note to each conditional jump. A global variable

split_branch_probability hold the probability of original branch in case it was an simple conditional jump, -1 otherwise. To simplify recomputing of edge frequencies, new sequence is required to have only forward jumps to the newly created labels.

For the common case where the pattern of a define_split exactly matches the pattern of a define_insn, use define_insn_and_split. It looks like this:

```
(define_insn_and_split
  [insn-pattern]
  "condition"
  "output-template"
  "split-condition"
  [new-insn-pattern-1
   new-insn-pattern-2
   ...]
  "preparation-statements"
  [insn-attributes])
```

insn-pattern, condition, output-template, and insn-attributes are used as in define_insn. The new-insn-pattern vector and the preparation-statements are used as in a define_split. The split-condition is also used as in define_split, with the additional behavior that if the condition starts with '&&', the condition used for the split will be the constructed as a logical "and" of the split condition with the insn condition. For example, from i386.md:

In this case, the actual split condition will be 'TARGET_ZERO_EXTEND_WITH_AND && !optimize_size && reload_completed'.

The define_insn_and_split construction provides exactly the same functionality as two separate define_insn and define_split patterns. It exists for compactness, and as a maintenance tool to prevent having to ensure the two patterns' templates match.

12.17 Including Patterns in Machine Descriptions.

The include pattern tells the compiler tools where to look for patterns that are in files other than in the file '.md'. This is used only at build time and there is no preprocessing allowed.

```
It looks like:

(include
pathname)

For example:
```

```
(include "filestuff")
```

Where pathname is a string that specifies the location of the file, specifies the include file to be in 'gcc/config/target/filestuff'. The directory 'gcc/config/target' is regarded as the default directory.

Machine descriptions may be split up into smaller more manageable subsections and placed into subdirectories.

By specifying:

```
(include "BOGUS/filestuff")
```

the include file is specified to be in 'gcc/config/target/BOGUS/filestuff'. Specifying an absolute path for the include file such as;

```
(include "/u2/BOGUS/filestuff")
```

is permitted but is not encouraged.

12.17.1 RTL Generation Tool Options for Directory Search

The '-Idir' option specifies directories to search for machine descriptions. For example:

```
genrecog -I/p1/abc/proc1 -I/p2/abcd/pro2 target.md
```

Add the directory dir to the head of the list of directories to be searched for header files. This can be used to override a system machine definition file, substituting your own version, since these directories are searched before the default machine description file directories. If you use more than one '-I' option, the directories are scanned in left-to-right order; the standard default directory come after.

12.18 Machine-Specific Peephole Optimizers

In addition to instruction patterns the 'md' file may contain definitions of machine-specific peephole optimizations.

The combiner does not notice certain peephole optimizations when the data flow in the program does not suggest that it should try them. For example, sometimes two consecutive insns related in purpose can be combined even though the second one does not appear to use a register computed in the first one. A machine-specific peephole optimizer can detect such opportunities.

There are two forms of peephole definitions that may be used. The original define_peephole is run at assembly output time to match insns and substitute assembly text. Use of define_peephole is deprecated.

A newer define_peephole2 matches insns and substitutes new insns. The peephole2 pass is run after register allocation but before scheduling, which may result in much better code for targets that do scheduling.

12.18.1 RTL to Text Peephole Optimizers

A definition looks like this:

```
(define_peephole
  [insn-pattern-1
   insn-pattern-2
   ...]
  "condition"
  "template"
  "optional-insn-attributes")
```

The last string operand may be omitted if you are not using any machine-specific information in this machine description. If present, it must obey the same rules as in a define_insn.

In this skeleton, insn-pattern-1 and so on are patterns to match consecutive insns. The optimization applies to a sequence of insns when insn-pattern-1 matches the first one, insn-pattern-2 matches the next, and so on.

Each of the insns matched by a peephole must also match a define_insn. Peepholes are checked only at the last stage just before code generation, and only optionally. Therefore, any insn which would match a peephole but no define_insn will cause a crash in code generation in an unoptimized compilation, or at various optimization stages.

The operands of the insns are matched with match_operands, match_operator, and match_dup, as usual. What is not usual is that the operand numbers apply to all the insn patterns in the definition. So, you can check for identical operands in two insns by using match_operand in one insn and match_dup in the other.

The operand constraints used in match_operand patterns do not have any direct effect on the applicability of the peephole, but they will be validated afterward, so make sure your constraints are general enough to apply whenever the peephole matches. If the peephole matches but the constraints are not satisfied, the compiler will crash.

It is safe to omit constraints in all the operands of the peephole; or you can write constraints which serve as a double-check on the criteria previously tested.

Once a sequence of insns matches the patterns, the *condition* is checked. This is a C expression which makes the final decision whether to perform the optimization (we do so if the expression is nonzero). If *condition* is omitted (in other words, the string is empty) then the optimization is applied to every sequence of insns that matches the patterns.

The defined peephole optimizations are applied after register allocation is complete. Therefore, the peephole definition can check which operands have ended up in which kinds of registers, just by looking at the operands.

The way to refer to the operands in *condition* is to write operands [i] for operand number i (as matched by (match_operand i ...)). Use the variable insn to refer to the last of the insns being matched; use prev_active_insn to find the preceding insns.

When optimizing computations with intermediate results, you can use condition to match only when the intermediate results are not used elsewhere. Use the C expression dead_or_set_p (insn, op), where insn is the insn in which you expect the value to be used for the last time (from the value of insn, together with use of prev_nonnote_insn), and op is the intermediate value (from operands[i]).

Applying the optimization means replacing the sequence of insns with one new insn. The template controls ultimate output of assembler code for this combined insn. It works exactly

like the template of a define_insn. Operand numbers in this template are the same ones used in matching the original sequence of insns.

The result of a defined peephole optimizer does not need to match any of the insn patterns in the machine description; it does not even have an opportunity to match them. The peephole optimizer definition itself serves as the insn pattern to control how the insn is output.

Defined peephole optimizers are run as assembler code is being output, so the insns they produce are never combined or rearranged in any way.

Here is an example, taken from the 68000 machine description:

```
(define_peephole
        [(set (reg:SI 15) (plus:SI (reg:SI 15) (const_int 4)))
         (set (match_operand:DF 0 "register_operand" "=f")
              (match_operand:DF 1 "register_operand" "ad"))]
        "FP_REG_P (operands[0]) && ! FP_REG_P (operands[1])"
      {
        rtx xoperands[2];
        xoperands[1] = gen_rtx_REG (SImode, REGNO (operands[1]) + 1);
      #ifdef MOTOROLA
        output_asm_insn ("move.l %1,(sp)", xoperands);
        output_asm_insn ("move.l %1,-(sp)", operands);
        return "fmove.d (sp)+,%0";
      #else
        output_asm_insn ("movel %1,sp@", xoperands);
        output_asm_insn ("movel %1,sp@-", operands);
        return "fmoved sp@+,%0";
      #endif
      })
  The effect of this optimization is to change
      jbsr _foobar
      addql #4,sp
      movel d1,sp@-
      movel d0,sp@-
      fmoved sp@+,fp0
into
      jbsr _foobar
      movel d1,sp@
      movel d0,sp@-
      fmoved sp@+,fp0
```

insn-pattern-1 and so on look almost like the second operand of define_insn. There is one important difference: the second operand of define_insn consists of one or more RTX's enclosed in square brackets. Usually, there is only one: then the same action can be written as an element of a define_peephole. But when there are multiple actions in a define_insn, they are implicitly enclosed in a parallel. Then you must explicitly write the parallel, and the square brackets within it, in the define_peephole. Thus, if an insn pattern looks like this,

```
"divs1%.1 %2,%3:%0")
```

then the way to mention this insn in a peephole is as follows:

12.18.2 RTL to RTL Peephole Optimizers

The define_peephole2 definition tells the compiler how to substitute one sequence of instructions for another sequence, what additional scratch registers may be needed and what their lifetimes must be.

```
(define_peephole2
  [insn-pattern-1
   insn-pattern-2
   ...]
  "condition"
  [new-insn-pattern-1
   new-insn-pattern-2
   ...]
  "preparation-statements")
```

The definition is almost identical to define_split (see Section 12.16 [Insn Splitting], page 220) except that the pattern to match is not a single instruction, but a sequence of instructions.

It is possible to request additional scratch registers for use in the output template. If appropriate registers are not free, the pattern will simply not match.

Scratch registers are requested with a match_scratch pattern at the top level of the input pattern. The allocated register (initially) will be dead at the point requested within the original sequence. If the scratch is used at more than a single point, a match_dup pattern at the top level of the input pattern marks the last position in the input sequence at which the register must be available.

Here is an example from the IA-32 machine description:

This pattern tries to split a load from its use in the hopes that we'll be able to schedule around the memory load latency. It allocates a single SImode register of class GENERAL_REGS ("r") that needs to be live only at the point just before the arithmetic.

A real example requiring extended scratch lifetimes is harder to come by, so here's a silly made-up example:

```
(define_peephole2
  [(match_scratch:SI 4 "r")
    (set (match_operand:SI 0 "" "") (match_operand:SI 1 "" ""))
    (set (match_operand:SI 2 "" "") (match_dup 1))
    (match_dup 4)
    (set (match_operand:SI 3 "" "") (match_dup 1))]
    "/* determine 1 does not overlap 0 and 2 */"
    [(set (match_dup 4) (match_dup 1))
    (set (match_dup 0) (match_dup 4))
    (set (match_dup 2) (match_dup 4))]
    (set (match_dup 3) (match_dup 4))]
    "")
```

If we had not added the (match_dup 4) in the middle of the input sequence, it might have been the case that the register we chose at the beginning of the sequence is killed by the first or second set.

12.19 Instruction Attributes

In addition to describing the instruction supported by the target machine, the 'md' file also defines a group of attributes and a set of values for each. Every generated insn is assigned a value for each attribute. One possible attribute would be the effect that the insn has on the machine's condition code. This attribute can then be used by NOTICE_UPDATE_CC to track the condition codes.

12.19.1 Defining Attributes and their Values

The define_attr expression is used to define each attribute required by the target machine. It looks like:

```
(define_attr name list-of-values default)
```

name is a string specifying the name of the attribute being defined.

list-of-values is either a string that specifies a comma-separated list of values that can be assigned to the attribute, or a null string to indicate that the attribute takes numeric values.

default is an attribute expression that gives the value of this attribute for insns that match patterns whose definition does not include an explicit value for this attribute. See Section 12.19.4 [Attr Example], page 233, for more information on the handling of defaults. See Section 12.19.6 [Constant Attributes], page 235, for information on attributes that do not depend on any particular insn.

For each defined attribute, a number of definitions are written to the 'insn-attr.h' file. For cases where an explicit set of values is specified for an attribute, the following are defined:

• A '#define' is written for the symbol 'HAVE_ATTR_name'.

- An enumerated class is defined for 'attr_name' with elements of the form 'upper-name_upper-value' where the attribute name and value are first converted to upper-case.
- A function 'get_attr_name' is defined that is passed an insn and returns the attribute value for that insn.

If the attribute takes numeric values, no enum type will be defined and the function to obtain the attribute's value will return int.

12.19.2 Attribute Expressions

RTL expressions used to define attributes use the codes described above plus a few specific to attribute definitions, to be discussed below. Attribute value expressions must have one of the following forms:

```
(const_int i)
```

The integer i specifies the value of a numeric attribute. i must be non-negative.

The value of a numeric attribute can be specified either with a const_int, or as an integer represented as a string in const_string, eq_attr (see below), attr, symbol_ref, simple arithmetic expressions, and set_attr overrides on specific instructions (see Section 12.19.3 [Tagging Insns], page 231).

(const_string value)

The string value specifies a constant attribute value. If value is specified as '"*", it means that the default value of the attribute is to be used for the insn containing this expression. '"*" obviously cannot be used in the default expression of a define_attr.

If the attribute whose value is being specified is numeric, value must be a string containing a non-negative integer (normally const_int would be used in this case). Otherwise, it must contain one of the valid values for the attribute.

(if_then_else test true-value false-value)

test specifies an attribute test, whose format is defined below. The value of this expression is true-value if test is true, otherwise it is false-value.

```
(cond [test1 value1 ...] default)
```

The first operand of this expression is a vector containing an even number of expressions and consisting of pairs of test and value expressions. The value of the cond expression is that of the value corresponding to the first true test expression. If none of the test expressions are true, the value of the cond expression is that of the default expression.

test expressions can have one of the following forms:

(const_int i)

This test is true if i is nonzero and false otherwise.

```
(not test)
(ior test1 test2)
(and test1 test2)
```

These tests are true if the indicated logical function is true.

(match_operand:m n pred constraints)

This test is true if operand n of the insn whose attribute value is being determined has mode m (this part of the test is ignored if m is VOIDmode) and the function specified by the string pred returns a nonzero value when passed operand n and mode m (this part of the test is ignored if pred is the null string).

The constraints operand is ignored and should be the null string.

```
(le arith1 arith2)
(leu arith1 arith2)
(lt arith1 arith2)
(ltu arith1 arith2)
(gt arith1 arith2)
(gt arith1 arith2)
(gtu arith1 arith2)
(ge arith1 arith2)
(geu arith1 arith2)
(ne arith1 arith2)
(eq arith1 arith2)
```

These tests are true if the indicated comparison of the two arithmetic expressions is true. Arithmetic expressions are formed with plus, minus, mult, div, mod, abs, neg, and, ior, xor, not, ashift, lshiftrt, and ashiftrt expressions.

const_int and symbol_ref are always valid terms (see Section 12.19.5 [Insn Lengths], page 234, for additional forms). symbol_ref is a string denoting a C expression that yields an int when evaluated by the 'get_attr_...' routine. It should normally be a global variable.

(eq_attr name value)

name is a string specifying the name of an attribute.

value is a string that is either a valid value for attribute name, a commaseparated list of values, or '!' followed by a value or list. If value does not begin with a '!', this test is true if the value of the name attribute of the current insn is in the list specified by value. If value begins with a '!', this test is true if the attribute's value is not in the specified list.

For example,

```
(eq_attr "type" "load,store")
is equivalent to
   (ior (eq_attr "type" "load") (eq_attr "type" "store"))
```

If name specifies an attribute of 'alternative', it refers to the value of the compiler variable which_alternative (see Section 12.6 [Output Statement], page 172) and the values must be small integers. For example,

Note that, for most attributes, an eq_attr test is simplified in cases where the value of the attribute being tested is known for all insns matching a particular pattern. This is by far the most common case.

(attr_flag name)

The value of an attr_flag expression is true if the flag specified by name is true for the insn currently being scheduled.

name is a string specifying one of a fixed set of flags to test. Test the flags forward and backward to determine the direction of a conditional branch. Test the flags very_likely, likely, very_unlikely, and unlikely to determine if a conditional branch is expected to be taken.

If the very_likely flag is true, then the likely flag is also true. Likewise for the very_unlikely and unlikely flags.

This example describes a conditional branch delay slot which can be nullified for forward branches that are taken (annul-true) or for backward branches which are not taken (annul-false).

```
(define_delay (eq_attr "type" "cbranch")
  [(eq_attr "in_branch_delay" "true")
        (and (eq_attr "in_branch_delay" "true")
              (attr_flag "forward"))
  (and (eq_attr "in_branch_delay" "true")
              (attr_flag "backward"))])
```

The forward and backward flags are false if the current insn being scheduled is not a conditional branch.

The very_likely and likely flags are true if the insn being scheduled is not a conditional branch. The very_unlikely and unlikely flags are false if the insn being scheduled is not a conditional branch.

attr_flag is only used during delay slot scheduling and has no meaning to other passes of the compiler.

(attr name)

The value of another attribute is returned. This is most useful for numeric attributes, as eq_attr and attr_flag produce more efficient code for non-numeric attributes.

12.19.3 Assigning Attribute Values to Insns

The value assigned to an attribute of an insn is primarily determined by which pattern is matched by that insn (or which define_peephole generated it). Every define_insn and define_peephole can have an optional last argument to specify the values of attributes for matching insns. The value of any attribute not specified in a particular insn is set to the default value for that attribute, as specified in its define_attr. Extensive use of default values for attributes permits the specification of the values for only one or two attributes in the definition of most insn patterns, as seen in the example in the next section.

The optional last argument of define_insn and define_peephole is a vector of expressions, each of which defines the value for a single attribute. The most general way of assigning an attribute's value is to use a set expression whose first operand is an attrespectation expression giving the name of the attribute being set. The second operand of the set is an attribute expression (see Section 12.19.2 [Expressions], page 229) giving the value of the attribute.

When the attribute value depends on the 'alternative' attribute (i.e., which is the applicable alternative in the constraint of the insn), the set_attr_alternative expression can be used. It allows the specification of a vector of attribute expressions, one for each alternative.

When the generality of arbitrary attribute expressions is not required, the simpler set_attr expression can be used, which allows specifying a string giving either a single attribute value or a list of attribute values, one for each alternative.

The form of each of the above specifications is shown below. In each case, name is a string specifying the attribute to be set.

(set_attr name value-string)

value-string is either a string giving the desired attribute value, or a string containing a comma-separated list giving the values for succeeding alternatives. The number of elements must match the number of alternatives in the constraint of the insn pattern.

Note that it may be useful to specify '*' for some alternative, in which case the attribute will assume its default value for insns matching that alternative.

(set_attr_alternative name [value1 value2 ...])

Depending on the alternative of the insn, the value will be one of the specified values. This is a shorthand for using a cond with tests on the 'alternative' attribute.

(set (attr name) value)

The first operand of this set must be the special RTL expression attr, whose sole operand is a string giving the name of the attribute being set. value is the value of the attribute.

The following shows three different ways of representing the same attribute value specification:

The define_asm_attributes expression provides a mechanism to specify the attributes assigned to insns produced from an asm statement. It has the form:

```
(define_asm_attributes [attr-sets])
```

where attr-sets is specified the same as for both the define_insn and the define_peephole expressions.

These values will typically be the "worst case" attribute values. For example, they might indicate that the condition code will be clobbered.

A specification for a length attribute is handled specially. The way to compute the length of an asm insn is to multiply the length specified in the expression define_asm_attributes by the number of machine instructions specified in the asm statement, determined by counting the number of semicolons and newlines in the string. Therefore, the value of the length attribute specified in a define_asm_attributes should be the maximum possible length of a single machine instruction.

12.19.4 Example of Attribute Specifications

The judicious use of defaulting is important in the efficient use of insn attributes. Typically, insns are divided into *types* and an attribute, customarily called **type**, is used to represent this value. This attribute is normally used only to define the default value for other attributes. An example will clarify this usage.

Assume we have a RISC machine with a condition code and in which only full-word operations are performed in registers. Let us assume that we can divide all insns into loads, stores, (integer) arithmetic operations, floating point operations, and branches.

Here we will concern ourselves with determining the effect of an insn on the condition code and will limit ourselves to the following possible effects: The condition code can be set unpredictably (clobbered), not be changed, be set to agree with the results of the operation, or only changed if the item previously set into the condition code has been modified.

Here is part of a sample 'md' file for such a machine:

```
(define_attr "type" "load, store, arith, fp, branch" (const_string "arith"))
(define_attr "cc" "clobber,unchanged,set,change0"
             (cond [(eq_attr "type" "load")
                         (const_string "change0")
                     (eq_attr "type" "store, branch")
                         (const_string "unchanged")
                     (eq_attr "type" "arith")
                         (if_then_else (match_operand:SI 0 "" "")
                                       (const_string "set")
                                       (const_string "clobber"))]
                   (const_string "clobber")))
(define_insn ""
  [(set (match_operand:SI 0 "general_operand" "=r,r,m")
        (match_operand:SI 1 "general_operand" "r,m,r"))]
  move %0,%1
  load %0,%1
   store %0,%1"
  [(set_attr "type" "arith,load,store")])
```

Note that we assume in the above example that arithmetic operations performed on quantities smaller than a machine word clobber the condition code since they will set the condition code to a value corresponding to the full-word result.

12.19.5 Computing the Length of an Insn

For many machines, multiple types of branch instructions are provided, each for different length branch displacements. In most cases, the assembler will choose the correct instruction to use. However, when the assembler cannot do so, GCC can when a special attribute, the 'length' attribute, is defined. This attribute must be defined to have numeric values by specifying a null string in its define_attr.

In the case of the 'length' attribute, two additional forms of arithmetic terms are allowed in test expressions:

```
(match_dup n)
```

This refers to the address of operand n of the current insn, which must be a label_ref.

(pc) This refers to the address of the *current* insn. It might have been more consistent with other usage to make this the address of the *next* insn but this would be confusing because the length of the current insn is to be computed.

For normal insns, the length will be determined by value of the 'length' attribute. In the case of addr_vec and addr_diff_vec insn patterns, the length is computed as the number of vectors multiplied by the size of each vector.

Lengths are measured in addressable storage units (bytes).

The following macros can be used to refine the length computation:

ADJUST INSN LENGTH (insn, length)

If defined, modifies the length assigned to instruction *insn* as a function of the context in which it is used. *length* is an lvalue that contains the initially computed length of the insn and should be updated with the correct length of the insn.

This macro will normally not be required. A case in which it is required is the ROMP. On this machine, the size of an addr_vec insn must be increased by two to compensate for the fact that alignment may be required.

The routine that returns get_attr_length (the value of the length attribute) can be used by the output routine to determine the form of the branch instruction to be written, as the example below illustrates.

As an example of the specification of variable-length branches, consider the IBM 360. If we adopt the convention that a register will be set to the starting address of a function, we can jump to labels within 4k of the start using a four-byte instruction. Otherwise, we need a six-byte sequence to load the address from memory and then branch to it.

On such a machine, a pattern for a branch instruction might be specified as follows:

12.19.6 Constant Attributes

A special form of define_attr, where the expression for the default value is a const expression, indicates an attribute that is constant for a given run of the compiler. Constant attributes may be used to specify which variety of processor is used. For example,

The routine generated for constant attributes has no parameters as it does not depend on any particular insn. RTL expressions used to define the value of a constant attribute may use the symbol_ref form, but may not use either the match_operand form or eq_attr forms involving insn attributes.

12.19.7 Delay Slot Scheduling

The insn attribute mechanism can be used to specify the requirements for delay slots, if any, on a target machine. An instruction is said to require a *delay slot* if some instructions that are physically after the instruction are executed as if they were located before it. Classic examples are branch and call instructions, which often execute the following instruction before the branch or call is performed.

On some machines, conditional branch instructions can optionally annul instructions in the delay slot. This means that the instruction will not be executed for certain branch outcomes. Both instructions that annul if the branch is true and instructions that annul if the branch is false are supported.

Delay slot scheduling differs from instruction scheduling in that determining whether an instruction needs a delay slot is dependent only on the type of instruction being generated, not on data flow between the instructions. See the next section for a discussion of data-dependent instruction scheduling.

The requirement of an insn needing one or more delay slots is indicated via the define_delay expression. It has the following form:

test is an attribute test that indicates whether this define_delay applies to a particular insn. If so, the number of required delay slots is determined by the length of the vector

specified as the second argument. An insn placed in delay slot n must satisfy attribute test delay-n. annul-true-n is an attribute test that specifies which insns may be annulled if the branch is true. Similarly, annul-false-n specifies which insns in the delay slot may be annulled if the branch is false. If annulling is not supported for that delay slot, (nil) should be coded.

For example, in the common case where branch and call insns require a single delay slot, which may contain any insn other than a branch or call, the following would be placed in the 'md' file:

Multiple define_delay expressions may be specified. In this case, each such expression specifies different delay slot requirements and there must be no insn for which tests in two define_delay expressions are both true.

For example, if we have a machine that requires one delay slot for branches but two for calls, no delay slot can contain a branch or call insn, and any valid insn in the delay slot for the branch can be annulled if the branch is true, we might represent this as follows:

12.19.8 Specifying processor pipeline description

To achieve better performance, most modern processors (super-pipelined, superscalar RISC, and VLIW processors) have many functional units on which several instructions can be executed simultaneously. An instruction starts execution if its issue conditions are satisfied. If not, the instruction is stalled until its conditions are satisfied. Such interlock (pipeline) delay causes interruption of the fetching of successor instructions (or demands nop instructions, e.g. for some MIPS processors).

There are two major kinds of interlock delays in modern processors. The first one is a data dependence delay determining instruction latency time. The instruction execution is not started until all source data have been evaluated by prior instructions (there are more complex cases when the instruction execution starts even when the data are not available but will be ready in given time after the instruction execution start). Taking the data dependence delays into account is simple. The data dependence (true, output, and anti-dependence) delay between two instructions is given by a constant. In most cases this approach is adequate. The second kind of interlock delays is a reservation delay. The reservation delay means that two instructions under execution will be in need of shared processors resources, i.e. buses, internal registers, and/or functional units, which are reserved for some time. Taking this kind of delay into account is complex especially for modern RISC processors.

The task of exploiting more processor parallelism is solved by an instruction scheduler. For a better solution to this problem, the instruction scheduler has to have an adequate description of the processor parallelism (or *pipeline description*). GCC machine descriptions

describe processor parallelism and functional unit reservations for groups of instructions with the aid of regular expressions.

The GCC instruction scheduler uses a *pipeline hazard recognizer* to figure out the possibility of the instruction issue by the processor on a given simulated processor cycle. The pipeline hazard recognizer is automatically generated from the processor pipeline description. The pipeline hazard recognizer generated from the machine description is based on a deterministic finite state automaton (DFA): the instruction issue is possible if there is a transition from one automaton state to another one. This algorithm is very fast, and furthermore, its speed is not dependent on processor complexity¹.

The rest of this section describes the directives that constitute an automaton-based processor pipeline description. The order of these constructions within the machine description file is not important.

The following optional construction describes names of automata generated and used for the pipeline hazards recognition. Sometimes the generated finite state automaton used by the pipeline hazard recognizer is large. If we use more than one automaton and bind functional units to the automata, the total size of the automata is usually less than the size of the single automaton. If there is no one such construction, only one finite state automaton is generated.

```
(define_automaton automata-names)
```

automata-names is a string giving names of the automata. The names are separated by commas. All the automata should have unique names. The automaton name is used in the constructions define_cpu_unit and define_query_cpu_unit.

Each processor functional unit used in the description of instruction reservations should be described by the following construction.

```
(define_cpu_unit unit-names [automaton-name])
```

unit-names is a string giving the names of the functional units separated by commas. Don't use name 'nothing', it is reserved for other goals.

automaton-name is a string giving the name of the automaton with which the unit is bound. The automaton should be described in construction define_automaton. You should give automaton-name, if there is a defined automaton.

The assignment of units to automata are constrained by the uses of the units in insn reservations. The most important constraint is: if a unit reservation is present on a particular cycle of an alternative for an insn reservation, then some unit from the same automaton must be present on the same cycle for the other alternatives of the insn reservation. The rest of the constraints are mentioned in the description of the subsequent constructions.

The following construction describes CPU functional units analogously to define_cpu_unit. The reservation of such units can be queried for an automaton state. The instruction scheduler never queries reservation of functional units for given automaton state. So as a rule, you don't need this construction. This construction could be used for future code generation goals (e.g. to generate VLIW insn templates).

¹ However, the size of the automaton depends on processor complexity. To limit this effect, machine descriptions can split orthogonal parts of the machine description among several automata: but then, since each of these must be stepped independently, this does cause a small decrease in the algorithm's performance.

```
(define_query_cpu_unit unit-names [automaton-name])
```

unit-names is a string giving names of the functional units separated by commas.

automaton-name is a string giving the name of the automaton with which the unit is bound.

The following construction is the major one to describe pipeline characteristics of an instruction.

default_latency is a number giving latency time of the instruction. There is an important difference between the old description and the automaton based pipeline description. The latency time is used for all dependencies when we use the old description. In the automaton based pipeline description, the given latency time is only used for true dependencies. The cost of anti-dependencies is always zero and the cost of output dependencies is the difference between latency times of the producing and consuming insns (if the difference is negative, the cost is considered to be zero). You can always change the default costs for any description by using the target hook TARGET_SCHED_ADJUST_COST (see Section 13.17 [Scheduling], page 326).

insn-name is a string giving the internal name of the insn. The internal names are used in constructions define_bypass and in the automaton description file generated for debugging. The internal name has nothing in common with the names in define_insn. It is a good practice to use insn classes described in the processor manual.

condition defines what RTL insns are described by this construction. You should remember that you will be in trouble if condition for two or more different define_insn_reservation constructions is TRUE for an insn. In this case what reservation will be used for the insn is not defined. Such cases are not checked during generation of the pipeline hazards recognizer because in general recognizing that two conditions may have the same value is quite difficult (especially if the conditions contain symbol_ref). It is also not checked during the pipeline hazard recognizer work because it would slow down the recognizer considerably.

regexp is a string describing the reservation of the cpu's functional units by the instruction. The reservations are described by a regular expression according to the following syntax:

- ',' is used for describing the start of the next cycle in the reservation.
- '|' is used for describing a reservation described by the first regular expression or a reservation described by the second regular expression or etc.
- '+' is used for describing a reservation described by the first regular expression **and** a reservation described by the second regular expression **and** etc.
- '*' is used for convenience and simply means a sequence in which the regular expression are repeated *number* times with cycle advancing (see ',').
- 'cpu_function_unit_name' denotes reservation of the named functional unit.
- 'reservation_name' see description of construction 'define_reservation'.
- 'nothing' denotes no unit reservations.

Sometimes unit reservations for different insus contain common parts. In such case, you can simplify the pipeline description by describing the common part by the following construction

```
(define_reservation reservation-name regexp)
```

reservation-name is a string giving name of regexp. Functional unit names and reservation names are in the same name space. So the reservation names should be different from the functional unit names and can not be the reserved name 'nothing'.

The following construction is used to describe exceptions in the latency time for given instruction pair. This is so called bypasses.

number defines when the result generated by the instructions given in string out_insn_names will be ready for the instructions given in string in_insn_names. The instructions in the string are separated by commas.

guard is an optional string giving the name of a C function which defines an additional guard for the bypass. The function will get the two insns as parameters. If the function returns zero the bypass will be ignored for this case. The additional guard is necessary to recognize complicated bypasses, e.g. when the consumer is only an address of insn 'store' (not a stored value).

The following five constructions are usually used to describe VLIW processors, or more precisely, to describe a placement of small instructions into VLIW instruction slots. They can be used for RISC processors, too.

```
(exclusion_set unit-names unit-names)
(presence_set unit-names patterns)
(final_presence_set unit-names patterns)
(absence_set unit-names patterns)
(final_absence_set unit-names patterns)
```

unit-names is a string giving names of functional units separated by commas.

patterns is a string giving patterns of functional units separated by comma. Currently pattern is is one unit or units separated by white-spaces.

The first construction ('exclusion_set') means that each functional unit in the first string can not be reserved simultaneously with a unit whose name is in the second string and vice versa. For example, the construction is useful for describing processors (e.g. some SPARC processors) with a fully pipelined floating point functional unit which can execute simultaneously only single floating point insns or only double floating point insns.

The second construction ('presence_set') means that each functional unit in the first string can not be reserved unless at least one of pattern of units whose names are in the second string is reserved. This is an asymmetric relation. For example, it is useful for description that VLIW 'slot1' is reserved after 'slot0' reservation. We could describe it by the following construction

```
(presence_set "slot1" "slot0")
```

Or 'slot1' is reserved only after 'slot0' and unit 'b0' reservation. In this case we could write

```
(presence_set "slot1" "slot0 b0")
```

The third construction ('final_presence_set') is analogous to 'presence_set'. The difference between them is when checking is done. When an instruction is issued in given automaton state reflecting all current and planned unit reservations, the automaton state is changed. The first state is a source state, the second one is a result state. Checking for 'presence_set' is done on the source state reservation, checking for 'final_presence_set' is done on the result reservation. This construction is useful to describe a reservation which is actually two subsequent reservations. For example, if we use

```
(presence_set "slot1" "slot0")
```

the following insn will be never issued (because 'slot1' requires 'slot0' which is absent in the source state).

```
(define_reservation "insn_and_nop" "slot0 + slot1")
```

but it can be issued if we use analogous 'final_presence_set'.

The forth construction ('absence_set') means that each functional unit in the first string can be reserved only if each pattern of units whose names are in the second string is not reserved. This is an asymmetric relation (actually 'exclusion_set' is analogous to this one but it is symmetric). For example, it is useful for description that VLIW 'slot0' can not be reserved after 'slot1' or 'slot2' reservation. We could describe it by the following construction

```
(absence_set "slot2" "slot0, slot1")
```

Or 'slot2' can not be reserved if 'slot0' and unit 'b0' are reserved or 'slot1' and unit 'b1' are reserved. In this case we could write

```
(absence_set "slot2" "slot0 b0, slot1 b1")
```

All functional units mentioned in a set should belong to the same automaton.

The last construction ('final_absence_set') is analogous to 'absence_set' but checking is done on the result (state) reservation. See comments for 'final_presence_set'.

You can control the generator of the pipeline hazard recognizer with the following construction.

```
(automata_option options)
```

options is a string giving options which affect the generated code. Currently there are the following options:

- no-minimization makes no minimization of the automaton. This is only worth to do when we are debugging the description and need to look more accurately at reservations of states
- time means printing additional time statistics about generation of automata.

- v means a generation of the file describing the result automata. The file has suffix '.dfa' and can be used for the description verification and debugging.
- w means a generation of warning instead of error for non-critical errors.
- ndfa makes nondeterministic finite state automata. This affects the treatment of operator '|' in the regular expressions. The usual treatment of the operator is to try the first alternative and, if the reservation is not possible, the second alternative. The non-deterministic treatment means trying all alternatives, some of them may be rejected by reservations in the subsequent insns. You can not query functional unit reservations in nondeterministic automaton states.
- progress means output of a progress bar showing how many states were generated so far for automaton being processed. This is useful during debugging a DFA description. If you see too many generated states, you could interrupt the generator of the pipeline hazard recognizer and try to figure out a reason for generation of the huge automaton.

As an example, consider a superscalar RISC machine which can issue three insns (two integer insns and one floating point insn) on the cycle but can finish only two insns. To describe this, we define the following functional units.

```
(define_cpu_unit "i0_pipeline, i1_pipeline, f_pipeline")
(define_cpu_unit "port0, port1")
```

All simple integer insns can be executed in any integer pipeline and their result is ready in two cycles. The simple integer insns are issued into the first pipeline unless it is reserved, otherwise they are issued into the second pipeline. Integer division and multiplication insns can be executed only in the second integer pipeline and their results are ready correspondingly in 8 and 4 cycles. The integer division is not pipelined, i.e. the subsequent integer division insn can not be issued until the current division insn finished. Floating point insns are fully pipelined and their results are ready in 3 cycles. Where the result of a floating point insn is used by an integer insn, an additional delay of one cycle is incurred. To describe all of this we could specify

12.20 Conditional Execution

A number of architectures provide for some form of conditional execution, or predication. The hallmark of this feature is the ability to nullify most of the instructions in the instruction set. When the instruction set is large and not entirely symmetric, it can be quite tedious to describe these forms directly in the '.md' file. An alternative is the define_cond_exec template.

```
(define_cond_exec
  [predicate-pattern]
  "condition"
  "output-template")
```

predicate-pattern is the condition that must be true for the insn to be executed at runtime and should match a relational operator. One can use match_operator to match several relational operators at once. Any match_operand operands must have no more than one alternative.

condition is a C expression that must be true for the generated pattern to match.

output-template is a string similar to the define_insn output template (see Section 12.5 [Output Template], page 170), except that the '*' and '@' special cases do not apply. This is only useful if the assembly text for the predicate is a simple prefix to the main insn. In order to handle the general case, there is a global variable current_insn_predicate that will contain the entire predicate if the current insn is predicated, and will otherwise be NULL.

When define_cond_exec is used, an implicit reference to the predicable instruction attribute is made. See Section 12.19 [Insn Attributes], page 228. This attribute must be boolean (i.e. have exactly two elements in its list-of-values). Further, it must not be used with complex expressions. That is, the default and all uses in the insns must be a simple constant, not dependent on the alternative or anything else.

For each define_insn for which the predicable attribute is true, a new define_insn pattern will be generated that matches a predicated version of the instruction. For example,

```
(define_insn "addsi"
        [(set (match_operand:SI 0 "register_operand" "r")
              (plus:SI (match_operand:SI 1 "register_operand" "r")
                       (match_operand:SI 2 "register_operand" "r")))]
        "test1"
        "add %2,%1,%0")
      (define_cond_exec
        [(ne (match_operand:CC 0 "register_operand" "c")
             (const_int 0))]
        "test2"
        "(%0)")
generates a new pattern
      (define_insn ""
        [(cond_exec
           (ne (match_operand:CC 3 "register_operand" "c") (const_int 0))
           (set (match_operand:SI 0 "register_operand" "r")
                (plus:SI (match_operand:SI 1 "register_operand" "r")
                         (match_operand:SI 2 "register_operand" "r"))))]
        "(test2) && (test1)"
        "(%3) add %2,%1,%0")
```

12.21 Constant Definitions

Using literal constants inside instruction patterns reduces legibility and can be a maintenance problem.

To overcome this problem, you may use the define_constants expression. It contains a vector of name-value pairs. From that point on, wherever any of the names appears in the MD file, it is as if the corresponding value had been written instead. You may use define_constants multiple times; each appearance adds more constants to the table. It is an error to redefine a constant with a different value.

To come back to the a29k load multiple example, instead of

```
(define_insn ""
      [(match_parallel 0 "load_multiple_operation"
         [(set (match_operand:SI 1 "gpc_reg_operand" "=r")
               (match_operand:SI 2 "memory_operand" "m"))
          (use (reg:SI 179))
          (clobber (reg:SI 179))])]
      "loadm 0,0,%1,%2")
You could write:
    (define_constants [
        (R_BP 177)
        (R_FC 178)
        (R_CR 179)
        (R_Q 180)
   1)
   (define_insn ""
      [(match_parallel 0 "load_multiple_operation"
         [(set (match_operand:SI 1 "gpc_reg_operand" "=r")
               (match_operand:SI 2 "memory_operand" "m"))
          (use (reg:SI R_CR))
          (clobber (reg:SI R_CR))])]
      "loadm 0,0,%1,%2")
```

The constants that are defined with a define_constant are also output in the insn-codes.h header file as #defines.

12.22 Macros

Ports often need to define similar patterns for more than one machine mode or for more than one rtx code. GCC provides some simple macro facilities to make this process easier.

12.22.1 Mode Macros

Ports often need to define similar patterns for two or more different modes. For example:

- If a processor has hardware support for both single and double floating-point arithmetic, the SFmode patterns tend to be very similar to the DFmode ones.
- If a port uses SImode pointers in one configuration and DImode pointers in another, it will usually have very similar SImode and DImode patterns for manipulating pointers.

Mode macros allow several patterns to be instantiated from one '.md' file template. They can be used with any type of rtx-based construct, such as a define_insn, define_split, or define_peephole2.

12.22.1.1 Defining Mode Macros

The syntax for defining a mode macro is:

```
(define_mode_macro name [(mode1 "cond1") ... (moden "condn")])
```

This allows subsequent '.md' file constructs to use the mode suffix :name. Every construct that does so will be expanded n times, once with every use of :name replaced by :mode1, once with every use replaced by :mode2, and so on. In the expansion for a particular modei, every C condition will also require that condi be true.

For example:

```
(define_mode_macro P [(SI "Pmode == SImode") (DI "Pmode == DImode")])
```

defines a new mode suffix: P. Every construct that uses: P will be expanded twice, once with every: P replaced by: SI and once with every: P replaced by: DI. The: SI version will only apply if Pmode == SImode and the: DI version will only apply if Pmode == DImode.

As with other '.md' conditions, an empty string is treated as "always true". (mode "") can also be abbreviated to mode. For example:

```
(define_mode_macro GPR [SI (DI "TARGET_64BIT")])
```

means that the :DI expansion only applies if TARGET_64BIT but that the :SI expansion has no such constraint.

Macros are applied in the order they are defined. This can be significant if two macros are used in a construct that requires string substitutions. See Section 12.22.1.2 [String Substitutions], page 244.

12.22.1.2 String Substitution in Mode Macros

If an '.md' file construct uses mode macros, each version of the construct will often need slightly different strings. For example:

- When a define_expand defines several addm3 patterns (see Section 12.9 [Standard Names], page 195), each expander will need to use the appropriate mode name for m.
- When a define_insn defines several instruction patterns, each instruction will often use a different assembler mnemonic.

GCC supports such variations through a system of "mode attributes". There are two standard attributes: mode, which is the name of the mode in lower case, and MODE, which is the same thing in upper case. You can define other attributes using:

```
(define_mode_attr name [(mode1 "value1") ... (moden "valuen")])
```

where name is the name of the attribute and valuei is the value associated with modei.

When GCC replaces some :macro with :mode, it will scan each string in the pattern for sequences of the form <macro:attr>, where attr is the name of a mode attribute. If the attribute is defined for mode, the whole <...> sequence will be replaced by the appropriate attribute value.

For example, suppose an '.md' file has:

```
(define_mode_macro P [(SI "Pmode == SImode") (DI "Pmode == DImode")])
(define_mode_attr load [(SI "lw") (DI "ld")])
```

If one of the patterns that uses: P contains the string "<P:load>\t%0,%1", the SI version of that pattern will use "lw\t%0,%1" and the DI version will use "ld\t%0,%1".

The macro: prefix may be omitted, in which case the substitution will be attempted for every macro expansion.

12.22.1.3 Mode Macro Examples

Here is an example from the MIPS port. It defines the following modes and attributes (among others):

```
(define_mode_macro GPR [SI (DI "TARGET_64BIT")])
    (define_mode_attr d [(SI "") (DI "d")])
and uses the following template to define both subsi3 and subdi3:
    (define_insn "sub<mode>3"
      [(set (match_operand:GPR 0 "register_operand" "=d")
            (minus:GPR (match_operand:GPR 1 "register_operand" "d")
                       (match_operand:GPR 2 "register_operand" "d")))]
      "<d>subu\t%0,%1,%2"
      [(set_attr "type" "arith")
       (set_attr "mode" "<MODE>")])
This is exactly equivalent to:
    (define_insn "subsi3"
      [(set (match_operand:SI 0 "register_operand" "=d")
            (minus:SI (match_operand:SI 1 "register_operand" "d")
                      (match_operand:SI 2 "register_operand" "d")))]
      "subu\t%0,%1,%2"
      [(set_attr "type" "arith")
       (set_attr "mode" "SI")])
    (define_insn "subdi3"
      [(set (match_operand:DI 0 "register_operand" "=d")
            (minus:DI (match_operand:DI 1 "register_operand" "d")
                      (match_operand:DI 2 "register_operand" "d")))]
      "dsubu\t%0,%1,%2"
      [(set_attr "type" "arith")
       (set_attr "mode" "DI")])
```

12.22.2 Code Macros

Code macros operate in a similar way to mode macros. See Section 12.22.1 [Mode Macros], page 243.

```
The construct:
```

```
(define_code_macro name [(code1 "cond1") ... (coden "condn")])
```

defines a pseudo rtx code name that can be instantiated as codei if condition condi is true. Each codei must have the same rtx format. See Section 10.2 [RTL Classes], page 108.

As with mode macros, each pattern that uses name will be expanded n times, once with all uses of name replaced by code1, once with all uses replaced by code2, and so on. See Section 12.22.1.1 [Defining Mode Macros], page 244.

It is possible to define attributes for codes as well as for modes. There are two standard code attributes: code, the name of the code in lower case, and CODE, the name of the code in upper case. Other attributes are defined using:

```
(define_code_attr name [(code1 "value1") ... (coden "valuen")])
Here's an example of code macros in action, taken from the MIPS port:
    (define_code_macro any_cond [unordered ordered unlt unge uneq ltgt unle ungt
                                  eq ne gt ge lt le gtu geu ltu leu])
    (define_expand "b<code>"
      [(set (pc)
            (if_then_else (any_cond:CC (cc0)
                                        (const_int 0))
                          (label_ref (match_operand 0 ""))
                          (pc)))]
      11 11
    {
      gen_conditional_branch (operands, <CODE>);
     DONE;
   })
This is equivalent to:
    (define_expand "bunordered"
      [(set (pc)
            (if_then_else (unordered:CC (cc0)
                                         (const_int 0))
                          (label_ref (match_operand 0 ""))
                          (pc)))]
    {
      gen_conditional_branch (operands, UNORDERED);
     DONE;
   })
    (define_expand "bordered"
      [(set (pc)
            (if_then_else (ordered:CC (cc0)
                                       (const_int 0))
                          (label_ref (match_operand 0 ""))
                          (pc)))]
      ** **
    {
      gen_conditional_branch (operands, ORDERED);
     DONE;
   })
```

13 Target Description Macros and Functions

In addition to the file 'machine.md', a machine description includes a C header file conventionally given the name 'machine.h' and a C source file named 'machine.c'. The header file defines numerous macros that convey the information about the target machine that does not fit into the scheme of the '.md' file. The file 'tm.h' should be a link to 'machine.h'. The header file 'config.h' includes 'tm.h' and most compiler source files include 'config.h'. The source file defines a variable targetm, which is a structure containing pointers to functions and data relating to the target machine. 'machine.c' should also contain their definitions, if they are not defined elsewhere in GCC, and other functions called through the macros defined in the '.h' file.

13.1 The Global targetm Variable

struct gcc_target targetm

[Variable

The target '.c' file must define the global targetm variable which contains pointers to functions and data relating to the target machine. The variable is declared in 'target.h'; 'target-def.h' defines the macro TARGET_INITIALIZER which is used to initialize the variable, and macros for the default initializers for elements of the structure. The '.c' file should override those macros for which the default definition is inappropriate. For example:

```
#include "target.h"
#include "target-def.h"

/* Initialize the GCC target structure. */
#undef TARGET_COMP_TYPE_ATTRIBUTES
#define TARGET_COMP_TYPE_ATTRIBUTES machine_comp_type_attributes
struct gcc_target targetm = TARGET_INITIALIZER;
```

Where a macro should be defined in the '.c' file in this manner to form part of the targetm structure, it is documented below as a "Target Hook" with a prototype. Many macros will change in future from being defined in the '.h' file to being part of the targetm structure.

13.2 Controlling the Compilation Driver, 'gcc'

You can control the compilation driver.

SWITCH_TAKES_ARG (char)

[Macro]

A C expression which determines whether the option '-char' takes arguments. The value should be the number of arguments that option takes-zero, for many options. By default, this macro is defined as DEFAULT_SWITCH_TAKES_ARG, which handles the standard options properly. You need not define SWITCH_TAKES_ARG unless you wish to add additional options which take arguments. Any redefinition should call DEFAULT_SWITCH_TAKES_ARG and then check for additional options.

WORD SWITCH TAKES ARG (name)

[Macro]

A C expression which determines whether the option '-name' takes arguments. The value should be the number of arguments that option takes—zero, for many options. This macro rather than SWITCH_TAKES_ARG is used for multi-character option names.

By default, this macro is defined as DEFAULT_WORD_SWITCH_TAKES_ARG, which handles the standard options properly. You need not define WORD_SWITCH_TAKES_ARG unless you wish to add additional options which take arguments. Any redefinition should call DEFAULT_WORD_SWITCH_TAKES_ARG and then check for additional options.

SWITCH_CURTAILS_COMPILATION (char)

[Macro]

A C expression which determines whether the option '-char' stops compilation before the generation of an executable. The value is boolean, nonzero if the option does stop an executable from being generated, zero otherwise.

By default, this macro is defined as <code>DEFAULT_SWITCH_CURTAILS_COMPILATION</code>, which handles the standard options properly. You need not define <code>SWITCH_CURTAILS_COMPILATION</code> unless you wish to add additional options which affect the generation of an executable. Any redefinition should call <code>DEFAULT_SWITCH_CURTAILS_COMPILATION</code> and then check for additional options.

SWITCHES_NEED_SPACES

[Macro]

A string-valued C expression which enumerates the options for which the linker needs a space between the option and its argument.

If this macro is not defined, the default value is "".

TARGET_OPTION_TRANSLATE_TABLE

[Macro]

If defined, a list of pairs of strings, the first of which is a potential command line target to the 'gcc' driver program, and the second of which is a space-separated (tabs and other whitespace are not supported) list of options with which to replace the first option. The target defining this list is responsible for assuring that the results are valid. Replacement options may not be the --opt style, they must be the -opt style. It is the intention of this macro to provide a mechanism for substitution that affects the multilibs chosen, such as one option that enables many options, some of which select multilibs. Example nonsensical definition, where '-malt-abi', '-EB', and '-mspoo' cause different multilibs to be chosen:

```
#define TARGET_OPTION_TRANSLATE_TABLE \
{ "-fast",     "-march=fast-foo -malt-abi -I/usr/fast-foo" }, \
{ "-compat", "-EB -malign=4 -mspoo" }
```

DRIVER SELF SPECS

[Macro]

A list of specs for the driver itself. It should be a suitable initializer for an array of strings, with no surrounding braces.

The driver applies these specs to its own command line between loading default 'specs' files (but not command-line specified ones) and choosing the multilib directory or running any subcommands. It applies them in the order given, so each spec can depend on the options added by earlier ones. It is also possible to remove options using '%<option' in the usual way.

This macro can be useful when a port has several interdependent target options. It provides a way of standardizing the command line so that the other specs are easier to write.

Do not define this macro if it does not need to do anything.

OPTION_DEFAULT_SPECS

[Macro]

A list of specs used to support configure-time default options (i.e. '--with' options) in the driver. It should be a suitable initializer for an array of structures, each containing two strings, without the outermost pair of surrounding braces.

The first item in the pair is the name of the default. This must match the code in 'config.gcc' for the target. The second item is a spec to apply if a default with this name was specified. The string '%(VALUE)' in the spec will be replaced by the value of the default everywhere it occurs.

The driver will apply these specs to its own command line between loading default 'specs' files and processing DRIVER_SELF_SPECS, using the same mechanism as DRIVER_SELF_SPECS.

Do not define this macro if it does not need to do anything.

CPP_SPEC [Macro]

A C string constant that tells the GCC driver program options to pass to CPP. It can also specify how to translate options you give to GCC into options for GCC to pass to the CPP.

Do not define this macro if it does not need to do anything.

CPLUSPLUS_CPP_SPEC

[Macro]

This macro is just like CPP_SPEC, but is used for C++, rather than C. If you do not define this macro, then the value of CPP_SPEC (if any) will be used instead.

CC1_SPEC [Macro]

A C string constant that tells the GCC driver program options to pass to cc1, cc1plus, f771, and the other language front ends. It can also specify how to translate options you give to GCC into options for GCC to pass to front ends.

Do not define this macro if it does not need to do anything.

CC1PLUS_SPEC [Macro]

A C string constant that tells the GCC driver program options to pass to cc1plus. It can also specify how to translate options you give to GCC into options for GCC to pass to the cc1plus.

Do not define this macro if it does not need to do anything. Note that everything defined in CC1_SPEC is already passed to cc1plus so there is no need to duplicate the contents of CC1_SPEC in CC1PLUS_SPEC.

ASM_SPEC [Macro]

A C string constant that tells the GCC driver program options to pass to the assembler. It can also specify how to translate options you give to GCC into options for GCC to pass to the assembler. See the file 'sun3.h' for an example of this.

Do not define this macro if it does not need to do anything.

ASM FINAL SPEC [Macro]

A C string constant that tells the GCC driver program how to run any programs which cleanup after the normal assembler. Normally, this is not needed. See the file 'mips.h' for an example of this.

Do not define this macro if it does not need to do anything.

AS_NEEDS_DASH_FOR_PIPED_INPUT

[Macro]

Define this macro, with no value, if the driver should give the assembler an argument consisting of a single dash, '-', to instruct it to read from its standard input (which will be a pipe connected to the output of the compiler proper). This argument is given after any '-o' option specifying the name of the output file.

If you do not define this macro, the assembler is assumed to read its standard input if given no non-option arguments. If your assembler cannot read standard input at all, use a '%{pipe:%e}' construct; see 'mips.h' for instance.

LINK_SPEC [Macro]

A C string constant that tells the GCC driver program options to pass to the linker. It can also specify how to translate options you give to GCC into options for GCC to pass to the linker.

Do not define this macro if it does not need to do anything.

LIB_SPEC [Macro]

Another C string constant used much like LINK_SPEC. The difference between the two is that LIB_SPEC is used at the end of the command given to the linker.

If this macro is not defined, a default is provided that loads the standard C library from the usual place. See 'gcc.c'.

LIBGCC_SPEC [Macro]

Another C string constant that tells the GCC driver program how and when to place a reference to 'libgcc.a' into the linker command line. This constant is placed both before and after the value of LIB_SPEC.

If this macro is not defined, the GCC driver provides a default that passes the string '-lgcc' to the linker.

REAL_LIBGCC_SPEC [Macro]

By default, if ENABLE_SHARED_LIBGCC is defined, the LIBGCC_SPEC is not directly used by the driver program but is instead modified to refer to different versions of 'libgcc.a' depending on the values of the command line flags '-static', '-shared', '-static-libgcc', and '-shared-libgcc'. On targets where these modifications are inappropriate, define REAL_LIBGCC_SPEC instead. REAL_LIBGCC_SPEC tells the driver how to place a reference to 'libgcc' on the link command line, but, unlike LIBGCC_SPEC, it is used unmodified.

USE_LD_AS_NEEDED [Macro]

A macro that controls the modifications to LIBGCC_SPEC mentioned in REAL_LIBGCC_SPEC. If nonzero, a spec will be generated that uses -as-needed and the shared libgcc in place of the static exception handler library, when linking without any of -static, -static-libgcc, or -shared-libgcc.

LINK EH SPEC [Macro]

If defined, this C string constant is added to LINK_SPEC. When USE_LD_AS_NEEDED is zero or undefined, it also affects the modifications to LIBGCC_SPEC mentioned in REAL_LIBGCC_SPEC.

STARTFILE_SPEC [Macro]

Another C string constant used much like LINK_SPEC. The difference between the two is that STARTFILE_SPEC is used at the very beginning of the command given to the linker.

If this macro is not defined, a default is provided that loads the standard C startup file from the usual place. See 'gcc.c'.

ENDFILE_SPEC [Macro]

Another C string constant used much like LINK_SPEC. The difference between the two is that ENDFILE_SPEC is used at the very end of the command given to the linker.

Do not define this macro if it does not need to do anything.

THREAD_MODEL_SPEC

[Macro]

GCC -v will print the thread model GCC was configured to use. However, this doesn't work on platforms that are multilibbed on thread models, such as AIX 4.3. On such platforms, define THREAD_MODEL_SPEC such that it evaluates to a string without blanks that names one of the recognized thread models. %*, the default value of this macro, will expand to the value of thread_file set in 'config.gcc'.

SYSROOT_SUFFIX_SPEC

[Macro]

Define this macro to add a suffix to the target sysroot when GCC is configured with a sysroot. This will cause GCC to search for usr/lib, et al, within sysroot+suffix.

SYSROOT HEADERS SUFFIX SPEC

[Macro]

Define this macro to add a headers_suffix to the target sysroot when GCC is configured with a sysroot. This will cause GCC to pass the updated sysroot+headers_suffix to CPP, causing it to search for usr/include, et al, within sysroot+headers_suffix.

EXTRA_SPECS [Macro]

Define this macro to provide additional specifications to put in the 'specs' file that can be used in various specifications like CC1_SPEC.

The definition should be an initializer for an array of structures, containing a string constant, that defines the specification name, and a string constant that provides the specification.

Do not define this macro if it does not need to do anything.

EXTRA_SPECS is useful when an architecture contains several related targets, which have various ..._SPECS which are similar to each other, and the maintainer would like one central place to keep these definitions.

For example, the PowerPC System V.4 targets use EXTRA_SPECS to define either _ CALL_SYSV when the System V calling sequence is used or _CALL_AIX when the older AIX-based calling sequence is used.

The 'config/rs6000/rs6000.h' target file defines:

#define CPP_SYS_DEFAULT ""

The 'config/rs6000/sysv.h' target file defines:

```
#undef CPP_SPEC
#define CPP_SPEC \
"%{posix: -D_POSIX_SOURCE } \
%{mcall-sysv: -D_CALL_SYSV } \
%{!mcall-sysv: %(cpp_sysv_default) } \
%{!mcall-sysv: %(cpp_sysv_default) } \
%{msoft-float: -D_SOFT_FLOAT} %{mcpu=403: -D_SOFT_FLOAT}"

#undef CPP_SYSV_DEFAULT
#define CPP_SYSV_DEFAULT "-D_CALL_SYSV"

while the 'config/rs6000/eabiaix.h' target file defines CPP_SYSV_DEFAULT as:
#undef CPP_SYSV_DEFAULT
#define CPP_SYSV_DEFAULT "-D_CALL_AIX"
```

LINK_LIBGCC_SPECIAL

[Macro]

Define this macro if the driver program should find the library 'libgcc.a' itself and should not pass '-L' options to the linker. If you do not define this macro, the driver program will pass the argument '-lgcc' to tell the linker to do the search and will pass '-L' options to it.

LINK_LIBGCC_SPECIAL_1

[Macro]

Define this macro if the driver program should find the library 'libgcc.a'. If you do not define this macro, the driver program will pass the argument '-lgcc' to tell the linker to do the search. This macro is similar to LINK_LIBGCC_SPECIAL, except that it does not affect '-L' options.

LINK GCC C SEQUENCE SPEC

[Macro]

The sequence in which libgcc and libc are specified to the linker. By default this is %G %L %G.

LINK COMMAND SPEC

[Macro]

A C string constant giving the complete command line need to execute the linker. When you do this, you will need to update your port each time a change is made to the link command line within 'gcc.c'. Therefore, define this macro only if you need to completely redefine the command line for invoking the linker and there is no other way to accomplish the effect you need. Overriding this macro may be avoidable by overriding LINK_GCC_C_SEQUENCE_SPEC instead.

LINK_ELIMINATE_DUPLICATE_LDIRECTORIES

[Macro]

A nonzero value causes collect2 to remove duplicate '-Ldirectory' search directories from linking commands. Do not give it a nonzero value if removing duplicate search directories changes the linker's semantics.

MULTILIB_DEFAULTS

[Macro]

Define this macro as a C expression for the initializer of an array of string to tell the driver program which options are defaults for this target and thus do not need to be handled specially when using MULTILIB_OPTIONS.

Do not define this macro if MULTILIB_OPTIONS is not defined in the target makefile fragment or if none of the options listed in MULTILIB_OPTIONS are set by default. See Section 15.1 [Target Fragment], page 389.

RELATIVE_PREFIX_NOT_LINKDIR

[Macro]

Define this macro to tell gcc that it should only translate a '-B' prefix into a '-L' linker option if the prefix indicates an absolute file name.

MD_EXEC_PREFIX

[Macro]

If defined, this macro is an additional prefix to try after STANDARD_EXEC_PREFIX. MD_EXEC_PREFIX is not searched when the '-b' option is used, or the compiler is built as a cross compiler. If you define MD_EXEC_PREFIX, then be sure to add it to the list of directories used to find the assembler in 'configure.in'.

STANDARD_STARTFILE_PREFIX

[Macro]

Define this macro as a C string constant if you wish to override the standard choice of libdir as the default prefix to try when searching for startup files such as 'crt0.o'. STANDARD_STARTFILE_PREFIX is not searched when the compiler is built as a cross compiler.

STANDARD_STARTFILE_PREFIX_1

[Macro]

Define this macro as a C string constant if you wish to override the standard choice of /lib as a prefix to try after the default prefix when searching for startup files such as 'crt0.o'. STANDARD_STARTFILE_PREFIX_1 is not searched when the compiler is built as a cross compiler.

STANDARD STARTFILE PREFIX 2

Macro

Define this macro as a C string constant if you wish to override the standard choice of /lib as yet another prefix to try after the default prefix when searching for startup files such as 'crt0.o'. STANDARD_STARTFILE_PREFIX_2 is not searched when the compiler is built as a cross compiler.

MD_STARTFILE_PREFIX

[Macro]

If defined, this macro supplies an additional prefix to try after the standard prefixes. MD_EXEC_PREFIX is not searched when the '-b' option is used, or when the compiler is built as a cross compiler.

MD_STARTFILE_PREFIX_1

[Macro]

If defined, this macro supplies yet another prefix to try after the standard prefixes. It is not searched when the '-b' option is used, or when the compiler is built as a cross compiler.

INIT_ENVIRONMENT

[Macro]

Define this macro as a C string constant if you wish to set environment variables for programs called by the driver, such as the assembler and loader. The driver passes the value of this macro to putenv to initialize the necessary environment variables.

LOCAL_INCLUDE_DIR

[Macro]

Define this macro as a C string constant if you wish to override the standard choice of '/usr/local/include' as the default prefix to try when searching for local header files. LOCAL_INCLUDE_DIR comes before SYSTEM_INCLUDE_DIR in the search order.

Cross compilers do not search either '/usr/local/include' or its replacement.

MODIFY_TARGET_NAME

[Macro]

Define this macro if you wish to define command-line switches that modify the default target name.

For each switch, you can include a string to be appended to the first part of the configuration name or a string to be deleted from the configuration name, if present. The definition should be an initializer for an array of structures. Each array element should have three elements: the switch name (a string constant, including the initial dash), one of the enumeration codes ADD or DELETE to indicate whether the string should be inserted or deleted, and the string to be inserted or deleted (a string constant).

For example, on a machine where '64' at the end of the configuration name denotes a 64-bit target and you want the '-32' and '-64' switches to select between 32- and 64-bit targets, you would code

```
#define MODIFY_TARGET_NAME \
    { "-32", DELETE, "64"}, \
          {"-64", ADD, "64"}}
```

SYSTEM INCLUDE DIR

[Macro]

Define this macro as a C string constant if you wish to specify a system-specific directory to search for header files before the standard directory. SYSTEM_INCLUDE_DIR comes before STANDARD_INCLUDE_DIR in the search order.

Cross compilers do not use this macro and do not search the directory specified.

STANDARD_INCLUDE_DIR

[Macro]

Define this macro as a C string constant if you wish to override the standard choice of '/usr/include' as the default prefix to try when searching for header files.

Cross compilers ignore this macro and do not search either '/usr/include' or its replacement.

STANDARD INCLUDE COMPONENT

[Macro]

The "component" corresponding to STANDARD_INCLUDE_DIR. See INCLUDE_DEFAULTS, below, for the description of components. If you do not define this macro, no component is used.

INCLUDE_DEFAULTS

[Macro]

Define this macro if you wish to override the entire default search path for include files. For a native compiler, the default search path usually consists of GCC_INCLUDE_DIR, LOCAL_INCLUDE_DIR, SYSTEM_INCLUDE_DIR, GPLUSPLUS_INCLUDE_DIR, and STANDARD_INCLUDE_DIR. In addition, GPLUSPLUS_INCLUDE_DIR and GCC_INCLUDE_DIR are defined automatically by 'Makefile', and specify private search areas for GCC. The directory GPLUSPLUS_INCLUDE_DIR is used only for C++ programs.

The definition should be an initializer for an array of structures. Each array element should have four elements: the directory name (a string constant), the component name (also a string constant), a flag for C++-only directories, and a flag showing that the includes in the directory don't need to be wrapped in extern 'C' when compiling C++. Mark the end of the array with a null element.

The component name denotes what GNU package the include file is part of, if any, in all uppercase letters. For example, it might be 'GCC' or 'BINUTILS'. If the package is part of a vendor-supplied operating system, code the component name as '0'.

For example, here is the definition used for VAX/VMS:

Here is the order of prefixes tried for exec files:

- 1. Any prefixes specified by the user with '-B'.
- 2. The environment variable GCC_EXEC_PREFIX, if any.
- 3. The directories specified by the environment variable COMPILER_PATH.
- 4. The macro STANDARD EXEC PREFIX.
- 5. '/usr/lib/gcc/'.
- 6. The macro MD_EXEC_PREFIX, if any.

Here is the order of prefixes tried for startfiles:

- 1. Any prefixes specified by the user with '-B'.
- 2. The environment variable GCC_EXEC_PREFIX, if any.
- 3. The directories specified by the environment variable LIBRARY_PATH (or port-specific name; native only, cross compilers do not use this).
- 4. The macro STANDARD_EXEC_PREFIX.
- 5. '/usr/lib/gcc/'.
- 6. The macro MD_EXEC_PREFIX, if any.
- 7. The macro MD_STARTFILE_PREFIX, if any.
- 8. The macro STANDARD_STARTFILE_PREFIX.
- 9. '/lib/'.
- 10. '/usr/lib/'.

13.3 Run-time Target Specification

Here are run-time target specifications.

```
TARGET_CPU_CPP_BUILTINS ()
```

[Macro]

This function-like macro expands to a block of code that defines built-in preprocessor macros and assertions for the target cpu, using the functions builtin_define, builtin_define_std and builtin_assert. When the front end calls this macro it provides a trailing semicolon, and since it has finished command line option processing your code can use those results freely.

builtin_assert takes a string in the form you pass to the command-line option '-A', such as cpu=mips, and creates the assertion. builtin_define takes a string in the form accepted by option '-D' and unconditionally defines the macro.

builtin_define_std takes a string representing the name of an object-like macro. If it doesn't lie in the user's namespace, builtin_define_std defines it unconditionally. Otherwise, it defines a version with two leading underscores, and another version with two leading and trailing underscores, and defines the original only if an ISO standard was not requested on the command line. For example, passing unix defines __unix, __unix__ and possibly unix; passing _mips defines __mips, __mips__ and possibly _mips, and passing _ABI64 defines only _ABI64.

You can also test for the C dialect being compiled. The variable c_language is set to one of clk_c, clk_cplusplus or clk_objective_c. Note that if we are preprocessing assembler, this variable will be clk_c but the function-like macro preprocessing_asm_p() will return true, so you might want to check for that first. If you need to check for strict ANSI, the variable flag_iso can be used. The function-like macro preprocessing_trad_p() can be used to check for traditional preprocessing.

TARGET_OS_CPP_BUILTINS ()

[Macro]

Similarly to TARGET_CPU_CPP_BUILTINS but this macro is optional and is used for the target operating system instead.

TARGET_OBJFMT_CPP_BUILTINS ()

[Macro]

Similarly to TARGET_CPU_CPP_BUILTINS but this macro is optional and is used for the target object format. 'elfos.h' uses this macro to define __ELF__, so you probably do not need to define it yourself.

extern int target_flags

[Variable]

This declaration should be present.

TARGET featurename

[Macro]

This series of macros is to allow compiler command arguments to enable or disable the use of optional features of the target machine. For example, one machine description serves both the 68000 and the 68020; a command argument tells the compiler whether it should use 68020-only instructions or not. This command argument works by means of a macro TARGET_68020 that tests a bit in target_flags.

Define a macro TARGET_featurename for each such option. Its definition should test a bit in target_flags. It is recommended that a helper macro MASK_featurename is defined for each bit-value to test, and used in TARGET_featurename and TARGET_SWITCHES. For example:

```
#define TARGET_MASK_68020 1
#define TARGET_68020 (target_flags & MASK_68020)
```

One place where these macros are used is in the condition-expressions of instruction patterns. Note how TARGET_68020 appears frequently in the 68000 machine description file, 'm68k.md'. Another place they are used is in the definitions of the other macros in the 'machine.h' file.

TARGET_SWITCHES [Macro]

This macro defines names of command options to set and clear bits in target_flags. Its definition is an initializer with a subgrouping for each command option.

Each subgrouping contains a string constant, that defines the option name, a number, which contains the bits to set in target_flags, and a second string which is the

description displayed by '--help'. If the number is negative then the bits specified by the number are cleared instead of being set. If the description string is present but empty, then no help information will be displayed for that option, but it will not count as an undocumented option. The actual option name is made by appending '-m' to the specified name. Non-empty description strings should be marked with $N_{-}(...)$ for xgettext. Please do not mark empty strings because the empty string is reserved by GNU gettext. gettext("") returns the header entry of the message catalog with meta information, not the empty string.

In addition to the description for '--help', more detailed documentation for each option should be added to 'invoke.texi'.

One of the subgroupings should have a null string. The number in this grouping is the default value for target_flags. Any target options act starting with that value.

Here is an example which defines '-m68000' and '-m68020' with opposite meanings, and picks the latter as the default:

```
#define TARGET_SWITCHES \
   { "68020", MASK_68020, "" }, \
        { "68000", -MASK_68020, \
            N_("Compile for the 68000") }, \
        { "", MASK_68020, "" }, \
}
```

TARGET_OPTIONS

[Macro]

This macro is similar to TARGET_SWITCHES but defines names of command options that have values. Its definition is an initializer with a subgrouping for each command option.

Each subgrouping contains a string constant, that defines the option name, the address of a variable, a description string, and a value. Non-empty description strings should be marked with N_(...) for xgettext. Please do not mark empty strings because the empty string is reserved by GNU gettext. gettext("") returns the header entry of the message catalog with meta information, not the empty string.

If the value listed in the table is NULL, then the variable, type char *, is set to the variable part of the given option if the fixed part matches. In other words, if the first part of the option matches what's in the table, the variable will be set to point to the rest of the option. This allows the user to specify a value for that option. The actual option name is made by appending '-m' to the specified name. Again, each option should also be documented in 'invoke.texi'.

If the value listed in the table is non-NULL, then the option must match the option in the table exactly (with '-m'), and the variable is set to point to the value listed in the table.

Here is an example which defines '-mshort-data-number'. If the given option is '-mshort-data-512', the variable m88k_short_data will be set to the string "512".

```
extern char *m88k_short_data;
#define TARGET_OPTIONS \
   { "short-data-", &m88k_short_data, \
        N_("Specify the size of the short data section"), 0 } }
```

Here is a variant of the above that allows the user to also specify just '-mshort-data' where a default of "64" is used.

```
extern char *m88k_short_data;
#define TARGET_OPTIONS \
   { "short-data-", &m88k_short_data, \
       N_("Specify the size of the short data section"), 0 } \
       { "short-data", &m88k_short_data, "", "64" },
    }
}
```

Here is an example which defines '-mno-alu', '-malu1', and '-malu2' as a three-state switch, along with suitable macros for checking the state of the option (documentation is elided for brevity).

TARGET_VERSION

[Macro]

This macro is a C statement to print on **stderr** a string describing the particular machine description choice. Every machine description should define **TARGET_VERSION**. For example:

```
#ifdef MOTOROLA
#define TARGET_VERSION \
   fprintf (stderr, " (68k, Motorola syntax)");
#else
#define TARGET_VERSION \
   fprintf (stderr, " (68k, MIT syntax)");
#endif
```

OVERRIDE OPTIONS

[Macro]

Sometimes certain combinations of command options do not make sense on a particular target machine. You can define a macro OVERRIDE_OPTIONS to take account of this. This macro, if defined, is executed once just after all the command options have been parsed.

Don't use this macro to turn on various extra optimizations for '-0'. That is what OPTIMIZATION_OPTIONS is for.

OPTIMIZATION_OPTIONS (level, size)

[Macro]

Some machines may desire to change what optimizations are performed for various optimization levels. This macro, if defined, is executed once just after the optimization level is determined and before the remainder of the command options have been parsed. Values set in this macro are used as the default values for the other command line options.

level is the optimization level specified; 2 if '-02' is specified, 1 if '-0' is specified, and 0 if neither is specified.

size is nonzero if '-0s' is specified and zero otherwise.

You should not use this macro to change options that are not machine-specific. These should uniformly selected by the same optimization level on all supported machines. Use this macro to enable machine-specific optimizations.

Do not examine write_symbols in this macro! The debugging options are not supposed to alter the generated code.

CAN_DEBUG_WITHOUT_FP

[Macro]

Define this macro if debugging can be performed even without a frame pointer. If this macro is defined, GCC will turn on the '-fomit-frame-pointer' option whenever '-0' is specified.

13.4 Defining data structures for per-function information.

If the target needs to store information on a per-function basis, GCC provides a macro and a couple of variables to allow this. Note, just using statics to store the information is a bad idea, since GCC supports nested functions, so you can be halfway through encoding one function when another one comes along.

GCC defines a data structure called **struct function** which contains all of the data specific to an individual function. This structure contains a field called **machine** whose type is **struct machine_function***, which can be used by targets to point to their own specific data.

If a target needs per-function specific data it should define the type struct machine_function and also the macro INIT_EXPANDERS. This macro should be used to initialize the function pointer init_machine_status. This pointer is explained below.

One typical use of per-function, target specific data is to create an RTX to hold the register containing the function's return address. This RTX can then be used to implement the __builtin_return_address function, for level 0.

Note—earlier implementations of GCC used a single data area to hold all of the perfunction information. Thus when processing of a nested function began the old per-function data had to be pushed onto a stack, and when the processing was finished, it had to be popped off the stack. GCC used to provide function pointers called <code>save_machine_status</code> and <code>restore_machine_status</code> to handle the saving and restoring of the target specific information. Since the single data area approach is no longer used, these pointers are no longer supported.

INIT_EXPANDERS [Macro]

Macro called to initialize any target specific information. This macro is called once per function, before generation of any RTL has begun. The intention of this macro is to allow the initialization of the function pointer init_machine_status.

void (*)(struct function *) init_machine_status

[Variable

If this function pointer is non-NULL it will be called once per function, before function compilation starts, in order to allow the target to perform any target specific initialization of the struct function structure. It is intended that this would be used to initialize the machine of that structure.

struct machine_function structures are expected to be freed by GC. Generally, any memory that they reference must be allocated by using ggc_alloc, including the structure itself.

13.5 Storage Layout

Note that the definitions of the macros in this table which are sizes or alignments measured in bits do not need to be constant. They can be C expressions that refer to static variables, such as the target_flags. See Section 13.3 [Run-time Target], page 255.

BITS_BIG_ENDIAN [Macro]

Define this macro to have the value 1 if the most significant bit in a byte has the lowest number; otherwise define it to have the value zero. This means that bit-field instructions count from the most significant bit. If the machine has no bit-field instructions, then this must still be defined, but it doesn't matter which value it is defined to. This macro need not be a constant.

This macro does not affect the way structure fields are packed into bytes or words; that is controlled by BYTES_BIG_ENDIAN.

BYTES_BIG_ENDIAN [Macro]

Define this macro to have the value 1 if the most significant byte in a word has the lowest number. This macro need not be a constant.

WORDS_BIG_ENDIAN [Macro]

Define this macro to have the value 1 if, in a multiword object, the most significant word has the lowest number. This applies to both memory locations and registers; GCC fundamentally assumes that the order of words in memory is the same as the order in registers. This macro need not be a constant.

LIBGCC2 WORDS BIG ENDIAN

Macro

Define this macro if WORDS_BIG_ENDIAN is not constant. This must be a constant value with the same meaning as WORDS_BIG_ENDIAN, which will be used only when compiling 'libgcc2.c'. Typically the value will be set based on preprocessor defines.

FLOAT_WORDS_BIG_ENDIAN

|Macro

Define this macro to have the value 1 if DFmode, XFmode or TFmode floating point numbers are stored in memory with the word containing the sign bit at the lowest address; otherwise define it to have the value 0. This macro need not be a constant.

You need not define this macro if the ordering is the same as for multi-word integers.

BITS_PER_UNIT [Macro]

Define this macro to be the number of bits in an addressable storage unit (byte). If you do not define this macro the default is 8.

BITS_PER_WORD [Macro]

Number of bits in a word. If you do not define this macro, the default is BITS_PER_UNIT * UNITS_PER_WORD.

MAX_BITS_PER_WORD

Macro

Maximum number of bits in a word. If this is undefined, the default is BITS_PER_WORD. Otherwise, it is the constant value that is the largest value that BITS_PER_WORD can have at run-time.

UNITS_PER_WORD [Macro]

Number of storage units in a word; normally 4.

MIN_UNITS_PER_WORD

[Macro]

Minimum number of units in a word. If this is undefined, the default is UNITS_PER_ WORD. Otherwise, it is the constant value that is the smallest value that UNITS_PER_ WORD can have at run-time.

POINTER_SIZE [Macro]

Width of a pointer, in bits. You must specify a value no wider than the width of Pmode. If it is not equal to the width of Pmode, you must define POINTERS_EXTEND_UNSIGNED. If you do not specify a value the default is BITS_PER_WORD.

POINTERS_EXTEND_UNSIGNED

[Macro]

A C expression whose value is greater than zero if pointers that need to be extended from being POINTER_SIZE bits wide to Pmode are to be zero-extended and zero if they are to be sign-extended. If the value is less then zero then there must be an "ptr_extend" instruction that extends a pointer from POINTER_SIZE to Pmode.

You need not define this macro if the POINTER_SIZE is equal to the width of Pmode.

PROMOTE_MODE (m, unsignedp, type)

[Macro]

A macro to update m and unsignedp when an object whose type is type and which has the specified mode and signedness is to be stored in a register. This macro is only called when type is a scalar type.

On most RISC machines, which only have operations that operate on a full register, define this macro to set m to word_mode if m is an integer mode narrower than BITS_PER_WORD. In most cases, only integer modes should be widened because wider-precision floating-point operations are usually more expensive than their narrower counterparts.

For most machines, the macro definition does not change unsigned p. However, some machines, have instructions that preferentially handle either signed or unsigned quantities of certain modes. For example, on the DEC Alpha, 32-bit loads from memory and 32-bit add instructions sign-extend the result to 64 bits. On such machines, set unsigned p according to which kind of extension is more efficient.

Do not define this macro if it would never modify m.

PROMOTE_FUNCTION_MODE

[Macro]

Like PROMOTE_MODE, but is applied to outgoing function arguments or function return values, as specified by TARGET_PROMOTE_FUNCTION_ARGS and TARGET_PROMOTE_FUNCTION_RETURN, respectively.

The default is PROMOTE_MODE.

bool TARGET_PROMOTE_FUNCTION_ARGS (tree fntype)

[Target Hook]

This target hook should return true if the promotion described by PROMOTE_FUNCTION_MODE should be done for outgoing function arguments.

bool TARGET_PROMOTE_FUNCTION_RETURN (tree fntype)

[Target Hook]

This target hook should return true if the promotion described by PROMOTE_FUNCTION_MODE should be done for the return value of functions.

If this target hook returns **true**, FUNCTION_VALUE must perform the same promotions done by PROMOTE_FUNCTION_MODE.

PARM_BOUNDARY [Macro]

Normal alignment required for function parameters on the stack, in bits. All stack parameters receive at least this much alignment regardless of data type. On most machines, this is the same as the size of an integer.

STACK_BOUNDARY [Macro]

Define this macro to the minimum alignment enforced by hardware for the stack pointer on this machine. The definition is a C expression for the desired alignment (measured in bits). This value is used as a default if PREFERRED_STACK_BOUNDARY is not defined. On most machines, this should be the same as PARM_BOUNDARY.

PREFERRED_STACK_BOUNDARY

[Macro]

Define this macro if you wish to preserve a certain alignment for the stack pointer, greater than what the hardware enforces. The definition is a C expression for the desired alignment (measured in bits). This macro must evaluate to a value equal to or larger than STACK_BOUNDARY.

FORCE PREFERRED STACK BOUNDARY IN MAIN

[Macro]

A C expression that evaluates true if PREFERRED_STACK_BOUNDARY is not guaranteed by the runtime and we should emit code to align the stack at the beginning of main. If PUSH_ROUNDING is not defined, the stack will always be aligned to the specified boundary. If PUSH_ROUNDING is defined and specifies a less strict alignment than PREFERRED_STACK_BOUNDARY, the stack may be momentarily unaligned while pushing arguments.

FUNCTION BOUNDARY

[Macro]

Alignment required for a function entry point, in bits.

BIGGEST ALIGNMENT

[Macro]

Biggest alignment that any data type can require on this machine, in bits.

MINIMUM_ATOMIC_ALIGNMENT

[Macro]

If defined, the smallest alignment, in bits, that can be given to an object that can be referenced in one operation, without disturbing any nearby object. Normally, this is BITS_PER_UNIT, but may be larger on machines that don't have byte or half-word store operations.

BIGGEST FIELD ALIGNMENT

[Macro]

Biggest alignment that any structure or union field can require on this machine, in bits. If defined, this overrides $BIGGEST_ALIGNMENT$ for structure and union fields only, unless the field alignment has been set by the $_$ attribute $_$ ((aligned (n))) construct.

ADJUST_FIELD_ALIGN (field, computed)

[Macro]

An expression for the alignment of a structure field field if the alignment computed in the usual way (including applying of BIGGEST_ALIGNMENT and BIGGEST_FIELD_ALIGNMENT to the alignment) is computed. It overrides alignment only if the field alignment has not been set by the __attribute__ ((aligned (n))) construct.

MAX_OFILE_ALIGNMENT

[Macro]

Biggest alignment supported by the object file format of this machine. Use this macro to limit the alignment which can be specified using the __attribute__ ((aligned (n))) construct. If not defined, the default value is BIGGEST_ALIGNMENT.

DATA_ALIGNMENT (type, basic-align)

[Macro]

If defined, a C expression to compute the alignment for a variable in the static store. type is the data type, and basic-align is the alignment that the object would ordinarily have. The value of this macro is used instead of that alignment to align the object.

If this macro is not defined, then basic-align is used.

One use of this macro is to increase alignment of medium-size data to make it all fit in fewer cache lines. Another is to cause character arrays to be word-aligned so that strcpy calls that copy constants to character arrays can be done inline.

CONSTANT_ALIGNMENT (constant, basic-align)

[Macro]

If defined, a C expression to compute the alignment given to a constant that is being placed in memory. constant is the constant and basic-align is the alignment that the object would ordinarily have. The value of this macro is used instead of that alignment to align the object.

If this macro is not defined, then basic-align is used.

The typical use of this macro is to increase alignment for string constants to be word aligned so that **strcpy** calls that copy constants can be done inline.

LOCAL_ALIGNMENT (type, basic-align)

[Macro]

If defined, a C expression to compute the alignment for a variable in the local store. type is the data type, and basic-align is the alignment that the object would ordinarily have. The value of this macro is used instead of that alignment to align the object.

If this macro is not defined, then basic-align is used.

One use of this macro is to increase alignment of medium-size data to make it all fit in fewer cache lines.

EMPTY_FIELD_BOUNDARY

[Macro]

Alignment in bits to be given to a structure bit-field that follows an empty field such as int : 0;.

If PCC_BITFIELD_TYPE_MATTERS is true, it overrides this macro.

STRUCTURE SIZE BOUNDARY

[Macro]

Number of bits which any structure or union's size must be a multiple of. Each structure or union's size is rounded up to a multiple of this.

If you do not define this macro, the default is the same as BITS_PER_UNIT.

STRICT ALIGNMENT

[Macro]

Define this macro to be the value 1 if instructions will fail to work if given data not on the nominal alignment. If instructions will merely go slower in that case, define this macro as 0.

PCC_BITFIELD_TYPE_MATTERS

[Macro]

Define this if you wish to imitate the way many other C compilers handle alignment of bit-fields and the structures that contain them.

The behavior is that the type written for a named bit-field (int, short, or other integer type) imposes an alignment for the entire structure, as if the structure really did contain an ordinary field of that type. In addition, the bit-field is placed within the structure so that it would fit within such a field, not crossing a boundary for it.

Thus, on most machines, a named bit-field whose type is written as **int** would not cross a four-byte boundary, and would force four-byte alignment for the whole structure. (The alignment used may not be four bytes; it is controlled by the other alignment parameters.)

An unnamed bit-field will not affect the alignment of the containing structure.

If the macro is defined, its definition should be a C expression; a nonzero value for the expression enables this behavior.

Note that if this macro is not defined, or its value is zero, some bit-fields may cross more than one alignment boundary. The compiler can support such references if there are 'insv', 'extv', and 'extzv' insns that can directly reference memory.

The other known way of making bit-fields work is to define STRUCTURE_SIZE_BOUNDARY as large as BIGGEST_ALIGNMENT. Then every structure can be accessed with fullwords.

Unless the machine has bit-field instructions or you define STRUCTURE_SIZE_BOUNDARY that way, you must define PCC_BITFIELD_TYPE_MATTERS to have a nonzero value.

If your aim is to make GCC use the same conventions for laying out bit-fields as are used by another compiler, here is how to investigate what the other compiler does. Compile and run this program:

```
struct foo1
  char x;
  char :0;
  char y;
};
struct foo2
{
  char x;
  int :0;
  char y;
}:
main ()
  printf ("Size of fool is %d\n",
          sizeof (struct foo1));
  printf ("Size of foo2 is %d\n",
          sizeof (struct foo2));
  exit (0);
```

If this prints 2 and 5, then the compiler's behavior is what you would get from PCC_BITFIELD_TYPE_MATTERS.

BITFIELD_NBYTES_LIMITED

[Macro]

Like PCC_BITFIELD_TYPE_MATTERS except that its effect is limited to aligning a bit-field within the structure.

bool TARGET_ALIGN_ANON_BITFIELDS (void)

[Target Hook]

When PCC_BITFIELD_TYPE_MATTERS is true this hook will determine whether unnamed bitfields affect the alignment of the containing structure. The hook should return true if the structure should inherit the alignment requirements of an unnamed bitfield's type.

MEMBER_TYPE_FORCES_BLK (field, mode)

[Macro]

Return 1 if a structure or array containing field should be accessed using BLKMODE.

If field is the only field in the structure, mode is its mode, otherwise mode is VOID-mode. mode is provided in the case where structures of one field would require the structure's mode to retain the field's mode.

Normally, this is not needed. See the file 'c4x.h' for an example of how to use this macro to prevent a structure having a floating point field from being accessed in an integer mode.

ROUND_TYPE_ALIGN (type, computed, specified)

[Macro]

Define this macro as an expression for the alignment of a type (given by type as a tree node) if the alignment computed in the usual way is computed and the alignment explicitly specified was specified.

The default is to use *specified* if it is larger; otherwise, use the smaller of *computed* and BIGGEST_ALIGNMENT

MAX_FIXED_MODE_SIZE

[Macro]

An integer expression for the size in bits of the largest integer machine mode that should actually be used. All integer machine modes of this size or smaller can be used for structures and unions with the appropriate sizes. If this macro is undefined, GET_MODE_BITSIZE (DImode) is assumed.

STACK_SAVEAREA_MODE (save_level)

Macro

If defined, an expression of type enum machine_mode that specifies the mode of the save area operand of a save_stack_level named pattern (see Section 12.9 [Standard Names], page 195). save_level is one of SAVE_BLOCK, SAVE_FUNCTION, or SAVE_NONLOCAL and selects which of the three named patterns is having its mode specified.

You need not define this macro if it always returns Pmode. You would most commonly define this macro if the save_stack_level patterns need to support both a 32- and a 64-bit mode.

STACK_SIZE_MODE

[Macro]

If defined, an expression of type enum machine_mode that specifies the mode of the size increment operand of an allocate_stack named pattern (see Section 12.9 [Standard Names], page 195).

You need not define this macro if it always returns word_mode. You would most commonly define this macro if the allocate_stack pattern needs to support both a 32- and a 64-bit mode.

TARGET_FLOAT_FORMAT

[Macro]

A code distinguishing the floating point format of the target machine. There are four defined values:

IEEE_FLOAT_FORMAT

This code indicates IEEE floating point. It is the default; there is no need to define TARGET_FLOAT_FORMAT when the format is IEEE.

VAX FLOAT FORMAT

This code indicates the "F float" (for float) and "D float" or "G float" formats (for double) used on the VAX and PDP-11.

IBM FLOAT FORMAT

This code indicates the format used on the IBM System/370.

C4X_FLOAT_FORMAT

This code indicates the format used on the TMS320C3x/C4x.

If your target uses a floating point format other than these, you must define a new name_FLOAT_FORMAT code for it, and add support for it to 'real.c'.

The ordering of the component words of floating point values stored in memory is controlled by FLOAT_WORDS_BIG_ENDIAN.

MODE_HAS_NANS (mode)

[Macro]

When defined, this macro should be true if *mode* has a NaN representation. The compiler assumes that NaNs are not equal to anything (including themselves) and that addition, subtraction, multiplication and division all return NaNs when one operand is NaN.

By default, this macro is true if *mode* is a floating-point mode and the target floating-point format is IEEE.

MODE_HAS_INFINITIES (mode)

[Macro]

This macro should be true if mode can represent infinity. At present, the compiler uses this macro to decide whether 'x - x' is always defined. By default, the macro is true when mode is a floating-point mode and the target format is IEEE.

MODE_HAS_SIGNED_ZEROS (mode)

[Macro]

True if *mode* distinguishes between positive and negative zero. The rules are expected to follow the IEEE standard:

- 'x + x' has the same sign as 'x'.
- If the sum of two values with opposite sign is zero, the result is positive for all rounding modes expect towards —infinity, for which it is negative.
- The sign of a product or quotient is negative when exactly one of the operands is negative.

The default definition is true if mode is a floating-point mode and the target format is IEEE.

MODE_HAS_SIGN_DEPENDENT_ROUNDING (mode)

[Macro]

If defined, this macro should be true for *mode* if it has at least one rounding mode in which 'x' and '-x' can be rounded to numbers of different magnitude. Two such modes are towards—infinity and towards +infinity.

The default definition of this macro is true if *mode* is a floating-point mode and the target format is IEEE.

ROUND_TOWARDS_ZERO

[Macro]

If defined, this macro should be true if the prevailing rounding mode is towards zero. A true value has the following effects:

- MODE_HAS_SIGN_DEPENDENT_ROUNDING will be false for all modes.
- 'libgcc.a''s floating-point emulator will round towards zero rather than towards nearest.
- The compiler's floating-point emulator will round towards zero after doing arithmetic, and when converting from the internal float format to the target format.

The macro does not affect the parsing of string literals. When the primary rounding mode is towards zero, library functions like strtod might still round towards nearest, and the compiler's parser should behave like the target's strtod where possible.

Not defining this macro is equivalent to returning zero.

LARGEST_EXPONENT_IS_NORMAL (size)

[Macro]

This macro should return true if floats with size bits do not have a NaN or infinity representation, but use the largest exponent for normal numbers instead.

Defining this macro to true for size causes MODE_HAS_NANS and MODE_HAS_INFINITIES to be false for size-bit modes. It also affects the way 'libgcc.a' and 'real.c' emulate floating-point arithmetic.

The default definition of this macro returns false for all sizes.

bool TARGET_VECTOR_OPAQUE_P (tree type)

[Target Hook]

This target hook should return **true** a vector is opaque. That is, if no cast is needed when copying a vector value of type *type* into another vector lvalue of the same size. Vector opaque types cannot be initialized. The default is that there are no such types.

bool TARGET_MS_BITFIELD_LAYOUT_P (tree record_type) [Target Hook]

This target hook returns **true** if bit-fields in the given $record_type$ are to be laid out following the rules of Microsoft Visual C/C++, namely: (i) a bit-field won't share the same storage unit with the previous bit-field if their underlying types have different sizes, and the bit-field will be aligned to the highest alignment of the underlying types of itself and of the previous bit-field; (ii) a zero-sized bit-field will affect the alignment of the whole enclosing structure, even if it is unnamed; except that (iii) a zero-sized bit-field will be disregarded unless it follows another bit-field of nonzero size. If this hook returns **true**, other macros that control bit-field layout are ignored.

When a bit-field is inserted into a packed record, the whole size of the underlying type is used by one or more same-size adjacent bit-fields (that is, if its long:3, 32 bits is used in the record, and any additional adjacent long bit-fields are packed into the same chunk of 32 bits. However, if the size changes, a new field of that size is allocated). In an unpacked record, this is the same as using alignment, but not equivalent when packing.

If both MS bit-fields and '__attribute__((packed))' are used, the latter will take precedence. If '__attribute__((packed))' is used on a single field when MS bit-fields are in use, it will take precedence for that field, but the alignment of the rest of the structure may affect its placement.

const char * TARGET_MANGLE_FUNDAMENTAL_TYPE (tree type) [Target Hook]

If your target defines any fundamental types, define this hook to return the appropriate encoding for these types as part of a C++ mangled name. The type argument is the tree structure representing the type to be mangled. The hook may be applied to trees which are not target-specific fundamental types; it should return NULL for all such types, as well as arguments it does not recognize. If the return value is not NULL, it must point to a statically-allocated string constant.

Target-specific fundamental types might be new fundamental types or qualified versions of ordinary fundamental types. Encode new fundamental types as 'u n name', where name is the name used for the type in source code, and n is the length of name in decimal. Encode qualified versions of ordinary types as 'U n name code', where name is the name used for the type qualifier in source code, n is the length of name as above, and code is the code used to represent the unqualified version of this type. (See write_builtin_type in 'cp/mangle.c' for the list of codes.) In both cases the spaces are for clarity; do not include any spaces in your string.

The default version of this hook always returns NULL, which is appropriate for a target that does not define any new fundamental types.

13.6 Layout of Source Language Data Types

These macros define the sizes and other characteristics of the standard basic data types used in programs being compiled. Unlike the macros in the previous section, these apply to specific features of C and related languages, rather than to fundamental aspects of storage layout.

INT_TYPE_SIZE [Macro]

A C expression for the size in bits of the type int on the target machine. If you don't define this, the default is one word.

SHORT_TYPE_SIZE [Macro]

A C expression for the size in bits of the type **short** on the target machine. If you don't define this, the default is half a word. (If this would be less than one storage unit, it is rounded up to one unit.)

LONG_TYPE_SIZE [Macro]

A C expression for the size in bits of the type long on the target machine. If you don't define this, the default is one word.

ADA_LONG_TYPE_SIZE [Macro

On some machines, the size used for the Ada equivalent of the type long by a native Ada compiler differs from that used by C. In that situation, define this macro to be a C expression to be used for the size of that type. If you don't define this, the default is the value of LONG_TYPE_SIZE.

LONG_LONG_TYPE_SIZE

[Macro]

A C expression for the size in bits of the type long long on the target machine. If you don't define this, the default is two words. If you want to support GNU Ada on your machine, the value of this macro must be at least 64.

CHAR_TYPE_SIZE [Macro]

A C expression for the size in bits of the type char on the target machine. If you don't define this, the default is BITS_PER_UNIT.

BOOL TYPE SIZE [Macro]

A C expression for the size in bits of the C++ type bool and C99 type _Bool on the target machine. If you don't define this, and you probably shouldn't, the default is CHAR TYPE SIZE.

FLOAT_TYPE_SIZE [Macro]

A C expression for the size in bits of the type float on the target machine. If you don't define this, the default is one word.

DOUBLE_TYPE_SIZE [Macro]

A C expression for the size in bits of the type double on the target machine. If you don't define this, the default is two words.

LONG_DOUBLE_TYPE_SIZE

[Macro]

A C expression for the size in bits of the type long double on the target machine. If you don't define this, the default is two words.

TARGET_FLT_EVAL_METHOD

[Macro]

A C expression for the value for FLT_EVAL_METHOD in 'float.h', assuming, if applicable, that the floating-point control word is in its default state. If you do not define this macro the value of FLT_EVAL_METHOD will be zero.

WIDEST_HARDWARE_FP_SIZE

[Macro]

A C expression for the size in bits of the widest floating-point format supported by the hardware. If you define this macro, you must specify a value less than or equal to the value of LONG_DOUBLE_TYPE_SIZE. If you do not define this macro, the value of LONG_DOUBLE_TYPE_SIZE is the default.

DEFAULT_SIGNED_CHAR

[Macro]

An expression whose value is 1 or 0, according to whether the type char should be signed or unsigned by default. The user can always override this default with the options '-fsigned-char' and '-funsigned-char'.

bool TARGET_DEFAULT_SHORT_ENUMS (void)

[Target Hook]

This target hook should return true if the compiler should give an enum type only as many bytes as it takes to represent the range of possible values of that type. It should return false if all enum types should be allocated like int.

The default is to return false.

SIZE_TYPE [Macro]

A C expression for a string describing the name of the data type to use for size values. The typedef name size_t is defined using the contents of the string.

The string can contain more than one keyword. If so, separate them with spaces, and write first any length keyword, then unsigned if appropriate, and finally int. The string must exactly match one of the data type names defined in the function init_decl_processing in the file 'c-decl.c'. You may not omit int or change the order—that would cause the compiler to crash on startup.

If you don't define this macro, the default is "long unsigned int".

PTRDIFF_TYPE [Macro]

A C expression for a string describing the name of the data type to use for the result of subtracting two pointers. The typedef name ptrdiff_t is defined using the contents of the string. See SIZE_TYPE above for more information.

If you don't define this macro, the default is "long int".

WCHAR_TYPE [Macro]

A C expression for a string describing the name of the data type to use for wide characters. The typedef name wchar_t is defined using the contents of the string. See SIZE_TYPE above for more information.

If you don't define this macro, the default is "int".

WCHAR_TYPE_SIZE [Macro]

A C expression for the size in bits of the data type for wide characters. This is used in cpp, which cannot make use of WCHAR_TYPE.

WINT_TYPE [Macro]

A C expression for a string describing the name of the data type to use for wide characters passed to printf and returned from getwc. The typedef name wint_t is defined using the contents of the string. See SIZE_TYPE above for more information.

If you don't define this macro, the default is "unsigned int".

INTMAX_TYPE [Macro]

A C expression for a string describing the name of the data type that can represent any value of any standard or extended signed integer type. The typedef name intmax_t is defined using the contents of the string. See SIZE_TYPE above for more information.

If you don't define this macro, the default is the first of "int", "long int", or "long long int" that has as much precision as long long int.

UINTMAX TYPE [Macro]

A C expression for a string describing the name of the data type that can represent any value of any standard or extended unsigned integer type. The typedef name uintmax_t is defined using the contents of the string. See SIZE_TYPE above for more information.

If you don't define this macro, the default is the first of "unsigned int", "long unsigned int", or "long long unsigned int" that has as much precision as long long unsigned int.

TARGET_PTRMEMFUNC_VBIT_LOCATION

[Macro]

The C++ compiler represents a pointer-to-member-function with a struct that looks like:

```
struct {
  union {
    void (*fn)();
    ptrdiff_t vtable_index;
  };
  ptrdiff_t delta;
};
```

The C++ compiler must use one bit to indicate whether the function that will be called through a pointer-to-member-function is virtual. Normally, we assume that the low-order bit of a function pointer must always be zero. Then, by ensuring that the vtable_index is odd, we can distinguish which variant of the union is in use. But, on some platforms function pointers can be odd, and so this doesn't work. In that case, we use the low-order bit of the delta field, and shift the remainder of the delta field to the left.

GCC will automatically make the right selection about where to store this bit using the FUNCTION_BOUNDARY setting for your platform. However, some platforms such as ARM/Thumb have FUNCTION_BOUNDARY set such that functions always start at even addresses, but the lowest bit of pointers to functions indicate whether the function at that address is in ARM or Thumb mode. If this is the case of your architecture, you should define this macro to ptrmemfunc_vbit_in_delta.

In general, you should not have to define this macro. On architectures in which function addresses are always even, according to FUNCTION_BOUNDARY, GCC will automatically define this macro to ptrmemfunc_vbit_in_pfn.

TARGET_VTABLE_USES_DESCRIPTORS

[Macro]

Normally, the C++ compiler uses function pointers in vtables. This macro allows the target to change to use "function descriptors" instead. Function descriptors are found on targets for whom a function pointer is actually a small data structure. Normally the data structure consists of the actual code address plus a data pointer to which the function's data is relative.

If vtables are used, the value of this macro should be the number of words that the function descriptor occupies.

TARGET_VTABLE_ENTRY_ALIGN

[Macro]

By default, the vtable entries are void pointers, the so the alignment is the same as pointer alignment. The value of this macro specifies the alignment of the vtable entry in bits. It should be defined only when special alignment is necessary. */

TARGET VTABLE DATA ENTRY DISTANCE

[Macro]

There are a few non-descriptor entries in the vtable at offsets below zero. If these entries must be padded (say, to preserve the alignment specified by TARGET_VTABLE_ENTRY_ALIGN), set this to the number of words in each data entry.

13.7 Target Character Escape Sequences

By default, GCC assumes that the C character escape sequences and other characters take on their ASCII values for the target. If this is not correct, you must explicitly define all of the macros below. All of them must evaluate to constants; they are used in case statements.

Macro	$_{\rm Escape}$	ASCII character
TARGET_BELL	\a	07, BEL
TARGET_BS	\ <i>b</i>	08, BS
TARGET_CR	\r	OD, CR
TARGET_DIGITO	0	30, ZERO
TARGET_ESC	\ <i>e</i> , \ <i>E</i>	1B, ESC
TARGET_FF	$\setminus f$	OC, FF
TARGET_NEWLINE	$\setminus n$	OA, LF
TARGET_TAB	\ t	09, HT
TARGET_VT	\ v	OB, VT

Note that the \e and \E escapes are GNU extensions, not part of the C standard.

13.8 Register Usage

This section explains how to describe what registers the target machine has, and how (in general) they can be used.

The description of which registers a specific instruction can use is done with register classes; see Section 13.9 [Register Classes], page 277. For information on using registers to access a stack frame, see Section 13.10.4 [Frame Registers], page 292. For passing values in registers, see Section 13.10.7 [Register Arguments], page 297. For returning values in registers, see Section 13.10.8 [Scalar Return], page 302.

13.8.1 Basic Characteristics of Registers

Registers have various characteristics.

FIRST PSEUDO REGISTER

[Macro]

Number of hardware registers known to the compiler. They receive numbers 0 through FIRST_PSEUDO_REGISTER-1; thus, the first pseudo register's number really is assigned the number FIRST_PSEUDO_REGISTER.

FIXED REGISTERS [Macro]

An initializer that says which registers are used for fixed purposes all throughout the compiled code and are therefore not available for general allocation. These would include the stack pointer, the frame pointer (except on machines where that can be used as a general register when no frame pointer is needed), the program counter on machines where that is considered one of the addressable registers, and any other numbered register with a standard use.

This information is expressed as a sequence of numbers, separated by commas and surrounded by braces. The nth number is 1 if register n is fixed, 0 otherwise.

The table initialized from this macro, and the table initialized by the following one, may be overridden at run time either automatically, by the actions of the macro CONDITIONAL_REGISTER_USAGE, or by the user with the command options '-ffixed-reg', '-fcall-used-reg' and '-fcall-saved-reg'.

CALL_USED_REGISTERS

[Macro]

Like FIXED_REGISTERS but has 1 for each register that is clobbered (in general) by function calls as well as for fixed registers. This macro therefore identifies the registers that are not available for general allocation of values that must live across function calls.

If a register has 0 in CALL_USED_REGISTERS, the compiler automatically saves it on function entry and restores it on function exit, if the register is used within the function.

CALL_REALLY_USED_REGISTERS

[Macro]

Like CALL_USED_REGISTERS except this macro doesn't require that the entire set of FIXED_REGISTERS be included. (CALL_USED_REGISTERS must be a superset of FIXED_REGISTERS). This macro is optional. If not specified, it defaults to the value of CALL_USED_REGISTERS.

HARD_REGNO_CALL_PART_CLOBBERED (regno, mode)

[Macro]

A C expression that is nonzero if it is not permissible to store a value of mode mode in hard register number regno across a call without some part of it being clobbered. For most machines this macro need not be defined. It is only required for machines that do not preserve the entire contents of a register across a call.

CONDITIONAL_REGISTER_USAGE

[Macro]

Zero or more C statements that may conditionally modify five variables fixed_regs, call_used_regs, global_regs, reg_names, and reg_class_contents, to take into account any dependence of these register sets on target flags. The first three of these are of type char [] (interpreted as Boolean vectors). global_regs is a const char *[], and reg_class_contents is a HARD_REG_SET. Before the macro is called, fixed_regs, call_used_regs, reg_class_contents, and reg_names have been initialized from FIXED_REGISTERS, CALL_USED_REGISTERS, REG_CLASS_CONTENTS, and REGISTER_NAMES, respectively. global_regs has been cleared, and any '-ffixed-reg', '-fcall-used-reg' and '-fcall-saved-reg' command options have been applied.

You need not define this macro if it has no work to do.

If the usage of an entire class of registers depends on the target flags, you may indicate this to GCC by using this macro to modify fixed_regs and call_used_regs to 1 for each of the registers in the classes which should not be used by GCC. Also define the macro REG_CLASS_FROM_LETTER / REG_CLASS_FROM_CONSTRAINT to return NO_REGS if it is called with a letter for a class that shouldn't be used.

(However, if this class is not included in GENERAL_REGS and all of the insn patterns whose constraints permit this class are controlled by target switches, then GCC will automatically avoid using these registers when the target switches are opposed to them.)

INCOMING REGNO (out)

Macro

Define this macro if the target machine has register windows. This C expression returns the register number as seen by the called function corresponding to the register number out as seen by the calling function. Return out if register number out is not an outbound register.

OUTGOING_REGNO (in)

[Macro]

Define this macro if the target machine has register windows. This C expression returns the register number as seen by the calling function corresponding to the register number in as seen by the called function. Return in if register number in is not an inbound register.

LOCAL_REGNO (regno)

[Macro]

Define this macro if the target machine has register windows. This C expression returns true if the register is call-saved but is in the register window. Unlike most call-saved registers, such registers need not be explicitly restored on function exit or during non-local gotos.

PC_REGNUM [Macro]

If the program counter has a register number, define this as that register number. Otherwise, do not define it.

13.8.2 Order of Allocation of Registers

Registers are allocated in order.

REG_ALLOC_ORDER

[Macro]

If defined, an initializer for a vector of integers, containing the numbers of hard registers in the order in which GCC should prefer to use them (from most preferred to least).

If this macro is not defined, registers are used lowest numbered first (all else being equal).

One use of this macro is on machines where the highest numbered registers must always be saved and the save-multiple-registers instruction supports only sequences of consecutive registers. On such machines, define REG_ALLOC_ORDER to be an initializer that lists the highest numbered allocable register first.

ORDER REGS FOR LOCAL ALLOC

[Macro]

A C statement (sans semicolon) to choose the order in which to allocate hard registers for pseudo-registers local to a basic block.

Store the desired register order in the array reg_alloc_order. Element 0 should be the register to allocate first; element 1, the next register; and so on.

The macro body should not assume anything about the contents of reg_alloc_order before execution of the macro.

On most machines, it is not necessary to define this macro.

13.8.3 How Values Fit in Registers

This section discusses the macros that describe which kinds of values (specifically, which machine modes) each register can hold, and how many consecutive registers are needed for a given mode.

HARD_REGNO_NREGS (regno, mode)

[Macro]

A C expression for the number of consecutive hard registers, starting at register number regno, required to hold a value of mode mode.

On a machine where all registers are exactly one word, a suitable definition of this macro is

```
#define HARD_REGNO_NREGS(REGNO, MODE)
    ((GET_MODE_SIZE (MODE) + UNITS_PER_WORD - 1) \
     / UNITS_PER_WORD)
```

REGMODE_NATURAL_SIZE (mode)

[Macro]

Define this macro if the natural size of registers that hold values of mode mode is not the word size. It is a C expression that should give the natural size in bytes for the specified mode. It is used by the register allocator to try to optimize its results. This happens for example on SPARC 64-bit where the natural size of floating-point registers is still 32-bit.

HARD_REGNO_MODE_OK (regno, mode)

Macro

A C expression that is nonzero if it is permissible to store a value of mode mode in hard register number regno (or in several registers starting with that one). For a machine where all registers are equivalent, a suitable definition is

```
#define HARD_REGNO_MODE_OK(REGNO, MODE) 1
```

You need not include code to check for the numbers of fixed registers, because the allocation mechanism considers them to be always occupied.

On some machines, double-precision values must be kept in even/odd register pairs. You can implement that by defining this macro to reject odd register numbers for such modes.

The minimum requirement for a mode to be OK in a register is that the 'movmode' instruction pattern support moves between the register and other hard register in the same class and that moving a value into the register and back out not alter it.

Since the same instruction used to move word_mode will work for all narrower integer modes, it is not necessary on any machine for HARD_REGNO_MODE_OK to distinguish between these modes, provided you define patterns 'movhi', etc., to take advantage of this. This is useful because of the interaction between HARD_REGNO_MODE_OK and MODES_TIEABLE_P; it is very desirable for all integer modes to be tieable.

Many machines have special registers for floating point arithmetic. Often people assume that floating point machine modes are allowed only in floating point registers. This is not true. Any registers that can hold integers can safely hold a floating point machine mode, whether or not floating arithmetic can be done on it in those registers. Integer move instructions can be used to move the values.

On some machines, though, the converse is true: fixed-point machine modes may not go in floating registers. This is true if the floating registers normalize any value stored in them, because storing a non-floating value there would garble it. In this case, HARD_REGNO_MODE_OK should reject fixed-point machine modes in floating registers. But if the floating registers do not automatically normalize, if you can store any bit pattern in one and retrieve it unchanged without a trap, then any machine mode may go in a floating register, so you can define this macro to say so.

The primary significance of special floating registers is rather that they are the registers acceptable in floating point arithmetic instructions. However, this is of no concern to HARD_REGNO_MODE_OK. You handle it by writing the proper constraints for those instructions.

On some machines, the floating registers are especially slow to access, so that it is better to store a value in a stack frame than in such a register if floating point arithmetic is not being done. As long as the floating registers are not in class GENERAL_REGS, they will not be used unless some pattern's constraint asks for one.

HARD_REGNO_RENAME_OK (from, to)

[Macro]

A C expression that is nonzero if it is OK to rename a hard register from to another hard register to.

One common use of this macro is to prevent renaming of a register to another register that is not saved by a prologue in an interrupt handler.

The default is always nonzero.

MODES_TIEABLE_P (mode1, mode2)

[Macro]

A C expression that is nonzero if a value of mode mode1 is accessible in mode mode2 without copying.

If HARD_REGNO_MODE_OK (r, mode1) and HARD_REGNO_MODE_OK (r, mode2) are always the same for any r, then MODES_TIEABLE_P (mode1, mode2) should be nonzero. If they differ for any r, you should define this macro to return zero unless some other mechanism ensures the accessibility of the value in a narrower mode.

You should define this macro to return nonzero in as many cases as possible since doing so will allow GCC to perform better register allocation.

AVOID_CCMODE_COPIES

[Macro]

Define this macro if the compiler should avoid copies to/from CCmode registers. You should only define this macro if support for copying to/from CCmode is incomplete.

13.8.4 Handling Leaf Functions

On some machines, a leaf function (i.e., one which makes no calls) can run more efficiently if it does not make its own register window. Often this means it is required to receive its arguments in the registers where they are passed by the caller, instead of the registers where they would normally arrive.

The special treatment for leaf functions generally applies only when other conditions are met; for example, often they may use only those registers for its own variables and temporaries. We use the term "leaf function" to mean a function that is suitable for this special handling, so that functions with no calls are not necessarily "leaf functions".

GCC assigns register numbers before it knows whether the function is suitable for leaf function treatment. So it needs to renumber the registers in order to output a leaf function. The following macros accomplish this.

LEAF_REGISTERS [Macro]

Name of a char vector, indexed by hard register number, which contains 1 for a register that is allowable in a candidate for leaf function treatment.

If leaf function treatment involves renumbering the registers, then the registers marked here should be the ones before renumbering—those that GCC would ordinarily allocate. The registers which will actually be used in the assembler code, after renumbering, should not be marked with 1 in this vector.

Define this macro only if the target machine offers a way to optimize the treatment of leaf functions.

LEAF_REG_REMAP (regno)

[Macro]

A C expression whose value is the register number to which regno should be renumbered, when a function is treated as a leaf function.

If regno is a register number which should not appear in a leaf function before renumbering, then the expression should yield -1, which will cause the compiler to abort.

Define this macro only if the target machine offers a way to optimize the treatment of leaf functions, and registers need to be renumbered to do this.

TARGET_ASM_FUNCTION_PROLOGUE and TARGET_ASM_FUNCTION_EPILOGUE must usually treat leaf functions specially. They can test the C variable current_function_is_leaf which is nonzero for leaf functions. current_function_is_leaf is set prior to local register allocation and is valid for the remaining compiler passes. They can also test the C variable current_function_uses_only_leaf_regs which is nonzero for leaf functions which only use leaf registers. current_function_uses_only_leaf_regs is valid after all passes that modify the instructions have been run and is only useful if LEAF_REGISTERS is defined.

13.8.5 Registers That Form a Stack

There are special features to handle computers where some of the "registers" form a stack. Stack registers are normally written by pushing onto the stack, and are numbered relative to the top of the stack.

Currently, GCC can only handle one group of stack-like registers, and they must be consecutively numbered. Furthermore, the existing support for stack-like registers is specific to the 80387 floating point coprocessor. If you have a new architecture that uses stack-like registers, you will need to do substantial work on 'reg-stack.c' and write your machine description to cooperate with it, as well as defining these macros.

STACK_REGS [Macro]

Define this if the machine has any stack-like registers.

FIRST_STACK_REG [Macro]

The number of the first stack-like register. This one is the top of the stack.

LAST_STACK_REG [Macro]

The number of the last stack-like register. This one is the bottom of the stack.

13.9 Register Classes

On many machines, the numbered registers are not all equivalent. For example, certain registers may not be allowed for indexed addressing; certain registers may not be allowed in some instructions. These machine restrictions are described to the compiler using register classes.

You define a number of register classes, giving each one a name and saying which of the registers belong to it. Then you can specify register classes that are allowed as operands to particular instruction patterns.

In general, each register will belong to several classes. In fact, one class must be named ALL_REGS and contain all the registers. Another class must be named NO_REGS and contain no registers. Often the union of two classes will be another class; however, this is not required.

One of the classes must be named GENERAL_REGS. There is nothing terribly special about the name, but the operand constraint letters 'r' and 'g' specify this class. If GENERAL_REGS is the same as ALL_REGS, just define it as a macro which expands to ALL_REGS.

Order the classes so that if class x is contained in class y then x has a lower class number than y.

The way classes other than GENERAL_REGS are specified in operand constraints is through machine-dependent operand constraint letters. You can define such letters to correspond to various classes, then use them in operand constraints.

You should define a class for the union of two classes whenever some instruction allows both classes. For example, if an instruction allows either a floating point (coprocessor) register or a general register for a certain operand, you should define a class FLOAT_OR_GENERAL_REGS which includes both of them. Otherwise you will get suboptimal code.

You must also specify certain redundant information about the register classes: for each class, which classes contain it and which ones are contained in it; for each pair of classes, the largest class contained in their union.

When a value occupying several consecutive registers is expected in a certain class, all the registers used must belong to that class. Therefore, register classes cannot be used to enforce a requirement for a register pair to start with an even-numbered register. The way to specify this requirement is with HARD_REGNO_MODE_OK.

Register classes used for input-operands of bitwise-and or shift instructions have a special requirement: each such class must have, for each fixed-point machine mode, a subclass whose registers can transfer that mode to or from memory. For example, on some machines, the operations for single-byte values (QImode) are limited to certain registers. When this is so, each register class that is used in a bitwise-and or shift instruction must have a subclass consisting of registers from which single-byte values can be loaded or stored. This is so that PREFERRED_RELOAD_CLASS can always have a possible value to return.

enum reg_class [Data type]

An enumerated type that must be defined with all the register class names as enumerated values. NO_REGS must be first. ALL_REGS must be the last register class, followed by one more enumerated value, LIM_REG_CLASSES, which is not a register class but rather tells how many classes there are.

Each register class has a number, which is the value of casting the class name to type int. The number serves as an index in many of the tables described below.

N_REG_CLASSES [Macro]

The number of distinct register classes, defined as follows:

#define N_REG_CLASSES (int) LIM_REG_CLASSES

REG_CLASS_NAMES [Macro]

An initializer containing the names of the register classes as C string constants. These names are used in writing some of the debugging dumps.

REG_CLASS_CONTENTS

[Macro]

An initializer containing the contents of the register classes, as integers which are bit masks. The *n*th integer specifies the contents of class n. The way the integer mask is interpreted is that register r is in the class if mask & (1 << r) is 1.

When the machine has more than 32 registers, an integer does not suffice. Then the integers are replaced by sub-initializers, braced groupings containing several integers. Each sub-initializer must be suitable as an initializer for the type HARD_REG_SET which is defined in 'hard-reg-set.h'. In this situation, the first integer in each sub-initializer corresponds to registers 0 through 31, the second integer to registers 32 through 63, and so on.

REGNO_REG_CLASS (regno)

[Macro]

A C expression whose value is a register class containing hard register regno. In general there is more than one such class; choose a class which is minimal, meaning that no smaller class also contains the register.

BASE_REG_CLASS [Macro]

A macro whose definition is the name of the class to which a valid base register must belong. A base register is one used in an address which is the register value plus a displacement.

MODE_BASE_REG_CLASS (mode)

[Macro]

This is a variation of the BASE_REG_CLASS macro which allows the selection of a base register in a mode dependent manner. If mode is VOIDmode then it should return the same value as BASE_REG_CLASS.

MODE_BASE_REG_REG_CLASS (mode)

[Macro]

A C expression whose value is the register class to which a valid base register must belong in order to be used in a base plus index register address. You should define this macro if base plus index addresses have different requirements than other base register uses.

INDEX REG CLASS [Macro]

A macro whose definition is the name of the class to which a valid index register must belong. An index register is one used in an address where its value is either multiplied by a scale factor or added to another register (as well as added to a displacement).

CONSTRAINT_LEN (char, str)

[Macro]

For the constraint at the start of str, which starts with the letter c, return the length. This allows you to have register class / constant / extra constraints that are longer than a single letter; you don't need to define this macro if you can do with single-letter constraints only. The definition of this macro should use DE-FAULT_CONSTRAINT_LEN for all the characters that you don't want to handle specially. There are some sanity checks in genoutput.c that check the constraint lengths for the md file, so you can also use this macro to help you while you are transitioning from a byzantine single-letter-constraint scheme: when you return a negative length for a constraint you want to re-use, genoutput will complain about every instance where it is used in the md file.

REG_CLASS_FROM_LETTER (char)

[Macro]

A C expression which defines the machine-dependent operand constraint letters for register classes. If *char* is such a letter, the value should be the register class corresponding to it. Otherwise, the value should be NO_REGS. The register letter 'r', corresponding to class GENERAL_REGS, will not be passed to this macro; you do not need to handle it.

REG_CLASS_FROM_CONSTRAINT (char, str)

[Macro]

Like REG_CLASS_FROM_LETTER, but you also get the constraint string passed in str, so that you can use suffixes to distinguish between different variants.

REGNO_OK_FOR_BASE_P (num)

[Macro]

A C expression which is nonzero if register number *num* is suitable for use as a base register in operand addresses. It may be either a suitable hard register or a pseudo register that has been allocated such a hard register.

REGNO_MODE_OK_FOR_BASE_P (num, mode)

[Macro]

A C expression that is just like REGNO_OK_FOR_BASE_P, except that that expression may examine the mode of the memory reference in *mode*. You should define this macro if the mode of the memory reference affects whether a register may be used as a base register. If you define this macro, the compiler will use it instead of REGNO_OK_FOR_BASE_P.

REGNO_MODE_OK_FOR_REG_BASE_P (num, mode)

[Macro

A C expression which is nonzero if register number *num* is suitable for use as a base register in base plus index operand addresses, accessing memory in mode *mode*. It may be either a suitable hard register or a pseudo register that has been allocated such a hard register. You should define this macro if base plus index addresses have different requirements than other base register uses.

REGNO_OK_FOR_INDEX_P (num)

[Macro]

A C expression which is nonzero if register number *num* is suitable for use as an index register in operand addresses. It may be either a suitable hard register or a pseudo register that has been allocated such a hard register.

The difference between an index register and a base register is that the index register may be scaled. If an address involves the sum of two registers, neither one of them scaled, then either one may be labeled the "base" and the other the "index"; but whichever labeling is used must fit the machine's constraints of which registers may serve in each capacity. The compiler will try both labelings, looking for one that is valid, and will reload one or both registers only if neither labeling works.

PREFERRED_RELOAD_CLASS (x, class)

Macro

A C expression that places additional restrictions on the register class to use when it is necessary to copy value x into a register in class class. The value is a register class; perhaps class, or perhaps another, smaller class. On many machines, the following definition is safe:

#define PREFERRED_RELOAD_CLASS(X,CLASS) CLASS

Sometimes returning a more restrictive class makes better code. For example, on the 68000, when x is an integer constant that is in range for a 'moveq' instruction, the

value of this macro is always DATA_REGS as long as class includes the data registers. Requiring a data register guarantees that a 'moveq' will be used.

One case where PREFERRED_RELOAD_CLASS must not return class is if x is a legitimate constant which cannot be loaded into some register class. By returning NO_REGS you can force x into a memory location. For example, rs6000 can load immediate values into general-purpose registers, but does not have an instruction for loading an immediate value into a floating-point register, so PREFERRED_RELOAD_CLASS returns NO_REGS when x is a floating-point constant. If the constant can't be loaded into any kind of register, code generation will be better if LEGITIMATE_CONSTANT_P makes the constant illegitimate instead of using PREFERRED_RELOAD_CLASS.

PREFERRED_OUTPUT_RELOAD_CLASS (x, class)

[Macro]

Like PREFERRED_RELOAD_CLASS, but for output reloads instead of input reloads. If you don't define this macro, the default is to use class, unchanged.

LIMIT_RELOAD_CLASS (mode, class)

[Macro]

A C expression that places additional restrictions on the register class to use when it is necessary to be able to hold a value of mode mode in a reload register for which class class would ordinarily be used.

Unlike PREFERRED_RELOAD_CLASS, this macro should be used when there are certain modes that simply can't go in certain reload classes.

The value is a register class; perhaps class, or perhaps another, smaller class.

Don't define this macro unless the target machine has limitations which require the macro to do something nontrivial.

```
SECONDARY_RELOAD_CLASS (class, mode, x) [Macro]
SECONDARY_INPUT_RELOAD_CLASS (class, mode, x) [Macro]
SECONDARY_OUTPUT_RELOAD_CLASS (class, mode, x) [Macro]
```

Many machines have some registers that cannot be copied directly to or from memory or even from other types of registers. An example is the 'MQ' register, which on most machines, can only be copied to or from general registers, but not memory. Some machines allow copying all registers to and from memory, but require a scratch register for stores to some memory locations (e.g., those with symbolic address on the RT, and those with certain symbolic address on the SPARC when compiling PIC). In some cases, both an intermediate and a scratch register are required.

You should define these macros to indicate to the reload phase that it may need to allocate at least one register for a reload in addition to the register to contain the data. Specifically, if copying x to a register class in mode requires an intermediate register, you should define SECONDARY_INPUT_RELOAD_CLASS to return the largest register class all of whose registers can be used as intermediate registers or scratch registers.

If copying a register class in mode to x requires an intermediate or scratch register, SECONDARY_OUTPUT_RELOAD_CLASS should be defined to return the largest register class required. If the requirements for input and output reloads are the same, the macro SECONDARY_RELOAD_CLASS should be used instead of defining both macros identically.

The values returned by these macros are often GENERAL_REGS. Return NO_REGS if no spare register is needed; i.e., if x can be directly copied to or from a register of class in mode without requiring a scratch register. Do not define this macro if it would always return NO_REGS.

If a scratch register is required (either with or without an intermediate register), you should define patterns for 'reload_inm' or 'reload_outm', as required (see Section 12.9 [Standard Names], page 195. These patterns, which will normally be implemented with a define_expand, should be similar to the 'movm' patterns, except that operand 2 is the scratch register.

Define constraints for the reload register and scratch register that contain a single register class. If the original reload register (whose class is *class*) can meet the constraint given in the pattern, the value returned by these macros is used for the class of the scratch register. Otherwise, two additional reload registers are required. Their classes are obtained from the constraints in the insn pattern.

x might be a pseudo-register or a subreg of a pseudo-register, which could either be in a hard register or in memory. Use true_regnum to find out; it will return -1 if the pseudo is in memory and the hard register number if it is in a register.

These macros should not be used in the case where a particular class of registers can only be copied to memory and not to another class of registers. In that case, secondary reload registers are not needed and would not be helpful. Instead, a stack location must be used to perform the copy and the movm pattern should use memory as an intermediate storage. This case often occurs between floating-point and general registers.

SECONDARY_MEMORY_NEEDED (class1, class2, m)

[Macro]

Certain machines have the property that some registers cannot be copied to some other registers without using memory. Define this macro on those machines to be a C expression that is nonzero if objects of mode m in registers of class 1 can only be copied to registers of class class 2 by storing a register of class 1 into memory and loading that memory location into a register of class 2.

Do not define this macro if its value would always be zero.

SECONDARY_MEMORY_NEEDED_RTX (mode)

[Macro]

Normally when SECONDARY_MEMORY_NEEDED is defined, the compiler allocates a stack slot for a memory location needed for register copies. If this macro is defined, the compiler instead uses the memory location defined by this macro.

Do not define this macro if you do not define SECONDARY_MEMORY_NEEDED.

SECONDARY_MEMORY_NEEDED_MODE (mode)

[Macro]

When the compiler needs a secondary memory location to copy between two registers of mode mode, it normally allocates sufficient memory to hold a quantity of BITS_PER_WORD bits and performs the store and load operations in a mode that many bits wide and whose class is the same as that of mode.

This is right thing to do on most machines because it ensures that all bits of the register are copied and prevents accesses to the registers in a narrower mode, which some machines prohibit for floating-point registers.

However, this default behavior is not correct on some machines, such as the DEC Alpha, that store short integers in floating-point registers differently than in integer registers. On those machines, the default widening will not work correctly and you must define this macro to suppress that widening in some cases. See the file 'alpha.h' for details.

Do not define this macro if you do not define SECONDARY_MEMORY_NEEDED or if widening mode to a mode that is BITS_PER_WORD bits wide is correct for your machine.

SMALL_REGISTER_CLASSES

Macrol

On some machines, it is risky to let hard registers live across arbitrary insns. Typically, these machines have instructions that require values to be in specific registers (like an accumulator), and reload will fail if the required hard register is used for another purpose across such an insn.

Define SMALL_REGISTER_CLASSES to be an expression with a nonzero value on these machines. When this macro has a nonzero value, the compiler will try to minimize the lifetime of hard registers.

It is always safe to define this macro with a nonzero value, but if you unnecessarily define it, you will reduce the amount of optimizations that can be performed in some cases. If you do not define this macro with a nonzero value when it is required, the compiler will run out of spill registers and print a fatal error message. For most machines, you should not define this macro at all.

CLASS_LIKELY_SPILLED_P (class)

[Macro]

A C expression whose value is nonzero if pseudos that have been assigned to registers of class class would likely be spilled because registers of class are needed for spill registers.

The default value of this macro returns 1 if class has exactly one register and zero otherwise. On most machines, this default should be used. Only define this macro to some other expression if pseudos allocated by 'local-alloc.c' end up in memory because their hard registers were needed for spill registers. If this macro returns nonzero for those classes, those pseudos will only be allocated by 'global.c', which knows how to reallocate the pseudo to another register. If there would not be another register available for reallocation, you should not change the definition of this macro since the only effect of such a definition would be to slow down register allocation.

CLASS_MAX_NREGS (class, mode)

Macro

A C expression for the maximum number of consecutive registers of class class needed to hold a value of mode mode.

This is closely related to the macro HARD_REGNO_NREGS. In fact, the value of the macro CLASS_MAX_NREGS (class, mode) should be the maximum value of HARD_REGNO_NREGS (regno, mode) for all regno values in the class class.

This macro helps control the handling of multiple-word values in the reload pass.

CANNOT_CHANGE_MODE_CLASS (from, to, class)

[Macro]

If defined, a C expression that returns nonzero for a *class* for which a change from mode *from* to mode *to* is invalid.

For the example, loading 32-bit integer or floating-point objects into floating-point registers on the Alpha extends them to 64 bits. Therefore loading a 64-bit object and then storing it as a 32-bit object does not store the low-order 32 bits, as would be the case for a normal register. Therefore, 'alpha.h' defines CANNOT_CHANGE_MODE_CLASS as below:

```
#define CANNOT_CHANGE_MODE_CLASS(FROM, TO, CLASS) \
  (GET_MODE_SIZE (FROM) != GET_MODE_SIZE (TO) \
  ? reg_classes_intersect_p (FLOAT_REGS, (CLASS)) : 0)
```

Three other special macros describe which operands fit which constraint letters.

CONST_OK_FOR_LETTER_P (value, c)

[Macro]

A C expression that defines the machine-dependent operand constraint letters ('I', 'J', 'K', ... 'P') that specify particular ranges of integer values. If c is one of those letters, the expression should check that value, an integer, is in the appropriate range and return 1 if so, 0 otherwise. If c is not one of those letters, the value should be 0 regardless of value.

CONST_OK_FOR_CONSTRAINT_P (value, c, str)

[Macro]

Like CONST_OK_FOR_LETTER_P, but you also get the constraint string passed in str, so that you can use suffixes to distinguish between different variants.

CONST_DOUBLE_OK_FOR_LETTER_P (value, c)

[Macro]

A C expression that defines the machine-dependent operand constraint letters that specify particular ranges of const_double values ('G' or 'H').

If c is one of those letters, the expression should check that value, an RTX of code $const_double$, is in the appropriate range and return 1 if so, 0 otherwise. If c is not one of those letters, the value should be 0 regardless of value.

const_double is used for all floating-point constants and for DImode fixed-point constants. A given letter can accept either or both kinds of values. It can use GET_MODE to distinguish between these kinds.

CONST_DOUBLE_OK_FOR_CONSTRAINT_P (value, c, str)

[Macro]

Like CONST_DOUBLE_OK_FOR_LETTER_P, but you also get the constraint string passed in str, so that you can use suffixes to distinguish between different variants.

EXTRA CONSTRAINT (value, c)

[Macro]

A C expression that defines the optional machine-dependent constraint letters that can be used to segregate specific types of operands, usually memory references, for the target machine. Any letter that is not elsewhere defined and not matched by REG_CLASS_FROM_LETTER / REG_CLASS_FROM_CONSTRAINT may be used. Normally this macro will not be defined.

If it is required for a particular target machine, it should return 1 if value corresponds to the operand type represented by the constraint letter c. If c is not defined as an extra constraint, the value returned should be 0 regardless of value.

For example, on the ROMP, load instructions cannot have their output in r0 if the memory reference contains a symbolic address. Constraint letter 'Q' is defined as representing a memory address that does *not* contain a symbolic address. An alternative is specified with a 'Q' constraint on the input and 'r' on the output. The next

alternative specifies 'm' on the input and a register class that does not include r0 on the output.

EXTRA_CONSTRAINT_STR (value, c, str)

[Macro]

Like EXTRA_CONSTRAINT, but you also get the constraint string passed in str, so that you can use suffixes to distinguish between different variants.

$EXTRA_MEMORY_CONSTRAINT$ (c, str)

[Macro]

A C expression that defines the optional machine-dependent constraint letters, amongst those accepted by EXTRA_CONSTRAINT, that should be treated like memory constraints by the reload pass.

It should return 1 if the operand type represented by the constraint at the start of str, the first letter of which is the letter c, comprises a subset of all memory references including all those whose address is simply a base register. This allows the reload pass to reload an operand, if it does not directly correspond to the operand type of c, by copying its address into a base register.

For example, on the S/390, some instructions do not accept arbitrary memory references, but only those that do not make use of an index register. The constraint letter 'Q' is defined via EXTRA_CONSTRAINT as representing a memory address of this type. If the letter 'Q' is marked as EXTRA_MEMORY_CONSTRAINT, a 'Q' constraint can handle any memory operand, because the reload pass knows it can be reloaded by copying the memory address into a base register if required. This is analogous to the way a 'o' constraint can handle any memory operand.

EXTRA_ADDRESS_CONSTRAINT (c, str)

[Macro]

A C expression that defines the optional machine-dependent constraint letters, amongst those accepted by EXTRA_CONSTRAINT / EXTRA_CONSTRAINT_STR, that should be treated like address constraints by the reload pass.

It should return 1 if the operand type represented by the constraint at the start of str, which starts with the letter c, comprises a subset of all memory addresses including all those that consist of just a base register. This allows the reload pass to reload an operand, if it does not directly correspond to the operand type of str, by copying it into a base register.

Any constraint marked as EXTRA_ADDRESS_CONSTRAINT can only be used with the address_operand predicate. It is treated analogously to the 'p' constraint.

13.10 Stack Layout and Calling Conventions

This describes the stack layout and calling conventions.

13.10.1 Basic Stack Layout

Here is the basic stack layout.

STACK GROWS DOWNWARD

[Macro]

Define this macro if pushing a word onto the stack moves the stack pointer to a smaller address.

When we say, "define this macro if . . . ", it means that the compiler checks this macro only with #ifdef so the precise definition used does not matter.

STACK_PUSH_CODE [Macro]

This macro defines the operation used when something is pushed on the stack. In RTL, a push operation will be (set (mem (STACK_PUSH_CODE (reg sp))) ...)

The choices are PRE_DEC, POST_DEC, PRE_INC, and POST_INC. Which of these is correct depends on the stack direction and on whether the stack pointer points to the last item on the stack or whether it points to the space for the next item on the stack.

The default is PRE_DEC when STACK_GROWS_DOWNWARD is defined, which is almost always right, and PRE_INC otherwise, which is often wrong.

FRAME_GROWS_DOWNWARD

[Macro]

Define this macro if the addresses of local variable slots are at negative offsets from the frame pointer.

ARGS_GROW_DOWNWARD

[Macro]

Define this macro if successive arguments to a function occupy decreasing addresses on the stack.

STARTING_FRAME_OFFSET

[Macro]

Offset from the frame pointer to the first local variable slot to be allocated.

If FRAME_GROWS_DOWNWARD, find the next slot's offset by subtracting the first slot's length from STARTING_FRAME_OFFSET. Otherwise, it is found by adding the length of the first slot to the value STARTING_FRAME_OFFSET.

STACK_ALIGNMENT_NEEDED

[Macro]

Define to zero to disable final alignment of the stack during reload. The nonzero default for this macro is suitable for most ports.

On ports where STARTING_FRAME_OFFSET is nonzero or where there is a register save block following the local block that doesn't require alignment to STACK_BOUNDARY, it may be beneficial to disable stack alignment and do it in the backend.

STACK_POINTER_OFFSET

[Macro]

Offset from the stack pointer register to the first location at which outgoing arguments are placed. If not specified, the default value of zero is used. This is the proper value for most machines.

If ARGS_GROW_DOWNWARD, this is the offset to the location above the first location at which outgoing arguments are placed.

FIRST_PARM_OFFSET (fundec1)

[Macro]

Offset from the argument pointer register to the first argument's address. On some machines it may depend on the data type of the function.

If ARGS_GROW_DOWNWARD, this is the offset to the location above the first argument's address.

STACK_DYNAMIC_OFFSET (fundec1)

[Macro]

Offset from the stack pointer register to an item dynamically allocated on the stack, e.g., by alloca.

The default value for this macro is STACK_POINTER_OFFSET plus the length of the outgoing arguments. The default is correct for most machines. See 'function.c' for details.

DYNAMIC_CHAIN_ADDRESS (frameaddr)

[Macro]

A C expression whose value is RTL representing the address in a stack frame where the pointer to the caller's frame is stored. Assume that frameaddr is an RTL expression for the address of the stack frame itself.

If you don't define this macro, the default is to return the value of frameaddr—that is, the stack frame address is also the address of the stack word that points to the previous frame.

SETUP_FRAME_ADDRESSES

[Macro]

If defined, a C expression that produces the machine-specific code to setup the stack so that arbitrary frames can be accessed. For example, on the SPARC, we must flush all of the register windows to the stack before we can access arbitrary stack frames. You will seldom need to define this macro.

bool TARGET_BUILTIN_SETJMP_FRAME_VALUE ()

[Target Hook]

This target hook should return an rtx that is used to store the address of the current frame into the built in setjmp buffer. The default value, virtual_stack_vars_rtx, is correct for most machines. One reason you may need to define this target hook is if hard_frame_pointer_rtx is the appropriate value on your machine.

RETURN_ADDR_RTX (count, frameaddr)

[Macro]

A C expression whose value is RTL representing the value of the return address for the frame count steps up from the current frame, after the prologue. frameaddr is the frame pointer of the count frame, or the frame pointer of the count - 1 frame if RETURN_ADDR_IN_PREVIOUS_FRAME is defined.

The value of the expression must always be the correct address when *count* is zero, but may be NULL_RTX if there is not way to determine the return address of other frames.

RETURN ADDR IN PREVIOUS FRAME

[Macro]

Define this if the return address of a particular stack frame is accessed from the frame pointer of the previous stack frame.

INCOMING_RETURN_ADDR_RTX

[Macro]

A C expression whose value is RTL representing the location of the incoming return address at the beginning of any function, before the prologue. This RTL is either a REG, indicating that the return value is saved in 'REG', or a MEM representing a location in the stack.

You only need to define this macro if you want to support call frame debugging information like that provided by DWARF 2.

If this RTL is a REG, you should also define DWARF_FRAME_RETURN_COLUMN to DWARF_FRAME_REGNUM (REGNO).

DWARF ALT FRAME RETURN COLUMN

Macro

A C expression whose value is an integer giving a DWARF 2 column number that may be used as an alternate return column. This should be defined only if DWARF_FRAME_RETURN_COLUMN is set to a general register, but an alternate column needs to be used for signal frames.

DWARF_ZERO_REG [Macro]

A C expression whose value is an integer giving a DWARF 2 register number that is considered to always have the value zero. This should only be defined if the target has an architected zero register, and someone decided it was a good idea to use that register number to terminate the stack backtrace. New ports should avoid this.

```
void TARGET_DWARF_HANDLE_FRAME_UNSPEC (const char *label, [Target Hook] rtx pattern, int index)
```

This target hook allows the backend to emit frame-related insns that contain UN-SPECs or UNSPEC_VOLATILES. The DWARF 2 call frame debugging info engine will invoke it on insns of the form

```
(set (reg) (unspec [...] UNSPEC_INDEX))
and
    (set (reg) (unspec_volatile [...] UNSPECV_INDEX)).
```

to let the backend emit the call frame instructions. *label* is the CFI label attached to the insn, *pattern* is the pattern of the insn and *index* is UNSPEC_INDEX or UNSPECV_INDEX.

INCOMING_FRAME_SP_OFFSET

[Macro]

A C expression whose value is an integer giving the offset, in bytes, from the value of the stack pointer register to the top of the stack frame at the beginning of any function, before the prologue. The top of the frame is defined to be the value of the stack pointer in the previous frame, just before the call instruction.

You only need to define this macro if you want to support call frame debugging information like that provided by DWARF 2.

ARG_POINTER_CFA_OFFSET (fundec1)

[Macro]

A C expression whose value is an integer giving the offset, in bytes, from the argument pointer to the canonical frame address (cfa). The final value should coincide with that calculated by INCOMING_FRAME_SP_OFFSET. Which is unfortunately not usable during virtual register instantiation.

The default value for this macro is FIRST_PARM_OFFSET (fundecl), which is correct for most machines; in general, the arguments are found immediately before the stack frame. Note that this is not the case on some targets that save registers into the caller's frame, such as SPARC and rs6000, and so such targets need to define this macro.

You only need to define this macro if the default is incorrect, and you want to support call frame debugging information like that provided by DWARF 2.

13.10.2 Exception Handling Support

EH_RETURN_DATA_REGNO (N)

[Macro]

A C expression whose value is the Nth register number used for data by exception handlers, or INVALID_REGNUM if fewer than N registers are usable.

The exception handling library routines communicate with the exception handlers via a set of agreed upon registers. Ideally these registers should be call-clobbered; it is possible to use call-saved registers, but may negatively impact code size. The target must support at least 2 data registers, but should define 4 if there are enough free registers.

You must define this macro if you want to support call frame exception handling like that provided by DWARF 2.

EH_RETURN_STACKADJ_RTX

[Macro]

A C expression whose value is RTL representing a location in which to store a stack adjustment to be applied before function return. This is used to unwind the stack to an exception handler's call frame. It will be assigned zero on code paths that return normally.

Typically this is a call-clobbered hard register that is otherwise untouched by the epilogue, but could also be a stack slot.

Do not define this macro if the stack pointer is saved and restored by the regular prolog and epilog code in the call frame itself; in this case, the exception handling library routines will update the stack location to be restored in place. Otherwise, you must define this macro if you want to support call frame exception handling like that provided by DWARF 2.

EH RETURN HANDLER RTX

[Macro]

A C expression whose value is RTL representing a location in which to store the address of an exception handler to which we should return. It will not be assigned on code paths that return normally.

Typically this is the location in the call frame at which the normal return address is stored. For targets that return by popping an address off the stack, this might be a memory address just below the *target* call frame rather than inside the current call frame. If defined, EH_RETURN_STACKADJ_RTX will have already been assigned, so it may be used to calculate the location of the target call frame.

Some targets have more complex requirements than storing to an address calculable during initial code generation. In that case the **eh_return** instruction pattern should be used instead.

If you want to support call frame exception handling, you must define either this macro or the eh_return instruction pattern.

RETURN_ADDR_OFFSET

[Macro]

If defined, an integer-valued C expression for which rtl will be generated to add it to the exception handler address before it is searched in the exception handling tables, and to subtract it again from the address before using it to return to the exception handler.

ASM_PREFERRED_EH_DATA_FORMAT (code, global)

[Macro]

This macro chooses the encoding of pointers embedded in the exception handling sections. If at all possible, this should be defined such that the exception handling section will not require dynamic relocations, and so may be read-only.

code is 0 for data, 1 for code labels, 2 for function pointers. global is true if the symbol may be affected by dynamic relocations. The macro should return a combination of the DW_EH_PE_* defines as found in 'dwarf2.h'.

If this macro is not defined, pointers will not be encoded but represented directly.

ASM_MAYBE_OUTPUT_ENCODED_ADDR_RTX (file, encoding, size, addr, done) [Macro]

This macro allows the target to emit whatever special magic is required to represent the encoding chosen by ASM_PREFERRED_EH_DATA_FORMAT. Generic code takes care of pc-relative and indirect encodings; this must be defined if the target uses text-relative or data-relative encodings.

This is a C statement that branches to *done* if the format was handled. *encoding* is the format chosen, *size* is the number of bytes that the format occupies, *addr* is the SYMBOL_REF to be emitted.

MD_UNWIND_SUPPORT

[Macro]

A string specifying a file to be #include'd in unwind-dw2.c. The file so included typically defines MD_FALLBACK_FRAME_STATE_FOR.

MD_FALLBACK_FRAME_STATE_FOR (context, fs)

[Macro]

This macro allows the target to add cpu and operating system specific code to the call-frame unwinder for use when there is no unwind data available. The most common reason to implement this macro is to unwind through signal frames.

This macro is called from uw_frame_state_for in 'unwind-dw2.c' and 'unwind-ia64.c'. context is an _Unwind_Context; fs is an _Unwind_FrameState. Examine context->ra for the address of the code being executed and context->cfa for the stack pointer value. If the frame can be decoded, the register save addresses should be updated in fs and the macro should evaluate to _URC_NO_REASON. If the frame cannot be decoded, the macro should evaluate to _URC_END_OF_STACK.

For proper signal handling in Java this macro is accompanied by MAKE_THROW_FRAME, defined in 'libjava/include/*-signal.h' headers.

MD_HANDLE_UNWABI (context, fs)

[Macro]

This macro allows the target to add operating system specific code to the call-frame unwinder to handle the IA-64 .unwabi unwinding directive, usually used for signal or interrupt frames.

This macro is called from uw_update_context in 'unwind-ia64.c'. context is an _Unwind_Context; fs is an _Unwind_FrameState. Examine fs->unwabi for the abi and context in the .unwabi directive. If the .unwabi directive can be handled, the register save addresses should be updated in fs.

TARGET_USES_WEAK_UNWIND_INFO

[Macro]

A C expression that evaluates to true if the target requires unwind info to be given comdat linkage. Define it to be 1 if comdat linkage is necessary. The default is 0.

13.10.3 Specifying How Stack Checking is Done

GCC will check that stack references are within the boundaries of the stack, if the '-fstack-check' is specified, in one of three ways:

1. If the value of the STACK_CHECK_BUILTIN macro is nonzero, GCC will assume that you have arranged for stack checking to be done at appropriate places in the configuration files, e.g., in TARGET_ASM_FUNCTION_PROLOGUE. GCC will do not other special processing.

- 2. If STACK_CHECK_BUILTIN is zero and you defined a named pattern called check_stack in your 'md' file, GCC will call that pattern with one argument which is the address to compare the stack value against. You must arrange for this pattern to report an error if the stack pointer is out of range.
- 3. If neither of the above are true, GCC will generate code to periodically "probe" the stack pointer using the values of the macros defined below.

Normally, you will use the default values of these macros, so GCC will use the third approach.

STACK_CHECK_BUILTIN

[Macro]

A nonzero value if stack checking is done by the configuration files in a machine-dependent manner. You should define this macro if stack checking is require by the ABI of your machine or if you would like to have to stack checking in some more efficient way than GCC's portable approach. The default value of this macro is zero.

STACK_CHECK_PROBE_INTERVAL

Macro

An integer representing the interval at which GCC must generate stack probe instructions. You will normally define this macro to be no larger than the size of the "guard pages" at the end of a stack area. The default value of 4096 is suitable for most systems.

STACK_CHECK_PROBE_LOAD

[Macro]

A integer which is nonzero if GCC should perform the stack probe as a load instruction and zero if GCC should use a store instruction. The default is zero, which is the most efficient choice on most systems.

STACK_CHECK_PROTECT

[Macro]

The number of bytes of stack needed to recover from a stack overflow, for languages where such a recovery is supported. The default value of 75 words should be adequate for most machines.

STACK_CHECK_MAX_FRAME_SIZE

[Macro]

The maximum size of a stack frame, in bytes. GCC will generate probe instructions in non-leaf functions to ensure at least this many bytes of stack are available. If a stack frame is larger than this size, stack checking will not be reliable and GCC will issue a warning. The default is chosen so that GCC only generates one instruction on most systems. You should normally not change the default value of this macro.

STACK_CHECK_FIXED_FRAME_SIZE

[Macro]

GCC uses this value to generate the above warning message. It represents the amount of fixed frame used by a function, not including space for any callee-saved registers, temporaries and user variables. You need only specify an upper bound for this amount and will normally use the default of four words.

STACK_CHECK_MAX_VAR_SIZE

Macro

The maximum size, in bytes, of an object that GCC will place in the fixed area of the stack frame when the user specifies '-fstack-check'. GCC computed the default from the values of the above macros and you will normally not need to override that default.

13.10.4 Registers That Address the Stack Frame

This discusses registers that address the stack frame.

STACK_POINTER_REGNUM

[Macro]

The register number of the stack pointer register, which must also be a fixed register according to FIXED_REGISTERS. On most machines, the hardware determines which register this is.

FRAME_POINTER_REGNUM

[Macro]

The register number of the frame pointer register, which is used to access automatic variables in the stack frame. On some machines, the hardware determines which register this is. On other machines, you can choose any register you wish for this purpose.

HARD_FRAME_POINTER_REGNUM

[Macro]

On some machines the offset between the frame pointer and starting offset of the automatic variables is not known until after register allocation has been done (for example, because the saved registers are between these two locations). On those machines, define FRAME_POINTER_REGNUM the number of a special, fixed register to be used internally until the offset is known, and define HARD_FRAME_POINTER_REGNUM to be the actual hard register number used for the frame pointer.

You should define this macro only in the very rare circumstances when it is not possible to calculate the offset between the frame pointer and the automatic variables until after register allocation has been completed. When this macro is defined, you must also indicate in your definition of ELIMINABLE_REGS how to eliminate FRAME_POINTER_REGNUM into either HARD_FRAME_POINTER_REGNUM or STACK_POINTER_REGNUM.

Do not define this macro if it would be the same as FRAME_POINTER_REGNUM.

ARG_POINTER_REGNUM

[Macro]

The register number of the arg pointer register, which is used to access the function's argument list. On some machines, this is the same as the frame pointer register. On some machines, the hardware determines which register this is. On other machines, you can choose any register you wish for this purpose. If this is not the same register as the frame pointer register, then you must mark it as a fixed register according to FIXED_REGISTERS, or arrange to be able to eliminate it (see Section 13.10.5 [Elimination], page 294).

RETURN_ADDRESS_POINTER_REGNUM

[Macro]

The register number of the return address pointer register, which is used to access the current function's return address from the stack. On some machines, the return address is not at a fixed offset from the frame pointer or stack pointer or argument pointer. This register can be defined to point to the return address on the stack, and then be converted by ELIMINABLE_REGS into either the frame pointer or stack pointer.

Do not define this macro unless there is no other way to get the return address from the stack.

STATIC_CHAIN_REGNUM STATIC_CHAIN_INCOMING_REGNUM

[Macro]

[Macro]

Register numbers used for passing a function's static chain pointer. If register windows are used, the register number as seen by the called function is STATIC_CHAIN_INCOMING_REGNUM, while the register number as seen by the calling function is STATIC_CHAIN_REGNUM. If these registers are the same, STATIC_CHAIN_INCOMING_REGNUM need not be defined.

The static chain register need not be a fixed register.

If the static chain is passed in memory, these macros should not be defined; instead, the next two macros should be defined.

STATIC_CHAIN STATIC CHAIN INCOMING

[Macro]

[Macro]

If the static chain is passed in memory, these macros provide rtx giving mem expressions that denote where they are stored. STATIC_CHAIN and STATIC_CHAIN_INCOMING give the locations as seen by the calling and called functions, respectively. Often the former will be at an offset from the stack pointer and the latter at an offset from the frame pointer.

The variables stack_pointer_rtx, frame_pointer_rtx, and arg_pointer_rtx will have been initialized prior to the use of these macros and should be used to refer to those items.

If the static chain is passed in a register, the two previous macros should be defined instead.

DWARF_FRAME_REGISTERS

[Macro]

This macro specifies the maximum number of hard registers that can be saved in a call frame. This is used to size data structures used in DWARF2 exception handling.

Prior to GCC 3.0, this macro was needed in order to establish a stable exception handling ABI in the face of adding new hard registers for ISA extensions. In GCC 3.0 and later, the EH ABI is insulated from changes in the number of hard registers. Nevertheless, this macro can still be used to reduce the runtime memory requirements of the exception handling routines, which can be substantial if the ISA contains a lot of registers that are not call-saved.

If this macro is not defined, it defaults to FIRST_PSEUDO_REGISTER.

PRE_GCC3_DWARF_FRAME_REGISTERS

[Macro]

This macro is similar to DWARF_FRAME_REGISTERS, but is provided for backward compatibility in pre GCC 3.0 compiled code.

If this macro is not defined, it defaults to DWARF_FRAME_REGISTERS.

DWARF_REG_TO_UNWIND_COLUMN (regno)

[Macro]

Define this macro if the target's representation for dwarf registers is different than the internal representation for unwind column. Given a dwarf register, this macro should return the internal unwind column number to use instead.

See the PowerPC's SPE target for an example.

DWARF_FRAME_REGNUM (regno)

[Macro]

Define this macro if the target's representation for dwarf registers used in .eh_frame or .debug_frame is different from that used in other debug info sections. Given a GCC hard register number, this macro should return the .eh_frame register number. The default is DBX_REGISTER_NUMBER (regno).

DWARF2_FRAME_REG_OUT (regno, for_eh)

[Macro]

Define this macro to map register numbers held in the call frame info that GCC has collected using DWARF_FRAME_REGNUM to those that should be output in .debug_frame (for_eh is zero) and .eh_frame (for_eh is nonzero). The default is to return regno.

13.10.5 Eliminating Frame Pointer and Arg Pointer

This is about eliminating the frame pointer and arg pointer.

FRAME_POINTER_REQUIRED

[Macro]

A C expression which is nonzero if a function must have and use a frame pointer. This expression is evaluated in the reload pass. If its value is nonzero the function will have a frame pointer.

The expression can in principle examine the current function and decide according to the facts, but on most machines the constant 0 or the constant 1 suffices. Use 0 when the machine allows code to be generated with no frame pointer, and doing so saves some time or space. Use 1 when there is no possible advantage to avoiding a frame pointer.

In certain cases, the compiler does not know how to produce valid code without a frame pointer. The compiler recognizes those cases and automatically gives the function a frame pointer regardless of what FRAME_POINTER_REQUIRED says. You don't need to worry about them.

In a function that does not require a frame pointer, the frame pointer register can be allocated for ordinary usage, unless you mark it as a fixed register. See FIXED_REGISTERS for more information.

INITIAL_FRAME_POINTER_OFFSET (depth-var)

[Macro]

A C statement to store in the variable depth-var the difference between the frame pointer and the stack pointer values immediately after the function prologue. The value would be computed from information such as the result of get_frame_size () and the tables of registers regs_ever_live and call_used_regs.

If ELIMINABLE_REGS is defined, this macro will be not be used and need not be defined. Otherwise, it must be defined even if FRAME_POINTER_REQUIRED is defined to always be true; in that case, you may set depth-var to anything.

ELIMINABLE_REGS [Macro]

If defined, this macro specifies a table of register pairs used to eliminate unneeded registers that point into the stack frame. If it is not defined, the only elimination attempted by the compiler is to replace references to the frame pointer with references to the stack pointer.

The definition of this macro is a list of structure initializations, each of which specifies an original and replacement register.

On some machines, the position of the argument pointer is not known until the compilation is completed. In such a case, a separate hard register must be used for the argument pointer. This register can be eliminated by replacing it with either the frame pointer or the argument pointer, depending on whether or not the frame pointer has been eliminated.

In this case, you might specify:

```
#define ELIMINABLE_REGS \
{{ARG_POINTER_REGNUM, STACK_POINTER_REGNUM}, \
{ARG_POINTER_REGNUM, FRAME_POINTER_REGNUM}, \
{FRAME_POINTER_REGNUM, STACK_POINTER_REGNUM}}
```

Note that the elimination of the argument pointer with the stack pointer is specified first since that is the preferred elimination.

CAN_ELIMINATE (from-reg, to-reg)

[Macro]

A C expression that returns nonzero if the compiler is allowed to try to replace register number from-reg with register number to-reg. This macro need only be defined if ELIMINABLE_REGS is defined, and will usually be the constant 1, since most of the cases preventing register elimination are things that the compiler already knows about.

INITIAL_ELIMINATION_OFFSET (from-reg, to-reg, offset-var)

[Macro]

This macro is similar to INITIAL_FRAME_POINTER_OFFSET. It specifies the initial difference between the specified pair of registers. This macro must be defined if ELIMINABLE_REGS is defined.

13.10.6 Passing Function Arguments on the Stack

The macros in this section control how arguments are passed on the stack. See the following section for other macros that control passing certain arguments in registers.

bool TARGET_PROMOTE_PROTOTYPES (tree fntype)

[Target Hook]

This target hook returns true if an argument declared in a prototype as an integral type smaller than int should actually be passed as an int. In addition to avoiding errors in certain cases of mismatch, it also makes for better code on certain machines. The default is to not promote prototypes.

PUSH ARGS [Macro]

A C expression. If nonzero, push insns will be used to pass outgoing arguments. If the target machine does not have a push instruction, set it to zero. That directs GCC to use an alternate strategy: to allocate the entire argument block and then store the arguments into it. When PUSH_ARGS is nonzero, PUSH_ROUNDING must be defined too.

PUSH ARGS REVERSED

[Macro]

A C expression. If nonzero, function arguments will be evaluated from last to first, rather than from first to last. If this macro is not defined, it defaults to PUSH_ARGS on targets where the stack and args grow in opposite directions, and 0 otherwise.

PUSH_ROUNDING (npushed)

[Macro]

A C expression that is the number of bytes actually pushed onto the stack when an instruction attempts to push npushed bytes.

On some machines, the definition

#define PUSH_ROUNDING(BYTES) (BYTES)

will suffice. But on other machines, instructions that appear to push one byte actually push two bytes in an attempt to maintain alignment. Then the definition should be #define PUSH_ROUNDING(BYTES) (((BYTES) + 1) & ~1)

ACCUMULATE_OUTGOING_ARGS

[Macro]

A C expression. If nonzero, the maximum amount of space required for outgoing arguments will be computed and placed into the variable current_function_outgoing_args_size. No space will be pushed onto the stack for each call; instead, the function prologue should increase the stack frame size by this amount.

Setting both PUSH_ARGS and ACCUMULATE_OUTGOING_ARGS is not proper.

REG_PARM_STACK_SPACE (fndec1)

[Macro]

Define this macro if functions should assume that stack space has been allocated for arguments even when their values are passed in registers.

The value of this macro is the size, in bytes, of the area reserved for arguments passed in registers for the function represented by *findecl*, which can be zero if GCC is calling a library function.

This space can be allocated by the caller, or be a part of the machine-dependent stack frame: OUTGOING_REG_PARM_STACK_SPACE says which.

OUTGOING REG PARM STACK SPACE

[Macro]

Define this if it is the responsibility of the caller to allocate the area reserved for arguments passed in registers.

If ACCUMULATE_OUTGOING_ARGS is defined, this macro controls whether the space for these arguments counts in the value of current_function_outgoing_args_size.

STACK PARMS IN REG PARM AREA

[Macro]

Define this macro if REG_PARM_STACK_SPACE is defined, but the stack parameters don't skip the area specified by it.

Normally, when a parameter is not passed in registers, it is placed on the stack beyond the REG_PARM_STACK_SPACE area. Defining this macro suppresses this behavior and causes the parameter to be passed on the stack in its natural location.

RETURN_POPS_ARGS (fundecl, funtype, stack-size)

[Macro]

A C expression that should indicate the number of bytes of its own arguments that a function pops on returning, or 0 if the function pops no arguments and the caller must therefore pop them all after the function returns.

fundecl is a C variable whose value is a tree node that describes the function in question. Normally it is a node of type FUNCTION_DECL that describes the declaration of the function. From this you can obtain the DECL_ATTRIBUTES of the function.

funtype is a C variable whose value is a tree node that describes the function in question. Normally it is a node of type FUNCTION_TYPE that describes the data type of the function. From this it is possible to obtain the data types of the value and arguments (if known).

When a call to a library function is being considered, fundecl will contain an identifier node for the library function. Thus, if you need to distinguish among various library

functions, you can do so by their names. Note that "library function" in this context means a function used to perform arithmetic, whose name is known specially in the compiler and was not mentioned in the C code being compiled.

stack-size is the number of bytes of arguments passed on the stack. If a variable number of bytes is passed, it is zero, and argument popping will always be the responsibility of the calling function.

On the VAX, all functions always pop their arguments, so the definition of this macro is stack-size. On the 68000, using the standard calling convention, no functions pop their arguments, so the value of the macro is always 0 in this case. But an alternative calling convention is available in which functions that take a fixed number of arguments pop them but other functions (such as printf) pop nothing (the caller pops all). When this convention is in use, funtype is examined to determine whether a function takes a fixed number of arguments.

CALL_POPS_ARGS (cum)

[Macro]

A C expression that should indicate the number of bytes a call sequence pops off the stack. It is added to the value of RETURN_POPS_ARGS when compiling a function call. cum is the variable in which all arguments to the called function have been accumulated.

On certain architectures, such as the SH5, a call trampoline is used that pops certain registers off the stack, depending on the arguments that have been passed to the function. Since this is a property of the call site, not of the called function, RETURN_POPS_ARGS is not appropriate.

13.10.7 Passing Arguments in Registers

This section describes the macros which let you control how various types of arguments are passed in registers or how they are arranged in the stack.

FUNCTION ARG (cum. mode. type. named)

[Macro]

A C expression that controls whether a function argument is passed in a register, and which register.

The arguments are *cum*, which summarizes all the previous arguments; *mode*, the machine mode of the argument; *type*, the data type of the argument as a tree node or 0 if that is not known (which happens for C support library functions); and *named*, which is 1 for an ordinary argument and 0 for nameless arguments that correspond to '...' in the called function's prototype. *type* can be an incomplete type if a syntax error has previously occurred.

The value of the expression is usually either a reg RTX for the hard register in which to pass the argument, or zero to pass the argument on the stack.

For machines like the VAX and 68000, where normally all arguments are pushed, zero suffices as a definition.

The value of the expression can also be a parallel RTX. This is used when an argument is passed in multiple locations. The mode of the parallel should be the mode of the entire argument. The parallel holds any number of expr_list pairs; each one describes where part of the argument is passed. In each expr_list the first operand must be a reg RTX for the hard register in which to pass this part

of the argument, and the mode of the register RTX indicates how large this part of the argument is. The second operand of the expr_list is a const_int which gives the offset in bytes into the entire argument of where this part starts. As a special exception the first expr_list in the parallel RTX may have a first operand of zero. This indicates that the entire argument is also stored on the stack.

The last time this macro is called, it is called with MODE == VOIDmode, and its result is passed to the call or call_value pattern as operands 2 and 3 respectively.

The usual way to make the ISO library 'stdarg.h' work on a machine where some arguments are usually passed in registers, is to cause nameless arguments to be passed on the stack instead. This is done by making FUNCTION_ARG return 0 whenever named is 0.

You may use the hook targetm.calls.must_pass_in_stack in the definition of this macro to determine if this argument is of a type that must be passed in the stack. If REG_PARM_STACK_SPACE is not defined and FUNCTION_ARG returns nonzero for such an argument, the compiler will abort. If REG_PARM_STACK_SPACE is defined, the argument will be computed in the stack and then loaded into a register.

bool TARGET_MUST_PASS_IN_STACK (enum machine_mode mode, tree type) [Target Hook]

This target hook should return **true** if we should not pass *type* solely in registers. The file 'expr.h' defines a definition that is usually appropriate, refer to 'expr.h' for additional documentation.

FUNCTION_INCOMING_ARG (cum, mode, type, named) [Macro]

Define this macro if the target machine has "register windows", so that the register in which a function sees an arguments is not necessarily the same as the one in which the caller passed the argument.

For such machines, FUNCTION_ARG computes the register in which the caller passes the value, and FUNCTION_INCOMING_ARG should be defined in a similar fashion to tell the function being called where the arguments will arrive.

If FUNCTION_INCOMING_ARG is not defined, FUNCTION_ARG serves both purposes.

int TARGET_ARG_PARTIAL_BYTES (CUMULATIVE_ARGS *cum, enum machine_mode mode, tree type, bool named) [Target Hook]

This target hook returns the number of bytes at the beginning of an argument that must be put in registers. The value must be zero for arguments that are passed entirely in registers or that are entirely pushed on the stack.

On some machines, certain arguments must be passed partially in registers and partially in memory. On these machines, typically the first few words of arguments are passed in registers, and the rest on the stack. If a multi-word argument (a double or a structure) crosses that boundary, its first few words must be passed in registers and the rest must be pushed. This macro tells the compiler when this occurs, and how many bytes should go in registers.

FUNCTION_ARG for these arguments should return the first register to be used by the caller for this argument; likewise FUNCTION_INCOMING_ARG, for the called function.

bool TARGET_PASS_BY_REFERENCE (CUMULATIVE_ARGS *cum, enum machine_mode mode, tree type, bool named) [Target Hook]

This target hook should return **true** if an argument at the position indicated by *cum* should be passed by reference. This predicate is queried after target independent reasons for being passed by reference, such as TREE_ADDRESSABLE (type).

If the hook returns true, a copy of that argument is made in memory and a pointer to the argument is passed instead of the argument itself. The pointer is passed in whatever way is appropriate for passing a pointer to that type.

bool TARGET_CALLEE_COPIES (CUMULATIVE_ARGS *cum, enum [Target Hook] machine_mode mode, tree type, bool named)

The function argument described by the parameters to this hook is known to be passed by reference. The hook should return true if the function argument should be copied by the callee instead of copied by the caller.

For any argument for which the hook returns true, if it can be determined that the argument is not modified, then a copy need not be generated.

The default version of this hook always returns false.

CUMULATIVE_ARGS [Macro]

A C type for declaring a variable that is used as the first argument of FUNCTION_ARG and other related values. For some target machines, the type int suffices and can hold the number of bytes of argument so far.

There is no need to record in CUMULATIVE_ARGS anything about the arguments that have been passed on the stack. The compiler has other variables to keep track of that. For target machines on which all arguments are passed on the stack, there is no need to store anything in CUMULATIVE_ARGS; however, the data structure must exist and should not be empty, so use int.

A C statement (sans semicolon) for initializing the variable cum for the state at the beginning of the argument list. The variable has type CUMULATIVE_ARGS. The value of fntype is the tree node for the data type of the function which will receive the args, or 0 if the args are to a compiler support library function. For direct calls that are not libcalls, fndecl contain the declaration node of the function. fndecl is also set when INIT_CUMULATIVE_ARGS is used to find arguments for the function being compiled. n_named_args is set to the number of named arguments, including a structure return address if it is passed as a parameter, when making a call. When processing incoming arguments, n_named_args is set to -1.

When processing a call to a compiler support library function, *libname* identifies which one. It is a symbol_ref rtx which contains the name of the function, as a string. *libname* is 0 when an ordinary C function call is being processed. Thus, each time this macro is called, either *libname* or *fntype* is nonzero, but never both of them at once.

INIT_CUMULATIVE_LIBCALL_ARGS (cum, mode, libname) [Macro]

Like INIT_CUMULATIVE_ARGS but only used for outgoing libcalls, it gets a MODE argument instead of *fntype*, that would be NULL. *indirect* would always be zero, too. If

this macro is not defined, INIT_CUMULATIVE_ARGS (cum, NULL_RTX, libname, 0) is used instead.

INIT_CUMULATIVE_INCOMING_ARGS (cum, fntype, libname)

[Macro]

Like INIT_CUMULATIVE_ARGS but overrides it for the purposes of finding the arguments for the function being compiled. If this macro is undefined, INIT_CUMULATIVE_ARGS is used instead.

The value passed for *libname* is always 0, since library routines with special calling conventions are never compiled with GCC. The argument *libname* exists for symmetry with INIT_CUMULATIVE_ARGS.

FUNCTION_ARG_ADVANCE (cum, mode, type, named)

[Macro]

A C statement (sans semicolon) to update the summarizer variable *cum* to advance past an argument in the argument list. The values *mode*, *type* and *named* describe that argument. Once this is done, the variable *cum* is suitable for analyzing the *following* argument with FUNCTION_ARG, etc.

This macro need not do anything if the argument in question was passed on the stack. The compiler knows how to track the amount of stack space used for arguments without any special help.

FUNCTION_ARG_PADDING (mode, type)

[Macro]

If defined, a C expression which determines whether, and in which direction, to pad out an argument with extra space. The value should be of type enum direction: either upward to pad above the argument, downward to pad below, or none to inhibit padding.

The amount of padding is always just enough to reach the next multiple of FUNCTION_ARG_BOUNDARY; this macro does not control it.

This macro has a default definition which is right for most systems. For little-endian machines, the default is to pad upward. For big-endian machines, the default is to pad downward for an argument of constant size shorter than an int, and upward otherwise.

PAD_VARARGS_DOWN

[Macro]

If defined, a C expression which determines whether the default implementation of va_arg will attempt to pad down before reading the next argument, if that argument is smaller than its aligned space as controlled by PARM_BOUNDARY. If this macro is not defined, all such arguments are padded down if BYTES_BIG_ENDIAN is true.

BLOCK_REG_PADDING (mode, type, first)

[Macro]

Specify padding for the last element of a block move between registers and memory. first is nonzero if this is the only element. Defining this macro allows better control of register function parameters on big-endian machines, without using PARALLEL rtl. In particular, MUST_PASS_IN_STACK need not test padding and mode of types in registers, as there is no longer a "wrong" part of a register; For example, a three byte aggregate may be passed in the high part of a register if so required.

FUNCTION_ARG_BOUNDARY (mode, type)

[Macro]

If defined, a C expression that gives the alignment boundary, in bits, of an argument with the specified mode and type. If it is not defined, PARM_BOUNDARY is used for all arguments.

FUNCTION_ARG_REGNO_P (regno)

[Macro]

A C expression that is nonzero if regno is the number of a hard register in which function arguments are sometimes passed. This does not include implicit arguments such as the static chain and the structure-value address. On many machines, no registers can be used for this purpose since all function arguments are pushed on the stack.

bool TARGET_SPLIT_COMPLEX_ARG (tree type)

[Target Hook]

This hook should return true if parameter of type type are passed as two scalar parameters. By default, GCC will attempt to pack complex arguments into the target's word size. Some ABIs require complex arguments to be split and treated as their individual components. For example, on AIX64, complex floats should be passed in a pair of floating point registers, even though a complex float would fit in one 64-bit floating point register.

The default value of this hook is NULL, which is treated as always false.

tree TARGET_BUILD_BUILTIN_VA_LIST (void)

[Target Hook]

This hook returns a type node for va_list for the target. The default version of the hook returns void*.

This hook performs target-specific gimplification of VA_ARG_EXPR. The first two parameters correspond to the arguments to va_arg; the latter two are as in gimplify.c:gimplify_expr.

bool TARGET_VALID_POINTER_MODE (enum machine_mode mode) [Target Hook]

Define this to return nonzero if the port can handle pointers with machine mode

mode. The default version of this hook returns true for both ptr_mode and Pmode.

bool TARGET_SCALAR_MODE_SUPPORTED_P (enum machine_mode [Target Hook] mode)

Define this to return nonzero if the port is prepared to handle insns involving scalar mode *mode*. For a scalar mode to be considered supported, all the basic arithmetic and comparisons must work.

The default version of this hook returns true for any mode required to handle the basic C types (as defined by the port). Included here are the double-word arithmetic supported by the code in 'optabs.c'.

bool TARGET_VECTOR_MODE_SUPPORTED_P (enum machine_mode [Target Hook] mode)

Define this to return nonzero if the port is prepared to handle insns involving vector mode *mode*. At the very least, it must have move patterns for this mode.

13.10.8 How Scalar Function Values Are Returned

This section discusses the macros that control returning scalars as values—values that can fit in registers.

FUNCTION_VALUE (valtype, func)

[Macro]

A C expression to create an RTX representing the place where a function returns a value of data type valtype. valtype is a tree node representing a data type. Write TYPE_MODE (valtype) to get the machine mode used to represent that type. On many machines, only the mode is relevant. (Actually, on most machines, scalar values are returned in the same place regardless of mode).

The value of the expression is usually a reg RTX for the hard register where the return value is stored. The value can also be a parallel RTX, if the return value is in multiple places. See FUNCTION_ARG for an explanation of the parallel form.

If TARGET_PROMOTE_FUNCTION_RETURN returns true, you must apply the same promotion rules specified in PROMOTE_MODE if valtype is a scalar type.

If the precise function being called is known, func is a tree node (FUNCTION_DECL) for it; otherwise, func is a null pointer. This makes it possible to use a different value-returning convention for specific functions when all their calls are known.

FUNCTION_VALUE is not used for return vales with aggregate data types, because these are returned in another way. See TARGET_STRUCT_VALUE_RTX and related macros, below.

FUNCTION_OUTGOING_VALUE (valtype, func)

[Macro

Define this macro if the target machine has "register windows" so that the register in which a function returns its value is not the same as the one in which the caller sees the value.

For such machines, FUNCTION_VALUE computes the register in which the caller will see the value. FUNCTION_OUTGOING_VALUE should be defined in a similar fashion to tell the function where to put the value.

If FUNCTION_OUTGOING_VALUE is not defined, FUNCTION_VALUE serves both purposes. FUNCTION_OUTGOING_VALUE is not used for return vales with aggregate data types, because these are returned in another way. See TARGET_STRUCT_VALUE_RTX and related macros, below.

LIBCALL_VALUE (mode)

[Macro]

A C expression to create an RTX representing the place where a library function returns a value of mode *mode*. If the precise function being called is known, *func* is a tree node (FUNCTION_DECL) for it; otherwise, *func* is a null pointer. This makes it possible to use a different value-returning convention for specific functions when all their calls are known.

Note that "library function" in this context means a compiler support routine, used to perform arithmetic, whose name is known specially by the compiler and was not mentioned in the C code being compiled.

The definition of LIBRARY_VALUE need not be concerned aggregate data types, because none of the library functions returns such types.

FUNCTION_VALUE_REGNO_P (regno)

[Macro]

A C expression that is nonzero if *regno* is the number of a hard register in which the values of called function may come back.

A register whose use for returning values is limited to serving as the second of a pair (for a value of type double, say) need not be recognized by this macro. So for most machines, this definition suffices:

#define FUNCTION_VALUE_REGNO_P(N) ((N) == 0)

If the machine has register windows, so that the caller and the called function use different registers for the return value, this macro should recognize only the caller's register numbers.

APPLY RESULT SIZE

[Macro]

Define this macro if 'untyped_call' and 'untyped_return' need more space than is implied by FUNCTION_VALUE_REGNO_P for saving and restoring an arbitrary return value.

bool TARGET_RETURN_IN_MSB (tree type)

[Target Hook]

This hook should return true if values of type type are returned at the most significant end of a register (in other words, if they are padded at the least significant end). You can assume that type is returned in a register; the caller is required to check this.

Note that the register provided by FUNCTION_VALUE must be able to hold the complete return value. For example, if a 1-, 2- or 3-byte structure is returned at the most significant end of a 4-byte register, FUNCTION_VALUE should provide an SImode rtx.

13.10.9 How Large Values Are Returned

When a function value's mode is BLKmode (and in some other cases), the value is not returned according to FUNCTION_VALUE (see Section 13.10.8 [Scalar Return], page 302). Instead, the caller passes the address of a block of memory in which the value should be stored. This address is called the *structure value address*.

This section describes how to control returning structure values in memory.

bool TARGET_RETURN_IN_MEMORY (tree type, tree fntype)

[Target Hook]

This target hook should return a nonzero value to say to return the function value in memory, just as large structures are always returned. Here *type* will be the data type of the value, and *fntype* will be the type of the function doing the returning, or NULL for libcalls.

Note that values of mode BLKmode must be explicitly handled by this function. Also, the option '-fpcc-struct-return' takes effect regardless of this macro. On most systems, it is possible to leave the hook undefined; this causes a default definition to be used, whose value is the constant 1 for BLKmode values, and 0 otherwise.

Do not use this hook to indicate that structures and unions should always be returned in memory. You should instead use DEFAULT_PCC_STRUCT_RETURN to indicate this.

DEFAULT PCC STRUCT RETURN

[Macro]

Define this macro to be 1 if all structure and union return values must be in memory. Since this results in slower code, this should be defined only if needed for compatibility with other compilers or with an ABI. If you define this macro to be 0, then the

conventions used for structure and union return values are decided by the TARGET_RETURN_IN_MEMORY target hook.

If not defined, this defaults to the value 1.

rtx TARGET_STRUCT_VALUE_RTX (tree fndecl, int incoming) [Target Hook]

This target hook should return the location of the structure value address (normally a mem or reg), or 0 if the address is passed as an "invisible" first argument. Note that findecl may be NULL, for libcalls. You do not need to define this target hook if the address is always passed as an "invisible" first argument.

On some architectures the place where the structure value address is found by the called function is not the same place that the caller put it. This can be due to register windows, or it could be because the function prologue moves it to a different place. *incoming* is **true** when the location is needed in the context of the called function, and false in the context of the caller.

If incoming is true and the address is to be found on the stack, return a mem which refers to the frame pointer.

PCC_STATIC_STRUCT_RETURN

[Macro]

Define this macro if the usual system convention on the target machine for returning structures and unions is for the called function to return the address of a static variable containing the value.

Do not define this if the usual system convention is for the caller to pass an address to the subroutine.

This macro has effect in '-fpcc-struct-return' mode, but it does nothing when you use '-freg-struct-return' mode.

13.10.10 Caller-Saves Register Allocation

If you enable it, GCC can save registers around function calls. This makes it possible to use call-clobbered registers to hold variables that must live across calls.

CALLER_SAVE_PROFITABLE (refs, calls)

Macro

A C expression to determine whether it is worthwhile to consider placing a pseudoregister in a call-clobbered hard register and saving and restoring it around each function call. The expression should be 1 when this is worth doing, and 0 otherwise.

If you don't define this macro, a default is used which is good on most machines: 4 * calls < refs.

HARD_REGNO_CALLER_SAVE_MODE (regno, nregs)

[Macro]

A C expression specifying which mode is required for saving *nregs* of a pseudo-register in call-clobbered hard register *regno*. If *regno* is unsuitable for caller save, VOIDmode should be returned. For most machines this macro need not be defined since GCC will select the smallest suitable mode.

13.10.11 Function Entry and Exit

This section describes the macros that output function entry (prologue) and exit (epilogue) code.

void TARGET_ASM_FUNCTION_PROLOGUE ($FILE *file, HOST_WIDE_INT size$)

[Target Hook]

If defined, a function that outputs the assembler code for entry to a function. The prologue is responsible for setting up the stack frame, initializing the frame pointer register, saving registers that must be saved, and allocating *size* additional bytes of storage for the local variables. *size* is an integer. *file* is a stdio stream to which the assembler code should be output.

The label for the beginning of the function need not be output by this macro. That has already been done when the macro is run.

To determine which registers to save, the macro can refer to the array regs_ever_live: element r is nonzero if hard register r is used anywhere within the function. This implies the function prologue should save register r, provided it is not one of the call-used registers. (TARGET_ASM_FUNCTION_EPILOGUE must likewise use regs_ever_live.)

On machines that have "register windows", the function entry code does not save on the stack the registers that are in the windows, even if they are supposed to be preserved by function calls; instead it takes appropriate steps to "push" the register stack, if any non-call-used registers are used in the function.

On machines where functions may or may not have frame-pointers, the function entry code must vary accordingly; it must set up the frame pointer if one is wanted, and not otherwise. To determine whether a frame pointer is in wanted, the macro can refer to the variable frame_pointer_needed. The variable's value will be 1 at run time in a function that needs a frame pointer. See Section 13.10.5 [Elimination], page 294.

The function entry code is responsible for allocating any stack space required for the function. This stack space consists of the regions listed below. In most cases, these regions are allocated in the order listed, with the last listed region closest to the top of the stack (the lowest address if STACK_GROWS_DOWNWARD is defined, and the highest address if it is not defined). You can use a different order for a machine if doing so is more convenient or required for compatibility reasons. Except in cases where required by standard or by a debugger, there is no reason why the stack layout used by GCC need agree with that used by other compilers for a machine.

void TARGET_ASM_FUNCTION_END_PROLOGUE (FILE *file)

[Target Hook]

If defined, a function that outputs assembler code at the end of a prologue. This should be used when the function prologue is being emitted as RTL, and you have some extra assembler that needs to be emitted. See [prologue instruction pattern], page 210.

void TARGET ASM FUNCTION BEGIN EPILOGUE (FILE *file) [Target Hook]

If defined, a function that outputs assembler code at the start of an epilogue. This should be used when the function epilogue is being emitted as RTL, and you have some extra assembler that needs to be emitted. See [epilogue instruction pattern], page 211.

void TARGET_ASM_FUNCTION_EPILOGUE (FILE *file, HOST_WIDE_INT size)

[Target Hook]

If defined, a function that outputs the assembler code for exit from a function. The epilogue is responsible for restoring the saved registers and stack pointer to their values when the function was called, and returning control to the caller. This macro takes the same arguments as the macro TARGET_ASM_FUNCTION_PROLOGUE, and the registers to restore are determined from regs_ever_live and CALL_USED_REGISTERS in the same way.

On some machines, there is a single instruction that does all the work of returning from the function. On these machines, give that instruction the name 'return' and do not define the macro TARGET_ASM_FUNCTION_EPILOGUE at all.

Do not define a pattern named 'return' if you want the TARGET_ASM_FUNCTION_ EPILOGUE to be used. If you want the target switches to control whether return instructions or epilogues are used, define a 'return' pattern with a validity condition that tests the target switches appropriately. If the 'return' pattern's validity condition is false, epilogues will be used.

On machines where functions may or may not have frame-pointers, the function exit code must vary accordingly. Sometimes the code for these two cases is completely different. To determine whether a frame pointer is wanted, the macro can refer to the variable frame_pointer_needed. The variable's value will be 1 when compiling a function that needs a frame pointer.

Normally, TARGET_ASM_FUNCTION_PROLOGUE and TARGET_ASM_FUNCTION_EPILOGUE must treat leaf functions specially. The C variable current_function_is_leaf is nonzero for such a function. See Section 13.8.4 [Leaf Functions], page 276.

On some machines, some functions pop their arguments on exit while others leave that for the caller to do. For example, the 68020 when given '-mrtd' pops arguments in functions that take a fixed number of arguments.

Your definition of the macro RETURN_POPS_ARGS decides which functions pop their own arguments. TARGET_ASM_FUNCTION_EPILOGUE needs to know what was decided. The variable that is called current_function_pops_args is the number of bytes of its arguments that a function should pop. See Section 13.10.8 [Scalar Return], page 302.

- A region of current_function_pretend_args_size bytes of uninitialized space just underneath the first argument arriving on the stack. (This may not be at the very start of the allocated stack region if the calling sequence has pushed anything else since pushing the stack arguments. But usually, on such machines, nothing else has been pushed yet, because the function prologue itself does all the pushing.) This region is used on machines where an argument may be passed partly in registers and partly in memory, and, in some cases to support the features in <stdarg.h>.
- An area of memory used to save certain registers used by the function. The size of this area, which may also include space for such things as the return address and pointers to previous stack frames, is machine-specific and usually depends on which registers have been used in the function. Machines with register windows often do not require a save area.

- A region of at least size bytes, possibly rounded up to an allocation boundary, to contain the local variables of the function. On some machines, this region and the save area may occur in the opposite order, with the save area closer to the top of the stack.
- Optionally, when ACCUMULATE_OUTGOING_ARGS is defined, a region of current_function_outgoing_args_size bytes to be used for outgoing argument lists of the function. See Section 13.10.6 [Stack Arguments], page 295.

EXIT_IGNORE_STACK

[Macro]

Define this macro as a C expression that is nonzero if the return instruction or the function epilogue ignores the value of the stack pointer; in other words, if it is safe to delete an instruction to adjust the stack pointer before a return from the function. The default is 0.

Note that this macro's value is relevant only for functions for which frame pointers are maintained. It is never safe to delete a final stack adjustment in a function that has no frame pointer, and the compiler knows this regardless of EXIT_IGNORE_STACK.

EPILOGUE_USES (regno)

Macro

Define this macro as a C expression that is nonzero for registers that are used by the epilogue or the 'return' pattern. The stack and frame pointer registers are already be assumed to be used as needed.

EH_USES (regno)

[Macro]

Define this macro as a C expression that is nonzero for registers that are used by the exception handling mechanism, and so should be considered live on entry to an exception edge.

DELAY_SLOTS_FOR_EPILOGUE

[Macro]

Define this macro if the function epilogue contains delay slots to which instructions from the rest of the function can be "moved". The definition should be a C expression whose value is an integer representing the number of delay slots there.

ELIGIBLE_FOR_EPILOGUE_DELAY (insn, n)

[Macro]

A C expression that returns 1 if insn can be placed in delay slot number n of the epilogue.

The argument n is an integer which identifies the delay slot now being considered (since different slots may have different rules of eligibility). It is never negative and is always less than the number of epilogue delay slots (what DELAY_SLOTS_FOR_EPILOGUE returns). If you reject a particular insn for a given delay slot, in principle, it may be reconsidered for a subsequent delay slot. Also, other insns may (at least in principle) be considered for the so far unfilled delay slot.

The insns accepted to fill the epilogue delay slots are put in an RTL list made with insn_list objects, stored in the variable current_function_epilogue_delay_list. The insn for the first delay slot comes first in the list. Your definition of the macro TARGET_ASM_FUNCTION_EPILOGUE should fill the delay slots by outputting the insns in this list, usually by calling final_scan_insn.

You need not define this macro if you did not define DELAY_SLOTS_FOR_EPILOGUE.

A function that outputs the assembler code for a thunk function, used to implement C++ virtual function calls with multiple inheritance. The thunk acts as a wrapper around a virtual function, adjusting the implicit object parameter before handing control off to the real function.

First, emit code to add the integer *delta* to the location that contains the incoming first argument. Assume that this argument contains a pointer, and is the one used to pass the **this** pointer in C++. This is the incoming argument *before* the function prologue, e.g. '%00' on a sparc. The addition must preserve the values of all other incoming arguments.

Then, if $vcall_offset$ is nonzero, an additional adjustment should be made after adding delta. In particular, if p is the adjusted pointer, the following adjustment should be made:

```
p += (*((ptrdiff_t **)p))[vcall_offset/sizeof(ptrdiff_t)]
```

After the additions, emit code to jump to function, which is a FUNCTION_DECL. This is a direct pure jump, not a call, and does not touch the return address. Hence returning from FUNCTION will return to whoever called the current 'thunk'.

The effect must be as if function had been called directly with the adjusted first argument. This macro is responsible for emitting all of the code for a thunk function; TARGET_ASM_FUNCTION_PROLOGUE and TARGET_ASM_FUNCTION_EPILOGUE are not invoked.

The thunk_fndecl is redundant. (delta and function have already been extracted from it.) It might possibly be useful on some targets, but probably not.

If you do not define this macro, the target-independent code in the C++ front end will generate a less efficient heavyweight thunk that calls function instead of jumping to it. The generic approach does not support varargs.

```
bool TARGET_ASM_CAN_OUTPUT_MI_THUNK (tree thunk_fndec1, [Target Hook] HOST_WIDE_INT delta, HOST_WIDE_INT vcall_offset, tree function)
```

A function that returns true if TARGET_ASM_OUTPUT_MI_THUNK would be able to output the assembler code for the thunk function specified by the arguments it is passed, and false otherwise. In the latter case, the generic approach will be used by the C++ front end, with the limitations previously exposed.

13.10.12 Generating Code for Profiling

These macros will help you generate code for profiling.

```
FUNCTION_PROFILER (file, labelno)
```

[Macro]

A C statement or compound statement to output to file some assembler code to call the profiling subroutine mcount.

The details of how mcount expects to be called are determined by your operating system environment, not by GCC. To figure them out, compile a small program for

profiling using the system's installed C compiler and look at the assembler code that results.

Older implementations of mcount expect the address of a counter variable to be loaded into some register. The name of this variable is 'LP' followed by the number *labelno*, so you would generate the name using 'LP%d' in a fprintf.

PROFILE_HOOK [Macro]

A C statement or compound statement to output to file some assembly code to call the profiling subroutine mcount even the target does not support profiling.

NO_PROFILE_COUNTERS

[Macro]

Define this macro if the **mcount** subroutine on your system does not need a counter variable allocated for each function. This is true for almost all modern implementations. If you define this macro, you must not use the *labelno* argument to FUNCTION_PROFILER.

PROFILE BEFORE PROLOGUE

[Macro]

Define this macro if the code for function profiling should come before the function prologue. Normally, the profiling code comes after.

13.10.13 Permitting tail calls

bool TARGET_FUNCTION_OK_FOR_SIBCALL (tree dec1, tree exp) [Target Hook]
True if it is ok to do sibling call optimization for the specified call expression exp.

decl will be the called function, or NULL if this is an indirect call.

It is not uncommon for limitations of calling conventions to prevent tail calls to functions outside the current unit of translation, or during PIC compilation. The hook is used to enforce these restrictions, as the sibcall md pattern can not fail, or fall over to a "normal" call. The criteria for successful sibling call optimization may vary greatly between different architectures.

13.11 Implementing the Varargs Macros

GCC comes with an implementation of <varargs.h> and <stdarg.h> that work without change on machines that pass arguments on the stack. Other machines require their own implementations of varargs, and the two machine independent header files must have conditionals to include it.

ISO <stdarg.h> differs from traditional <varargs.h> mainly in the calling convention for va_start. The traditional implementation takes just one argument, which is the variable in which to store the argument pointer. The ISO implementation of va_start takes an additional second argument. The user is supposed to write the last named argument of the function here.

However, va_start should not use this argument. The way to find the end of the named arguments is with the built-in functions described below.

__builtin_saveregs ()

[Macro]

Use this built-in function to save the argument registers in memory so that the varargs mechanism can access them. Both ISO and traditional versions of va_start must use

__builtin_saveregs, unless you use TARGET_SETUP_INCOMING_VARARGS (see below) instead.

On some machines, __builtin_saveregs is open-coded under the control of the target hook TARGET_EXPAND_BUILTIN_SAVEREGS. On other machines, it calls a routine written in assembler language, found in 'libgccl.c'.

Code generated for the call to __builtin_saveregs appears at the beginning of the function, as opposed to where the call to __builtin_saveregs is written, regardless of what the code is. This is because the registers must be saved before the function starts to use them for its own purposes.

__builtin_args_info (category)

[Macro]

Use this built-in function to find the first anonymous arguments in registers.

In general, a machine may have several categories of registers used for arguments, each for a particular category of data types. (For example, on some machines, floating-point registers are used for floating-point arguments while other arguments are passed in the general registers.) To make non-varargs functions use the proper calling convention, you have defined the CUMULATIVE_ARGS data type to record how many registers in each category have been used so far

__builtin_args_info accesses the same data structure of type CUMULATIVE_ARGS after the ordinary argument layout is finished with it, with *category* specifying which word to access. Thus, the value indicates the first unused register in a given category.

Normally, you would use __builtin_args_info in the implementation of va_start, accessing each category just once and storing the value in the va_list object. This is because va_list will have to update the values, and there is no way to alter the values accessed by __builtin_args_info.

__builtin_next_arg (lastarg)

[Macro]

This is the equivalent of __builtin_args_info, for stack arguments. It returns the address of the first anonymous stack argument, as type void *. If ARGS_GROW_DOWNWARD, it returns the address of the location above the first anonymous stack argument. Use it in va_start to initialize the pointer for fetching arguments from the stack. Also use it in va_start to verify that the second parameter lastarg is the last named argument of the current function.

__builtin_classify_type (object)

[Macro]

Since each machine has its own conventions for which data types are passed in which kind of register, your implementation of va_arg has to embody these conventions. The easiest way to categorize the specified data type is to use __builtin_classify_type together with sizeof and __alignof__.

__builtin_classify_type ignores the value of object, considering only its data type. It returns an integer describing what kind of type that is—integer, floating, pointer, structure, and so on.

The file 'typeclass.h' defines an enumeration that you can use to interpret the values of __builtin_classify_type.

These machine description macros help implement varargs:

rtx TARGET_EXPAND_BUILTIN_SAVEREGS (void)

[Target Hook]

If defined, this hook produces the machine-specific code for a call to __builtin_saveregs. This code will be moved to the very beginning of the function, before any parameter access are made. The return value of this function should be an RTX that contains the value to use as the return of __builtin_saveregs.

void TARGET_SETUP_INCOMING_VARARGS (CUMULATIVE_ARGS

[Target Hook]

*args_so_far, enum machine_mode mode, tree type, int

*pretend_args_size, int second_time)

This target hook offers an alternative to using __builtin_saveregs and defining the hook TARGET_EXPAND_BUILTIN_SAVEREGS. Use it to store the anonymous register arguments into the stack so that all the arguments appear to have been passed consecutively on the stack. Once this is done, you can use the standard implementation of varargs that works for machines that pass all their arguments on the stack.

The argument $args_so_far$ points to the CUMULATIVE_ARGS data structure, containing the values that are obtained after processing the named arguments. The arguments mode and type describe the last named argument—its machine mode and its data type as a tree node.

The target hook should do two things: first, push onto the stack all the argument registers *not* used for the named arguments, and second, store the size of the data thus pushed into the int-valued variable pointed to by *pretend_args_size*. The value that you store here will serve as additional offset for setting up the stack frame.

Because you must generate code to push the anonymous arguments at compile time without knowing their data types, TARGET_SETUP_INCOMING_VARARGS is only useful on machines that have just a single category of argument register and use it uniformly for all data types.

If the argument $second_time$ is nonzero, it means that the arguments of the function are being analyzed for the second time. This happens for an inline function, which is not actually compiled until the end of the source file. The hook TARGET_SETUP_INCOMING_VARARGS should not generate any instructions in this case.

bool TARGET_STRICT_ARGUMENT_NAMING (CUMULATIVE_ARGS [Target Hook] *ca)

Define this hook to return **true** if the location where a function argument is passed depends on whether or not it is a named argument.

This hook controls how the named argument to FUNCTION_ARG is set for varargs and stdarg functions. If this hook returns true, the named argument is always true for named arguments, and false for unnamed arguments. If it returns false, but TARGET_PRETEND_OUTGOING_VARARGS_NAMED returns true, then all arguments are treated as named. Otherwise, all named arguments except the last are treated as named.

You need not define this hook if it always returns zero.

bool TARGET PRETEND OUTGOING VARARGS NAMED

[Target Hook]

If you need to conditionally change ABIs so that one works with TARGET_SETUP_INCOMING_VARARGS, but the other works like neither TARGET_SETUP_INCOMING_VARARGS nor TARGET_STRICT_ARGUMENT_NAMING was defined, then define this hook

to return true if TARGET_SETUP_INCOMING_VARARGS is used, false otherwise. Otherwise, you should not define this hook.

13.12 Trampolines for Nested Functions

A trampoline is a small piece of code that is created at run time when the address of a nested function is taken. It normally resides on the stack, in the stack frame of the containing function. These macros tell GCC how to generate code to allocate and initialize a trampoline.

The instructions in the trampoline must do two things: load a constant address into the static chain register, and jump to the real address of the nested function. On CISC machines such as the m68k, this requires two instructions, a move immediate and a jump. Then the two addresses exist in the trampoline as word-long immediate operands. On RISC machines, it is often necessary to load each address into a register in two parts. Then pieces of each address form separate immediate operands.

The code generated to initialize the trampoline must store the variable parts—the static chain value and the function address—into the immediate operands of the instructions. On a CISC machine, this is simply a matter of copying each address to a memory reference at the proper offset from the start of the trampoline. On a RISC machine, it may be necessary to take out pieces of the address and store them separately.

TRAMPOLINE_TEMPLATE (file)

[Macro]

A C statement to output, on the stream file, assembler code for a block of data that contains the constant parts of a trampoline. This code should not include a label—the label is taken care of automatically.

If you do not define this macro, it means no template is needed for the target. Do not define this macro on systems where the block move code to copy the trampoline into place would be larger than the code to generate it on the spot.

TRAMPOLINE_SECTION

[Macro]

The name of a subroutine to switch to the section in which the trampoline template is to be placed (see Section 13.18 [Sections], page 330). The default is a value of 'readonly_data_section', which places the trampoline in the section containing read-only data.

TRAMPOLINE_SIZE [Macro]

A C expression for the size in bytes of the trampoline, as an integer.

TRAMPOLINE ALIGNMENT

[Macro]

Alignment required for trampolines, in bits.

If you don't define this macro, the value of BIGGEST_ALIGNMENT is used for aligning trampolines.

INITIALIZE_TRAMPOLINE (addr, fnaddr, static_chain)

[Macro]

A C statement to initialize the variable parts of a trampoline. addr is an RTX for the address of the trampoline; fnaddr is an RTX for the address of the nested function; static_chain is an RTX for the static chain value that should be passed to the function when it is called.

TRAMPOLINE_ADJUST_ADDRESS (addr)

[Macro]

A C statement that should perform any machine-specific adjustment in the address of the trampoline. Its argument contains the address that was passed to INITIALIZE_TRAMPOLINE. In case the address to be used for a function call should be different from the address in which the template was stored, the different address should be assigned to addr. If this macro is not defined, addr will be used for function calls.

If this macro is not defined, by default the trampoline is allocated as a stack slot. This default is right for most machines. The exceptions are machines where it is impossible to execute instructions in the stack area. On such machines, you may have to implement a separate stack, using this macro in conjunction with TARGET_ASM_FUNCTION_PROLOGUE and TARGET_ASM_FUNCTION_EPILOGUE.

fp points to a data structure, a **struct function**, which describes the compilation status of the immediate containing function of the function which the trampoline is for. The stack slot for the trampoline is in the stack frame of this containing function. Other allocation strategies probably must do something analogous with this information.

Implementing trampolines is difficult on many machines because they have separate instruction and data caches. Writing into a stack location fails to clear the memory in the instruction cache, so when the program jumps to that location, it executes the old contents.

Here are two possible solutions. One is to clear the relevant parts of the instruction cache whenever a trampoline is set up. The other is to make all trampolines identical, by having them jump to a standard subroutine. The former technique makes trampoline execution faster; the latter makes initialization faster.

To clear the instruction cache when a trampoline is initialized, define the following macro.

CLEAR_INSN_CACHE (beg. end)

[Macro]

If defined, expands to a C expression clearing the *instruction cache* in the specified interval. The definition of this macro would typically be a series of asm statements. Both beg and end are both pointer expressions.

The operating system may also require the stack to be made executable before calling the trampoline. To implement this requirement, define the following macro.

ENABLE_EXECUTE_STACK

[Macro]

Define this macro if certain operations must be performed before executing code located on the stack. The macro should expand to a series of C file-scope constructs (e.g. functions) and provide a unique entry point named <code>__enable_execute_stack</code>. The target is responsible for emitting calls to the entry point in the code, for example from the <code>INITIALIZE_TRAMPOLINE</code> macro.

To use a standard subroutine, define the following macro. In addition, you must make sure that the instructions in a trampoline fill an entire cache line with identical instructions, or else ensure that the beginning of the trampoline code is always aligned at the same point in its cache line. Look in 'm68k.h' as a guide.

TRANSFER_FROM_TRAMPOLINE

[Macro]

Define this macro if trampolines need a special subroutine to do their work. The macro should expand to a series of asm statements which will be compiled with GCC. They go in a library function named __transfer_from_trampoline.

If you need to avoid executing the ordinary prologue code of a compiled C function when you jump to the subroutine, you can do so by placing a special label of your own in the assembler code. Use one asm statement to generate an assembler label, and another to make the label global. Then trampolines can use that label to jump directly to your special assembler code.

13.13 Implicit Calls to Library Routines

Here is an explanation of implicit calls to library routines.

DECLARE_LIBRARY_RENAMES

[Macro]

This macro, if defined, should expand to a piece of C code that will get expanded when compiling functions for libgcc.a. It can be used to provide alternate names for GCC's internal library functions if there are ABI-mandated names that the compiler should provide.

void TARGET_INIT_LIBFUNCS (void)

[Target Hook]

This hook should declare additional library routines or rename existing ones, using the functions set_optab_libfunc and init_one_libfunc defined in 'optabs.c'. init_optabs calls this macro after initializing all the normal library routines.

The default is to do nothing. Most ports don't need to define this hook.

FLOAT_LIB_COMPARE_RETURNS_BOOL (mode, comparison)

[Macro]

This macro should return **true** if the library routine that implements the floating point comparison operator *comparison* in mode *mode* will return a boolean, and *false* if it will return a tristate.

GCC's own floating point libraries return tristates from the comparison operators, so the default returns false always. Most ports don't need to define this macro.

TARGET_LIB_INT_CMP_BIASED

[Macro]

This macro should evaluate to **true** if the integer comparison functions (like $_$ cmpdi2) return 0 to indicate that the first operand is smaller than the second, 1 to indicate that they are equal, and 2 to indicate that the first operand is greater than the second. If this macro evalutes to false the comparison functions return -1, 0, and 1 instead of 0, 1, and 2. If the target uses the routines in 'libgcc.a', you do not need to define this macro.

US_SOFTWARE_GOFAST

[Macro]

Define this macro if your system C library uses the US Software GOFAST library to provide floating point emulation.

In addition to defining this macro, your architecture must set TARGET_INIT_LIBFUNCS to gofast_maybe_init_libfuncs, or else call that function from its version of that hook. It is defined in 'config/gofast.h', which must be included by your architecture's 'cpu.c' file. See 'sparc/sparc.c' for an example.

If this macro is defined, the TARGET_FLOAT_LIB_COMPARE_RETURNS_BOOL target hook must return false for SFmode and DFmode comparisons.

TARGET_EDOM [Macro]

The value of EDOM on the target machine, as a C integer constant expression. If you don't define this macro, GCC does not attempt to deposit the value of EDOM into errno directly. Look in '/usr/include/errno.h' to find the value of EDOM on your system.

If you do not define TARGET_EDOM, then compiled code reports domain errors by calling the library function and letting it report the error. If mathematical functions on your system use matherr when there is an error, then you should leave TARGET_EDOM undefined so that matherr is used normally.

GEN_ERRNO_RTX [Macro]

Define this macro as a C expression to create an rtl expression that refers to the global "variable" errno. (On certain systems, errno may not actually be a variable.) If you don't define this macro, a reasonable default is used.

TARGET_C99_FUNCTIONS

[Macro]

When this macro is nonzero, GCC will implicitly optimize sin calls into sinf and similarly for other functions defined by C99 standard. The default is nonzero that should be proper value for most modern systems, however number of existing systems lacks support for these functions in the runtime so they needs this macro to be redefined to 0.

NEXT_OBJC_RUNTIME

[Macro]

Define this macro to generate code for Objective-C message sending using the calling convention of the NeXT system. This calling convention involves passing the object, the selector and the method arguments all at once to the method-lookup library function.

The default calling convention passes just the object and the selector to the lookup function, which returns a pointer to the method.

13.14 Addressing Modes

This is about addressing modes.

HAVE_PRE_INCREMENT [Macro]
HAVE_PRE_DECREMENT [Macro]
HAVE_POST_INCREMENT [Macro]
HAVE_POST_DECREMENT [Macro]

A C expression that is nonzero if the machine supports pre-increment, pre-decrement, post-increment, or post-decrement addressing respectively.

HAVE_PRE_MODIFY_DISP HAVE_POST_MODIFY_DISP [Macro]

[Macro]

A C expression that is nonzero if the machine supports pre- or post-address side-effect generation involving constants other than the size of the memory operand.

HAVE_PRE_MODIFY_REG HAVE_POST_MODIFY_REG

[Macro]

[Macro]

A C expression that is nonzero if the machine supports pre- or post-address side-effect generation involving a register displacement.

CONSTANT_ADDRESS_P (x)

[Macro]

A C expression that is 1 if the RTX x is a constant which is a valid address. On most machines, this can be defined as CONSTANT_P (x), but a few machines are more restrictive in which constant addresses are supported.

$CONSTANT_P(x)$

[Macro]

CONSTANT_P, which is defined by target-independent code, accepts integer-values expressions whose values are not explicitly known, such as symbol_ref, label_ref, and high expressions and const arithmetic expressions, in addition to const_int and const_double expressions.

MAX_REGS_PER_ADDRESS

Macro

A number, the maximum number of registers that can appear in a valid memory address. Note that it is up to you to specify a value equal to the maximum number that GO_IF_LEGITIMATE_ADDRESS would ever accept.

GO_IF_LEGITIMATE_ADDRESS (mode, x, label)

[Macro]

A C compound statement with a conditional goto label; executed if x (an RTX) is a legitimate memory address on the target machine for a memory operand of mode mode.

It usually pays to define several simpler macros to serve as subroutines for this one. Otherwise it may be too complicated to understand.

This macro must exist in two variants: a strict variant and a non-strict one. The strict variant is used in the reload pass. It must be defined so that any pseudo-register that has not been allocated a hard register is considered a memory reference. In contexts where some kind of register is required, a pseudo-register with no hard register must be rejected.

The non-strict variant is used in other passes. It must be defined to accept all pseudoregisters in every context where some kind of register is required.

Compiler source files that want to use the strict variant of this macro define the macro REG_OK_STRICT. You should use an #ifdef REG_OK_STRICT conditional to define the strict variant in that case and the non-strict variant otherwise.

Subroutines to check for acceptable registers for various purposes (one for base registers, one for index registers, and so on) are typically among the subroutines used to define GO_IF_LEGITIMATE_ADDRESS. Then only these subroutine macros need have two variants; the higher levels of macros may be the same whether strict or not.

Normally, constant addresses which are the sum of a symbol_ref and an integer are stored inside a const RTX to mark them as constant. Therefore, there is no need to recognize such sums specifically as legitimate addresses. Normally you would simply recognize any const as legitimate.

Usually PRINT_OPERAND_ADDRESS is not prepared to handle constant sums that are not marked with const. It assumes that a naked plus indicates indexing. If so, then

you must reject such naked constant sums as illegitimate addresses, so that none of them will be given to PRINT_OPERAND_ADDRESS.

On some machines, whether a symbolic address is legitimate depends on the section that the address refers to. On these machines, define the target hook TARGET_ENCODE_SECTION_INFO to store the information into the symbol_ref, and then check for it here. When you see a const, you will have to look inside it to find the symbol_ref in order to determine the section. See Section 13.20 [Assembler Format], page 335.

$REG_OK_FOR_BASE_P(x)$

 $_{
m Macro}$

A C expression that is nonzero if x (assumed to be a reg RTX) is valid for use as a base register. For hard registers, it should always accept those which the hardware permits and reject the others. Whether the macro accepts or rejects pseudo registers must be controlled by REG_OK_STRICT as described above. This usually requires two variant definitions, of which REG_OK_STRICT controls the one actually used.

REG_MODE_OK_FOR_BASE_P (x, mode)

[Macro]

A C expression that is just like REG_OK_FOR_BASE_P, except that that expression may examine the mode of the memory reference in *mode*. You should define this macro if the mode of the memory reference affects whether a register may be used as a base register. If you define this macro, the compiler will use it instead of REG_OK_FOR_BASE P.

REG_MODE_OK_FOR_REG_BASE_P (x, mode)

[Macro]

A C expression which is nonzero if x (assumed to be a reg RTX) is suitable for use as a base register in base plus index operand addresses, accessing memory in mode mode. It may be either a suitable hard register or a pseudo register that has been allocated such a hard register. You should define this macro if base plus index addresses have different requirements than other base register uses.

REG OK FOR INDEX P (x)

[Macro]

A C expression that is nonzero if x (assumed to be a reg RTX) is valid for use as an index register.

The difference between an index register and a base register is that the index register may be scaled. If an address involves the sum of two registers, neither one of them scaled, then either one may be labeled the "base" and the other the "index"; but whichever labeling is used must fit the machine's constraints of which registers may serve in each capacity. The compiler will try both labelings, looking for one that is valid, and will reload one or both registers only if neither labeling works.

$FIND_BASE_TERM(x)$

[Macro]

A C expression to determine the base term of address x. This macro is used in only one place: 'find_base_term' in alias.c.

It is always safe for this macro to not be defined. It exists so that alias analysis can understand machine-dependent addresses.

The typical use of this macro is to handle addresses containing a label_ref or symbol_ref within an UNSPEC.

LEGITIMIZE_ADDRESS (x, oldx, mode, win)

[Macro]

A C compound statement that attempts to replace x with a valid memory address for an operand of mode mode. win will be a C statement label elsewhere in the code; the macro definition may use

```
GO_IF_LEGITIMATE_ADDRESS (mode, x, win);
```

to avoid further processing if the address has become legitimate.

x will always be the result of a call to break_out_memory_refs, and oldx will be the operand that was given to that function to produce x.

The code generated by this macro should not alter the substructure of x. If it transforms x into a more legitimate form, it should assign x (which will always be a C variable) a new value.

It is not necessary for this macro to come up with a legitimate address. The compiler has standard ways of doing so in all cases. In fact, it is safe to omit this macro. But often a machine-dependent strategy can generate better code.

LEGITIMIZE_RELOAD_ADDRESS (x, mode, opnum, type, ind_levels, win) [Macro] A C compound statement that attempts to replace x, which is an address that needs reloading, with a valid memory address for an operand of mode mode. win will be a C statement label elsewhere in the code. It is not necessary to define this macro, but

it might be useful for performance reasons.

For example, on the i386, it is sometimes possible to use a single reload register instead of two by reloading a sum of two pseudo registers into a register. On the other hand, for number of RISC processors offsets are limited so that often an intermediate address needs to be generated in order to address a stack slot. By defining LEGITIMIZE_RELOAD_ADDRESS appropriately, the intermediate addresses generated for adjacent some stack slots can be made identical, and thus be shared.

Note: This macro should be used with caution. It is necessary to know something of how reload works in order to effectively use this, and it is quite easy to produce macros that build in too much knowledge of reload internals.

Note: This macro must be able to reload an address created by a previous invocation of this macro. If it fails to handle such addresses then the compiler may generate incorrect code or abort.

The macro definition should use push_reload to indicate parts that need reloading; opnum, type and ind_levels are usually suitable to be passed unaltered to push_reload.

The code generated by this macro must not alter the substructure of x. If it transforms x into a more legitimate form, it should assign x (which will always be a C variable) a new value. This also applies to parts that you change indirectly by calling push_reload.

The macro definition may use strict_memory_address_p to test if the address has become legitimate.

If you want to change only a part of x, one standard way of doing this is to use copy_rtx. Note, however, that is unshares only a single level of rtl. Thus, if the part to be changed is not at the top level, you'll need to replace first the top level.

It is not necessary for this macro to come up with a legitimate address; but often a machine-dependent strategy can generate better code.

GO_IF_MODE_DEPENDENT_ADDRESS (addr, label)

[Macro]

A C statement or compound statement with a conditional goto label; executed if memory address x (an RTX) can have different meanings depending on the machine mode of the memory reference it is used for or if the address is valid for some modes but not others.

Autoincrement and autodecrement addresses typically have mode-dependent effects because the amount of the increment or decrement is the size of the operand being addressed. Some machines have other mode-dependent addresses. Many RISC machines have no mode-dependent addresses.

You may assume that addr is a valid address for the machine.

LEGITIMATE CONSTANT P (x)

[Macro]

A C expression that is nonzero if x is a legitimate constant for an immediate operand on the target machine. You can assume that x satisfies CONSTANT_P, so you need not check this. In fact, '1' is a suitable definition for this macro on machines where anything CONSTANT P is valid.

rtx TARGET_DELEGITIMIZE_ADDRESS (rtx x)

[Target Hook]

This hook is used to undo the possibly obfuscating effects of the LEGITIMIZE_ADDRESS and LEGITIMIZE_RELOAD_ADDRESS target macros. Some backend implementations of these macros wrap symbol references inside an UNSPEC rtx to represent PIC or similar addressing modes. This target hook allows GCC's optimizers to understand the semantics of these opaque UNSPECs by converting them back into their original form.

bool TARGET_CANNOT_FORCE_CONST_MEM (rtx x)

[Target Hook]

This hook should return true if x is of a form that cannot (or should not) be spilled to the constant pool. The default version of this hook returns false.

The primary reason to define this hook is to prevent reload from deciding that a non-legitimate constant would be better reloaded from the constant pool instead of spilling and reloading a register holding the constant. This restriction is often true of addresses of TLS symbols for various targets.

tree TARGET_VECTORIZE_BUILTIN_MASK_FOR_LOAD (void)

[Target Hook]

This hook should return the DECL of a function f that given an address addr as an argument returns a mask m that can be used to extract from two vectors the relevant data that resides in addr in case addr is not properly aligned.

The autovectrizer, when vectorizing a load operation from an address addr that may be unaligned, will generate two vector loads from the two aligned addresses around addr. It then generates a REALIGN_LOAD operation to extract the relevant data from the two loaded vectors. The first two arguments to REALIGN_LOAD, v1 and v2, are the two vectors, each of size VS, and the third argument, OFF, defines how the data will be extracted from these two vectors: if OFF is 0, then the returned vector is v2; otherwise, the returned vector is composed from the last VS-OFF elements of v1 concatenated to the first OFF elements of v2.

If this hook is defined, the autovectorizer will generate a call to f (using the DECL tree that this hook returns) and will use the return value of f as the argument OFF to REALIGN_LOAD. Therefore, the mask m returned by f should comply with the semantics expected by REALIGN_LOAD described above. If this hook is not defined, then addr will be used as the argument OFF to REALIGN_LOAD, in which case the low $\log 2(VS)$ -1 bits of addr will be considered.

13.15 Condition Code Status

This describes the condition code status.

The file 'conditions.h' defines a variable cc_status to describe how the condition code was computed (in case the interpretation of the condition code depends on the instruction that it was set by). This variable contains the RTL expressions on which the condition code is currently based, and several standard flags.

Sometimes additional machine-specific flags must be defined in the machine description header file. It can also add additional machine-specific information by defining CC_STATUS_MDEP.

CC_STATUS_MDEP [Macro]

C code for a data type which is used for declaring the mdep component of cc_status. It defaults to int.

This macro is not used on machines that do not use cc0.

CC_STATUS_MDEP_INIT

[Macro]

A C expression to initialize the mdep field to "empty". The default definition does nothing, since most machines don't use the field anyway. If you want to use the field, you should probably define this macro to initialize it.

This macro is not used on machines that do not use cc0.

NOTICE_UPDATE_CC (exp, insn)

[Macro]

A C compound statement to set the components of cc_status appropriately for an insn insn whose body is exp. It is this macro's responsibility to recognize insns that set the condition code as a byproduct of other activity as well as those that explicitly set (cc0).

This macro is not used on machines that do not use cc0.

If there are insns that do not set the condition code but do alter other machine registers, this macro must check to see whether they invalidate the expressions that the condition code is recorded as reflecting. For example, on the 68000, insns that store in address registers do not set the condition code, which means that usually NOTICE_UPDATE_CC can leave cc_status unaltered for such insns. But suppose that the previous insn set the condition code based on location 'a40(102)' and the current insn stores a new value in 'a4'. Although the condition code is not changed by this, it will no longer be true that it reflects the contents of 'a40(102)'. Therefore, NOTICE_UPDATE_CC must alter cc_status in this case to say that nothing is known about the condition code value.

The definition of NOTICE_UPDATE_CC must be prepared to deal with the results of peephole optimization: insns whose patterns are parallel RTXs containing various

reg, mem or constants which are just the operands. The RTL structure of these insns is not sufficient to indicate what the insns actually do. What NOTICE_UPDATE_CC should do when it sees one is just to run CC_STATUS_INIT.

A possible definition of NOTICE_UPDATE_CC is to call a function that looks at an attribute (see Section 12.19 [Insn Attributes], page 228) named, for example, 'cc'. This avoids having detailed information about patterns in two places, the 'md' file and in NOTICE_UPDATE_CC.

SELECT_CC_MODE (op, x, y)

[Macro]

Returns a mode from class MODE_CC to be used when comparison operation code op is applied to rtx x and y. For example, on the SPARC, SELECT_CC_MODE is defined as (see see Section 12.12 [Jump Patterns], page 213 for a description of the reason for this definition)

You should define this macro if and only if you define extra CC modes in 'machine-modes.def'.

CANONICALIZE_COMPARISON (code, op0, op1)

[Macro]

On some machines not all possible comparisons are defined, but you can convert an invalid comparison into a valid one. For example, the Alpha does not have a GT comparison, but you can use an LT comparison instead and swap the order of the operands.

On such machines, define this macro to be a C statement to do any required conversions. code is the initial comparison code and op0 and op1 are the left and right operands of the comparison, respectively. You should modify code, op0, and op1 as required.

GCC will not assume that the comparison resulting from this macro is valid but will see if the resulting insn matches a pattern in the 'md' file.

You need not define this macro if it would never change the comparison code or operands.

REVERSIBLE_CC_MODE (mode)

[Macro]

A C expression whose value is one if it is always safe to reverse a comparison whose mode is *mode*. If SELECT_CC_MODE can ever return *mode* for a floating-point inequality comparison, then REVERSIBLE_CC_MODE (*mode*) must be zero.

You need not define this macro if it would always returns zero or if the floating-point format is anything other than IEEE_FLOAT_FORMAT. For example, here is the definition used on the SPARC, where floating-point inequality comparisons are always given CCFPEmode:

#define REVERSIBLE_CC_MODE(MODE) ((MODE) != CCFPEmode)

REVERSE_CONDITION (code, mode)

[Macro]

A C expression whose value is reversed condition code of the *code* for comparison done in CC_MODE *mode*. The macro is used only in case REVERSIBLE_CC_MODE

(mode) is nonzero. Define this macro in case machine has some non-standard way how to reverse certain conditionals. For instance in case all floating point conditions are non-trapping, compiler may freely convert unordered compares to ordered one. Then definition may look like:

```
#define REVERSE_CONDITION(CODE, MODE) \
  ((MODE) != CCFPmode ? reverse_condition (CODE) \
    : reverse_condition_maybe_unordered (CODE))
```

REVERSE_CONDEXEC_PREDICATES_P (op1, op2)

[Macro]

A C expression that returns true if the conditional execution predicate op1, a comparison operation, is the inverse of op2 and vice versa. Define this to return 0 if the target has conditional execution predicates that cannot be reversed safely. There is no need to validate that the arguments of op1 and op2 are the same, this is done separately. If no expansion is specified, this macro is defined as follows:

```
#define REVERSE_CONDEXEC_PREDICATES_P (x, y) \
   (GET_CODE ((x)) == reversed_comparison_code ((y), NULL))
```

On targets which do not use (cc0), and which use a hard register rather than a pseudo-register to hold condition codes, the regular CSE passes are often not able to identify cases in which the hard register is set to a common value. Use this hook to enable a small pass which optimizes such cases. This hook should return true to enable this pass, and it should set the integers to which its arguments point to the hard register numbers used for condition codes. When there is only one such register, as is true on most systems, the integer pointed to by the second argument should be set to INVALID_REGNUM.

The default version of this hook returns false.

```
enum machine_mode TARGET_CC_MODES_COMPATIBLE (enum machine_mode, enum machine_mode) [Target Hook]
```

On targets which use multiple condition code modes in class MODE_CC, it is sometimes the case that a comparison can be validly done in more than one mode. On such a system, define this target hook to take two mode arguments and to return a mode in which both comparisons may be validly done. If there is no such mode, return VOIDmode.

The default version of this hook checks whether the modes are the same. If they are, it returns that mode. If they are different, it returns VOIDmode.

13.16 Describing Relative Costs of Operations

These macros let you describe the relative speed of various operations on the target machine.

```
REGISTER_MOVE_COST (mode, from, to)
```

[Macro]

A C expression for the cost of moving data of mode mode from a register in class from to one in class to. The classes are expressed using the enumeration values such as GENERAL_REGS. A value of 2 is the default; other values are interpreted relative to that.

It is not required that the cost always equal 2 when from is the same as to; on some machines it is expensive to move between registers if they are not general registers.

If reload sees an insn consisting of a single set between two hard registers, and if REGISTER_MOVE_COST applied to their classes returns a value of 2, reload does not check to ensure that the constraints of the insn are met. Setting a cost of other than 2 will allow reload to verify that the constraints are met. You should do this if the 'movm' pattern's constraints do not allow such copying.

MEMORY_MOVE_COST (mode, class, in)

[Macro]

A C expression for the cost of moving data of mode mode between a register of class class and memory; in is zero if the value is to be written to memory, nonzero if it is to be read in. This cost is relative to those in REGISTER_MOVE_COST. If moving between registers and memory is more expensive than between two registers, you should define this macro to express the relative cost.

If you do not define this macro, GCC uses a default cost of 4 plus the cost of copying via a secondary reload register, if one is needed. If your machine requires a secondary reload register to copy between memory and a register of class but the reload mechanism is more complex than copying via an intermediate, define this macro to reflect the actual cost of the move.

GCC defines the function memory_move_secondary_cost if secondary reloads are needed. It computes the costs due to copying via a secondary register. If your machine copies from memory using a secondary register in the conventional way but the default base value of 4 is not correct for your machine, define this macro to add some other value to the result of that function. The arguments to that function are the same as to this macro.

BRANCH_COST [Macro]

A C expression for the cost of a branch instruction. A value of 1 is the default; other values are interpreted relative to that.

Here are additional macros which do not specify precise relative costs, but only that certain actions are more expensive than GCC would ordinarily expect.

SLOW_BYTE_ACCESS [Macro]

Define this macro as a C expression which is nonzero if accessing less than a word of memory (i.e. a char or a short) is no faster than accessing a word of memory, i.e., if such access require more than one instruction or if there is no difference in cost between byte and (aligned) word loads.

When this macro is not defined, the compiler will access a field by finding the smallest containing object; when it is defined, a fullword load will be used if alignment permits. Unless bytes accesses are faster than word accesses, using word accesses is preferable since it may eliminate subsequent memory access if subsequent accesses occur to other fields in the same word of the structure, but to different bytes.

SLOW_UNALIGNED_ACCESS (mode, alignment)

Macro

Define this macro to be the value 1 if memory accesses described by the *mode* and alignment parameters have a cost many times greater than aligned accesses, for example if they are emulated in a trap handler.

When this macro is nonzero, the compiler will act as if STRICT_ALIGNMENT were nonzero when generating code for block moves. This can cause significantly more instructions to be produced. Therefore, do not set this macro nonzero if unaligned accesses only add a cycle or two to the time for a memory access.

If the value of this macro is always zero, it need not be defined. If this macro is defined, it should produce a nonzero value when STRICT_ALIGNMENT is nonzero.

MOVE_RATIO [Macro]

The threshold of number of scalar memory-to-memory move insns, below which a sequence of insns should be generated instead of a string move insn or a library call. Increasing the value will always make code faster, but eventually incurs high cost in increased code size.

Note that on machines where the corresponding move insn is a define_expand that emits a sequence of insns, this macro counts the number of such sequences.

If you don't define this, a reasonable default is used.

MOVE_BY_PIECES_P (size, alignment)

[Macro]

A C expression used to determine whether move_by_pieces will be used to copy a chunk of memory, or whether some other block move mechanism will be used. Defaults to 1 if move_by_pieces_ninsns returns less than MOVE_RATIO.

MOVE_MAX_PIECES [Macro]

A C expression used by move_by_pieces to determine the largest unit a load or store used to copy memory is. Defaults to MOVE_MAX.

CLEAR_RATIO [Macro]

The threshold of number of scalar move insns, below which a sequence of insns should be generated to clear memory instead of a string clear insn or a library call. Increasing the value will always make code faster, but eventually incurs high cost in increased code size.

If you don't define this, a reasonable default is used.

CLEAR BY PIECES P (size, alignment)

[Macro]

A C expression used to determine whether clear_by_pieces will be used to clear a chunk of memory, or whether some other block clear mechanism will be used. Defaults to 1 if move_by_pieces_ninsns returns less than CLEAR_RATIO.

STORE_BY_PIECES_P (size, alignment)

[Macro]

A C expression used to determine whether store_by_pieces will be used to set a chunk of memory to a constant value, or whether some other mechanism will be used. Used by __builtin_memset when storing values other than constant zero and by __builtin_strcpy when when called with a constant source string. Defaults to to 1 if move_by_pieces_ninsns returns less than MOVE_RATIO.

USE_LOAD_POST_INCREMENT (mode)

[Macro]

A C expression used to determine whether a load postincrement is a good thing to use for a given mode. Defaults to the value of HAVE_POST_INCREMENT.

USE_LOAD_POST_DECREMENT (mode)

[Macro]

A C expression used to determine whether a load postdecrement is a good thing to use for a given mode. Defaults to the value of HAVE_POST_DECREMENT.

USE_LOAD_PRE_INCREMENT (mode)

Macro

A C expression used to determine whether a load preincrement is a good thing to use for a given mode. Defaults to the value of HAVE_PRE_INCREMENT.

USE_LOAD_PRE_DECREMENT (mode)

[Macro]

A C expression used to determine whether a load predecrement is a good thing to use for a given mode. Defaults to the value of HAVE_PRE_DECREMENT.

USE_STORE_POST_INCREMENT (mode)

[Macro]

A C expression used to determine whether a store postincrement is a good thing to use for a given mode. Defaults to the value of HAVE_POST_INCREMENT.

USE_STORE_POST_DECREMENT (mode)

[Macro]

A C expression used to determine whether a store postdecrement is a good thing to use for a given mode. Defaults to the value of HAVE_POST_DECREMENT.

USE_STORE_PRE_INCREMENT (mode)

[Macro]

This macro is used to determine whether a store preincrement is a good thing to use for a given mode. Defaults to the value of HAVE_PRE_INCREMENT.

USE_STORE_PRE_DECREMENT (mode)

[Macro]

This macro is used to determine whether a store predecrement is a good thing to use for a given mode. Defaults to the value of HAVE_PRE_DECREMENT.

NO FUNCTION CSE

[Macro]

Define this macro if it is as good or better to call a constant function address than to call an address kept in a register.

RANGE TEST NON SHORT CIRCUIT

[Macro]

Define this macro if a non-short-circuit operation produced by 'fold_range_test ()' is optimal. This macro defaults to true if BRANCH_COST is greater than or equal to the value 2.

[Target Hook]

This target hook describes the relative costs of RTL expressions.

The cost may depend on the precise form of the expression, which is available for examination in x, and the rtx code of the expression in which it is contained, found in $outer_code$. code is the expression code—redundant, since it can be obtained with GET_CODE (x).

In implementing this hook, you can use the construct $COSTS_N_INSNS$ (n) to specify a cost equal to n fast instructions.

On entry to the hook, *total contains a default estimate for the cost of the expression. The hook should modify this value as necessary. Traditionally, the default costs are COSTS_N_INSNS (5) for multiplications, COSTS_N_INSNS (7) for division and modulus operations, and COSTS_N_INSNS (1) for all other operations.

When optimizing for code size, i.e. when optimize_size is nonzero, this target hook should be used to estimate the relative size cost of an expression, again relative to COSTS_N_INSNS.

The hook returns true when all subexpressions of x have been processed, and false when rtx_cost should recurse.

int TARGET_ADDRESS_COST (rtx address)

[Target Hook]

This hook computes the cost of an addressing mode that contains address. If not defined, the cost is computed from the address expression and the TARGET_RTX_COST hook.

For most CISC machines, the default cost is a good approximation of the true cost of the addressing mode. However, on RISC machines, all instructions normally have the same length and execution time. Hence all addresses will have equal costs.

In cases where more than one form of an address is known, the form with the lowest cost will be used. If multiple forms have the same, lowest, cost, the one that is the most complex will be used.

For example, suppose an address that is equal to the sum of a register and a constant is used twice in the same basic block. When this macro is not defined, the address will be computed in a register and memory references will be indirect through that register. On machines where the cost of the addressing mode containing the sum is no higher than that of a simple indirect reference, this will produce an additional instruction and possibly require an additional register. Proper specification of this macro eliminates this overhead for such machines.

This hook is never called with an invalid address.

On machines where an address involving more than one register is as cheap as an address computation involving only one register, defining TARGET_ADDRESS_COST to reflect this can cause two registers to be live over a region of code where only one would have been if TARGET_ADDRESS_COST were not defined in that manner. This effect should be considered in the definition of this macro. Equivalent costs should probably only be given to addresses with different numbers of registers on machines with lots of registers.

13.17 Adjusting the Instruction Scheduler

The instruction scheduler may need a fair amount of machine-specific adjustment in order to produce good code. GCC provides several target hooks for this purpose. It is usually enough to define just a few of them: try the first ones in this list first.

int TARGET_SCHED_ISSUE_RATE (void)

[Target Hook]

This hook returns the maximum number of instructions that can ever issue at the same time on the target machine. The default is one. Although the insn scheduler can define itself the possibility of issue an insn on the same cycle, the value can serve as an additional constraint to issue insns on the same simulated processor cycle (see hooks 'TARGET_SCHED_REORDER' and 'TARGET_SCHED_REORDER2'). This value must be constant over the entire compilation. If you need it to vary depending on what the instructions are, you must use 'TARGET_SCHED_VARIABLE_ISSUE'.

You could define this hook to return the value of the macro MAX_DFA_ISSUE_RATE.

int TARGET_SCHED_VARIABLE_ISSUE (FILE *file, int verbose, rtx insn, int more) [Target Hook]

This hook is executed by the scheduler after it has scheduled an insn from the ready list. It should return the number of insns which can still be issued in the current cycle. The default is 'more - 1' for insns other than CLOBBER and USE, which normally are not counted against the issue rate. You should define this hook if some insns take more machine resources than others, so that fewer insns can follow them in the same cycle. file is either a null pointer, or a stdio stream to write any debug output to. verbose is the verbose level provided by '-fsched-verbose-n'. insn is the instruction that was scheduled.

int TARGET_SCHED_ADJUST_COST (rtx insn, rtx link, rtx dep_insn, int cost) [Target Hook]

This function corrects the value of cost based on the relationship between insn and dep_insn through the dependence link. It should return the new value. The default is to make no adjustment to cost. This can be used for example to specify to the scheduler using the traditional pipeline description that an output- or anti-dependence does not incur the same cost as a data-dependence. If the scheduler using the automaton based pipeline description, the cost of anti-dependence is zero and the cost of output-dependence is maximum of one and the difference of latency times of the first and the second insns. If these values are not acceptable, you could use the hook to modify them too. See also see Section 12.19.8 [Processor pipeline description], page 236.

int TARGET_SCHED_ADJUST_PRIORITY (rtx insn, int priority) [Target Hook] This hook adjusts the integer scheduling priority priority of insn. It should return the new priority. Reduce the priority to execute insn earlier, increase the priority to execute insn later. Do not define this hook if you do not need to adjust the scheduling priorities of insns.

This hook is executed by the scheduler after it has scheduled the ready list, to allow the machine description to reorder it (for example to combine two small instructions together on 'VLIW' machines). file is either a null pointer, or a stdio stream to write any debug output to. verbose is the verbose level provided by '-fsched-verbose-n'. ready is a pointer to the ready list of instructions that are ready to be scheduled. n_readyp is a pointer to the number of elements in the ready list. The scheduler reads the ready list in reverse order, starting with ready[*n_readyp-1] and going to ready[0]. clock is the timer tick of the scheduler. You may modify the ready list and the number of ready insns. The return value is the number of insns that can issue this cycle; normally this is just issue_rate. See also 'TARGET_SCHED_REORDER2'.

Like 'TARGET_SCHED_REORDER', but called at a different time. That function is called whenever the scheduler starts a new cycle. This one is called once per iteration over a cycle, immediately after 'TARGET_SCHED_VARIABLE_ISSUE'; it can reorder the ready list and return the number of insns to be scheduled in the same cycle. Defining this

hook can be useful if there are frequent situations where scheduling one inso causes other insons to become ready in the same cycle. These other insons can then be taken into account properly.

void TARGET_SCHED_DEPENDENCIES_EVALUATION_HOOK (rtx head, rtx tail) [Target Hook]

This hook is called after evaluation forward dependencies of insns in chain given by two parameter values (head and tail correspondingly) but before insns scheduling of the insn chain. For example, it can be used for better insn classification if it requires analysis of dependencies. This hook can use backward and forward dependencies of the insn scheduler because they are already calculated.

This hook is executed by the scheduler at the beginning of each block of instructions that are to be scheduled. *file* is either a null pointer, or a stdio stream to write any debug output to. *verbose* is the verbose level provided by '-fsched-verbose-n'. *max_ready* is the maximum number of insns in the current scheduling region that can be live at the same time. This can be used to allocate scratch space if it is needed, e.g. by 'TARGET_SCHED_REORDER'.

void TARGET_SCHED_FINISH (FILE *file, int verbose) [Target Hook]

This hook is executed by the scheduler at the end of each block of instructions that are to be scheduled. It can be used to perform cleanup of any actions done by the other scheduling hooks. *file* is either a null pointer, or a stdio stream to write any debug output to. *verbose* is the verbose level provided by '-fsched-verbose-n'.

This hook is executed by the scheduler after function level initializations. file is either a null pointer, or a stdio stream to write any debug output to. verbose is the verbose level provided by '-fsched-verbose-n'. old_max_uid is the maximum insn uid when scheduling begins.

void TARGET_SCHED_FINISH_GLOBAL (FILE *file, int verbose) [Target Hook]

This is the cleanup hook corresponding to TARGET_SCHED_INIT_GLOBAL. file is either a null pointer, or a stdio stream to write any debug output to. verbose is the verbose level provided by '-fsched-verbose-n'.

int TARGET_SCHED_DFA_PRE_CYCLE_INSN (void) [Target Hook]

The hook returns an RTL insn. The automaton state used in the pipeline hazard recognizer is changed as if the insn were scheduled when the new simulated processor cycle starts. Usage of the hook may simplify the automaton pipeline description for some VLIW processors. If the hook is defined, it is used only for the automaton based pipeline description. The default is not to change the state when the new simulated processor cycle starts.

void TARGET_SCHED_INIT_DFA_PRE_CYCLE_INSN (void) [Target Hook] The hook can be used to initialize data used by the previous hook.

int TARGET_SCHED_DFA_POST_CYCLE_INSN (void)

[Target Hook]

The hook is analogous to 'TARGET_SCHED_DFA_PRE_CYCLE_INSN' but used to changed the state as if the insn were scheduled when the new simulated processor cycle finishes.

void TARGET_SCHED_INIT_DFA_POST_CYCLE_INSN (void)

[Target Hook]

The hook is analogous to 'TARGET_SCHED_INIT_DFA_PRE_CYCLE_INSN' but used to initialize data used by the previous hook.

int TARGET_SCHED_FIRST_CYCLE_MULTIPASS_DFA_LOOKAHEAD [Target Hook] (void)

This hook controls better choosing an insn from the ready insn queue for the DFA-based insn scheduler. Usually the scheduler chooses the first insn from the queue. If the hook returns a positive value, an additional scheduler code tries all permutations of 'TARGET_SCHED_FIRST_CYCLE_MULTIPASS_DFA_LOOKAHEAD ()' subsequent ready insns to choose an insn whose issue will result in maximal number of issued insns on the same cycle. For the VLIW processor, the code could actually solve the problem of packing simple insns into the VLIW insn. Of course, if the rules of VLIW packing are described in the automaton.

This code also could be used for superscalar RISC processors. Let us consider a superscalar RISC processor with 3 pipelines. Some insns can be executed in pipelines A or B, some insns can be executed only in pipelines B or C, and one insn can be executed in pipeline B. The processor may issue the 1st insn into A and the 2nd one into B. In this case, the 3rd insn will wait for freeing B until the next cycle. If the scheduler issues the 3rd insn the first, the processor could issue all 3 insns per cycle. Actually this code demonstrates advantages of the automaton based pipeline hazard recognizer. We try quickly and easy many insn schedules to choose the best one. The default is no multipass scheduling.

int

[Target Hook]

TARGET_SCHED_FIRST_CYCLE_MULTIPASS_DFA_LOOKAHEAD_GUARD (rtx)

This hook controls what insns from the ready insn queue will be considered for the multipass insn scheduling. If the hook returns zero for insn passed as the parameter, the insn will be not chosen to be issued.

The default is that any ready insist can be chosen to be issued.

This hook is called by the insn scheduler before issuing insn passed as the third parameter on given cycle. If the hook returns nonzero, the insn is not issued on given processors cycle. Instead of that, the processor cycle is advanced. If the value passed through the last parameter is zero, the insn ready queue is not sorted on the new cycle start as usually. The first parameter passes file for debugging output. The second one passes the scheduler verbose level of the debugging output. The forth and the fifth parameter values are correspondingly processor cycle on which the previous insn has been issued and the current processor cycle.

This hook is used to define which dependences are considered costly by the target, so costly that it is not advisable to schedule the insns that are involved in the de-

pendence too close to one another. The parameters to this hook are as follows: The second parameter insn2 is dependent upon the first parameter insn1. The dependence between insn1 and insn2 is represented by the third parameter dep_link . The fourth parameter cost is the cost of the dependence, and the fifth parameter distance is the distance in cycles between the two insns. The hook returns true if considering the distance between the two insns the dependence between them is considered costly by the target, and false otherwise.

Defining this hook can be useful in multiple-issue out-of-order machines, where (a) it's practically hopeless to predict the actual data/resource delays, however: (b) there's a better chance to predict the actual grouping that will be formed, and (c) correctly emulating the grouping can be very important. In such targets one may want to allow issuing dependent insns closer to one another—i.e., closer than the dependence distance; however, not in cases of "costly dependences", which this hooks allows to define.

Macros in the following table are generated by the program 'genattr' and can be useful for writing the hooks.

MAX DFA ISSUE RATE

[Macro]

The macro definition is generated in the automaton based pipeline description interface. Its value is calculated from the automaton based pipeline description and is equal to maximal number of all insns described in constructions 'define_insn_reservation' which can be issued on the same processor cycle.

13.18 Dividing the Output into Sections (Texts, Data, ...)

An object file is divided into sections containing different types of data. In the most common case, there are three sections: the *text section*, which holds instructions and read-only data; the *data section*, which holds initialized writable data; and the *bss section*, which holds uninitialized data. Some systems have other kinds of sections.

The compiler must tell the assembler when to switch sections. These macros control what commands to output to tell the assembler this. You can also define additional sections.

TEXT_SECTION_ASM_OP

Macro

A C expression whose value is a string, including spacing, containing the assembler operation that should precede instructions and read-only data. Normally "\t.text" is right.

HOT_TEXT_SECTION_NAME

[Macro]

If defined, a C string constant for the name of the section containing most frequently executed functions of the program. If not defined, GCC will provide a default definition if the target supports named sections.

UNLIKELY_EXECUTED_TEXT_SECTION_NAME

[Macro]

If defined, a C string constant for the name of the section containing unlikely executed functions in the program.

DATA_SECTION_ASM_OP

[Macro]

A C expression whose value is a string, including spacing, containing the assembler operation to identify the following data as writable initialized data. Normally "\t.data" is right.

READONLY_DATA_SECTION_ASM_OP

[Macro]

A C expression whose value is a string, including spacing, containing the assembler operation to identify the following data as read-only initialized data.

READONLY_DATA_SECTION

[Macro]

A macro naming a function to call to switch to the proper section for read-only data. The default is to use READONLY_DATA_SECTION_ASM_OP if defined, else fall back to text_section.

The most common definition will be data_section, if the target does not have a special read-only data section, and does not put data in the text section.

BSS_SECTION_ASM_OP

[Macro]

If defined, a C expression whose value is a string, including spacing, containing the assembler operation to identify the following data as uninitialized global data. If not defined, and neither ASM_OUTPUT_BSS nor ASM_OUTPUT_ALIGNED_BSS are defined, uninitialized global data will be output in the data section if '-fno-common' is passed, otherwise ASM_OUTPUT_COMMON will be used.

INIT SECTION ASM OP

[Macro]

If defined, a C expression whose value is a string, including spacing, containing the assembler operation to identify the following data as initialization code. If not defined, GCC will assume such a section does not exist.

FINI SECTION ASM OP

[Macro]

If defined, a C expression whose value is a string, including spacing, containing the assembler operation to identify the following data as finalization code. If not defined, GCC will assume such a section does not exist.

CRT_CALL_STATIC_FUNCTION (section_op, function)

[Macro]

If defined, an ASM statement that switches to a different section via $section_op$, calls function, and switches back to the text section. This is used in 'crtstuff.c' if INIT_SECTION_ASM_OP or FINI_SECTION_ASM_OP to calls to initialization and finalization functions from the init and fini sections. By default, this macro uses a simple function call. Some ports need hand-crafted assembly code to avoid dependencies on registers initialized in the function prologue or to ensure that constant pools don't end up too far way in the text section.

FORCE_CODE_SECTION_ALIGN

[Macro]

If defined, an ASM statement that aligns a code section to some arbitrary boundary. This is used to force all fragments of the .init and .fini sections to have to same alignment and thus prevent the linker from having to add any padding.

EXTRA_SECTIONS

[Macro]

A list of names for sections other than the standard two, which are in_text and in_data. You need not define this macro on a system with no other sections (that GCC needs to use).

EXTRA_SECTION_FUNCTIONS

[Macro]

One or more functions to be defined in 'varasm.c'. These functions should do jobs analogous to those of text_section and data_section, for your additional sections. Do not define this macro if you do not define EXTRA_SECTIONS.

JUMP_TABLES_IN_TEXT_SECTION

[Macro]

Define this macro to be an expression with a nonzero value if jump tables (for tablejump insns) should be output in the text section, along with the assembler instructions. Otherwise, the readonly data section is used.

This macro is irrelevant if there is no separate readonly data section.

Switches to the appropriate section for output of exp. You can assume that exp is either a VAR_DECL node or a constant of some sort. reloc indicates whether the initial value of exp requires link-time relocations. Bit 0 is set when variable contains local relocations only, while bit 1 is set for global relocations. Select the section by calling data_section or one of the alternatives for other sections. align is the constant alignment in bits.

The default version of this function takes care of putting read-only variables in readonly_data_section.

See also USE_SELECT_SECTION_FOR_FUNCTIONS.

USE_SELECT_SECTION_FOR_FUNCTIONS

[Macro]

Define this macro if you wish TARGET_ASM_SELECT_SECTION to be called for FUNCTION_DECLs as well as for variables and constants.

In the case of a FUNCTION_DECL, reloc will be zero if the function has been determined to be likely to be called, and nonzero if it is unlikely to be called.

void TARGET_ASM_UNIQUE_SECTION (tree dec1, int reloc) [Target Hook] Build up a unique section name, expressed as a STRING_CST node, and assign it to 'DECL_SECTION_NAME (dec1)'. As with TARGET_ASM_SELECT_SECTION, reloc indicates whether the initial value of exp requires link-time relocations.

The default version of this function appends the symbol name to the ELF section name that would normally be used for the symbol. For example, the function foo would be placed in .text.foo. Whatever the actual target object format, this is often good enough.

void TARGET_ASM_FUNCTION_RODATA_SECTION (tree decl) [Target Hook] Switches to a readonly data section associated with 'DECL_SECTION_NAME (decl)'. The default version of this function switches to .gnu.linkonce.r.name section if function's section is .gnu.linkonce.t.name, to .rodata.name if function is in .text.name section and otherwise switches to the normal readonly data section.

Switches to the appropriate section for output of constant pool entry x in mode. You can assume that x is some kind of constant in RTL. The argument mode is redundant

except in the case of a const_int rtx. Select the section by calling readonly_data_section or one of the alternatives for other sections. align is the constant alignment in bits.

The default version of this function takes care of putting symbolic constants in flag_pic mode in data_section and everything else in readonly_data_section.

Define this hook if references to a symbol or a constant must be treated differently depending on something about the variable or function named by the symbol (such as what section it is in).

The hook is executed immediately after rtl has been created for decl, which may be a variable or function declaration or an entry in the constant pool. In either case, rtl is the rtl in question. Do not use DECL_RTL (decl) in this hook; that field may not have been initialized yet.

In the case of a constant, it is safe to assume that the rtl is a mem whose address is a symbol_ref. Most decls will also have this form, but that is not guaranteed. Global register variables, for instance, will have a reg for their rtl. (Normally the right thing to do with such unusual rtl is leave it alone.)

The new_decl_p argument will be true if this is the first time that TARGET_ENCODE_SECTION_INFO has been invoked on this decl. It will be false for subsequent invocations, which will happen for duplicate declarations. Whether or not anything must be done for the duplicate declaration depends on whether the hook examines DECL_ATTRIBUTES. new_decl_p is always true when the hook is called for a constant.

The usual thing for this hook to do is to record flags in the <code>symbol_ref</code>, using <code>SYMBOL_REF_FLAG</code> or <code>SYMBOL_REF_FLAGS</code>. Historically, the name string was modified if it was necessary to encode more than one bit of information, but this practice is now discouraged; use <code>SYMBOL_REF_FLAGS</code>.

The default definition of this hook, default_encode_section_info in 'varasm.c', sets a number of commonly-useful bits in SYMBOL_REF_FLAGS. Check whether the default does what you need before overriding it.

Decode name and return the real name part, sans the characters that TARGET_ENCODE_SECTION_INFO may have added.

bool TARGET_IN_SMALL_DATA_P (tree exp) [Target Hook] Returns true if exp should be placed into a "small data" section. The default version of this hook always returns false.

Target Hook bool TARGET_HAVE_SRODATA_SECTION [Variable] Contains the value true if the target places read-only "small data" into a separate section. The default value is false.

bool TARGET_BINDS_LOCAL_P (tree exp) [Target Hook] Returns true if exp names an object for which name resolution rules must resolve to the current "module" (dynamic shared library or executable image).

The default version of this hook implements the name resolution rules for ELF, which has a looser model of global name binding than other currently supported object file formats.

Target Hook bool TARGET_HAVE_TLS

[Variable]

Contains the value true if the target supports thread-local storage. The default value is false.

13.19 Position Independent Code

This section describes macros that help implement generation of position independent code. Simply defining these macros is not enough to generate valid PIC; you must also add support to the macros GO_IF_LEGITIMATE_ADDRESS and PRINT_OPERAND_ADDRESS, as well as LEGITIMIZE_ADDRESS. You must modify the definition of 'movsi' to do something appropriate when the source operand contains a symbolic address. You may also need to alter the handling of switch statements so that they use relative addresses.

PIC_OFFSET_TABLE_REGNUM

[Macro]

The register number of the register used to address a table of static data addresses in memory. In some cases this register is defined by a processor's "application binary interface" (ABI). When this macro is defined, RTL is generated for this register once, as with the stack pointer and frame pointer registers. If this macro is not defined, it is up to the machine-dependent files to allocate such a register (if necessary). Note that this register must be fixed when in use (e.g. when flag_pic is true).

PIC_OFFSET_TABLE_REG_CALL_CLOBBERED

[Macro]

Define this macro if the register defined by PIC_OFFSET_TABLE_REGNUM is clobbered by calls. Do not define this macro if PIC_OFFSET_TABLE_REGNUM is not defined.

FINALIZE_PIC [Macro]

By generating position-independent code, when two different programs (A and B) share a common library (libC.a), the text of the library can be shared whether or not the library is linked at the same address for both programs. In some of these environments, position-independent code requires not only the use of different addressing modes, but also special code to enable the use of these addressing modes.

The FINALIZE_PIC macro serves as a hook to emit these special codes once the function is being compiled into assembly code, but not before. (It is not done before, because in the case of compiling an inline function, it would lead to multiple PIC prologues being included in functions which used inline functions and were compiled to assembly language.)

LEGITIMATE_PIC_OPERAND_P (x)

Macro

A C expression that is nonzero if x is a legitimate immediate operand on the target machine when generating position independent code. You can assume that x satisfies CONSTANT_P, so you need not check this. You can also assume $flag_pic$ is true, so you need not check it either. You need not define this macro if all constants (including SYMBOL_REF) can be immediate operands when generating position independent code.

13.20 Defining the Output Assembler Language

This section describes macros whose principal purpose is to describe how to write instructions in assembler language—rather than what the instructions do.

13.20.1 The Overall Framework of an Assembler File

This describes the overall framework of an assembly file.

void TARGET_ASM_FILE_START ()

[Target Hook]

Output to asm_out_file any text which the assembler expects to find at the beginning of a file. The default behavior is controlled by two flags, documented below. Unless your target's assembler is quite unusual, if you override the default, you should call default_file_start at some point in your target hook. This lets other target files rely on these variables.

bool TARGET_ASM_FILE_START_APP_OFF

[Target Hook]

If this flag is true, the text of the macro ASM_APP_OFF will be printed as the very first line in the assembly file, unless '-fverbose-asm' is in effect. (If that macro has been defined to the empty string, this variable has no effect.) With the normal definition of ASM_APP_OFF, the effect is to notify the GNU assembler that it need not bother stripping comments or extra whitespace from its input. This allows it to work a bit faster.

The default is false. You should not set it to true unless you have verified that your port does not generate any extra whitespace or comments that will cause GAS to issue errors in NO_APP mode.

bool TARGET_ASM_FILE_START_FILE_DIRECTIVE

[Target Hook]

If this flag is true, output_file_directive will be called for the primary source file, immediately after printing ASM_APP_OFF (if that is enabled). Most ELF assemblers expect this to be done. The default is false.

void TARGET_ASM_FILE_END ()

[Target Hook]

Output to asm_out_file any text which the assembler expects to find at the end of a file. The default is to output nothing.

void file_end_indicate_exec_stack ()

[Function]

Some systems use a common convention, the '.note.GNU-stack' special section, to indicate whether or not an object file relies on the stack being executable. If your system uses this convention, you should define TARGET_ASM_FILE_END to this function. If you need to do other things in that hook, have your hook function call this function.

ASM COMMENT START

[Macro]

A C string constant describing how to begin a comment in the target assembler language. The compiler assumes that the comment will end at the end of the line.

ASM APP ON

Macro

A C string constant for text to be output before each asm statement or group of consecutive ones. Normally this is "#APP", which is a comment that has no effect on most assemblers but tells the GNU assembler that it must check the lines that follow for all valid assembler constructs.

ASM_APP_OFF [Macro]

A C string constant for text to be output after each asm statement or group of consecutive ones. Normally this is "#NO_APP", which tells the GNU assembler to resume making the time-saving assumptions that are valid for ordinary compiler output.

ASM_OUTPUT_SOURCE_FILENAME (stream, name)

Macro

A C statement to output COFF information or DWARF debugging information which indicates that filename name is the current source file to the stdio stream stream.

This macro need not be defined if the standard form of output for the file format in use is appropriate.

OUTPUT_QUOTED_STRING (stream, string)

[Macro]

A C statement to output the string string to the stdio stream stream. If you do not call the function output_quoted_string in your config files, GCC will only call it to output filenames to the assembler source. So you can use it to canonicalize the format of the filename using this macro.

ASM_OUTPUT_IDENT (stream, string)

[Macro]

A C statement to output something to the assembler file to handle a '#ident' directive containing the text string. If this macro is not defined, nothing is output for a '#ident' directive.

Output assembly directives to switch to section name. The section should have attributes as specified by flags, which is a bit mask of the SECTION_* flags defined in 'output.h'. If align is nonzero, it contains an alignment in bytes to be used for the section, otherwise some target default should be used. Only targets that must specify an alignment within the section directive need pay attention to align — we will still use ASM_OUTPUT_ALIGN.

bool TARGET_HAVE_NAMED_SECTIONS

[Target Hook]

This flag is true if the target supports TARGET_ASM_NAMED_SECTION.

unsigned int TARGET_SECTION_TYPE_FLAGS (tree dec1, const [Target Hook] char *name, int reloc)

Choose a set of section attributes for use by TARGET_ASM_NAMED_SECTION based on a variable or function decl, a section name, and whether or not the declaration's initializer may contain runtime relocations. *decl* may be null, in which case readwrite data should be assumed.

The default version if this function handles choosing code vs data, read-only vs read-write data, and flag_pic. You should only need to override this if your target has special flags that might be set via __attribute__.

13.20.2 Output of Data

const char	*	TARGET_ASM_BYTE_OP	[Target Hook]
const char	*	TARGET_ASM_ALIGNED_HI_OP	[Target Hook]
const char	*	TARGET_ASM_ALIGNED_SI_OP	[Target Hook]
const char	*	TARGET_ASM_ALIGNED_DI_OP	[Target Hook]
const char	*	TARGET_ASM_ALIGNED_TI_OP	[Target Hook]
const char	*	TARGET_ASM_UNALIGNED_HI_OP	[Target Hook]
const char	*	TARGET_ASM_UNALIGNED_SI_OP	[Target Hook]
const char	*	TARGET_ASM_UNALIGNED_DI_OP	[Target Hook]
const char	*	TARGET_ASM_UNALIGNED_TI_OP	[Target Hook]

These hooks specify assembly directives for creating certain kinds of integer object. The TARGET_ASM_BYTE_OP directive creates a byte-sized object, the TARGET_ASM_ALIGNED_HI_OP one creates an aligned two-byte object, and so on. Any of the hooks may be NULL, indicating that no suitable directive is available.

The compiler will print these strings at the start of a new line, followed immediately by the object's initial value. In most cases, the string should contain a tab, a pseudo-op, and then another tab.

bool TARGET_ASM_INTEGER (rtx x, unsigned int size, int aligned_p) [Target Hook]

The assemble_integer function uses this hook to output an integer object. x is the object's value, size is its size in bytes and aligned_p indicates whether it is aligned. The function should return true if it was able to output the object. If it returns false, assemble_integer will try to split the object into smaller parts.

The default implementation of this hook will use the TARGET_ASM_BYTE_OP family of strings, returning false when the relevant string is NULL.

OUTPUT_ADDR_CONST_EXTRA (stream, x, fail)

[Macro]

A C statement to recognize rtx patterns that $output_addr_const$ can't deal with, and output assembly code to stream corresponding to the pattern x. This may be used to allow machine-dependent UNSPECs to appear within constants.

If OUTPUT_ADDR_CONST_EXTRA fails to recognize a pattern, it must goto fail, so that a standard error message is printed. If it prints an error message itself, by calling, for example, output_operand_lossage, it may just complete normally.

ASM_OUTPUT_ASCII (stream, ptr, len)

[Macro]

A C statement to output to the stdio stream stream an assembler instruction to assemble a string constant containing the len bytes at ptr. ptr will be a C expression of type char * and len a C expression of type int.

If the assembler has a .ascii pseudo-op as found in the Berkeley Unix assembler, do not define the macro ASM_OUTPUT_ASCII.

ASM_OUTPUT_FDESC (stream, decl, n)

[Macro]

A C statement to output word n of a function descriptor for decl. This must be defined if TARGET_VTABLE_USES_DESCRIPTORS is defined, and is otherwise unused.

CONSTANT_POOL_BEFORE_FUNCTION

[Macro]

You may define this macro as a C expression. You should define the expression to have a nonzero value if GCC should output the constant pool for a function before the code for the function, or a zero value if GCC should output the constant pool after the function. If you do not define this macro, the usual case, GCC will output the constant pool before the function.

ASM_OUTPUT_POOL_PROLOGUE (file, funname, fundecl, size)

[Macro]

A C statement to output assembler commands to define the start of the constant pool for a function. funname is a string giving the name of the function. Should the return type of the function be required, it can be obtained via fundecl. size is the size, in bytes, of the constant pool that will be written immediately after this call.

If no constant-pool prefix is required, the usual case, this macro need not be defined.

ASM_OUTPUT_SPECIAL_POOL_ENTRY (file, x, mode, align, labelno, jumpto) [Macro]

A C statement (with or without semicolon) to output a constant in the constant pool, if it needs special treatment. (This macro need not do anything for RTL expressions that can be output normally.)

The argument file is the standard I/O stream to output the assembler code on. x is the RTL expression for the constant to output, and mode is the machine mode (in case x is a 'const_int'). align is the required alignment for the value x; you should output an assembler directive to force this much alignment.

The argument *labelno* is a number to use in an internal label for the address of this pool entry. The definition of this macro is responsible for outputting the label definition at the proper place. Here is how to do this:

```
(*targetm.asm_out.internal_label) (file, "LC", labelno);
```

When you output a pool entry specially, you should end with a **goto** to the label *jumpto*. This will prevent the same pool entry from being output a second time in the usual manner.

You need not define this macro if it would do nothing.

ASM_OUTPUT_POOL_EPILOGUE (file funname fundecl size)

[Macro]

A C statement to output assembler commands to at the end of the constant pool for a function. funname is a string giving the name of the function. Should the return type of the function be required, you can obtain it via fundecl. size is the size, in bytes, of the constant pool that GCC wrote immediately before this call.

If no constant-pool epilogue is required, the usual case, you need not define this macro.

$IS_ASM_LOGICAL_LINE_SEPARATOR$ (C)

[Macro]

Define this macro as a C expression which is nonzero if C is used as a logical line separator by the assembler.

If you do not define this macro, the default is that only the character ';' is treated as a logical line separator.

const char * TARGET_ASM_OPEN_PAREN

[Target Hook]

const char * TARGET_ASM_CLOSE_PAREN

[Target Hook]

These target hooks are C string constants, describing the syntax in the assembler for grouping arithmetic expressions. If not overridden, they default to normal parentheses, which is correct for most assemblers.

These macros are provided by 'real.h' for writing the definitions of ASM_OUTPUT_DOUBLE and the like:

```
REAL_VALUE_TO_TARGET_SINGLE (x, 1) [Macro]
REAL_VALUE_TO_TARGET_DOUBLE (x, 1) [Macro]
REAL_VALUE_TO_TARGET_LONG_DOUBLE (x, 1) [Macro]
```

These translate x, of type REAL_VALUE_TYPE, to the target's floating point representation, and store its bit pattern in the variable l. For REAL_VALUE_TO_TARGET_SINGLE, this variable should be a simple long int. For the others, it should be an array of long int. The number of elements in this array is determined by the size of the desired target floating point data type: 32 bits of it go in each long int array element. Each array element holds 32 bits of the result, even if long int is wider than 32 bits on the host machine.

The array element values are designed so that you can print them out using fprintf in the order they should appear in the target machine's memory.

13.20.3 Output of Uninitialized Variables

Each of the macros in this section is used to do the whole job of outputting a single uninitialized variable.

ASM_OUTPUT_COMMON (stream, name, size, rounded)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream the assembler definition of a common-label named name whose size is size bytes. The variable rounded is the size rounded up to whatever alignment the caller wants.

Use the expression assemble_name (stream, name) to output the name itself; before and after that, output the additional assembler syntax for defining the name, and a newline.

This macro controls how the assembler definitions of uninitialized common global variables are output.

ASM_OUTPUT_ALIGNED_COMMON (stream, name, size, alignment) [Macro]

Like ASM_OUTPUT_COMMON except takes the required alignment as a separate, explicit argument. If you define this macro, it is used in place of ASM_OUTPUT_COMMON, and gives you more flexibility in handling the required alignment of the variable. The alignment is specified as the number of bits.

Like ASM_OUTPUT_ALIGNED_COMMON except that *decl* of the variable to be output, if there is one, or NULL_TREE if there is no corresponding variable. If you define this macro, GCC will use it in place of both ASM_OUTPUT_COMMON and ASM_OUTPUT_ALIGNED_COMMON. Define this macro when you need to see the variable's decl in order to chose what to output.

ASM_OUTPUT_SHARED_COMMON (stream, name, size, rounded) [Macro] If defined, it is similar to ASM_OUTPUT_COMMON, except that it is used when name is shared. If not defined, ASM_OUTPUT_COMMON will be used.

ASM_OUTPUT_BSS (stream, decl, name, size, rounded)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream the assembler definition of uninitialized global decl named name whose size is size bytes. The variable rounded is the size rounded up to whatever alignment the caller wants.

Try to use function asm_output_bss defined in 'varasm.c' when defining this macro. If unable, use the expression assemble_name (stream, name) to output the name itself; before and after that, output the additional assembler syntax for defining the name, and a newline.

This macro controls how the assembler definitions of uninitialized global variables are output. This macro exists to properly support languages like C++ which do not have common data. However, this macro currently is not defined for all targets. If this macro and ASM_OUTPUT_ALIGNED_BSS are not defined then ASM_OUTPUT_COMMON or ASM_OUTPUT_ALIGNED_COMMON or ASM_OUTPUT_ALIGNED_DECL_COMMON is used.

ASM_OUTPUT_ALIGNED_BSS (stream, decl, name, size, alignment) [Macro] Like ASM_OUTPUT_BSS except takes the required alignment as a separate, explicit argument. If you define this macro, it is used in place of ASM_OUTPUT_BSS, and gives you more flexibility in handling the required alignment of the variable. The alignment is specified as the number of bits.

Try to use function asm_output_aligned_bss defined in file 'varasm.c' when defining this macro.

ASM_OUTPUT_SHARED_BSS (stream, decl, name, size, rounded) [Macro]
If defined, it is similar to ASM_OUTPUT_BSS, except that it is used when name is shared.
If not defined, ASM_OUTPUT_BSS will be used.

ASM_OUTPUT_LOCAL (stream, name, size, rounded)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream the assembler definition of a local-common-label named name whose size is size bytes. The variable rounded is the size rounded up to whatever alignment the caller wants.

Use the expression assemble_name (stream, name) to output the name itself; before and after that, output the additional assembler syntax for defining the name, and a newline.

This macro controls how the assembler definitions of uninitialized static variables are output.

ASM_OUTPUT_ALIGNED_LOCAL (stream, name, size, alignment) [Macro

Like ASM_OUTPUT_LOCAL except takes the required alignment as a separate, explicit argument. If you define this macro, it is used in place of ASM_OUTPUT_LOCAL, and gives you more flexibility in handling the required alignment of the variable. The alignment is specified as the number of bits.

ASM_OUTPUT_ALIGNED_DECL_LOCAL (stream, dec1, name, size, alignment) [Macro]

Like ASM_OUTPUT_ALIGNED_DECL except that decl of the variable to be output, if there is one, or NULL_TREE if there is no corresponding variable. If you define this macro, GCC will use it in place of both ASM_OUTPUT_DECL and ASM_OUTPUT_ALIGNED_DECL. Define this macro when you need to see the variable's decl in order to chose what to output.

ASM_OUTPUT_SHARED_LOCAL (stream, name, size, rounded)

[Macro]

If defined, it is similar to ASM_OUTPUT_LOCAL, except that it is used when name is shared. If not defined, ASM_OUTPUT_LOCAL will be used.

13.20.4 Output and Generation of Labels

This is about outputting labels.

ASM_OUTPUT_LABEL (stream, name)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream the assembler definition of a label named name. Use the expression assemble_name (stream, name) to output the name itself; before and after that, output the additional assembler syntax for defining the name, and a newline. A default definition of this macro is provided which is correct for most systems.

ASM_OUTPUT_INTERNAL_LABEL (stream, name)

[Macro]

Identical to ASM_OUTPUT_1ABEL, except that name is known to refer to a compiler-generated label. The default definition uses assemble_name_raw, which is like assemble_name except that it is more efficient.

SIZE_ASM_OP [Macro]

A C string containing the appropriate assembler directive to specify the size of a symbol, without any arguments. On systems that use ELF, the default (in 'config/elfos.h') is '"\t.size\t"'; on other systems, the default is not to define this macro.

Define this macro only if it is correct to use the default definitions of ASM_OUTPUT_SIZE_DIRECTIVE and ASM_OUTPUT_MEASURED_SIZE for your system. If you need your own custom definitions of those macros, or if you do not need explicit symbol sizes at all, do not define this macro.

ASM_OUTPUT_SIZE_DIRECTIVE (stream, name, size)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream a directive telling the assembler that the size of the symbol name is size. size is a HOST_WIDE_INT. If you define SIZE_ASM_OP, a default definition of this macro is provided.

ASM_OUTPUT_MEASURED_SIZE (stream, name)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream a directive telling the assembler to calculate the size of the symbol name by subtracting its address from the current address.

If you define SIZE_ASM_OP, a default definition of this macro is provided. The default assumes that the assembler recognizes a special '.' symbol as referring to the current

address, and can calculate the difference between this and another symbol. If your assembler does not recognize '.' or cannot do calculations with it, you will need to redefine ASM_OUTPUT_MEASURED_SIZE to use some other technique.

TYPE_ASM_OP [Macro]

A C string containing the appropriate assembler directive to specify the type of a symbol, without any arguments. On systems that use ELF, the default (in 'config/elfos.h') is '"\t.type\t"'; on other systems, the default is not to define this macro.

Define this macro only if it is correct to use the default definition of ASM_OUTPUT_TYPE_DIRECTIVE for your system. If you need your own custom definition of this macro, or if you do not need explicit symbol types at all, do not define this macro.

TYPE_OPERAND_FMT [Macro

A C string which specifies (using printf syntax) the format of the second operand to TYPE_ASM_OP. On systems that use ELF, the default (in 'config/elfos.h') is '"@%s"'; on other systems, the default is not to define this macro.

Define this macro only if it is correct to use the default definition of ASM_OUTPUT_ TYPE_DIRECTIVE for your system. If you need your own custom definition of this macro, or if you do not need explicit symbol types at all, do not define this macro.

ASM_OUTPUT_TYPE_DIRECTIVE (stream, type)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream a directive telling the assembler that the type of the symbol name is type. type is a C string; currently, that string is always either '"function" or '"object", but you should not count on this.

If you define TYPE_ASM_OP and TYPE_OPERAND_FMT, a default definition of this macro is provided.

ASM_DECLARE_FUNCTION_NAME (stream, name, decl)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream any text necessary for declaring the name name of a function which is being defined. This macro is responsible for outputting the label definition (perhaps using ASM_OUTPUT_LABEL). The argument decl is the FUNCTION_DECL tree node representing the function.

If this macro is not defined, then the function name is defined in the usual manner as a label (by means of ASM_OUTPUT_LABEL).

You may wish to use ASM_OUTPUT_TYPE_DIRECTIVE in the definition of this macro.

ASM_DECLARE_FUNCTION_SIZE (stream, name, decl)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream any text necessary for declaring the size of a function which is being defined. The argument name is the name of the function. The argument decl is the FUNCTION_DECL tree node representing the function.

If this macro is not defined, then the function size is not defined.

You may wish to use ASM_OUTPUT_MEASURED_SIZE in the definition of this macro.

ASM_DECLARE_OBJECT_NAME (stream, name, decl)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream any text necessary for declaring the name name of an initialized variable which is being defined. This macro must output the label definition (perhaps using ASM_OUTPUT_LABEL). The argument decl is the VAR_DECL tree node representing the variable.

If this macro is not defined, then the variable name is defined in the usual manner as a label (by means of ASM_OUTPUT_LABEL).

You may wish to use ASM_OUTPUT_TYPE_DIRECTIVE and/or ASM_OUTPUT_SIZE_DIRECTIVE in the definition of this macro.

ASM_DECLARE_CONSTANT_NAME (stream, name, exp, size)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream any text necessary for declaring the name name of a constant which is being defined. This macro is responsible for outputting the label definition (perhaps using ASM_OUTPUT_LABEL). The argument exp is the value of the constant, and size is the size of the constant in bytes. name will be an internal label.

If this macro is not defined, then the *name* is defined in the usual manner as a label (by means of ASM_OUTPUT_LABEL).

You may wish to use ASM_OUTPUT_TYPE_DIRECTIVE in the definition of this macro.

ASM_DECLARE_REGISTER_GLOBAL (stream, decl, regno, name)

Macro

A C statement (sans semicolon) to output to the stdio stream stream any text necessary for claiming a register regno for a global variable decl with name name.

If you don't define this macro, that is equivalent to defining it to do nothing.

ASM_FINISH_DECLARE_OBJECT (stream, decl, toplevel, atend)

Macro

A C statement (sans semicolon) to finish up declaring a variable name once the compiler has processed its initializer fully and thus has had a chance to determine the size of an array when controlled by an initializer. This is used on systems where it's necessary to declare something about the size of the object.

If you don't define this macro, that is equivalent to defining it to do nothing.

You may wish to use ASM_OUTPUT_SIZE_DIRECTIVE and/or ASM_OUTPUT_MEASURED_SIZE in the definition of this macro.

This target hook is a function to output to the stdio stream stream some commands that will make the label name global; that is, available for reference from other files. The default implementation relies on a proper definition of GLOBAL_ASM_OP.

ASM_WEAKEN_LABEL (stream, name)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream some commands that will make the label name weak; that is, available for reference from other files but only used if no other definition is available. Use the expression assemble_name (stream, name) to output the name itself; before and after that, output the additional assembler syntax for making that name weak, and a newline.

If you don't define this macro or ASM_WEAKEN_DECL, GCC will not support weak symbols and you should not define the SUPPORTS_WEAK macro.

ASM_WEAKEN_DECL (stream, decl, name, value)

[Macro]

Combines (and replaces) the function of ASM_WEAKEN_LABEL and ASM_OUTPUT_WEAK_ALIAS, allowing access to the associated function or variable decl. If value is not NULL, this C statement should output to the stdio stream stream assembler code which defines (equates) the weak symbol name to have the value value. If value is NULL, it should output commands to make name weak.

SUPPORTS_WEAK [Macro]

A C expression which evaluates to true if the target supports weak symbols.

If you don't define this macro, 'defaults.h' provides a default definition. If either ASM_WEAKEN_LABEL or ASM_WEAKEN_DECL is defined, the default definition is '1'; otherwise, it is '0'. Define this macro if you want to control weak symbol support with a compiler flag such as '-melf'.

MAKE_DECL_ONE_ONLY (dec1)

[Macro]

A C statement (sans semicolon) to mark decl to be emitted as a public symbol such that extra copies in multiple translation units will be discarded by the linker. Define this macro if your object file format provides support for this concept, such as the 'COMDAT' section flags in the Microsoft Windows PE/COFF format, and this support requires changes to decl, such as putting it in a separate section.

SUPPORTS_ONE_ONLY

[Macro]

A C expression which evaluates to true if the target supports one-only semantics.

If you don't define this macro, 'varasm.c' provides a default definition. If MAKE_DECL_ONE_ONLY is defined, the default definition is '1'; otherwise, it is '0'. Define this macro if you want to control one-only symbol support with a compiler flag, or if setting the DECL_ONE_ONLY flag is enough to mark a declaration to be emitted as one-only.

This target hook is a function to output to asm_out_file some commands that will make the symbol(s) associated with decl have hidden, protected or internal visibility as specified by visibility.

TARGET_WEAK_NOT_IN_ARCHIVE_TOC

[Macro]

A C expression that evaluates to true if the target's linker expects that weak symbols do not appear in a static archive's table of contents. The default is 0.

Leaving weak symbols out of an archive's table of contents means that, if a symbol will only have a definition in one translation unit and will have undefined references from other translation units, that symbol should not be weak. Defining this macro to be nonzero will thus have the effect that certain symbols that would normally be weak (explicit template instantiations, and vtables for polymorphic classes with noninline key methods) will instead be nonweak.

The C++ ABI requires this macro to be zero. Define this macro for targets where full C++ ABI compliance is impossible and where linker restrictions require weak symbols to be left out of a static archive's table of contents.

ASM_OUTPUT_EXTERNAL (stream, decl, name)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream any text necessary for declaring the name of an external symbol named name which is referenced in this compilation but not defined. The value of decl is the tree node for the declaration.

This macro need not be defined if it does not need to output anything. The GNU assembler and most Unix assemblers don't require anything.

void TARGET_ASM_EXTERNAL_LIBCALL (rtx symref)

[Target Hook]

This target hook is a function to output to asm_out_file an assembler pseudo-op to declare a library function name external. The name of the library function is given by symref, which is a $symbol_ref$.

void TARGET_ASM_MARK_DECL_PRESERVED (tree decl)

[Target Hook]

This target hook is a function to output to asm_out_file an assembler directive to annotate used symbol. Darwin target use .no_dead_code_strip directive.

ASM_OUTPUT_LABELREF (stream, name)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream a reference in assembler syntax to a label named name. This should add '_' to the front of the name, if that is customary on your operating system, as it is in most Berkeley Unix systems. This macro is used in assemble_name.

ASM_OUTPUT_SYMBOL_REF (stream, sym)

[Macro]

A C statement (sans semicolon) to output a reference to SYMBOL_REF sym. If not defined, assemble_name will be used to output the name of the symbol. This macro may be used to modify the way a symbol is referenced depending on information encoded by TARGET_ENCODE_SECTION_INFO.

ASM_OUTPUT_LABEL_REF (stream, buf)

[Macro]

A C statement (sans semicolon) to output a reference to buf, the result of ASM_GENERATE_INTERNAL_LABEL. If not defined, assemble_name will be used to output the name of the symbol. This macro is not used by output_asm_label, or the %1 specifier that calls it; the intention is that this macro should be set when it is necessary to output a label differently when its address is being taken.

A function to output to the stdio stream stream a label whose name is made from the string prefix and the number labelno.

It is absolutely essential that these labels be distinct from the labels used for user-level functions and variables. Otherwise, certain programs will have name conflicts with internal labels.

It is desirable to exclude internal labels from the symbol table of the object file. Most assemblers have a naming convention for labels that should be excluded; on many systems, the letter 'L' at the beginning of a label has this effect. You should find out what convention your system uses, and follow it.

The default version of this function utilizes ASM_GENERATE_INTERNAL_LABEL.

ASM_OUTPUT_DEBUG_LABEL (stream, prefix, num)

[Macro]

A C statement to output to the stdio stream stream a debug info label whose name is made from the string prefix and the number num. This is useful for VLIW targets, where debug info labels may need to be treated differently than branch target labels. On some systems, branch target labels must be at the beginning of instruction bundles, but debug info labels can occur in the middle of instruction bundles.

If this macro is not defined, then (*targetm.asm_out.internal_label) will be used.

ASM_GENERATE_INTERNAL_LABEL (string, prefix, num)

[Macro]

A C statement to store into the string string a label whose name is made from the string prefix and the number num.

This string, when output subsequently by assemble_name, should produce the output that (*targetm.asm_out.internal_label) would produce with the same *prefix* and *num*.

If the string begins with '*', then assemble_name will output the rest of the string unchanged. It is often convenient for ASM_GENERATE_INTERNAL_LABEL to use '*' in this way. If the string doesn't start with '*', then ASM_OUTPUT_LABELREF gets to output the string, and may change it. (Of course, ASM_OUTPUT_LABELREF is also part of your machine description, so you should know what it does on your machine.)

ASM_FORMAT_PRIVATE_NAME (outvar, name, number)

[Macro]

A C expression to assign to *outvar* (which is a variable of type char *) a newly allocated string made from the string name and the number number, with some suitable punctuation added. Use alloca to get space for the string.

The string will be used as an argument to ASM_OUTPUT_LABELREF to produce an assembler label for an internal static variable whose name is name. Therefore, the string must be such as to result in valid assembler code. The argument number is different each time this macro is executed; it prevents conflicts between similarly-named internal static variables in different scopes.

Ideally this string should not be a valid C identifier, to prevent any conflict with the user's own symbols. Most assemblers allow periods or percent signs in assembler symbols; putting at least one of these between the name and the number will suffice. If this macro is not defined, a default definition will be provided which is correct for most systems.

ASM_OUTPUT_DEF (stream, name, value)

[Macro]

A C statement to output to the stdio stream stream assembler code which defines (equates) the symbol name to have the value value.

If SET_ASM_OP is defined, a default definition is provided which is correct for most systems.

${\tt ASM_OUTPUT_DEF_FROM_DECLS~(stream,~decl_of_name,}$

[Macro]

decl_of_value)

A C statement to output to the stdio stream stream assembler code which defines (equates) the symbol whose tree node is decl_of_name to have the value of the tree node decl_of_value. This macro will be used in preference to 'ASM_OUTPUT_DEF' if it is defined and if the tree nodes are available.

If SET_ASM_OP is defined, a default definition is provided which is correct for most systems.

TARGET_DEFERRED_OUTPUT_DEFS (decl_of_name, decl_of_value) [Macro]

A C statement that evaluates to true if the assembler code which defines (equates) the symbol whose tree node is $decl_of_name$ to have the value of the tree node $decl_of_value$ should be emitted near the end of the current compilation unit. The default is to not defer output of defines. This macro affects defines output by 'ASM_OUTPUT_DEF' and 'ASM_OUTPUT_DEF_FROM_DECLS'.

ASM_OUTPUT_WEAK_ALIAS (stream, name, value)

[Macro]

A C statement to output to the stdio stream stream assembler code which defines (equates) the weak symbol name to have the value value. If value is NULL, it defines name as an undefined weak symbol.

Define this macro if the target only supports weak aliases; define ASM_OUTPUT_DEF instead if possible.

OBJC_GEN_METHOD_LABEL (buf, is_inst, class_name, cat_name, sel_name) [Macro]

Define this macro to override the default assembler names used for Objective-C methods.

The default name is a unique method number followed by the name of the class (e.g. '_1_Foo'). For methods in categories, the name of the category is also included in the assembler name (e.g. '_1_Foo_Bar').

These names are safe on most systems, but make debugging difficult since the method's selector is not present in the name. Therefore, particular systems define other ways of computing names.

buf is an expression of type char * which gives you a buffer in which to store the name; its length is as long as class_name, cat_name and sel_name put together, plus 50 characters extra.

The argument is_inst specifies whether the method is an instance method or a class method; class_name is the name of the class; cat_name is the name of the category (or NULL if the method is not in a category); and sel_name is the name of the selector.

On systems where the assembler can handle quoted names, you can use this macro to provide more human-readable names.

ASM_DECLARE_CLASS_REFERENCE (stream, name)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream commands to declare that the label name is an Objective-C class reference. This is only needed for targets whose linkers have special support for NeXT-style runtimes.

ASM_DECLARE_UNRESOLVED_REFERENCE (stream, name)

[Macro]

A C statement (sans semicolon) to output to the stdio stream stream commands to declare that the label name is an unresolved Objective-C class reference. This is only needed for targets whose linkers have special support for NeXT-style runtimes.

13.20.5 How Initialization Functions Are Handled

The compiled code for certain languages includes constructors (also called initialization routines)—functions to initialize data in the program when the program is started. These functions need to be called before the program is "started"—that is to say, before main is called.

Compiling some languages generates destructors (also called termination routines) that should be called when the program terminates.

To make the initialization and termination functions work, the compiler must output something in the assembler code to cause those functions to be called at the appropriate time. When you port the compiler to a new system, you need to specify how to do this.

There are two major ways that GCC currently supports the execution of initialization and termination functions. Each way has two variants. Much of the structure is common to all four variations.

The linker must build two lists of these functions—a list of initialization functions, called __CTOR_LIST__, and a list of termination functions, called __DTOR_LIST__.

Each list always begins with an ignored function pointer (which may hold 0, -1, or a count of the function pointers after it, depending on the environment). This is followed by a series of zero or more function pointers to constructors (or destructors), followed by a function pointer containing zero.

Depending on the operating system and its executable file format, either 'crtstuff.c' or 'libgccl.c' traverses these lists at startup time and exit time. Constructors are called in reverse order of the list; destructors in forward order.

The best way to handle static constructors works only for object file formats which provide arbitrarily-named sections. A section is set aside for a list of constructors, and another for a list of destructors. Traditionally these are called '.ctors' and '.dtors'. Each object file that defines an initialization function also puts a word in the constructor section to point to that function. The linker accumulates all these words into one contiguous '.ctors' section. Termination functions are handled similarly.

This method will be chosen as the default by 'target-def.h' if TARGET_ASM_NAMED_ SECTION is defined. A target that does not support arbitrary sections, but does support special designated constructor and destructor sections may define CTORS_SECTION_ASM_OP and DTORS_SECTION_ASM_OP to achieve the same effect.

When arbitrary sections are available, there are two variants, depending upon how the code in 'crtstuff.c' is called. On systems that support a .init section which is executed at program startup, parts of 'crtstuff.c' are compiled into that section. The program is linked by the gcc driver like this:

```
ld -o output_file crti.o crtbegin.o ... -lgcc crtend.o crtn.o
```

The prologue of a function (__init) appears in the .init section of 'crti.o'; the epilogue appears in 'crtn.o'. Likewise for the function __fini in the .fini section. Normally these files are provided by the operating system or by the GNU C library, but are provided by GCC for a few targets.

The objects 'crtbegin.o' and 'crtend.o' are (for most targets) compiled from 'crtstuff.c'. They contain, among other things, code fragments within the .init and .fini sections that branch to routines in the .text section. The linker will pull all parts

of a section together, which results in a complete __init function that invokes the routines we need at startup.

To use this variant, you must define the INIT_SECTION_ASM_OP macro properly.

If no init section is available, when GCC compiles any function called main (or more accurately, any function designated as a program entry point by the language front end calling expand_main_function), it inserts a procedure call to __main as the first executable code after the function prologue. The __main function is defined in 'libgcc2.c' and runs the global constructors.

In file formats that don't support arbitrary sections, there are again two variants. In the simplest variant, the GNU linker (GNU 1d) and an 'a.out' format must be used. In this case, TARGET_ASM_CONSTRUCTOR is defined to produce a .stabs entry of type 'N_SETT', referencing the name __CTOR_LIST__, and with the address of the void function containing the initialization code as its value. The GNU linker recognizes this as a request to add the value to a set; the values are accumulated, and are eventually placed in the executable as a vector in the format described above, with a leading (ignored) count and a trailing zero element. TARGET_ASM_DESTRUCTOR is handled similarly. Since no init section is available, the absence of INIT_SECTION_ASM_OP causes the compilation of main to call __main as above, starting the initialization process.

The last variant uses neither arbitrary sections nor the GNU linker. This is preferable when you want to do dynamic linking and when using file formats which the GNU linker does not support, such as 'ECOFF'. In this case, TARGET_HAVE_CTORS_DTORS is false, initialization and termination functions are recognized simply by their names. This requires an extra program in the linkage step, called collect2. This program pretends to be the linker, for use with GCC; it does its job by running the ordinary linker, but also arranges to include the vectors of initialization and termination functions. These functions are called via __main as described above. In order to use this method, use_collect2 must be defined in the target in 'config.gcc'.

13.20.6 Macros Controlling Initialization Routines

Here are the macros that control how the compiler handles initialization and termination functions:

INIT_SECTION_ASM_OP

[Macro]

If defined, a C string constant, including spacing, for the assembler operation to identify the following data as initialization code. If not defined, GCC will assume such a section does not exist. When you are using special sections for initialization and termination functions, this macro also controls how 'crtstuff.c' and 'libgcc2.c' arrange to run the initialization functions.

HAS_INIT_SECTION

[Macro]

If defined, main will not call __main as described above. This macro should be defined for systems that control start-up code on a symbol-by-symbol basis, such as OSF/1, and should not be defined explicitly for systems that support INIT_SECTION_ASM_OP.

LD_INIT_SWITCH

[Macro]

If defined, a C string constant for a switch that tells the linker that the following symbol is an initialization routine.

LD_FINI_SWITCH [Macro]

If defined, a C string constant for a switch that tells the linker that the following symbol is a finalization routine.

COLLECT_SHARED_INIT_FUNC (stream, func)

[Macro]

If defined, a C statement that will write a function that can be automatically called when a shared library is loaded. The function should call *func*, which takes no arguments. If not defined, and the object format requires an explicit initialization function, then a function called <code>_GLOBAL__DI</code> will be generated.

This function and the following one are used by collect when linking a shared library that needs constructors or destructors, or has DWARF2 exception tables embedded in the code.

COLLECT_SHARED_FINI_FUNC (stream, func)

[Macro]

If defined, a C statement that will write a function that can be automatically called when a shared library is unloaded. The function should call *func*, which takes no arguments. If not defined, and the object format requires an explicit finalization function, then a function called _GLOBAL__DD will be generated.

INVOKE__main [Macro]

If defined, main will call __main despite the presence of INIT_SECTION_ASM_OP. This macro should be defined for systems where the init section is not actually run automatically, but is still useful for collecting the lists of constructors and destructors.

SUPPORTS_INIT_PRIORITY

[Macro]

If nonzero, the C++ init_priority attribute is supported and the compiler should emit instructions to control the order of initialization of objects. If zero, the compiler will issue an error message upon encountering an init_priority attribute.

bool TARGET HAVE CTORS DTORS

[Target Hook]

This value is true if the target supports some "native" method of collecting constructors and destructors to be run at startup and exit. It is false if we must use collect2.

void TARGET_ASM_CONSTRUCTOR (rtx symbol, int priority) [Target Hook]

If defined, a function that outputs assembler code to arrange to call the function referenced by symbol at initialization time.

Assume that symbol is a SYMBOL_REF for a function taking no arguments and with no return value. If the target supports initialization priorities, priority is a value between 0 and MAX_INIT_PRIORITY; otherwise it must be DEFAULT_INIT_PRIORITY.

If this macro is not defined by the target, a suitable default will be chosen if (1) the target supports arbitrary section names, (2) the target defines CTORS_SECTION_ASM_OP, or (3) USE_COLLECT2 is not defined.

void TARGET_ASM_DESTRUCTOR (rtx symbol, int priority) [Target Hook] This is like TARGET ASM CONSTRUCTOR but used for termination functions rather than

This is like TARGET_ASM_CONSTRUCTOR but used for termination functions rather than initialization functions.

If TARGET_HAVE_CTORS_DTORS is true, the initialization routine generated for the generated object file will have static linkage.

If your system uses collect2 as the means of processing constructors, then that program normally uses nm to scan an object file for constructor functions to be called.

On certain kinds of systems, you can define this macro to make collect2 work faster (and, in some cases, make it work at all):

OBJECT_FORMAT_COFF

[Macro]

Define this macro if the system uses COFF (Common Object File Format) object files, so that collect2 can assume this format and scan object files directly for dynamic constructor/destructor functions.

This macro is effective only in a native compiler; collect2 as part of a cross compiler always uses nm for the target machine.

REAL_NM_FILE_NAME

[Macro]

Define this macro as a C string constant containing the file name to use to execute nm. The default is to search the path normally for nm.

If your system supports shared libraries and has a program to list the dynamic dependencies of a given library or executable, you can define these macros to enable support for running initialization and termination functions in shared libraries:

LDD_SUFFIX [Macro]

Define this macro to a C string constant containing the name of the program which lists dynamic dependencies, like "ldd" under SunOS 4.

PARSE_LDD_OUTPUT (ptr)

[Macro]

Define this macro to be C code that extracts filenames from the output of the program denoted by LDD_SUFFIX. ptr is a variable of type char * that points to the beginning of a line of output from LDD_SUFFIX. If the line lists a dynamic dependency, the code must advance ptr to the beginning of the filename on that line. Otherwise, it must set ptr to NULL.

13.20.7 Output of Assembler Instructions

This describes assembler instruction output.

REGISTER_NAMES [Macro]

A C initializer containing the assembler's names for the machine registers, each one as a C string constant. This is what translates register numbers in the compiler into assembler language.

ADDITIONAL_REGISTER_NAMES

[Macro]

If defined, a C initializer for an array of structures containing a name and a register number. This macro defines additional names for hard registers, thus allowing the asm option in declarations to refer to registers using alternate names.

ASM_OUTPUT_OPCODE (stream, ptr)

[Macro]

Define this macro if you are using an unusual assembler that requires different names for the machine instructions.

The definition is a C statement or statements which output an assembler instruction opcode to the stdio stream stream. The macro-operand ptr is a variable of type char * which points to the opcode name in its "internal" form—the form that is written in the machine description. The definition should output the opcode name to stream, performing any translation you desire, and increment the variable ptr to point at the end of the opcode so that it will not be output twice.

In fact, your macro definition may process less than the entire opcode name, or more than the opcode name; but if you want to process text that includes '%'-sequences to substitute operands, you must take care of the substitution yourself. Just be sure to increment *ptr* over whatever text should not be output normally.

If you need to look at the operand values, they can be found as the elements of recog_data.operand.

If the macro definition does nothing, the instruction is output in the usual way.

FINAL_PRESCAN_INSN (insn, opvec, noperands)

[Macro]

If defined, a C statement to be executed just prior to the output of assembler code for *insn*, to modify the extracted operands so they will be output differently.

Here the argument opvec is the vector containing the operands extracted from insn, and noperands is the number of elements of the vector which contain meaningful data for this insn. The contents of this vector are what will be used to convert the insn template into assembler code, so you can change the assembler output by changing the contents of the vector.

This macro is useful when various assembler syntaxes share a single file of instruction patterns; by defining this macro differently, you can cause a large class of instructions to be output differently (such as with rearranged operands). Naturally, variations in assembler syntax affecting individual insu patterns ought to be handled by writing conditional output routines in those patterns.

If this macro is not defined, it is equivalent to a null statement.

PRINT_OPERAND (stream, x, code)

[Macro]

A C compound statement to output to stdio stream stream the assembler syntax for an instruction operand x. x is an RTL expression.

code is a value that can be used to specify one of several ways of printing the operand. It is used when identical operands must be printed differently depending on the context. code comes from the '%' specification that was used to request printing of the operand. If the specification was just '%digit' then code is 0; if the specification was '%ltr digit' then code is the ASCII code for ltr.

If x is a register, this macro should print the register's name. The names can be found in an array reg_names whose type is char *[]. reg_names is initialized from REGISTER_NAMES.

When the machine description has a specification '%punct' (a '%' followed by a punctuation character), this macro is called with a null pointer for x and the punctuation character for code.

PRINT_OPERAND_PUNCT_VALID_P (code)

[Macro]

A C expression which evaluates to true if *code* is a valid punctuation character for use in the PRINT_OPERAND macro. If PRINT_OPERAND_PUNCT_VALID_P is not defined,

it means that no punctuation characters (except for the standard one, '%') are used in this way.

PRINT_OPERAND_ADDRESS (stream, x)

[Macro]

A C compound statement to output to stdio stream stream the assembler syntax for an instruction operand that is a memory reference whose address is x. x is an RTL expression.

On some machines, the syntax for a symbolic address depends on the section that the address refers to. On these machines, define the hook TARGET_ENCODE_SECTION_INFO to store the information into the symbol_ref, and then check for it here. See Section 13.20 [Assembler Format], page 335.

DBR_OUTPUT_SEQEND (file)

[Macro]

A C statement, to be executed after all slot-filler instructions have been output. If necessary, call dbr_sequence_length to determine the number of slots filled in a sequence (zero if not currently outputting a sequence), to decide how many no-ops to output, or whatever.

Don't define this macro if it has nothing to do, but it is helpful in reading assembly output if the extent of the delay sequence is made explicit (e.g. with white space).

Note that output routines for instructions with delay slots must be prepared to deal with not being output as part of a sequence (i.e. when the scheduling pass is not run, or when no slot fillers could be found.) The variable final_sequence is null when not processing a sequence, otherwise it contains the sequence rtx being output.

REGISTER_PREFIX LOCAL_LABEL_PREFIX USER_LABEL_PREFIX IMMEDIATE_PREFIX

If defined, C string expressions to be used for the '%R', '%L', '%U', and '%I' options of asm_fprintf (see 'final.c'). These are useful when a single 'md' file must support multiple assembler formats. In that case, the various 'tm.h' files can define these macros differently.

ASM_FPRINTF_EXTENSIONS (file, argptr, format)

[Macro]

[Macro]

[Macro]

[Macro]

[Macro]

If defined this macro should expand to a series of case statements which will be parsed inside the switch statement of the asm_fprintf function. This allows targets to define extra printf formats which may useful when generating their assembler statements. Note that uppercase letters are reserved for future generic extensions to asm_fprintf, and so are not available to target specific code. The output file is given by the parameter file. The varargs input pointer is argptr and the rest of the format string, starting the character after the one that is being switched upon, is pointed to by format.

ASSEMBLER DIALECT

[Macro]

If your target supports multiple dialects of assembler language (such as different opcodes), define this macro as a C expression that gives the numeric index of the assembler language dialect to use, with zero as the first variant.

If this macro is defined, you may use constructs of the form

```
'{option0|option1|option2...}'
```

in the output templates of patterns (see Section 12.5 [Output Template], page 170) or in the first argument of asm_fprintf. This construct outputs 'option0', 'option1', 'option2', etc., if the value of ASSEMBLER_DIALECT is zero, one, two, etc. Any special characters within these strings retain their usual meaning. If there are fewer alternatives within the braces than the value of ASSEMBLER_DIALECT, the construct outputs nothing.

If you do not define this macro, the characters '{', '|' and '}' do not have any special meaning when used in templates or operands to asm_fprintf.

Define the macros REGISTER_PREFIX, LOCAL_LABEL_PREFIX, USER_LABEL_PREFIX and IMMEDIATE_PREFIX if you can express the variations in assembler language syntax with that mechanism. Define ASSEMBLER_DIALECT and use the '{option0|option1}' syntax if the syntax variant are larger and involve such things as different opcodes or operand order.

ASM_OUTPUT_REG_PUSH (stream, regno)

[Macro]

A C expression to output to *stream* some assembler code which will push hard register number *regno* onto the stack. The code need not be optimal, since this macro is used only when profiling.

ASM_OUTPUT_REG_POP (stream, regno)

[Macro]

A C expression to output to *stream* some assembler code which will pop hard register number *regno* off of the stack. The code need not be optimal, since this macro is used only when profiling.

13.20.8 Output of Dispatch Tables

This concerns dispatch tables.

ASM_OUTPUT_ADDR_DIFF_ELT (stream, body, value, rel)

[Macro]

A C statement to output to the stdio stream stream an assembler pseudo-instruction to generate a difference between two labels. value and rel are the numbers of two internal labels. The definitions of these labels are output using (*targetm.asm_out.internal_label), and they must be printed in the same way here. For example,

You must provide this macro on machines where the addresses in a dispatch table are relative to the table's own address. If defined, GCC will also use this macro on all machines when producing PIC. body is the body of the ADDR_DIFF_VEC; it is provided so that the mode and flags can be read.

ASM_OUTPUT_ADDR_VEC_ELT (stream, value)

Macro

This macro should be provided on machines where the addresses in a dispatch table are absolute.

The definition should be a C statement to output to the stdio stream stream an assembler pseudo-instruction to generate a reference to a label. value is the number of an internal label whose definition is output using (*targetm.asm_out.internal_label). For example,

```
fprintf (stream, "\t.word L%d\n", value)
```

ASM_OUTPUT_CASE_LABEL (stream, prefix, num, table)

[Macro]

Define this if the label before a jump-table needs to be output specially. The first three arguments are the same as for (*targetm.asm_out.internal_label); the fourth argument is the jump-table which follows (a jump_insn containing an addr_vec or addr_diff_vec).

This feature is used on system V to output a swbeg statement for the table.

If this macro is not defined, these labels are output with (*targetm.asm_out.internal_label).

ASM_OUTPUT_CASE_END (stream, num, table)

[Macro]

Define this if something special must be output at the end of a jump-table. The definition should be a C statement to be executed after the assembler code for the table is written. It should write the appropriate code to stdio stream *stream*. The argument *table* is the jump-table insn, and *num* is the label-number of the preceding label.

If this macro is not defined, nothing special is output at the end of the jump-table.

void TARGET_ASM_EMIT_UNWIND_LABEL (stream, dec1, for_eh, empty) [Target Hook]

This target hook emits a label at the beginning of each FDE. It should be defined on targets where FDEs need special labels, and it should write the appropriate label, for the FDE associated with the function declaration decl, to the stdio stream stream. The third argument, for_eh, is a boolean: true if this is for an exception table. The fourth argument, empty, is a boolean: true if this is a placeholder label for an omitted FDE.

The default is that FDEs are not given nonlocal labels.

void TARGET_UNWIND_EMIT (FILE * stream, rtx insn)

[Taget Hook]

This target hook emits and assembly directives required to unwind the given instruction. This is only used when TARGET_UNWIND_INFO is set.

13.20.9 Assembler Commands for Exception Regions

This describes commands marking the start and the end of an exception region.

EH_FRAME_SECTION_NAME

[Macro]

If defined, a C string constant for the name of the section containing exception handling frame unwind information. If not defined, GCC will provide a default definition if the target supports named sections. 'crtstuff.c' uses this macro to switch to the appropriate section.

You should define this symbol if your target supports DWARF 2 frame unwind information and the default definition does not work.

EH_FRAME_IN_DATA_SECTION

[Macro]

If defined, DWARF 2 frame unwind information will be placed in the data section even though the target supports named sections. This might be necessary, for instance, if the system linker does garbage collection and sections cannot be marked as not to be collected.

Do not define this macro unless TARGET_ASM_NAMED_SECTION is also defined.

EH_TABLES_CAN_BE_READ_ONLY

[Macro]

Define this macro to 1 if your target is such that no frame unwind information encoding used with non-PIC code will ever require a runtime relocation, but the linker may not support merging read-only and read-write sections into a single read-write section.

MASK_RETURN_ADDR

[Macro]

An rtx used to mask the return address found via RETURN_ADDR_RTX, so that it does not contain any extraneous set bits in it.

DWARF2_UNWIND_INFO

[Macro]

Define this macro to 0 if your target supports DWARF 2 frame unwind information, but it does not yet work with exception handling. Otherwise, if your target supports this information (if it defines 'INCOMING_RETURN_ADDR_RTX' and either 'UNALIGNED_INT_ASM_OP' or 'OBJECT_FORMAT_ELF'), GCC will provide a default definition of 1.

If TARGET_UNWIND_INFO is defined, the target specific unwinder will be used in all cases. Defining this macro will enable the generation of DWARF 2 frame debugging information.

If TARGET_UNWIND_INFO is not defined, and this macro is defined to 1, the DWARF 2 unwinder will be the default exception handling mechanism; otherwise, setjmp/longjmp will be used by default.

TARGET_UNWIND_INFO

[Macro]

Define this macro if your target has ABI specified unwind tables. Usually these will be output by TARGET_UNWIND_EMIT.

MUST_USE_SJLJ_EXCEPTIONS

[Macro]

This macro need only be defined if DWARF2_UNWIND_INFO is runtime-variable. In that case, 'except.h' cannot correctly determine the corresponding definition of MUST_USE_SJLJ_EXCEPTIONS, so the target must provide it directly.

DWARF_CIE_DATA_ALIGNMENT

[Macro]

This macro need only be defined if the target might save registers in the function prologue at an offset to the stack pointer that is not aligned to UNITS_PER_WORD. The definition should be the negative minimum alignment if STACK_GROWS_DOWNWARD is defined, and the positive minimum alignment otherwise. See Section 13.21.5 [SDB and DWARF], page 363. Only applicable if the target supports DWARF 2 frame unwind information.

void TARGET_ASM_EXCEPTION_SECTION ()

[Target Hook]

If defined, a function that switches to the section in which the main exception table is to be placed (see Section 13.18 [Sections], page 330). The default is a function that switches to a section named .gcc_except_table on machines that support named sections via TARGET_ASM_NAMED_SECTION, otherwise if '-fpic' or '-fPIC' is in effect, the data_section, otherwise the readonly_data_section.

void TARGET_ASM_EH_FRAME_SECTION ()

[Target Hook]

If defined, a function that switches to the section in which the DWARF 2 frame unwind information to be placed (see Section 13.18 [Sections], page 330). The default is a

function that outputs a standard GAS section directive, if EH_FRAME_SECTION_NAME is defined, or else a data section directive followed by a synthetic label.

Target Hook bool TARGET_TERMINATE_DW2_EH_FRAME_INFO [Variable]

Contains the value true if the target should add a zero word onto the end of a Dwarf-2 frame info section when used for exception handling. Default value is false if EH_FRAME_SECTION_NAME is defined, and true otherwise.

rtx TARGET_DWARF_REGISTER_SPAN (rtx reg)

[Target Hook]

Given a register, this hook should return a parallel of registers to represent where to find the register pieces. Define this hook if the register and its mode are represented in Dwarf in non-contiguous locations, or if the register should be represented in more than one register in Dwarf. Otherwise, this hook should return NULL_RTX. If not defined, the default is to return NULL_RTX.

13.20.10 Assembler Commands for Alignment

This describes commands for alignment.

JUMP_ALIGN (label)

[Macro]

The alignment (log base 2) to put in front of *label*, which is a common destination of jumps and has no fallthru incoming edge.

This macro need not be defined if you don't want any special alignment to be done at such a time. Most machine descriptions do not currently define the macro.

Unless it's necessary to inspect the *label* parameter, it is better to set the variable *align_jumps* in the target's OVERRIDE_OPTIONS. Otherwise, you should try to honor the user's selection in *align_jumps* in a JUMP_ALIGN implementation.

LABEL_ALIGN_AFTER_BARRIER (label)

[Macro]

The alignment (log base 2) to put in front of label, which follows a BARRIER.

This macro need not be defined if you don't want any special alignment to be done at such a time. Most machine descriptions do not currently define the macro.

LABEL_ALIGN_AFTER_BARRIER_MAX_SKIP

[Macro]

The maximum number of bytes to skip when applying LABEL_ALIGN_AFTER_BARRIER. This works only if ASM_OUTPUT_MAX_SKIP_ALIGN is defined.

LOOP_ALIGN (label)

[Macro]

The alignment (log base 2) to put in front of *label*, which follows a NOTE_INSN_LOOP_BEG note.

This macro need not be defined if you don't want any special alignment to be done at such a time. Most machine descriptions do not currently define the macro.

Unless it's necessary to inspect the *label* parameter, it is better to set the variable align_loops in the target's OVERRIDE_OPTIONS. Otherwise, you should try to honor the user's selection in align_loops in a LOOP_ALIGN implementation.

LOOP_ALIGN_MAX_SKIP

[Macro]

The maximum number of bytes to skip when applying LOOP_ALIGN. This works only if ASM_OUTPUT_MAX_SKIP_ALIGN is defined.

LABEL_ALIGN (label)

[Macro]

The alignment (log base 2) to put in front of label. If LABEL_ALIGN_AFTER_BARRIER / LOOP_ALIGN specify a different alignment, the maximum of the specified values is used.

Unless it's necessary to inspect the *label* parameter, it is better to set the variable align_labels in the target's OVERRIDE_OPTIONS. Otherwise, you should try to honor the user's selection in align_labels in a LABEL_ALIGN implementation.

LABEL_ALIGN_MAX_SKIP

[Macro]

The maximum number of bytes to skip when applying LABEL_ALIGN. This works only if ASM_OUTPUT_MAX_SKIP_ALIGN is defined.

ASM_OUTPUT_SKIP (stream, nbytes)

[Macro]

A C statement to output to the stdio stream stream an assembler instruction to advance the location counter by nbytes bytes. Those bytes should be zero when loaded. nbytes will be a C expression of type int.

ASM_NO_SKIP_IN_TEXT

[Macro]

Define this macro if ASM_OUTPUT_SKIP should not be used in the text section because it fails to put zeros in the bytes that are skipped. This is true on many Unix systems, where the pseudo—op to skip bytes produces no-op instructions rather than zeros when used in the text section.

ASM_OUTPUT_ALIGN (stream, power)

[Macro]

A C statement to output to the stdio stream an assembler command to advance the location counter to a multiple of 2 to the *power* bytes. *power* will be a C expression of type int.

ASM_OUTPUT_ALIGN_WITH_NOP (stream, power)

[Macro]

Like ASM_OUTPUT_ALIGN, except that the "nop" instruction is used for padding, if necessary.

ASM_OUTPUT_MAX_SKIP_ALIGN (stream, power, max_skip)

[Macro]

A C statement to output to the stdio stream an assembler command to advance the location counter to a multiple of 2 to the *power* bytes, but only if max_skip or fewer bytes are needed to satisfy the alignment request. *power* and max_skip will be a C expression of type int.

13.21 Controlling Debugging Information Format

This describes how to specify debugging information.

13.21.1 Macros Affecting All Debugging Formats

These macros affect all debugging formats.

DBX_REGISTER_NUMBER (regno)

[Macro]

A C expression that returns the DBX register number for the compiler register number regno. In the default macro provided, the value of this expression will be regno itself. But sometimes there are some registers that the compiler knows about and DBX does not, or vice versa. In such cases, some register may need to have one number in the compiler and another for DBX.

If two registers have consecutive numbers inside GCC, and they can be used as a pair to hold a multiword value, then they *must* have consecutive numbers after renumbering with DBX_REGISTER_NUMBER. Otherwise, debuggers will be unable to access such a pair, because they expect register pairs to be consecutive in their own numbering scheme.

If you find yourself defining DBX_REGISTER_NUMBER in way that does not preserve register pairs, then what you must do instead is redefine the actual register numbering scheme.

DEBUGGER_AUTO_OFFSET (x)

[Macro]

A C expression that returns the integer offset value for an automatic variable having address x (an RTL expression). The default computation assumes that x is based on the frame-pointer and gives the offset from the frame-pointer. This is required for targets that produce debugging output for DBX or COFF-style debugging output for SDB and allow the frame-pointer to be eliminated when the '-g' options is used.

DEBUGGER_ARG_OFFSET (offset, x)

[Macro]

A C expression that returns the integer offset value for an argument having address x (an RTL expression). The nominal offset is offset.

PREFERRED_DEBUGGING_TYPE

[Macro]

A C expression that returns the type of debugging output GCC should produce when the user specifies just '-g'. Define this if you have arranged for GCC to support more than one format of debugging output. Currently, the allowable values are DBX_DEBUG, SDB_DEBUG, DWARF_DEBUG, DWARF2_DEBUG, XCOFF_DEBUG, VMS_DEBUG, and VMS_AND_DWARF2_DEBUG.

When the user specifies '-ggdb', GCC normally also uses the value of this macro to select the debugging output format, but with two exceptions. If DWARF2_DEBUGGING_INFO is defined, GCC uses the value DWARF2_DEBUG. Otherwise, if DBX_DEBUGGING_INFO is defined, GCC uses DBX_DEBUG.

The value of this macro only affects the default debugging output; the user can always get a specific type of output by using '-gstabs', '-gcoff', '-gdwarf-2', '-gxcoff', or '-gvms'.

13.21.2 Specific Options for DBX Output

These are specific options for DBX output.

DBX_DEBUGGING_INFO

[Macro]

Define this macro if GCC should produce debugging output for DBX in response to the '-g' option.

XCOFF_DEBUGGING_INFO

[Macro]

Define this macro if GCC should produce XCOFF format debugging output in response to the '-g' option. This is a variant of DBX format.

DEFAULT_GDB_EXTENSIONS

[Macro]

Define this macro to control whether GCC should by default generate GDB's extended version of DBX debugging information (assuming DBX-format debugging information is enabled at all). If you don't define the macro, the default is 1: always generate the extended information if there is any occasion to.

DEBUG_SYMS_TEXT

[Macro]

Define this macro if all .stabs commands should be output while in the text section.

ASM_STABS_OP

[Macro]

A C string constant, including spacing, naming the assembler pseudo op to use instead of "\t.stabs\t" to define an ordinary debugging symbol. If you don't define this macro, "\t.stabs\t" is used. This macro applies only to DBX debugging information format.

ASM_STABD_OP

[Macro]

A C string constant, including spacing, naming the assembler pseudo op to use instead of "\t.stabd\t" to define a debugging symbol whose value is the current location. If you don't define this macro, "\t.stabd\t" is used. This macro applies only to DBX debugging information format.

ASM_STABN_OP

[Macro]

A C string constant, including spacing, naming the assembler pseudo op to use instead of "\t.stabn\t" to define a debugging symbol with no name. If you don't define this macro, "\t.stabn\t" is used. This macro applies only to DBX debugging information format.

DBX NO XREFS

[Macro]

Define this macro if DBX on your system does not support the construct 'xs tagname'. On some systems, this construct is used to describe a forward reference to a structure named tagname. On other systems, this construct is not supported at all.

DBX_CONTIN_LENGTH

[Macro]

A symbol name in DBX-format debugging information is normally continued (split into two separate .stabs directives) when it exceeds a certain length (by default, 80 characters). On some operating systems, DBX requires this splitting; on others, splitting must not be done. You can inhibit splitting by defining this macro with the value zero. You can override the default splitting-length by defining this macro as an expression for the length you desire.

DBX_CONTIN_CHAR [Macro]

Normally continuation is indicated by adding a '\' character to the end of a .stabs string when a continuation follows. To use a different character instead, define this macro as a character constant for the character you want to use. Do not define this macro if backslash is correct for your system.

DBX STATIC STAB DATA SECTION

[Macro]

Define this macro if it is necessary to go to the data section before outputting the '.stabs' pseudo-op for a non-global static variable.

DBX_TYPE_DECL_STABS_CODE

[Macro]

The value to use in the "code" field of the .stabs directive for a typedef. The default is N_LSYM.

DBX_STATIC_CONST_VAR_CODE

[Macro]

The value to use in the "code" field of the .stabs directive for a static variable located in the text section. DBX format does not provide any "right" way to do this. The default is N_FUN.

DBX_REGPARM_STABS_CODE

[Macro]

The value to use in the "code" field of the .stabs directive for a parameter passed in registers. DBX format does not provide any "right" way to do this. The default is N_RSYM.

DBX_REGPARM_STABS_LETTER

[Macro]

The letter to use in DBX symbol data to identify a symbol as a parameter passed in registers. DBX format does not customarily provide any way to do this. The default is 'P'.

DBX_FUNCTION_FIRST

[Macro]

Define this macro if the DBX information for a function and its arguments should precede the assembler code for the function. Normally, in DBX format, the debugging information entirely follows the assembler code.

DBX_BLOCKS_FUNCTION_RELATIVE

[Macro]

Define this macro, with value 1, if the value of a symbol describing the scope of a block (N_LBRAC or N_RBRAC) should be relative to the start of the enclosing function. Normally, GCC uses an absolute address.

DBX_LINES_FUNCTION_RELATIVE

[Macro]

Define this macro, with value 1, if the value of a symbol indicating the current line number (N_SLINE) should be relative to the start of the enclosing function. Normally, GCC uses an absolute address.

DBX_USE_BINCL

[Macro]

Define this macro if GCC should generate N_BINCL and N_EINCL stabs for included header files, as on Sun systems. This macro also directs GCC to output a type number as a pair of a file number and a type number within the file. Normally, GCC does not generate N_BINCL or N_EINCL stabs, and it outputs a single number for a type number.

13.21.3 Open-Ended Hooks for DBX Format

These are hooks for DBX format.

DBX_OUTPUT_LBRAC (stream, name)

[Macro]

Define this macro to say how to output to *stream* the debugging information for the start of a scope level for variable names. The argument *name* is the name of an assembler symbol (for use with assemble_name) whose value is the address where the scope begins.

DBX_OUTPUT_RBRAC (stream, name)

[Macro]

Like DBX_OUTPUT_LBRAC, but for the end of a scope level.

DBX_OUTPUT_NFUN (stream, lscope_label, decl)

[Macro]

Define this macro if the target machine requires special handling to output an N_FUN entry for the function decl.

DBX_OUTPUT_SOURCE_LINE (stream, line, counter)

[Macro]

A C statement to output DBX debugging information before code for line number *line* of the current source file to the stdio stream *stream*. *counter* is the number of time the macro was invoked, including the current invocation; it is intended to generate unique labels in the assembly output.

This macro should not be defined if the default output is correct, or if it can be made correct by defining DBX_LINES_FUNCTION_RELATIVE.

NO_DBX_FUNCTION_END

[Macro]

Some stabs encapsulation formats (in particular ECOFF), cannot handle the .stabs "", N_FUN,,0,0,Lscope-function-1 gdb dbx extension construct. On those machines, define this macro to turn this feature off without disturbing the rest of the gdb extensions.

NO_DBX_BNSYM_ENSYM

[Macro]

Some assemblers cannot handle the .stabd BNSYM/ENSYM,0,0 gdb dbx extension construct. On those machines, define this macro to turn this feature off without disturbing the rest of the gdb extensions.

13.21.4 File Names in DBX Format

This describes file names in DBX format.

DBX_OUTPUT_MAIN_SOURCE_FILENAME (stream, name)

[Macro]

A C statement to output DBX debugging information to the stdio stream stream, which indicates that file name is the main source file—the file specified as the input file for compilation. This macro is called only once, at the beginning of compilation.

This macro need not be defined if the standard form of output for DBX debugging information is appropriate.

It may be necessary to refer to a label equal to the beginning of the text section. You can use 'assemble_name (stream, ltext_label_name)' to do so. If you do this, you must also set the variable used_ltext_label_name to true.

NO_DBX_MAIN_SOURCE_DIRECTORY

[Macro]

Define this macro, with value 1, if GCC should not emit an indication of the current directory for compilation and current source language at the beginning of the file.

NO_DBX_GCC_MARKER

[Macro]

Define this macro, with value 1, if GCC should not emit an indication that this object file was compiled by GCC. The default is to emit an N_OPT stab at the beginning of every source file, with 'gcc2_compiled.' for the string and value 0.

DBX_OUTPUT_MAIN_SOURCE_FILE_END (stream, name)

[Macro]

A C statement to output DBX debugging information at the end of compilation of the main source file name. Output should be written to the stdio stream stream.

If you don't define this macro, nothing special is output at the end of compilation, which is correct for most machines.

DBX_OUTPUT_NULL_N_SO_AT_MAIN_SOURCE_FILE_END

Macro

Define this macro *instead of* defining DBX_OUTPUT_MAIN_SOURCE_FILE_END, if what needs to be output at the end of compilation is a N_SO stab with an empty string, whose value is the highest absolute text address in the file.

13.21.5 Macros for SDB and DWARF Output

Here are macros for SDB and DWARF output.

SDB_DEBUGGING_INFO

[Macro]

Define this macro if GCC should produce COFF-style debugging output for SDB in response to the '-g' option.

DWARF2_DEBUGGING_INFO

[Macro]

Define this macro if GCC should produce dwarf version 2 format debugging output in response to the '-g' option.

int TARGET_DWARF_CALLING_CONVENTION (tree function) [Target Hook] Define this to enable the dwarf attribute DW_AT_calling_convention to be emitted for each function. Instead of an integer return the enum value for the DW_CC_ tag.

To support optional call frame debugging information, you must also define INCOMING_RETURN_ADDR_RTX and either set RTX_FRAME_RELATED_P on the prologue insns if you use RTL for the prologue, or call dwarf2out_def_cfa and dwarf2out_reg_save as appropriate from TARGET_ASM_FUNCTION_PROLOGUE if you don't.

DWARF2 FRAME INFO

[Macro]

Define this macro to a nonzero value if GCC should always output Dwarf 2 frame information. If DWARF2_UNWIND_INFO (see Section 13.20.9 [Exception Region Output], page 355 is nonzero, GCC will output this information not matter how you define DWARF2_FRAME_INFO.

DWARF2_ASM_LINE_DEBUG_INFO

[Macro]

Define this macro to be a nonzero value if the assembler can generate Dwarf 2 line debug info sections. This will result in much more compact line number tables, and hence is desirable if it works.

ASM_OUTPUT_DWARF_DELTA (stream, size, label1, label2)

[Macro]

A C statement to issue assembly directives that create a difference between the two given labels, using an integer of the given size.

ASM_OUTPUT_DWARF_OFFSET (stream, size, label)

[Macro]

A C statement to issue assembly directives that create a section-relative reference to the given label, using an integer of the given size.

ASM_OUTPUT_DWARF_PCREL (stream, size, label)

Macro

A C statement to issue assembly directives that create a self-relative reference to the given label, using an integer of the given size.

PUT SDB ...

[Macro]

Define these macros to override the assembler syntax for the special SDB assembler directives. See 'sdbout.c' for a list of these macros and their arguments. If the standard syntax is used, you need not define them yourself.

SDB_DELIM

[Macro]

Some assemblers do not support a semicolon as a delimiter, even between SDB assembler directives. In that case, define this macro to be the delimiter to use (usually '\n'). It is not necessary to define a new set of PUT_SDB_op macros if this is the only change required.

SDB_ALLOW_UNKNOWN_REFERENCES

[Macro]

Define this macro to allow references to unknown structure, union, or enumeration tags to be emitted. Standard COFF does not allow handling of unknown references, MIPS ECOFF has support for it.

SDB ALLOW FORWARD REFERENCES

[Macro]

Define this macro to allow references to structure, union, or enumeration tags that have not yet been seen to be handled. Some assemblers choke if forward tags are used, while some require it.

SDB_OUTPUT_SOURCE_LINE (stream, line)

[Macro]

A C statement to output SDB debugging information before code for line number line of the current source file to the stdio stream stream. The default is to emit an .1n directive.

13.21.6 Macros for VMS Debug Format

Here are macros for VMS debug format.

VMS_DEBUGGING_INFO

[Macro]

Define this macro if GCC should produce debugging output for VMS in response to the '-g' option. The default behavior for VMS is to generate minimal debug info for a traceback in the absence of '-g' unless explicitly overridden with '-g0'. This behavior is controlled by OPTIMIZATION_OPTIONS and OVERRIDE_OPTIONS.

13.22 Cross Compilation and Floating Point

While all modern machines use twos-complement representation for integers, there are a variety of representations for floating point numbers. This means that in a cross-compiler the representation of floating point numbers in the compiled program may be different from that used in the machine doing the compilation.

Because different representation systems may offer different amounts of range and precision, all floating point constants must be represented in the target machine's format. Therefore, the cross compiler cannot safely use the host machine's floating point arithmetic; it must emulate the target's arithmetic. To ensure consistency, GCC always uses emulation to work with floating point values, even when the host and target floating point formats are identical.

The following macros are provided by 'real.h' for the compiler to use. All parts of the compiler which generate or optimize floating-point calculations must use these macros. They may evaluate their operands more than once, so operands must not have side effects.

REAL_VALUE_TYPE [Magnetic for the content of the co

The C data type to be used to hold a floating point value in the target machine's format. Typically this is a struct containing an array of HOST_WIDE_INT, but all code should treat it as an opaque quantity.

int REAL_VALUES_EQUAL (REAL_VALUE_TYPE x, REAL_VALUE_TYPE [Macro] y)

Compares for equality the two values, x and y. If the target floating point format supports negative zeroes and/or NaNs, 'REAL_VALUES_EQUAL (-0.0, 0.0)' is true, and 'REAL_VALUES_EQUAL (NaN, NaN)' is false.

Tests whether x is less than y.

HOST_WIDE_INT REAL_VALUE_FIX (REAL_VALUE_TYPE x)

[Macro]

Truncates x to a signed integer, rounding toward zero.

unsigned HOST_WIDE_INT REAL_VALUE_UNSIGNED_FIX [Macro] (REAL_VALUE_TYPE x)

Truncates x to an unsigned integer, rounding toward zero. If x is negative, returns zero.

REAL_VALUE_TYPE REAL_VALUE_ATOF (const char *string, enum machine_mode mode) [Macro]

Converts string into a floating point number in the target machine's representation for mode mode. This routine can handle both decimal and hexadecimal floating point constants, using the syntax defined by the C language for both.

- int REAL_VALUE_NEGATIVE (REAL_VALUE_TYPE x) [Macro]
 Returns 1 if x is negative (including negative zero), 0 otherwise.
- int REAL_VALUE_ISINF (REAL_VALUE_TYPE x) [Macro]

 Determines whether x represents infinity (positive or negative).
- int REAL_VALUE_ISNAN (REAL_VALUE_TYPE x) [Macro]
 Determines whether x represents a "NaN" (not-a-number).
- void REAL_ARITHMETIC (REAL_VALUE_TYPE output, enum tree_code code, REAL_VALUE_TYPE x, REAL_VALUE_TYPE y)

Calculates an arithmetic operation on the two floating point values x and y, storing the result in output (which must be a variable).

The operation to be performed is specified by *code*. Only the following codes are supported: PLUS_EXPR, MINUS_EXPR, MULT_EXPR, RDIV_EXPR, MAX_EXPR, MIN_EXPR.

If REAL_ARITHMETIC is asked to evaluate division by zero and the target's floating point format cannot represent infinity, it will call abort. Callers should check for this situation first, using MODE_HAS_INFINITIES. See Section 13.5 [Storage Layout], page 260.

- REAL_VALUE_TYPE REAL_VALUE_NEGATE (REAL_VALUE_TYPE x) [Macro] Returns the negative of the floating point value x.
- REAL_VALUE_TYPE REAL_VALUE_ABS ($REAL_VALUE_TYPE x$) [Macro] Returns the absolute value of x.
- REAL_VALUE_TYPE REAL_VALUE_TRUNCATE (REAL_VALUE_TYPE mode, enum machine_mode x) [Macro]

Truncates the floating point value x to fit in *mode*. The return value is still a full-size REAL_VALUE_TYPE, but it has an appropriate bit pattern to be output as a floating constant whose precision accords with mode *mode*.

void REAL_VALUE_TO_INT (HOST_WIDE_INT low, HOST_WIDE_INT [Macro] high, REAL_VALUE_TYPE x)

Converts a floating point value x into a double-precision integer which is then stored into low and high. If the value is not integral, it is truncated.

void REAL_VALUE_FROM_INT (REAL_VALUE_TYPE x, HOST_WIDE_INT [Macro] low, HOST_WIDE_INT high, enum machine_mode mode)

Converts a double-precision integer found in *low* and *high*, into a floating point value which is then stored into x. The value is truncated to fit in mode *mode*.

13.23 Mode Switching Instructions

The following macros control mode switching optimizations:

OPTIMIZE_MODE_SWITCHING (entity)

[Macro]

Define this macro if the port needs extra instructions inserted for mode switching in an optimizing compilation.

For an example, the SH4 can perform both single and double precision floating point operations, but to perform a single precision operation, the FPSCR PR bit has to be cleared, while for a double precision operation, this bit has to be set. Changing the PR bit requires a general purpose register as a scratch register, hence these FPSCR sets have to be inserted before reload, i.e. you can't put this into instruction emitting or TARGET_MACHINE_DEPENDENT_REORG.

You can have multiple entities that are mode-switched, and select at run time which entities actually need it. OPTIMIZE_MODE_SWITCHING should return nonzero for any entity that needs mode-switching. If you define this macro, you also have to define NUM_MODES_FOR_MODE_SWITCHING, MODE_NEEDED, MODE_PRIORITY_TO_MODE and EMIT_MODE_SET. MODE_AFTER, MODE_ENTRY, and MODE_EXIT are optional.

NUM_MODES_FOR_MODE_SWITCHING

[Macro]

If you define OPTIMIZE_MODE_SWITCHING, you have to define this as initializer for an array of integers. Each initializer element N refers to an entity that needs mode switching, and specifies the number of different modes that might need to be set for this entity. The position of the initializer in the initializer—starting counting at zero—determines the integer that is used to refer to the mode-switched entity in question. In macros that take mode arguments / yield a mode result, modes are represented as numbers $0 \dots N-1$. N is used to specify that no mode switch is needed / supplied.

MODE_NEEDED (entity, insn)

[Macro]

entity is an integer specifying a mode-switched entity. If OPTIMIZE_MODE_SWITCHING is defined, you must define this macro to return an integer value not larger than the corresponding element in NUM_MODES_FOR_MODE_SWITCHING, to denote the mode that entity must be switched into prior to the execution of insn.

MODE_AFTER (mode, insn)

[Macro]

If this macro is defined, it is evaluated for every *insn* during mode switching. It determines the mode that an insn results in (if different from the incoming mode).

MODE_ENTRY (entity)

[Macro]

If this macro is defined, it is evaluated for every *entity* that needs mode switching. It should evaluate to an integer, which is a mode that *entity* is assumed to be switched to at function entry. If MODE ENTRY is defined then MODE EXIT must be defined.

MODE_EXIT (entity)

[Macro]

If this macro is defined, it is evaluated for every *entity* that needs mode switching. It should evaluate to an integer, which is a mode that *entity* is assumed to be switched to at function exit. If MODE_EXIT is defined then MODE_ENTRY must be defined.

MODE_PRIORITY_TO_MODE (entity, n)

[Macro]

This macro specifies the order in which modes for *entity* are processed. 0 is the highest priority, NUM_MODES_FOR_MODE_SWITCHING[*entity*] - 1 the lowest. The value of the macro should be an integer designating a mode for *entity*. For any fixed *entity*, mode_priority_to_mode (*entity*, n) shall be a bijection in 0 ... num_modes_for_mode_switching[*entity*] - 1.

EMIT_MODE_SET (entity, mode, hard_regs_live)

[Macro]

Generate one or more insns to set *entity* to *mode*. *hard_reg_live* is the set of hard registers live at the point where the insn(s) are to be inserted.

13.24 Defining target-specific uses of __attribute__

Target-specific attributes may be defined for functions, data and types. These are described using the following target hooks; they also need to be documented in 'extend.texi'.

- const struct attribute_spec * TARGET_ATTRIBUTE_TABLE [Target Hook] If defined, this target hook points to an array of 'struct attribute_spec' (defined in 'tree.h') specifying the machine specific attributes for this target and some of the restrictions on the entities to which these attributes are applied and the arguments they take.
- int TARGET_COMP_TYPE_ATTRIBUTES (tree type1, tree type2) [Target Hook] If defined, this target hook is a function which returns zero if the attributes on type1 and type2 are incompatible, one if they are compatible, and two if they are nearly compatible (which causes a warning to be generated). If this is not defined, machine-specific attributes are supposed always to be compatible.
- void TARGET_SET_DEFAULT_TYPE_ATTRIBUTES (tree type) [Target Hook] If defined, this target hook is a function which assigns default attributes to newly defined type.
- tree TARGET_MERGE_TYPE_ATTRIBUTES (tree type1, tree type2) [Target Hook]

 Define this target hook if the merging of type attributes needs special handling. If
 defined, the result is a list of the combined TYPE_ATTRIBUTES of type1 and type2. It
 is assumed that comptypes has already been called and returned 1. This function
 may call merge_attributes to handle machine-independent merging.

Define this target hook if the merging of decl attributes needs special handling. If defined, the result is a list of the combined DECL_ATTRIBUTES of olddecl and newdecl. newdecl is a duplicate declaration of olddecl. Examples of when this is needed are when one attribute overrides another, or when an attribute is nullified by a subsequent definition. This function may call merge_attributes to handle machine-independent merging.

If the only target-specific handling you require is 'dllimport' for Microsoft Windows targets, you should define the macro TARGET_DLLIMPORT_DECL_ATTRIBUTES to 1. The compiler will then define a function called merge_dllimport_decl_attributes

which can then be defined as the expansion of TARGET_MERGE_DECL_ATTRIBUTES. You can also add handle_dll_attribute in the attribute table for your port to perform initial processing of the 'dllimport' and 'dllexport' attributes. This is done in 'i386/cygwin.h' and 'i386/i386.c', for example.

TARGET_DECLSPEC [Macro]

Define this macro to a nonzero value if you want to treat __declspec(X) as equivalent to __attribute((X)). By default, this behavior is enabled only for targets that define TARGET_DLLIMPORT_DECL_ATTRIBUTES. The current implementation of __declspec is via a built-in macro, but you should not rely on this implementation detail.

void TARGET_INSERT_ATTRIBUTES (tree node, tree *attr_ptr) [Target Hook]

Define this target hook if you want to be able to add attributes to a decl when it is being created. This is normally useful for back ends which wish to implement a pragma by using the attributes which correspond to the pragma's effect. The node argument is the decl which is being created. The attr_ptr argument is a pointer to the attribute list for this decl. The list itself should not be modified, since it may be shared with other decls, but attributes may be chained on the head of the list and *attr_ptr modified to point to the new attributes, or a copy of the list may be made if further changes are needed.

bool TARGET_FUNCTION_ATTRIBUTE_INLINABLE_P (tree fndec1) [Target Hook]
This target hook returns true if it is ok to inline fndecl into the current function,
despite its having target-specific attributes, false otherwise. By default, if a function
has a target specific attribute attached to it, it will not be inlined.

13.25 Defining coprocessor specifics for MIPS targets.

The MIPS specification allows MIPS implementations to have as many as 4 coprocessors, each with as many as 32 private registers. GCC supports accessing these registers and transferring values between the registers and memory using asm-ized variables. For example:

```
d = cp0count + 3;
```

("c0r1" is the default name of register 1 in coprocessor 0; alternate names may be added as described below, or the default names may be overridden entirely in SUBTARGET_CONDITIONAL_REGISTER_USAGE.)

Coprocessor registers are assumed to be epilogue-used; sets to them will be preserved even if it does not appear that the register is used again later in the function.

Another note: according to the MIPS spec, coprocessor 1 (if present) is the FPU. One accesses COP1 registers through standard mips floating-point support; they are not included in this mechanism.

There is one macro used in defining the MIPS coprocessor interface which you may want to override in subtargets; it is described below.

ALL_COP_ADDITIONAL_REGISTER_NAMES

[Macro]

A comma-separated list (with leading comma) of pairs describing the alternate names of coprocessor registers. The format of each entry should be

{ alternatename, register_number}

Default: empty.

13.26 Parameters for Precompiled Header Validity Checking

void * TARGET_GET_PCH_VALIDITY (size_t * sz)

[Target Hook]

Define this hook if your target needs to check a different collection of flags than the default, which is every flag defined by TARGET_SWITCHES and TARGET_OPTIONS. It should return some data which will be saved in the PCH file and presented to TARGET_PCH_VALID_P later; it should set SZ to the size of the data.

Define this hook if your target needs to check a different collection of flags than the default, which is every flag defined by TARGET_SWITCHES and TARGET_OPTIONS. It is given data which came from TARGET_GET_PCH_VALIDITY (in this version of this compiler, so there is no need for extensive validity checking). It returns NULL if it is safe to load a PCH file with this data, or a suitable error message if not. The error message will be presented to the user, so it should be localized.

13.27 C++ ABI parameters

tree TARGET_CXX_GUARD_TYPE (void)

[Target Hook]

Define this hook to override the integer type used for guard variables. These are used to implement one-time construction of static objects. The default is long_long_integer_type_node.

bool TARGET_CXX_GUARD_MASK_BIT (void)

[Target Hook]

This hook determines how guard variables are used. It should return false (the default) if first byte should be used. A return value of true indicates the least significant bit should be used.

tree TARGET_CXX_GET_COOKIE_SIZE (tree type)

[Target Hook]

This hook returns the size of the cookie to use when allocating an array whose elements have the indicated *type*. Assumes that it is already known that a cookie is needed. The default is max(sizeof (size_t), alignof(type)), as defined in section 2.7 of the IA64/Generic C++ ABI.

bool TARGET_CXX_COOKIE_HAS_SIZE (void)

[Target Hook]

This hook should return true if the element size should be stored in array cookies. The default is to return false.

[Target Hook]

If defined by a backend this hook allows the decision made to export class type to be overruled. Upon entry $import_export$ will contain 1 if the class is going to be exported, -1 if it is going to be imported and 0 otherwise. This function should return the modified value and perform any other actions necessary to support the backend's targeted operating system.

bool TARGET_CXX_CDTOR_RETURNS_THIS (void)

[Target Hook]

This hook should return **true** if constructors and destructors return the address of the object created/destroyed. The default is to return **false**.

bool TARGET_CXX_KEY_METHOD_MAY_BE_INLINE (void)

[Target Hook]

This hook returns true if the key method for a class (i.e., the method which, if defined in the current translation unit, causes the virtual table to be emitted) may be an inline function. Under the standard Itanium C++ ABI the key method may be an inline function so long as the function is not declared inline in the class definition. Under some variants of the ABI, an inline function can never be the key method. The default is to return true.

bool TARGET_CXX_EXPORT_CLASS_DATA (void)

[Target Hook]

[Macro]

If this hook returns false (the default), then virtual tables and RTTI data structures will have the ELF visibility of their containing class. If this hook returns true, then these data structures will have ELF "default" visibility, independently of the visibility of the containing class.

13.28 Miscellaneous Parameters

Here are several miscellaneous parameters.

PREDICATE_CODES

Define this if you have defined special-purpose predicates in the file 'machine.c'. This macro is called within an initializer of an array of structures. The first field in the structure is the name of a predicate and the second field is an array of rtl codes. For each predicate, list all rtl codes that can be in expressions matched by the predicate. The list should have a trailing comma. Here is an example of two entries in the list for a typical RISC machine:

```
#define PREDICATE_CODES \
    {"gen_reg_rtx_operand", {SUBREG, REG}}, \
    {"reg_or_short_cint_operand", {SUBREG, REG, CONST_INT}},
```

Defining this macro does not affect the generated code (however, incorrect definitions that omit an rtl code that may be matched by the predicate can cause the compiler to malfunction). Instead, it allows the table built by 'genrecog' to be more compact and efficient, thus speeding up the compiler. The most important predicates to include in the list specified by this macro are those used in the most inso patterns.

For each predicate function named in PREDICATE_CODES, a declaration will be generated in 'insn-codes.h'.

Use of this macro is deprecated; use define_predicate instead. See Section 12.7.2 [Defining Predicates], page 176.

SPECIAL_MODE_PREDICATES

[Macro]

Define this if you have special predicates that know special things about modes. Genrecog will warn about certain forms of match_operand without a mode; if the operand predicate is listed in SPECIAL_MODE_PREDICATES, the warning will be suppressed.

Here is an example from the IA-32 port (ext_register_operand specially checks for HImode or SImode in preparation for a byte extraction from %ah etc.).

#define SPECIAL_MODE_PREDICATES \
 "ext_register_operand",

Use of this macro is deprecated; use define_special_predicate instead. See Section 12.7.2 [Defining Predicates], page 176.

HAS LONG COND BRANCH

[Macro]

Define this boolean macro to indicate whether or not your architecture has conditional branches that can span all of memory. It is used in conjunction with an optimization that partitions hot and cold basic blocks into separate sections of the executable. If this macro is set to false, gcc will convert any conditional branches that attempt to cross between sections into unconditional branches or indirect jumps.

HAS_LONG_UNCOND_BRANCH

[Macro]

Define this boolean macro to indicate whether or not your architecture has unconditional branches that can span all of memory. It is used in conjunction with an optimization that partitions hot and cold basic blocks into separate sections of the executable. If this macro is set to false, gcc will convert any unconditional branches that attempt to cross between sections into indirect jumps.

CASE_VECTOR_MODE

[Macro]

An alias for a machine mode name. This is the machine mode that elements of a jump-table should have.

CASE_VECTOR_SHORTEN_MODE (min_offset, max_offset, body)

[Macro]

Optional: return the preferred mode for an addr_diff_vec when the minimum and maximum offset are known. If you define this, it enables extra code in branch shortening to deal with addr_diff_vec. To make this work, you also have to define INSN_ALIGN and make the alignment for addr_diff_vec explicit. The body argument is provided so that the offset_unsigned and scale flags can be updated.

CASE_VECTOR_PC_RELATIVE

[Macro]

Define this macro to be a C expression to indicate when jump-tables should contain relative addresses. You need not define this macro if jump-tables never contain relative addresses, or jump-tables should contain relative addresses only when '-fPIC' or '-fPIC' is in effect.

CASE_VALUES_THRESHOLD

[Macro]

Define this to be the smallest number of different values for which it is best to use a jump-table instead of a tree of conditional branches. The default is four for machines with a casesi instruction and five otherwise. This is best for most machines.

CASE_USE_BIT_TESTS

[Macro]

Define this macro to be a C expression to indicate whether C switch statements may be implemented by a sequence of bit tests. This is advantageous on processors that can efficiently implement left shift of 1 by the number of bits held in a register, but inappropriate on targets that would require a loop. By default, this macro returns true if the target defines an ashlsi3 pattern, and false otherwise.

WORD_REGISTER_OPERATIONS

[Macro]

Define this macro if operations between registers with integral mode smaller than a word are always performed on the entire register. Most RISC machines have this property and most CISC machines do not.

LOAD_EXTEND_OP (mem_mode)

[Macro]

Define this macro to be a C expression indicating when insns that read memory in mem_mode , an integral mode narrower than a word, set the bits outside of mem_mode to be either the sign-extension or the zero-extension of the data read. Return SIGN_EXTEND for values of mem_mode for which the insn sign-extends, ZERO_EXTEND for which it zero-extends, and UNKNOWN for other modes.

This macro is not called with mem_mode non-integral or with a width greater than or equal to BITS_PER_WORD, so you may return any value in this case. Do not define this macro if it would always return UNKNOWN. On machines where this macro is defined, you will normally define it as the constant SIGN_EXTEND or ZERO_EXTEND.

You may return a non-UNKNOWN value even if for some hard registers the sign extension is not performed, if for the REGNO_REG_CLASS of these hard registers CANNOT_CHANGE_MODE_CLASS returns nonzero when the *from* mode is *mem_mode* and the *to* mode is any integral mode larger than this but not larger than word_mode.

You must return UNKNOWN if for some hard registers that allow this mode, CANNOT_CHANGE_MODE_CLASS says that they cannot change to word_mode, but that they can change to another integral mode that is larger then mem_mode but still smaller than word_mode.

SHORT_IMMEDIATES_SIGN_EXTEND

[Macro]

Define this macro if loading short immediate values into registers sign extends.

FIXUNS_TRUNC_LIKE_FIX_TRUNC

[Macro]

Define this macro if the same instructions that convert a floating point number to a signed fixed point number also convert validly to an unsigned one.

MOVE MAX [Macro]

The maximum number of bytes that a single instruction can move quickly between memory and registers or between two memory locations.

MAX_MOVE_MAX [Macro]

The maximum number of bytes that a single instruction can move quickly between memory and registers or between two memory locations. If this is undefined, the default is MOVE_MAX. Otherwise, it is the constant value that is the largest value that MOVE_MAX can have at run-time.

SHIFT_COUNT_TRUNCATED

[Macro]

A C expression that is nonzero if on this machine the number of bits actually used for the count of a shift operation is equal to the number of bits needed to represent the size of the object being shifted. When this macro is nonzero, the compiler will assume that it is safe to omit a sign-extend, zero-extend, and certain bitwise 'and' instructions that truncates the count of a shift operation. On machines that have instructions that act on bit-fields at variable positions, which may include 'bit test'

instructions, a nonzero SHIFT_COUNT_TRUNCATED also enables deletion of truncations of the values that serve as arguments to bit-field instructions.

If both types of instructions truncate the count (for shifts) and position (for bit-field operations), or if no variable-position bit-field instructions exist, you should define this macro.

However, on some machines, such as the 80386 and the 680x0, truncation only applies to shift operations and not the (real or pretended) bit-field operations. Define SHIFT_COUNT_TRUNCATED to be zero on such machines. Instead, add patterns to the 'md' file that include the implied truncation of the shift instructions.

You need not define this macro if it would always have the value of zero.

int TARGET_SHIFT_TRUNCATION_MASK (enum machine_mode mode) [Target Hook] This function describes how the standard shift patterns for mode deal with shifts by negative amounts or by more than the width of the mode. See [shift patterns], page 199.

On many machines, the shift patterns will apply a mask m to the shift count, meaning that a fixed-width shift of x by y is equivalent to an arbitrary-width shift of x by y & m. If this is true for mode mode, the function should return m, otherwise it should return 0. A return value of 0 indicates that no particular behavior is guaranteed.

Note that, unlike SHIFT_COUNT_TRUNCATED, this function does *not* apply to general shift rtxes; it applies only to instructions that are generated by the named shift patterns.

The default implementation of this function returns <code>GET_MODE_BITSIZE</code> (<code>mode</code>) - 1 if <code>SHIFT_COUNT_TRUNCATED</code> and 0 otherwise. This definition is always safe, but if <code>SHIFT_COUNT_TRUNCATED</code> is false, and some shift patterns nevertheless truncate the shift count, you may get better code by overriding it.

TRULY_NOOP_TRUNCATION (outprec, inprec)

[Macro]

A C expression which is nonzero if on this machine it is safe to "convert" an integer of inprec bits to one of outprec bits (where outprec is smaller than inprec) by merely operating on it as if it had only outprec bits.

On many machines, this expression can be 1.

When TRULY_NOOP_TRUNCATION returns 1 for a pair of sizes for modes for which MODES_TIEABLE_P is 0, suboptimal code can result. If this is the case, making TRULY_NOOP_TRUNCATION return 0 in such cases may improve things.

STORE_FLAG_VALUE [Macro]

A C expression describing the value returned by a comparison operator with an integral mode and stored by a store-flag instruction ('scond') when the condition is true. This description must apply to all the 'scond' patterns and all the comparison operators whose results have a MODE_INT mode.

A value of 1 or -1 means that the instruction implementing the comparison operator returns exactly 1 or -1 when the comparison is true and 0 when the comparison is false. Otherwise, the value indicates which bits of the result are guaranteed to be 1 when the comparison is true. This value is interpreted in the mode of the comparison

operation, which is given by the mode of the first operand in the 'scond' pattern. Either the low bit or the sign bit of STORE_FLAG_VALUE be on. Presently, only those bits are used by the compiler.

If STORE_FLAG_VALUE is neither 1 or -1, the compiler will generate code that depends only on the specified bits. It can also replace comparison operators with equivalent operations if they cause the required bits to be set, even if the remaining bits are undefined. For example, on a machine whose comparison operators return an SImode value and where STORE_FLAG_VALUE is defined as '0x80000000', saying that just the sign bit is relevant, the expression

```
(ne:SI (and:SI x (const_int power-of-2)) (const_int 0))
can be converted to
    (ashift:SI x (const_int n))
```

where n is the appropriate shift count to move the bit being tested into the sign bit.

There is no way to describe a machine that always sets the low-order bit for a true value, but does not guarantee the value of any other bits, but we do not know of any machine that has such an instruction. If you are trying to port GCC to such a machine, include an instruction to perform a logical-and of the result with 1 in the pattern for the comparison operators and let us know at gcc@gcc.gnu.org.

Often, a machine will have multiple instructions that obtain a value from a comparison (or the condition codes). Here are rules to guide the choice of value for STORE_FLAG_VALUE, and hence the instructions to be used:

- Use the shortest sequence that yields a valid definition for STORE_FLAG_VALUE. It is more efficient for the compiler to "normalize" the value (convert it to, e.g., 1 or 0) than for the comparison operators to do so because there may be opportunities to combine the normalization with other operations.
- For equal-length sequences, use a value of 1 or -1, with -1 being slightly preferred on machines with expensive jumps and 1 preferred on other machines.
- As a second choice, choose a value of '0x80000001' if instructions exist that set both the sign and low-order bits but do not define the others.
- Otherwise, use a value of '0x80000000'.

Many machines can produce both the value chosen for STORE_FLAG_VALUE and its negation in the same number of instructions. On those machines, you should also define a pattern for those cases, e.g., one matching

```
(set A (neg:m (ne:m B C)))
```

Some machines can also perform and or plus operations on condition code values with less instructions than the corresponding 'scond' insn followed by and or plus. On those machines, define the appropriate patterns. Use the names incscc and decscc, respectively, for the patterns which perform plus or minus operations on condition code values. See 'rs6000.md' for some examples. The GNU Superoptizer can be used to find such instruction sequences on other machines.

If this macro is not defined, the default value, 1, is used. You need not define STORE_FLAG_VALUE if the machine has no store-flag instructions, or if the value generated by these instructions is 1.

FLOAT_STORE_FLAG_VALUE (mode)

[Macro]

A C expression that gives a nonzero REAL_VALUE_TYPE value that is returned when comparison operators with floating-point results are true. Define this macro on machines that have comparison operations that return floating-point values. If there are no such operations, do not define this macro.

VECTOR_STORE_FLAG_VALUE (mode)

[Macro]

A C expression that gives a rtx representing the non-zero true element for vector comparisons. The returned rtx should be valid for the inner mode of *mode* which is guaranteed to be a vector mode. Define this macro on machines that have vector comparison operations that return a vector result. If there are no such operations, do not define this macro. Typically, this macro is defined as const1_rtx or constm1_rtx. This macro may return NULL_RTX to prevent the compiler optimizing such vector comparison operations for the given mode.

CLZ_DEFINED_VALUE_AT_ZERO (mode, value)

[Macro]

CTZ_DEFINED_VALUE_AT_ZERO (mode, value)

[Macro]

A C expression that evaluates to true if the architecture defines a value for clz or ctz with a zero operand. If so, value should be set to this value. If this macro is not defined, the value of clz or ctz is assumed to be undefined.

This macro must be defined if the target's expansion for ffs relies on a particular value to get correct results. Otherwise it is not necessary, though it may be used to optimize some corner cases.

Note that regardless of this macro the "definedness" of clz and ctz at zero do not extend to the builtin functions visible to the user. Thus one may be free to adjust the value at will to match the target expansion of these operations without fear of breaking the API.

Pmode [Macro]

An alias for the machine mode for pointers. On most machines, define this to be the integer mode corresponding to the width of a hardware pointer; SImode on 32-bit machine or DImode on 64-bit machines. On some machines you must define this to be one of the partial integer modes, such as PSImode.

The width of Pmode must be at least as large as the value of POINTER_SIZE. If it is not equal, you must define the macro POINTERS_EXTEND_UNSIGNED to specify how pointers are extended to Pmode.

FUNCTION_MODE [Macro]

An alias for the machine mode used for memory references to functions being called, in call RTL expressions. On most machines this should be QImode.

STDC_O_IN_SYSTEM_HEADERS

|Macro

In normal operation, the preprocessor expands __STDC__ to the constant 1, to signify that GCC conforms to ISO Standard C. On some hosts, like Solaris, the system compiler uses a different convention, where __STDC__ is normally 0, but is 1 if the user specifies strict conformance to the C Standard.

Defining STDC_O_IN_SYSTEM_HEADERS makes GNU CPP follows the host convention when processing system header files, but when processing user files __STDC__ will always expand to 1.

NO_IMPLICIT_EXTERN_C

[Macro]

Define this macro if the system header files support C++ as well as C. This macro inhibits the usual method of using system header files in C++, which is to pretend that the file's contents are enclosed in 'extern "C" {...}'.

REGISTER_TARGET_PRAGMAS ()

[Macro]

Define this macro if you want to implement any target-specific pragmas. If defined, it is a C expression which makes a series of calls to c_register_pragma or c_register_pragma_with_expansion for each pragma. The macro may also do any setup required for the pragmas.

The primary reason to define this macro is to provide compatibility with other compilers for the same target. In general, we discourage definition of target-specific pragmas for GCC.

If the pragma can be implemented by attributes then you should consider defining the target hook 'TARGET_INSERT_ATTRIBUTES' as well.

Preprocessor macros that appear on pragma lines are not expanded. All '#pragma' directives that do not match any registered pragma are silently ignored, unless the user specifies '-Wunknown-pragmas'.

Each call to c_register_pragma or c_register_pragma_with_expansion establishes one pragma. The *callback* routine will be called when the preprocessor encounters a pragma of the form

```
#pragma [space] name ...
```

space is the case-sensitive namespace of the pragma, or NULL to put the pragma in the global namespace. The callback routine receives pfile as its first argument, which can be passed on to cpplib's functions if necessary. You can lex tokens after the name by calling c_lex. Tokens that are not read by the callback will be silently ignored. The end of the line is indicated by a token of type CPP_EOF. Macro expansion occurs on the arguments of pragmas registered with c_register_pragma_with_expansion but not on the arguments of pragmas registered with c_register_pragma.

For an example use of this routine, see 'c4x.h' and the callback routines defined in 'c4x-c.c'.

Note that the use of c_lex is specific to the C and C++ compilers. It will not work in the Java or Fortran compilers, or any other language compilers for that matter. Thus if c_lex is going to be called from target-specific code, it must only be done so when building the C and C++ compilers. This can be done by defining the variables c_target_objs and cxx_target_objs in the target entry in the 'config.gcc' file. These variables should name the target-specific, language-specific object file which contains the code that uses c_lex. Note it will also be necessary to add a rule to the makefile fragment pointed to by tmake_file that shows how to build this object file.

HANDLE_SYSV_PRAGMA

[Macro]

Define this macro (to a value of 1) if you want the System V style pragmas '#pragma pack(<n>)' and '#pragma weak <name> [=<value>]' to be supported by gcc.

The pack pragma specifies the maximum alignment (in bytes) of fields within a structure, in much the same way as the '__aligned__' and '__packed__' __attribute__s do. A pack value of zero resets the behavior to the default.

A subtlety for Microsoft Visual C/C++ style bit-field packing (e.g. -mms-bitfields) for targets that support it: When a bit-field is inserted into a packed record, the whole size of the underlying type is used by one or more same-size adjacent bit-fields (that is, if its long:3, 32 bits is used in the record, and any additional adjacent long bit-fields are packed into the same chunk of 32 bits. However, if the size changes, a new field of that size is allocated).

If both MS bit-fields and '__attribute__((packed))' are used, the latter will take precedence. If '__attribute__((packed))' is used on a single field when MS bit-fields are in use, it will take precedence for that field, but the alignment of the rest of the structure may affect its placement.

The weak pragma only works if SUPPORTS_WEAK and ASM_WEAKEN_LABEL are defined. If enabled it allows the creation of specifically named weak labels, optionally with a value.

HANDLE_PRAGMA_PACK_PUSH_POP

[Macro]

Define this macro (to a value of 1) if you want to support the Win32 style pragmas '#pragma pack(push[,n])' and '#pragma pack(pop)'. The 'pack(push,[n])' pragma specifies the maximum alignment (in bytes) of fields within a structure, in much the same way as the '__aligned__' and '__packed__' __attribute__s do. A pack value of zero resets the behavior to the default. Successive invocations of this pragma cause the previous values to be stacked, so that invocations of '#pragma pack(pop)' will return to the previous value.

HANDLE_PRAGMA_PACK_WITH_EXPANSION

[Macro]

Define this macro, as well as HANDLE_SYSV_PRAGMA, if macros should be expanded in the arguments of '#pragma pack'.

TARGET DEFAULT PACK STRUCT

[Macro]

If your target requires a structure packing default other than 0 (meaning the machine default), define this macro the the necessary value (in bytes). This must be a value that would also valid to be used with '#pragma pack()' (that is, a small power of two).

DOLLARS_IN_IDENTIFIERS

[Macro]

Define this macro to control use of the character '\$' in identifier names for the C family of languages. 0 means '\$' is not allowed by default; 1 means it is allowed. 1 is the default; there is no need to define this macro in that case.

NO_DOLLAR_IN_LABEL

[Macro]

Define this macro if the assembler does not accept the character '\$' in label names. By default constructors and destructors in G++ have '\$' in the identifiers. If this macro is defined, '.' is used instead.

NO_DOT_IN_LABEL [Macro]

Define this macro if the assembler does not accept the character '.' in label names. By default constructors and destructors in G++ have names that use '.'. If this macro is defined, these names are rewritten to avoid '.'.

INSN_SETS_ARE_DELAYED (insn)

[Macro]

Define this macro as a C expression that is nonzero if it is safe for the delay slot scheduler to place instructions in the delay slot of *insn*, even if they appear to use a resource set or clobbered in *insn*. *insn* is always a jump_insn or an insn; GCC knows that every call_insn has this behavior. On machines where some insn or jump_insn is really a function call and hence has this behavior, you should define this macro.

You need not define this macro if it would always return zero.

INSN_REFERENCES_ARE_DELAYED (insn)

[Macro]

Define this macro as a C expression that is nonzero if it is safe for the delay slot scheduler to place instructions in the delay slot of *insn*, even if they appear to set or clobber a resource referenced in *insn*. *insn* is always a <code>jump_insn</code> or an <code>insn</code>. On machines where some <code>insn</code> or <code>jump_insn</code> is really a function call and its operands are registers whose use is actually in the subroutine it calls, you should define this macro. Doing so allows the delay slot scheduler to move instructions which copy arguments into the argument registers into the delay slot of *insn*.

You need not define this macro if it would always return zero.

MULTIPLE_SYMBOL_SPACES

[Macro]

Define this macro as a C expression that is nonzero if, in some cases, global symbols from one translation unit may not be bound to undefined symbols in another translation unit without user intervention. For instance, under Microsoft Windows symbols must be explicitly imported from shared libraries (DLLs).

You need not define this macro if it would always evaluate to zero.

tree TARGET_MD_ASM_CLOBBERS (tree clobbers)

[Target Hook]

This target hook should add to *clobbers* STRING_CST trees for any hard regs the port wishes to automatically clobber for all asms. It should return the result of the last tree_cons used to add a clobber.

MATH_LIBRARY [Macro]

Define this macro as a C string constant for the linker argument to link in the system math library, or """ if the target does not have a separate math library.

You need only define this macro if the default of '"-lm" is wrong.

LIBRARY_PATH_ENV [Macro]

Define this macro as a C string constant for the environment variable that specifies where the linker should look for libraries.

You need only define this macro if the default of "LIBRARY_PATH" is wrong.

TARGET_HAS_F_SETLKW

[Macro]

Define this macro if the target supports file locking with fcntl / F_SETLKW. Note that this functionality is part of POSIX. Defining TARGET_HAS_F_SETLKW will enable

the test coverage code to use file locking when exiting a program, which avoids race conditions if the program has forked.

MAX_CONDITIONAL_EXECUTE

[Macro]

A C expression for the maximum number of instructions to execute via conditional execution instructions instead of a branch. A value of BRANCH_COST+1 is the default if the machine does not use cc0, and 1 if it does use cc0.

IFCVT_MODIFY_TESTS (ce_info, true_expr, false_expr)

[Macro]

Used if the target needs to perform machine-dependent modifications on the conditionals used for turning basic blocks into conditionally executed code. ce_info points to a data structure, struct ce_if_block, which contains information about the currently processed blocks. true_expr and false_expr are the tests that are used for converting the then-block and the else-block, respectively. Set either true_expr or false_expr to a null pointer if the tests cannot be converted.

IFCVT_MODIFY_MULTIPLE_TESTS (ce_info, bb, true_expr,

[Macro]

false_expr)

Like IFCVT_MODIFY_TESTS, but used when converting more complicated if-statements into conditions combined by and and or operations. bb contains the basic block that contains the test that is currently being processed and about to be turned into a condition.

IFCVT_MODIFY_INSN (ce_info, pattern, insn)

[Macro]

A C expression to modify the *PATTERN* of an *INSN* that is to be converted to conditional execution format. *ce_info* points to a data structure, **struct ce_if_block**, which contains information about the currently processed blocks.

IFCVT MODIFY FINAL (ce info)

[Macro]

A C expression to perform any final machine dependent modifications in converting code to conditional execution. The involved basic blocks can be found in the struct ce_if_block structure that is pointed to by ce_info.

IFCVT_MODIFY_CANCEL (ce_info)

[Macro]

A C expression to cancel any machine dependent modifications in converting code to conditional execution. The involved basic blocks can be found in the struct ce_if_block structure that is pointed to by ce_info.

IFCVT_INIT_EXTRA_FIELDS (ce_info)

[Macro]

A C expression to initialize any extra fields in a struct ce_if_block structure, which are defined by the IFCVT_EXTRA_FIELDS macro.

IFCVT_EXTRA_FIELDS

[Macro]

If defined, it should expand to a set of field declarations that will be added to the struct ce_if_block structure. These should be initialized by the IFCVT_INIT_EXTRA_FIELDS macro.

void TARGET MACHINE DEPENDENT REORG ()

[Target Hook]

If non-null, this hook performs a target-specific pass over the instruction stream. The compiler will run it at all optimization levels, just before the point at which it normally does delayed-branch scheduling.

The exact purpose of the hook varies from target to target. Some use it to do transformations that are necessary for correctness, such as laying out in-function constant pools or avoiding hardware hazards. Others use it as an opportunity to do some machine-dependent optimizations.

You need not implement the hook if it has nothing to do. The default definition is null.

void TARGET_INIT_BUILTINS ()

[Target Hook]

Define this hook if you have any machine-specific built-in functions that need to be defined. It should be a function that performs the necessary setup.

Machine specific built-in functions can be useful to expand special machine instructions that would otherwise not normally be generated because they have no equivalent in the source language (for example, SIMD vector instructions or prefetch instructions).

To create a built-in function, call the function lang_hooks.builtin_function which is defined by the language front end. You can use any type nodes set up by build_common_tree_nodes and build_common_tree_nodes_2; only language front ends that use those two functions will call 'TARGET_INIT_BUILTINS'.

rtx TARGET_EXPAND_BUILTIN (tree exp, rtx target, rtx subtarget, enum machine_mode mode, int ignore)

[Target Hook]

Expand a call to a machine specific built-in function that was set up by 'TARGET_INIT_BUILTINS'. exp is the expression for the function call; the result should go to target if that is convenient, and have mode mode if that is convenient. subtarget may be used as the target for computing one of exp's operands. ignore is

nonzero if the value is to be ignored. This function should return the result of the call to the built-in function.

tree TARGET_FOLD_BUILTIN (tree exp. bool ignore)

[Target Hook]

Expand a call to a machine specific built-in function that was set up by 'TARGET_INIT_BUILTINS'. exp is the expression for the function call; the result is another tree containing a simplified expression for the call's result. If *ignore* is true the value will be ignored.

MD_CAN_REDIRECT_BRANCH (branch1, branch2)

[Macro]

Take a branch insn in branch1 and another in branch2. Return true if redirecting branch1 to the destination of branch2 is possible.

On some targets, branches may have a limited range. Optimizing the filling of delay slots can result in branches being redirected, and this may in turn cause a branch offset to overflow.

ALLOCATE_INITIAL_VALUE (hard_reg)

[Macro]

When the initial value of a hard register has been copied in a pseudo register, it is often not necessary to actually allocate another register to this pseudo register, because the original hard register or a stack slot it has been saved into can be used. ALLOCATE_INITIAL_VALUE, if defined, is called at the start of register allocation once for each hard register that had its initial value copied by using get_func_hard_reg_initial_val or get_hard_reg_initial_val. Possible values are NULL_RTX, if you

don't want to do any special allocation, a REG rtx—that would typically be the hard register itself, if it is known not to be clobbered—or a MEM. If you are returning a MEM, this is only a hint for the allocator; it might decide to use another register anyways. You may use current_function_leaf_function in the definition of the macro, functions that use REG_N_SETS, to determine if the hard register in question will not be clobbered.

TARGET_OBJECT_SUFFIX

[Macro]

Define this macro to be a C string representing the suffix for object files on your target machine. If you do not define this macro, GCC will use '.o' as the suffix for object files.

TARGET_EXECUTABLE_SUFFIX

[Macro]

Define this macro to be a C string representing the suffix to be automatically added to executable files on your target machine. If you do not define this macro, GCC will use the null string as the suffix for executable files.

COLLECT_EXPORT_LIST

[Macro]

If defined, collect2 will scan the individual object files specified on its command line and create an export list for the linker. Define this macro for systems like AIX, where the linker discards object files that are not referenced from main and uses export lists.

MODIFY_JNI_METHOD_CALL (mdecl)

[Macro]

Define this macro to a C expression representing a variant of the method call mdecl, if Java Native Interface (JNI) methods must be invoked differently from other methods on your target. For example, on 32-bit Microsoft Windows, JNI methods must be invoked using the stdcall calling convention and this macro is then defined as this expression:

bool TARGET_CANNOT_MODIFY_JUMPS_P (void)

[Target Hook]

This target hook returns **true** past the point in which new jump instructions could be created. On machines that require a register for every jump such as the SHmedia ISA of SH5, this point would typically be reload, so this target hook should be defined to a function such as:

```
static bool
cannot_modify_jumps_past_reload_p ()
{
   return (reload_completed || reload_in_progress);
}
```

int TARGET_BRANCH_TARGET_REGISTER_CLASS (void)

[Target Hook

This target hook returns a register class for which branch target register optimizations should be applied. All registers in this class should be usable interchangeably. After reload, registers in this class will be re-allocated and loads will be hoisted out of loops and be subjected to inter-block scheduling.

bool TARGET_BRANCH_TARGET_REGISTER_CALLEE_SAVED (bool after_prologue_epilogue_gen) [Target Hook]

Branch target register optimization will by default exclude callee-saved registers that are not already live during the current function; if this target hook returns true, they will be included. The target code must than make sure that all target registers in the class returned by 'TARGET_BRANCH_TARGET_REGISTER_CLASS' that might need saving are saved. after_prologue_epilogue_gen indicates if prologues and epilogues have already been generated. Note, even if you only return true when after_prologue_epilogue_gen is false, you still are likely to have to make special provisions in INITIAL_ELIMINATION_OFFSET to reserve space for caller-saved target registers.

POWI_MAX_MULTS [Macro]

If defined, this macro is interpreted as a signed integer C expression that specifies the maximum number of floating point multiplications that should be emitted when expanding exponentiation by an integer constant inline. When this value is defined, exponentiation requiring more than this number of multiplications is implemented by calling the system library's pow, powf or powl routines. The default value places no upper bound on the multiplication count.

This target hook should register any extra include files for the target. The parameter *stdinc* indicates if normal include files are present. The parameter *sysroot* is the system root directory. The parameter *iprefix* is the prefix for the gcc directory.

This target hook should register any extra include files for the target before any standard headers. The parameter stdinc indicates if normal include files are present. The parameter sysroot is the system root directory. The parameter iprefix is the prefix for the gcc directory.

void TARGET_OPTF (char *path)

[Macro]

This target hook should register special include paths for the target. The parameter path is the include to register. On Darwin systems, this is used for Framework includes, which have semantics that are different from '-I'.

bool TARGET_USE_LOCAL_THUNK_ALIAS_P (tree fndec1) [Target Hook]

This target hook returns **true** if it is safe to use a local alias for a virtual function *findecl* when constructing thunks, **false** otherwise. By default, the hook returns **true** for all functions, if a target supports aliases (i.e. defines ASM_OUTPUT_DEF), **false** otherwise,

TARGET FORMAT TYPES

[Macro]

If defined, this macro is the name of a global variable containing target-specific format checking information for the '-Wformat' option. The default is to have no target-specific format checks.

TARGET_N_FORMAT_TYPES

[Macro]

If defined, this macro is the number of entries in TARGET_FORMAT_TYPES.

bool TARGET_RELAXED_ORDERING

[Target Hook]

If set to true, means that the target's memory model does not guarantee that loads which do not depend on one another will access main memory in the order of the instruction stream; if ordering is important, an explicit memory barrier must be used. This is true of many recent processors which implement a policy of "relaxed," "weak," or "release" memory consistency, such as Alpha, PowerPC, and ia64. The default is false.

TARGET_USE_JCR_SECTION

[Macro]

This macro determines whether to use the JCR section to register Java classes. By default, TARGET_USE_JCR_SECTION is defined to 1 if both SUPPORTS_WEAK and TARGET_HAVE_NAMED_SECTIONS are true, else 0.

14 Host Configuration

Most details about the machine and system on which the compiler is actually running are detected by the configure script. Some things are impossible for configure to detect; these are described in two ways, either by macros defined in a file named 'xm-machine.h' or by hook functions in the file specified by the out_host_hook_obj variable in 'config.gcc'. (The intention is that very few hosts will need a header file but nearly every fully supported host will need to override some hooks.)

If you need to define only a few macros, and they have simple definitions, consider using the xm_defines variable in your 'config.gcc' entry instead of creating a host configuration header. See Section 6.3.2.2 [System Config], page 22.

14.1 Host Common

Some things are just not portable, even between similar operating systems, and are too difficult for autoconf to detect. They get implemented using hook functions in the file specified by the *host_hook_obj* variable in 'config.gcc'.

void HOST_HOOKS_EXTRA_SIGNALS (void)

[Host Hook]

This host hook is used to set up handling for extra signals. The most common thing to do in this hook is to detect stack overflow.

void * HOST_HOOKS_GT_PCH_GET_ADDRESS (size_t size, int fd) [Host Hook]
This host hook returns the address of some space that is likely to be free in some subsequent invocation of the compiler. We intend to load the PCH data at this address such that the data need not be relocated. The area should be able to hold size bytes. If the host uses mmap, fd is an open file descriptor that can be used for probing.

This host hook is called when a PCH file is about to be loaded. We want to load size bytes from fd at offset into memory at address. The given address will be the result of a previous invocation of HOST_HOOKS_GT_PCH_GET_ADDRESS. Return -1 if we couldn't allocate size bytes at address. Return 0 if the memory is allocated but the data is not loaded. Return 1 if the hook has performed everything.

If the implementation uses reserved address space, free any reserved space beyond size, regardless of the return value. If no PCH will be loaded, this hook may be called with size zero, in which case all reserved address space should be freed.

Do not try to handle values of address that could not have been returned by this executable; just return -1. Such values usually indicate an out-of-date PCH file (built by some other GCC executable), and such a PCH file won't work.

size_t HOST_HOOKS_GT_PCH_ALLOC_GRANULARITY (void); [Host Hook]

This host hook returns the alignment required for allocating virtual memory. Usually this is the same as getpagesize, but on some hosts the alignment for reserving memory differs from the pagesize for committing memory.

14.2 Host Filesystem

GCC needs to know a number of things about the semantics of the host machine's filesystem. Filesystems with Unix and MS-DOS semantics are automatically detected. For other systems, you can define the following macros in 'xm-machine.h'.

HAVE_DOS_BASED_FILE_SYSTEM

This macro is automatically defined by 'system.h' if the host file system obeys the semantics defined by MS-DOS instead of Unix. DOS file systems are case insensitive, file specifications may begin with a drive letter, and both forward slash and backslash ('/' and '\') are directory separators.

DIR_SEPARATOR

DIR_SEPARATOR_2

If defined, these macros expand to character constants specifying separators for directory names within a file specification. 'system.h' will automatically give them appropriate values on Unix and MS-DOS file systems. If your file system is neither of these, define one or both appropriately in 'xm-machine.h'.

However, operating systems like VMS, where constructing a pathname is more complicated than just stringing together directory names separated by a special character, should not define either of these macros.

PATH SEPARATOR

If defined, this macro should expand to a character constant specifying the separator for elements of search paths. The default value is a colon (':'). DOS-based systems usually, but not always, use semicolon (';').

VMS Define this macro if the host system is VMS.

HOST_OBJECT_SUFFIX

Define this macro to be a C string representing the suffix for object files on your host machine. If you do not define this macro, GCC will use '.o' as the suffix for object files.

HOST_EXECUTABLE_SUFFIX

Define this macro to be a C string representing the suffix for executable files on your host machine. If you do not define this macro, GCC will use the null string as the suffix for executable files.

HOST_BIT_BUCKET

A pathname defined by the host operating system, which can be opened as a file and written to, but all the information written is discarded. This is commonly known as a bit bucket or null device. If you do not define this macro, GCC will use '/dev/null' as the bit bucket. If the host does not support a bit bucket, define this macro to an invalid filename.

UPDATE_PATH_HOST_CANONICALIZE (path)

If defined, a C statement (sans semicolon) that performs host-dependent canonicalization when a path used in a compilation driver or preprocessor is canonicalized. path is a malloc-ed path to be canonicalized. If the C statement does canonicalize path into a different buffer, the old path should be freed and the new buffer should have been allocated with malloc.

DUMPFILE_FORMAT

Define this macro to be a C string representing the format to use for constructing the index part of debugging dump file names. The resultant string must fit in fifteen bytes. The full filename will be the concatenation of: the prefix of the assembler file name, the string resulting from applying this format to an index number, and a string unique to each dump file kind, e.g. 'rtl'.

If you do not define this macro, GCC will use '.%02d.'. You should define this macro if using the default will create an invalid file name.

DELETE_IF_ORDINARY

Define this macro to be a C statement (sans semicolon) that performs host-dependent removal of ordinary temp files in the compilation driver.

If you do not define this macro, GCC will use the default version. You should define this macro if the default version does not reliably remove the temp file as, for example, on VMS which allows multiple versions of a file.

HOST_LACKS_INODE_NUMBERS

Define this macro if the host filesystem does not report meaningful inode numbers in struct stat.

14.3 Host Misc

FATAL_EXIT_CODE

A C expression for the status code to be returned when the compiler exits after serious errors. The default is the system-provided macro 'EXIT_FAILURE', or '1' if the system doesn't define that macro. Define this macro only if these defaults are incorrect.

SUCCESS_EXIT_CODE

A C expression for the status code to be returned when the compiler exits without serious errors. (Warnings are not serious errors.) The default is the system-provided macro 'EXIT_SUCCESS', or '0' if the system doesn't define that macro. Define this macro only if these defaults are incorrect.

USE_C_ALLOCA

Define this macro if GCC should use the C implementation of alloca provided by 'libiberty.a'. This only affects how some parts of the compiler itself allocate memory. It does not change code generation.

When GCC is built with a compiler other than itself, the C alloca is always used. This is because most other implementations have serious bugs. You should define this macro only on a system where no stack-based alloca can possibly work. For instance, if a system has a small limit on the size of the stack, GCC's builtin alloca will not work reliably.

COLLECT2_HOST_INITIALIZATION

If defined, a C statement (sans semicolon) that performs host-dependent initialization when collect2 is being initialized.

GCC_DRIVER_HOST_INITIALIZATION

If defined, a C statement (sans semicolon) that performs host-dependent initialization when a compilation driver is being initialized.

SMALL_ARG_MAX

Define this macro if the host system has a small limit on the total size of an argument vector. This causes the driver to take more care not to pass unnecessary arguments to subprocesses.

HOST_LONG_LONG_FORMAT

If defined, the string used to indicate an argument of type long long to functions like printf. The default value is "ll".

In addition, if configure generates an incorrect definition of any of the macros in 'auto-host.h', you can override that definition in a host configuration header. If you need to do this, first see if it is possible to fix configure.

15 Makefile Fragments

When you configure GCC using the 'configure' script, it will construct the file 'Makefile' from the template file 'Makefile.in'. When it does this, it can incorporate makefile fragments from the 'config' directory. These are used to set Makefile parameters that are not amenable to being calculated by autoconf. The list of fragments to incorporate is set by 'config.gcc' (and occasionally 'config.build' and 'config.host'); See Section 6.3.2.2 [System Config], page 22.

Fragments are named either 't-target' or 'x-host', depending on whether they are relevant to configuring GCC to produce code for a particular target, or to configuring GCC to run on a particular host. Here target and host are mnemonics which usually have some relationship to the canonical system name, but no formal connection.

If these files do not exist, it means nothing needs to be added for a given target or host. Most targets need a few 't-target' fragments, but needing 'x-host' fragments is rare.

15.1 Target Makefile Fragments

Target makefile fragments can set these Makefile variables.

LIBGCC2_CFLAGS

Compiler flags to use when compiling 'libgcc2.c'.

LIB2FUNCS EXTRA

A list of source file names to be compiled or assembled and inserted into 'libgcc.a'.

Floating Point Emulation

To have GCC include software floating point libraries in 'libgcc.a' define FPBIT and DPBIT along with a few rules as follows:

You may need to provide additional #defines at the beginning of 'fp-bit.c' and 'dp-bit.c' to control target endianness and other options.

CRTSTUFF_T_CFLAGS

Special flags used when compiling 'crtstuff.c'. See Section 13.20.5 [Initialization], page 348.

CRTSTUFF_T_CFLAGS_S

Special flags used when compiling 'crtstuff.c' for shared linking. Used if you use 'crtbeginS.o' and 'crtendS.o' in EXTRA-PARTS. See Section 13.20.5 [Initialization], page 348.

MULTILIB_OPTIONS

For some targets, invoking GCC in different ways produces objects that can not be linked together. For example, for some targets GCC produces both big and little endian code. For these targets, you must arrange for multiple versions of 'libgcc.a' to be compiled, one for each set of incompatible options. When GCC invokes the linker, it arranges to link in the right version of 'libgcc.a', based on the command line options used.

The MULTILIB_OPTIONS macro lists the set of options for which special versions of 'libgcc.a' must be built. Write options that are mutually incompatible side by side, separated by a slash. Write options that may be used together separated by a space. The build procedure will build all combinations of compatible options.

For example, if you set MULTILIB_OPTIONS to 'm68000/m68020 msoft-float', 'Makefile' will build special versions of 'libgcc.a' using the following sets of options: '-m68000', '-m68020', '-msoft-float', '-m68000 -msoft-float', and '-m68020 -msoft-float'.

MULTILIB DIRNAMES

If MULTILIB_OPTIONS is used, this variable specifies the directory names that should be used to hold the various libraries. Write one element in MULTILIB_DIRNAMES for each element in MULTILIB_OPTIONS. If MULTILIB_DIRNAMES is not used, the default value will be MULTILIB_OPTIONS, with all slashes treated as spaces.

For example, if MULTILIB_OPTIONS is set to 'm68000/m68020 msoft-float', then the default value of MULTILIB_DIRNAMES is 'm68000 m68020 msoft-float'. You may specify a different value if you desire a different set of directory names.

MULTILIB_MATCHES

Sometimes the same option may be written in two different ways. If an option is listed in MULTILIB_OPTIONS, GCC needs to know about any synonyms. In that case, set MULTILIB_MATCHES to a list of items of the form 'option=option' to describe all relevant synonyms. For example, 'm68000=mc68000 m68020=mc68020'.

MULTILIB_EXCEPTIONS

Sometimes when there are multiple sets of MULTILIB_OPTIONS being specified, there are combinations that should not be built. In that case, set MULTILIB_EXCEPTIONS to be all of the switch exceptions in shell case syntax that should not be built.

For example the ARM processor cannot execute both hardware floating point instructions and the reduced size THUMB instructions at the same time, so there is no need to build libraries with both of these options enabled. Therefore MULTILIB_EXCEPTIONS is set to:

*mthumb/*mhard-float*

MULTILIB EXTRA OPTS

Sometimes it is desirable that when building multiple versions of 'libgcc.a' certain options should always be passed on to the compiler. In that case, set MULTILIB_EXTRA_OPTS to be the list of options to be used for all builds. If you set this, you should probably set CRTSTUFF_T_CFLAGS to a dash followed by it.

SPECS

Unfortunately, setting MULTILIB_EXTRA_OPTS is not enough, since it does not affect the build of target libraries, at least not the build of the default multilib. One possible work-around is to use DRIVER_SELF_SPECS to bring options from the 'specs' file as if they had been passed in the compiler driver command line. However, you don't want to be adding these options after the toolchain is installed, so you can instead tweak the 'specs' file that will be used during the toolchain build, while you still install the original, built-in 'specs'. The trick is to set SPECS to some other filename (say 'specs.install'), that will then be created out of the built-in specs, and introduce a 'Makefile' rule to generate the 'specs' file that's going to be used at build time out of your 'specs.install'.

15.2 Host Makefile Fragments

The use of 'x-host' fragments is discouraged. You should do so only if there is no other mechanism to get the behavior desired. Host fragments should never forcibly override variables set by the configure script, as they may have been adjusted by the user.

Variables provided for host fragments to set include:

X_CFLAGS

X_CPPFLAGS

These are extra flags to pass to the C compiler and preprocessor, respectively. They are used both when building GCC, and when compiling things with the just-built GCC.

XCFLAGS

These are extra flags to use when building the compiler. They are not used when compiling 'libgcc.a'. However, they *are* used when recompiling the compiler with itself in later stages of a bootstrap.

BOOT_LDFLAGS

Flags to be passed to the linker when recompiling the compiler with itself in later stages of a bootstrap. You might need to use this if, for instance, one of the front ends needs more text space than the linker provides by default.

EXTRA_PROGRAMS

A list of additional programs required to use the compiler on this host, which should be compiled with GCC and installed alongside the front ends. If you set this variable, you must also provide rules to build the extra programs.

16 collect2

GCC uses a utility called collect2 on nearly all systems to arrange to call various initialization functions at start time.

The program collect2 works by linking the program once and looking through the linker output file for symbols with particular names indicating they are constructor functions. If it finds any, it creates a new temporary '.c' file containing a table of them, compiles it, and links the program a second time including that file.

The actual calls to the constructors are carried out by a subroutine called __main, which is called (automatically) at the beginning of the body of main (provided main was compiled with GNU CC). Calling __main is necessary, even when compiling C code, to allow linking C and C++ object code together. (If you use '-nostdlib', you get an unresolved reference to __main, since it's defined in the standard GCC library. Include '-lgcc' at the end of your compiler command line to resolve this reference.)

The program collect2 is installed as 1d in the directory where the passes of the compiler are installed. When collect2 needs to find the real 1d, it tries the following file names:

- 'real-ld' in the directories listed in the compiler's search directories.
- 'real-ld' in the directories listed in the environment variable PATH.
- The file specified in the REAL_LD_FILE_NAME configuration macro, if specified.
- 'ld' in the compiler's search directories, except that collect2 will not execute itself recursively.
- 'ld' in PATH.

"The compiler's search directories" means all the directories where gcc searches for passes of the compiler. This includes directories that you specify with '-B'.

Cross-compilers search a little differently:

- 'real-ld' in the compiler's search directories.
- 'target-real-ld' in PATH.
- The file specified in the REAL_LD_FILE_NAME configuration macro, if specified.
- 'ld' in the compiler's search directories.
- 'target-ld' in PATH.

collect2 explicitly avoids running 1d using the file name under which collect2 itself was invoked. In fact, it remembers up a list of such names—in case one copy of collect2 finds another copy (or version) of collect2 installed as 1d in a second place in the search path.

collect2 searches for the utilities nm and strip using the same algorithm as above for ld.

17 Standard Header File Directories

GCC_INCLUDE_DIR means the same thing for native and cross. It is where GCC stores its private include files, and also where GCC stores the fixed include files. A cross compiled GCC runs fixincludes on the header files in '\$(tooldir)/include'. (If the cross compilation header files need to be fixed, they must be installed before GCC is built. If the cross compilation header files are already suitable for GCC, nothing special need be done).

GPLUSPLUS_INCLUDE_DIR means the same thing for native and cross. It is where g++ looks first for header files. The C++ library installs only target independent header files in that directory.

LOCAL_INCLUDE_DIR is used only by native compilers. GCC doesn't install anything there. It is normally '/usr/local/include'. This is where local additions to a packaged system should place header files.

CROSS_INCLUDE_DIR is used only by cross compilers. GCC doesn't install anything there.

TOOL_INCLUDE_DIR is used for both native and cross compilers. It is the place for other packages to install header files that GCC will use. For a cross-compiler, this is the equivalent of '/usr/include'. When you build a cross-compiler, fixincludes processes any header files in this directory.

18 Memory Management and Type Information

GCC uses some fairly sophisticated memory management techniques, which involve determining information about GCC's data structures from GCC's source code and using this information to perform garbage collection and implement precompiled headers.

A full C parser would be too complicated for this task, so a limited subset of C is interpreted and special markers are used to determine what parts of the source to look at. All struct and union declarations that define data structures that are allocated under control of the garbage collector must be marked. All global variables that hold pointers to garbage-collected memory must also be marked. Finally, all global variables that need to be saved and restored by a precompiled header must be marked. (The precompiled header mechanism can only save static variables if they're scalar. Complex data structures must be allocated in garbage-collected memory to be saved in a precompiled header.)

The full format of a marker is

```
GTY (([option] [(param)], [option] [(param)] ...))
```

but in most cases no options are needed. The outer double parentheses are still necessary, though: GTY(()). Markers can appear:

- In a structure definition, before the open brace;
- In a global variable declaration, after the keyword static or extern; and
- In a structure field definition, before the name of the field.

Here are some examples of marking simple data structures and globals.

```
struct tag GTY(())
{
  fields...
};

typedef struct tag GTY(())
{
  fields...
} *typename;

static GTY(()) struct tag *list; /* points to GC memory */
static GTY(()) int counter; /* save counter in a PCH */
```

The parser understands simple typedefs such as typedef struct tag *name; and typedef int name;. These don't need to be marked.

18.1 The Inside of a GTY(())

Sometimes the C code is not enough to fully describe the type structure. Extra information can be provided with GTY options and additional markers. Some options take a parameter, which may be either a string or a type name, depending on the parameter. If an option takes no parameter, it is acceptable either to omit the parameter entirely, or to provide an empty string as a parameter. For example, GTY ((skip)) and GTY ((skip (""))) are equivalent.

When the parameter is a string, often it is a fragment of C code. Four special escapes may be used in these strings, to refer to pieces of the data structure being marked:

%h The current structure.

- 71 The structure that immediately contains the current structure.
- The outermost structure that contains the current structure.
- %a A partial expression of the form [i1][i2]... that indexes the array item currently being marked.

For instance, suppose that you have a structure of the form

```
struct A {
    ...
};
struct B {
    struct A foo[12];
};
```

and b is a variable of type struct B. When marking 'b.foo[11]', %h would expand to 'b.foo[11]', %0 and %1 would both expand to 'b', and %a would expand to '[11]'.

As in ordinary C, adjacent strings will be concatenated; this is helpful when you have a complicated expression.

The available options are:

length ("expression")

There are two places the type machinery will need to be explicitly told the length of an array. The first case is when a structure ends in a variable-length array, like this:

```
struct rtvec_def GTY(()) {
  int num_elem; /* number of elements */
  rtx GTY ((length ("%h.num_elem"))) elem[1];
};
```

In this case, the **length** option is used to override the specified array length (which should usually be 1). The parameter of the option is a fragment of C code that calculates the length.

The second case is when a structure or a global variable contains a pointer to an array, like this:

```
tree *
    GTY ((length ("%h.regno_pointer_align_length"))) regno_decl;
In this case, regno_decl has been allocated by writing something like
    x->regno_decl =
        ggc_alloc (x->regno_pointer_align_length * sizeof (tree));
and the length provides the length of the field.
This second use of length also works on global variables, like:
    static GTY((length ("reg_base_value_size")))
    rtx *reg_base_value;
```

skip

If skip is applied to a field, the type machinery will ignore it. This is somewhat dangerous; the only safe use is in a union when one field really isn't ever used.

```
desc ("expression")
tag ("constant")
default
```

The type machinery needs to be told which field of a union is currently active. This is done by giving each field a constant tag value, and then specifying a discriminator using desc. The value of the expression given by desc is compared against each tag value, each of which should be different. If no tag is matched, the field marked with default is used if there is one, otherwise no field in the union will be marked.

In the desc option, the "current structure" is the union that it discriminates. Use %1 to mean the structure containing it. There are no escapes available to the tag option, since it is a constant.

For example,

```
struct tree_binding GTY(())
{
   struct tree_common common;
   union tree_binding_u {
      tree GTY ((tag ("0"))) scope;
      struct cp_binding_level * GTY ((tag ("1"))) level;
   } GTY ((desc ("BINDING_HAS_LEVEL_P ((tree)&%0)"))) xscope;
   tree value;
};
```

In this example, the value of BINDING_HAS_LEVEL_P when applied to a struct tree_binding * is presumed to be 0 or 1. If 1, the type mechanism will treat the field level as being present and if 0, will treat the field scope as being present.

```
param_is (type)
use_param
```

Sometimes it's convenient to define some data structure to work on generic pointers (that is, PTR) and then use it with a specific type. param_is specifies the real type pointed to, and use_param says where in the generic data structure that type should be put.

For instance, to have a htab_t that points to trees, one would write the definition of htab_t like this:

In more complicated cases, the data structure might need to work on several different types, which might not necessarily all be pointers. For this, param1_is through param9_is may be used to specify the real type of a field identified by use_param1 through use_param9.

use_params

When a structure contains another structure that is parameterized, there's no need to do anything special, the inner structure inherits the parameters of the outer one. When a structure contains a pointer to a parameterized structure,

the type machinery won't automatically detect this (it could, it just doesn't yet), so it's necessary to tell it that the pointed-to structure should use the same parameters as the outer structure. This is done by marking the pointer with the use_params option.

deletable

deletable, when applied to a global variable, indicates that when garbage collection runs, there's no need to mark anything pointed to by this variable, it can just be set to NULL instead. This is used to keep a list of free structures around for re-use.

if_marked ("expression")

Suppose you want some kinds of object to be unique, and so you put them in a hash table. If garbage collection marks the hash table, these objects will never be freed, even if the last other reference to them goes away. GGC has special handling to deal with this: if you use the if_marked option on a global hash table, GGC will call the routine whose name is the parameter to the option on each hash table entry. If the routine returns nonzero, the hash table entry will be marked as usual. If the routine returns zero, the hash table entry will be deleted.

The routine ggc_marked_p can be used to determine if an element has been marked already; in fact, the usual case is to use if_marked ("ggc_marked_p").

maybe_undef

When applied to a field, maybe_undef indicates that it's OK if the structure that this fields points to is never defined, so long as this field is always NULL. This is used to avoid requiring backends to define certain optional structures. It doesn't work with language frontends.

nested_ptr (type, "to expression", "from expression")

The type machinery expects all pointers to point to the start of an object. Sometimes for abstraction purposes it's convenient to have a pointer which points inside an object. So long as it's possible to convert the original object to and from the pointer, such pointers can still be used. type is the type of the original object, the to expression returns the pointer given the original object, and the from expression returns the original object given the pointer. The pointer will be available using the \hat{h} escape.

chain_next ("expression") chain_prev ("expression")

It's helpful for the type machinery to know if objects are often chained together in long lists; this lets it generate code that uses less stack space by iterating along the list instead of recursing down it. chain_next is an expression for the next item in the list, chain_prev is an expression for the previous item. For singly linked lists, use only chain_next; for doubly linked lists, use both. The machinery requires that taking the next item of the previous item gives the original item.

reorder ("function name")

Some data structures depend on the relative ordering of pointers. If the precompiled header machinery needs to change that ordering, it will call the function referenced by the reorder option, before changing the pointers in the object that's pointed to by the field the option applies to. The function must take four arguments, with the signature 'void*, void*, gt_pointer_operator, void*'. The first parameter is a pointer to the structure that contains the object being updated, or the object itself if there is no containing structure. The second parameter is a cookie that should be ignored. The third parameter is a routine that, given a pointer, will update it to its correct new value. The fourth parameter is a cookie that must be passed to the second parameter.

PCH cannot handle data structures that depend on the absolute values of pointers. reorder functions can be expensive. When possible, it is better to depend on properties of the data, like an ID number or the hash of a string instead.

special ("name")

The special option is used to mark types that have to be dealt with by special case machinery. The parameter is the name of the special case. See 'gengtype.c' for further details. Avoid adding new special cases unless there is no other alternative.

18.2 Marking Roots for the Garbage Collector

In addition to keeping track of types, the type machinery also locates the global variables (roots) that the garbage collector starts at. Roots must be declared using one of the following syntaxes:

- extern GTY(([options])) type name;
- static GTY(([options])) type name;

The syntax

• GTY(([options])) type name;

is not accepted. There should be an extern declaration of such a variable in a header somewhere—mark that, not the definition. Or, if the variable is only used in one file, make it static.

18.3 Source Files Containing Type Information

Whenever you add GTY markers to a source file that previously had none, or create a new source file containing GTY markers, there are three things you need to do:

- 1. You need to add the file to the list of source files the type machinery scans. There are four cases:
 - a. For a back-end file, this is usually done automatically; if not, you should add it to target_gtfiles in the appropriate port's entries in 'config.gcc'.
 - b. For files shared by all front ends, add the filename to the GTFILES variable in 'Makefile.in'.
 - c. For files that are part of one front end, add the filename to the gtfiles variable defined in the appropriate 'config-lang.in'. For C, the file is 'c-config-lang.in'.
 - d. For files that are part of some but not all front ends, add the filename to the gtfiles variable of all the front ends that use it.

- 2. If the file was a header file, you'll need to check that it's included in the right place to be visible to the generated files. For a back-end header file, this should be done automatically. For a front-end header file, it needs to be included by the same file that includes 'gtype-lang.h'. For other header files, it needs to be included in 'gtype-desc.c', which is a generated file, so add it to ifiles in open_base_file in 'gengtype.c'.
 - For source files that aren't header files, the machinery will generate a header file that should be included in the source file you just changed. The file will be called 'gt-path.h' where path is the pathname relative to the 'gcc' directory with slashes replaced by -, so for example the header file to be included in 'cp/parser.c' is called 'gt-cp-parser.c'. The generated header file should be included after everything else in the source file. Don't forget to mention this file as a dependency in the 'Makefile'!
- 3. If a new 'gt-path.h' file is needed, you need to arrange to add a 'Makefile' rule that will ensure this file can be built. This is done by making it a dependency of s-gtype, like this:

```
gt-path.h : s-gtype ; @true
```

For language frontends, there is another file that needs to be included somewhere. It will be called 'gtype-lang.h', where lang is the name of the subdirectory the language is contained in. It will need 'Makefile' rules just like the other generated files.

Funding Free Software

If you want to have more free software a few years from now, it makes sense for you to help encourage people to contribute funds for its development. The most effective approach known is to encourage commercial redistributors to donate.

Users of free software systems can boost the pace of development by encouraging forafee distributors to donate part of their selling price to free software developers—the Free Software Foundation, and others.

The way to convince distributors to do this is to demand it and expect it from them. So when you compare distributors, judge them partly by how much they give to free software development. Show distributors they must compete to be the one who gives the most.

To make this approach work, you must insist on numbers that you can compare, such as, "We will donate ten dollars to the Frobnitz project for each disk sold." Don't be satisfied with a vague promise, such as "A portion of the profits are donated," since it doesn't give a basis for comparison.

Even a precise fraction "of the profits from this disk" is not very meaningful, since creative accounting and unrelated business decisions can greatly alter what fraction of the sales price counts as profit. If the price you pay is \$50, ten percent of the profit is probably less than a dollar; it might be a few cents, or nothing at all.

Some redistributors do development work themselves. This is useful too; but to keep everyone honest, you need to inquire how much they do, and what kind. Some kinds of development make much more long-term difference than others. For example, maintaining a separate version of a program contributes very little; maintaining the standard version of a program for the whole community contributes much. Easy new ports contribute little, since someone else would surely do them; difficult ports such as adding a new CPU to the GNU Compiler Collection contribute more; major new features or packages contribute the most.

By establishing the idea that supporting further development is "the proper thing to do" when distributing free software for a fee, we can assure a steady flow of resources into making more free software.

Copyright © 1994 Free Software Foundation, Inc. Verbatim copying and redistribution of this section is permitted without royalty; alteration is not permitted.

The GNU Project and GNU/Linux

The GNU Project was launched in 1984 to develop a complete Unix-like operating system which is free software: the GNU system. (GNU is a recursive acronym for "GNU's Not Unix"; it is pronounced "guh-NEW".) Variants of the GNU operating system, which use the kernel Linux, are now widely used; though these systems are often referred to as "Linux", they are more accurately called GNU/Linux systems.

For more information, see:

http://www.gnu.org/ http://www.gnu.org/gnu/linux-and-gnu.html

GNU GENERAL PUBLIC LICENSE

Version 2, June 1991

Copyright © 1989, 1991 Free Software Foundation, Inc. 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public License is intended to guarantee your freedom to share and change free software—to make sure the software is free for all its users. This General Public License applies to most of the Free Software Foundation's software and to any other program whose authors commit to using it. (Some other Free Software Foundation software is covered by the GNU Library General Public License instead.) You can apply it to your programs, too.

When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs; and that you know you can do these things.

To protect your rights, we need to make restrictions that forbid anyone to deny you these rights or to ask you to surrender the rights. These restrictions translate to certain responsibilities for you if you distribute copies of the software, or if you modify it.

For example, if you distribute copies of such a program, whether gratis or for a fee, you must give the recipients all the rights that you have. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.

We protect your rights with two steps: (1) copyright the software, and (2) offer you this license which gives you legal permission to copy, distribute and/or modify the software.

Also, for each author's protection and ours, we want to make certain that everyone understands that there is no warranty for this free software. If the software is modified by someone else and passed on, we want its recipients to know that what they have is not the original, so that any problems introduced by others will not reflect on the original authors' reputations.

Finally, any free program is threatened constantly by software patents. We wish to avoid the danger that redistributors of a free program will individually obtain patent licenses, in effect making the program proprietary. To prevent this, we have made it clear that any patent must be licensed for everyone's free use or not licensed at all.

The precise terms and conditions for copying, distribution and modification follow.

TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

- 0. This License applies to any program or other work which contains a notice placed by the copyright holder saying it may be distributed under the terms of this General Public License. The "Program", below, refers to any such program or work, and a "work based on the Program" means either the Program or any derivative work under copyright law: that is to say, a work containing the Program or a portion of it, either verbatim or with modifications and/or translated into another language. (Hereinafter, translation is included without limitation in the term "modification".) Each licensee is addressed as "you".
 - Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running the Program is not restricted, and the output from the Program is covered only if its contents constitute a work based on the Program (independent of having been made by running the Program). Whether that is true depends on what the Program does.
- 1. You may copy and distribute verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and give any other recipients of the Program a copy of this License along with the Program.
 - You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.
- 2. You may modify your copy or copies of the Program or any portion of it, thus forming a work based on the Program, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:
 - a. You must cause the modified files to carry prominent notices stating that you changed the files and the date of any change.
 - b. You must cause any work that you distribute or publish, that in whole or in part contains or is derived from the Program or any part thereof, to be licensed as a whole at no charge to all third parties under the terms of this License.
 - c. If the modified program normally reads commands interactively when run, you must cause it, when started running for such interactive use in the most ordinary way, to print or display an announcement including an appropriate copyright notice and a notice that there is no warranty (or else, saying that you provide a warranty) and that users may redistribute the program under these conditions, and telling the user how to view a copy of this License. (Exception: if the Program itself is interactive but does not normally print such an announcement, your work based on the Program is not required to print an announcement.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Program, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Program, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Program.

In addition, mere aggregation of another work not based on the Program with the Program (or with a work based on the Program) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

- 3. You may copy and distribute the Program (or a work based on it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you also do one of the following:
 - a. Accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
 - b. Accompany it with a written offer, valid for at least three years, to give any third party, for a charge no more than your cost of physically performing source distribution, a complete machine-readable copy of the corresponding source code, to be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
 - c. Accompany it with the information you received as to the offer to distribute corresponding source code. (This alternative is allowed only for noncommercial distribution and only if you received the program in object code or executable form with such an offer, in accord with Subsection b above.)

The source code for a work means the preferred form of the work for making modifications to it. For an executable work, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the executable. However, as a special exception, the source code distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

If distribution of executable or object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place counts as distribution of the source code, even though third parties are not compelled to copy the source along with the object code.

- 4. You may not copy, modify, sublicense, or distribute the Program except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense or distribute the Program is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.
- 5. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Program or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Program (or any work based on the Program), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Program or works based on it.

- 6. Each time you redistribute the Program (or any work based on the Program), the recipient automatically receives a license from the original licensor to copy, distribute or modify the Program subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties to this License.
- 7. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Program at all. For example, if a patent license would not permit royalty-free redistribution of the Program by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Program.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system, which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

- 8. If the distribution and/or use of the Program is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Program under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.
- 9. The Free Software Foundation may publish revised and/or new versions of the General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.
 - Each version is given a distinguishing version number. If the Program specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of this License, you may choose any version ever published by the Free Software Foundation.
- 10. If you wish to incorporate parts of the Program into other free programs whose distribution conditions are different, write to the author to ask for permission. For software

which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY

- 11. BECAUSE THE PROGRAM IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.
- 12. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Programs

If you develop a new program, and you want it to be of the greatest possible use to the public, the best way to achieve this is to make it free software which everyone can redistribute and change under these terms.

To do so, attach the following notices to the program. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

```
one line to give the program's name and a brief idea of what it does. Copyright (C) year name of author
```

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.

Also add information on how to contact you by electronic and paper mail.

If the program is interactive, make it output a short notice like this when it starts in an interactive mode:

```
Gnomovision version 69, Copyright (C) year name of author Gnomovision comes with ABSOLUTELY NO WARRANTY; for details type 'show w'.

This is free software, and you are welcome to redistribute it under certain conditions; type 'show c' for details.
```

The hypothetical commands 'show w' and 'show c' should show the appropriate parts of the General Public License. Of course, the commands you use may be called something other than 'show w' and 'show c'; they could even be mouse-clicks or menu items—whatever suits your program.

You should also get your employer (if you work as a programmer) or your school, if any, to sign a "copyright disclaimer" for the program, if necessary. Here is a sample; alter the names:

```
Yoyodyne, Inc., hereby disclaims all copyright interest in the program 'Gnomovision' (which makes passes at compilers) written by James Hacker.

signature of Ty Coon, 1 April 1989
Ty Coon, President of Vice
```

This General Public License does not permit incorporating your program into proprietary programs. If your program is a subroutine library, you may consider it more useful to permit linking proprietary applications with the library. If this is what you want to do, use the GNU Library General Public License instead of this License.

GNU Free Documentation License

Version 1.2, November 2002

Copyright © 2000,2001,2002 Free Software Foundation, Inc. 59 Temple Place, Suite 330, Boston, MA 02111-1307, USA

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document free in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released

under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.

- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements."

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called

an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warrany Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See http://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

Copyright (C) year your name.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled ''GNU Free Documentation License''.

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

with the Invariant Sections being list their titles, with the Front-Cover Texts being list, and with the Back-Cover Texts being list.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.

Contributors to GCC

The GCC project would like to thank its many contributors. Without them the project would not have been nearly as successful as it has been. Any omissions in this list are accidental. Feel free to contact law@redhat.com or gerald@pfeifer.com if you have been left out or some of your contributions are not listed. Please keep this list in alphabetical order.

- Analog Devices helped implement the support for complex data types and iterators.
- John David Anglin for threading-related fixes and improvements to libstdc++-v3, and the HP-UX port.
- James van Artsdalen wrote the code that makes efficient use of the Intel 80387 register stack.
- Abramo and Roberto Bagnara for the SysV68 Motorola 3300 Delta Series port.
- Alasdair Baird for various bug fixes.
- Giovanni Bajo for analyzing lots of complicated C++ problem reports.
- Peter Barada for his work to improve code generation for new ColdFire cores.
- Gerald Baumgartner added the signature extension to the C++ front end.
- Godmar Back for his Java improvements and encouragement.
- Scott Bambrough for help porting the Java compiler.
- Wolfgang Bangerth for processing tons of bug reports.
- Jon Beniston for his Microsoft Windows port of Java.
- Daniel Berlin for better DWARF2 support, faster/better optimizations, improved alias analysis, plus migrating GCC to Bugzilla.
- Geoff Berry for his Java object serialization work and various patches.
- Eric Blake for helping to make GCJ and libgej conform to the specifications.
- Janne Blomqvist for contributions to gfortran.
- Segher Boessenkool for various fixes.
- Hans-J. Boehm for his garbage collector, IA-64 libffi port, and other Java work.
- Neil Booth for work on cpplib, lang hooks, debug hooks and other miscellaneous cleanups.
- Steven Bosscher for integrating the gfortran front end into GCC and for contributing to the tree-ssa branch.
- Eric Botcazou for fixing middle- and backend bugs left and right.
- Per Bothner for his direction via the steering committee and various improvements to the infrastructure for supporting new languages. Chill front end implementation. Initial implementations of cpplib, fix-header, config.guess, libio, and past C++ library (libg++) maintainer. Dreaming up, designing and implementing much of GCJ.
- Devon Bowen helped port GCC to the Tahoe.
- Don Bowman for mips-vxworks contributions.
- Dave Brolley for work on cpplib and Chill.
- Paul Brook for work on the ARM architecture and maintaining gfortran.

- Robert Brown implemented the support for Encore 32000 systems.
- Christian Bruel for improvements to local store elimination.
- Herman A.J. ten Brugge for various fixes.
- Joerg Brunsmann for Java compiler hacking and help with the GCJ FAQ.
- Joe Buck for his direction via the steering committee.
- Craig Burley for leadership of the G77 Fortran effort.
- Stephan Buys for contributing Doxygen notes for libstdc++.
- Paolo Carlini for libstdc++ work: lots of efficiency improvements to the C++ strings, streambufs and formatted I/O, hard detective work on the frustrating localization issues, and keeping up with the problem reports.
- John Carr for his alias work, SPARC hacking, infrastructure improvements, previous contributions to the steering committee, loop optimizations, etc.
- Stephane Carrez for 68HC11 and 68HC12 ports.
- Steve Chamberlain for support for the Renesas SH and H8 processors and the PicoJava processor, and for GCJ config fixes.
- Glenn Chambers for help with the GCJ FAQ.
- John-Marc Chandonia for various libgej patches.
- Scott Christley for his Objective-C contributions.
- Eric Christopher for his Java porting help and clean-ups.
- Branko Cibej for more warning contributions.
- The GNU Classpath project for all of their merged runtime code.
- Nick Clifton for arm, mcore, fr30, v850, m32r work, '--help', and other random hacking.
- Michael Cook for libstdc++ cleanup patches to reduce warnings.
- R. Kelley Cook for making GCC buildable from a read-only directory as well as other miscellaneous build process and documentation clean-ups.
- Ralf Corsepius for SH testing and minor bugfixing.
- Stan Cox for care and feeding of the x86 port and lots of behind the scenes hacking.
- Alex Crain provided changes for the 3b1.
- Ian Dall for major improvements to the NS32k port.
- Paul Dale for his work to add uClinux platform support to the m68k backend.
- Dario Dariol contributed the four varieties of sample programs that print a copy of their source.
- Russell Davidson for fstream and stringstream fixes in libstdc++.
- Bud Davis for work on the G77 and gfortran compilers.
- Mo DeJong for GCJ and libgej bug fixes.
- DJ Delorie for the DJGPP port, build and libiberty maintenance, and various bug fixes.
- Arnaud Desitter for helping to debug gfortran.

- Gabriel Dos Reis for contributions to G++, contributions and maintenance of GCC diagnostics infrastructure, libstdc++-v3, including valarray<>, complex<>, maintaining the numerics library (including that pesky imits>:-) and keeping up-to-date anything to do with numbers.
- Ulrich Drepper for his work on glibc, testing of GCC using glibc, ISO C99 support, CFG dumping support, etc., plus support of the C++ runtime libraries including for all kinds of C interface issues, contributing and maintaining complex<>, sanity checking and disbursement, configuration architecture, libio maintenance, and early math work.
- Zdenek Dvorak for a new loop unroller and various fixes.
- Richard Earnshaw for his ongoing work with the ARM.
- David Edelsohn for his direction via the steering committee, ongoing work with the RS6000/PowerPC port, help cleaning up Haifa loop changes, doing the entire AIX port of libstdc++ with his bare hands, and for ensuring GCC properly keeps working on AIX.
- Kevin Ediger for the floating point formatting of num_put::do_put in libstdc++.
- Phil Edwards for libstdc++ work including configuration hackery, documentation maintainer, chief breaker of the web pages, the occasional iostream bug fix, and work on shared library symbol versioning.
- Paul Eggert for random hacking all over GCC.
- Mark Elbrecht for various DJGPP improvements, and for libstdc++ configuration support for locales and fstream-related fixes.
- Vadim Egorov for libstdc++ fixes in strings, streambufs, and iostreams.
- Christian Ehrhardt for dealing with bug reports.
- Ben Elliston for his work to move the Objective-C runtime into its own subdirectory and for his work on autoconf.
- Marc Espie for OpenBSD support.
- Doug Evans for much of the global optimization framework, arc, m32r, and SPARC work.
- Christopher Faylor for his work on the Cygwin port and for caring and feeding the gcc.gnu.org box and saving its users tons of spam.
- Fred Fish for BeOS support and Ada fixes.
- Ivan Fontes Garcia for the Portugese translation of the GCJ FAQ.
- Peter Gerwinski for various bug fixes and the Pascal front end.
- Kaveh Ghazi for his direction via the steering committee, amazing work to make '-W -Wall' useful, and continuously testing GCC on a plethora of platforms.
- John Gilmore for a donation to the FSF earmarked improving GNU Java.
- Judy Goldberg for c++ contributions.
- Torbjorn Granlund for various fixes and the c-torture testsuite, multiply- and divideby-constant optimization, improved long long support, improved leaf function register allocation, and his direction via the steering committee.
- Anthony Green for his '-Os' contributions and Java front end work.
- Stu Grossman for gdb hacking, allowing GCJ developers to debug Java code.

- Michael K. Gschwind contributed the port to the PDP-11.
- Ron Guilmette implemented the protoize and unprotoize tools, the support for Dwarf symbolic debugging information, and much of the support for System V Release 4. He has also worked heavily on the Intel 386 and 860 support.
- Bruno Haible for improvements in the runtime overhead for EH, new warnings and assorted bug fixes.
- Andrew Haley for his amazing Java compiler and library efforts.
- Chris Hanson assisted in making GCC work on HP-UX for the 9000 series 300.
- Michael Hayes for various thankless work he's done trying to get the c30/c40 ports functional. Lots of loop and unroll improvements and fixes.
- Dara Hazeghi for wading through myriads of target-specific bug reports.
- Kate Hedstrom for staking the G77 folks with an initial testsuite.
- Richard Henderson for his ongoing SPARC, alpha, ia32, and ia64 work, loop opts, and generally fixing lots of old problems we've ignored for years, flow rewrite and lots of further stuff, including reviewing tons of patches.
- Aldy Hernandez for working on the PowerPC port, SIMD support, and various fixes.
- Nobuyuki Hikichi of Software Research Associates, Tokyo, contributed the support for the Sony NEWS machine.
- Kazu Hirata for caring and feeding the Renesas H8/300 port and various fixes.
- Katherine Holcomb for work on gfortran.
- Manfred Hollstein for his ongoing work to keep the m88k alive, lots of testing and bug fixing, particularly of GCC configury code.
- Steve Holmgren for MachTen patches.
- Jan Hubicka for his x86 port improvements.
- Falk Hueffner for working on C and optimization bug reports.
- Bernardo Innocenti for his m68k work, including merging of ColdFire improvements and uClinux support.
- Christian Iseli for various bug fixes.
- Kamil Iskra for general m68k hacking.
- Lee Iverson for random fixes and MIPS testing.
- Andreas Jaeger for testing and benchmarking of GCC and various bug fixes.
- Jakub Jelinek for his SPARC work and sibling call optimizations as well as lots of bug fixes and test cases, and for improving the Java build system.
- Janis Johnson for ia64 testing and fixes, her quality improvement sidetracks, and web page maintenance.
- Kean Johnston for SCO OpenServer support and various fixes.
- Tim Josling for the sample language treelang based originally on Richard Kenner's "toy" language.
- Nicolai Josuttis for additional libstdc++ documentation.
- Klaus Kaempf for his ongoing work to make alpha-vms a viable target.
- Steven G. Kargl for work on gfortran.

- David Kashtan of SRI adapted GCC to VMS.
- Ryszard Kabatek for many, many libstdc++ bug fixes and optimizations of strings, especially member functions, and for auto_ptr fixes.
- Geoffrey Keating for his ongoing work to make the PPC work for GNU/Linux and his automatic regression tester.
- Brendan Kehoe for his ongoing work with G++ and for a lot of early work in just about every part of libstdc++.
- Oliver M. Kellogg of Deutsche Aerospace contributed the port to the MIL-STD-1750A.
- Richard Kenner of the New York University Ultracomputer Research Laboratory wrote the machine descriptions for the AMD 29000, the DEC Alpha, the IBM RT PC, and the IBM RS/6000 as well as the support for instruction attributes. He also made changes to better support RISC processors including changes to common subexpression elimination, strength reduction, function calling sequence handling, and condition code support, in addition to generalizing the code for frame pointer elimination and delay slot scheduling. Richard Kenner was also the head maintainer of GCC for several years.
- Mumit Khan for various contributions to the Cygwin and Mingw32 ports and maintaining binary releases for Microsoft Windows hosts, and for massive libstdc++ porting work to Cygwin/Mingw32.
- Robin Kirkham for cpu32 support.
- Mark Klein for PA improvements.
- Thomas Koenig for various bug fixes.
- Bruce Korb for the new and improved fixincludes code.
- Benjamin Kosnik for his G++ work and for leading the libstdc++-v3 effort.
- Charles LaBrec contributed the support for the Integrated Solutions 68020 system.
- Jeff Law for his direction via the steering committee, coordinating the entire egcs project and GCC 2.95, rolling out snapshots and releases, handling merges from GCC2, reviewing tons of patches that might have fallen through the cracks else, and random but extensive hacking.
- Marc Lehmann for his direction via the steering committee and helping with analysis and improvements of x86 performance.
- Victor Leikehman for work on gfortran.
- Ted Lemon wrote parts of the RTL reader and printer.
- Kriang Lerdsuwanakij for C++ improvements including template as template parameter support, and many C++ fixes.
- Warren Levy for tremendous work on libgcj (Java Runtime Library) and random work on the Java front end.
- Alain Lichnewsky ported GCC to the MIPS CPU.
- Oskar Liljeblad for hacking on AWT and his many Java bug reports and patches.
- Robert Lipe for OpenServer support, new testsuites, testing, etc.
- Weiwen Liu for testing and various bug fixes.
- Dave Love for his ongoing work with the Fortran front end and runtime libraries.

- Martin von Löwis for internal consistency checking infrastructure, various C++ improvements including namespace support, and tons of assistance with libstdc++/compiler merges.
- H.J. Lu for his previous contributions to the steering committee, many x86 bug reports, prototype patches, and keeping the GNU/Linux ports working.
- Greg McGary for random fixes and (someday) bounded pointers.
- Andrew MacLeod for his ongoing work in building a real EH system, various code generation improvements, work on the global optimizer, etc.
- Vladimir Makarov for hacking some ugly i960 problems, PowerPC hacking improvements to compile-time performance, overall knowledge and direction in the area of instruction scheduling, and design and implementation of the automaton based instruction scheduler.
- Bob Manson for his behind the scenes work on dejagnu.
- Philip Martin for lots of libstdc++ string and vector iterator fixes and improvements, and string clean up and testsuites.
- All of the Mauve project contributors, for Java test code.
- Bryce McKinlay for numerous GCJ and libgcj fixes and improvements.
- Adam Megacz for his work on the Microsoft Windows port of GCJ.
- Michael Meissner for LRS framework, ia32, m32r, v850, m88k, MIPS, powerpc, haifa, ECOFF debug support, and other assorted hacking.
- Jason Merrill for his direction via the steering committee and leading the G++ effort.
- David Miller for his direction via the steering committee, lots of SPARC work, improvements in jump.c and interfacing with the Linux kernel developers.
- Gary Miller ported GCC to Charles River Data Systems machines.
- Alfred Minarik for libstdc++ string and ios bug fixes, and turning the entire libstdc++ testsuite namespace-compatible.
- Mark Mitchell for his direction via the steering committee, mountains of C++ work, load/store hoisting out of loops, alias analysis improvements, ISO C restrict support, and serving as release manager for GCC 3.x.
- Alan Modra for various GNU/Linux bits and testing.
- Toon Moene for his direction via the steering committee, Fortran maintenance, and his ongoing work to make us make Fortran run fast.
- Jason Molenda for major help in the care and feeding of all the services on the gcc.gnu.org (formerly egcs.cygnus.com) machine—mail, web services, ftp services, etc etc. Doing all this work on scrap paper and the backs of envelopes would have been... difficult.
- Catherine Moore for fixing various ugly problems we have sent her way, including the haifa bug which was killing the Alpha & PowerPC Linux kernels.
- Mike Moreton for his various Java patches.
- David Mosberger-Tang for various Alpha improvements, and for the initial IA-64 port.
- Stephen Moshier contributed the floating point emulator that assists in cross-compilation and permits support for floating point numbers wider than 64 bits and for ISO C99 support.

- Bill Moyer for his behind the scenes work on various issues.
- Philippe De Muyter for his work on the m68k port.
- Joseph S. Myers for his work on the PDP-11 port, format checking and ISO C99 support, and continuous emphasis on (and contributions to) documentation.
- Nathan Myers for his work on libstdc++-v3: architecture and authorship through the first three snapshots, including implementation of locale infrastructure, string, shadow C headers, and the initial project documentation (DESIGN, CHECKLIST, and so forth). Later, more work on MT-safe string and shadow headers.
- Felix Natter for documentation on porting libstdc++.
- Nathanael Nerode for cleaning up the configuration/build process.
- NeXT, Inc. donated the front end that supports the Objective-C language.
- Hans-Peter Nilsson for the CRIS and MMIX ports, improvements to the search engine setup, various documentation fixes and other small fixes.
- Geoff Noer for his work on getting cygwin native builds working.
- Diego Novillo for his SPEC performance tracking web pages and assorted fixes in the middle end and various back ends.
- David O'Brien for the FreeBSD/alpha, FreeBSD/AMD x86-64, FreeBSD/ARM, FreeBSD/PowerPC, and FreeBSD/SPARC64 ports and related infrastructure improvements.
- Alexandre Oliva for various build infrastructure improvements, scripts and amazing testing work, including keeping libtool issues sane and happy.
- Stefan Olsson for work on mt_alloc.
- Melissa O'Neill for various NeXT fixes.
- Rainer Orth for random MIPS work, including improvements to GCC's o32 ABI support, improvements to dejagnu's MIPS support, Java configuration clean-ups and porting work, etc.
- Hartmut Penner for work on the s390 port.
- Paul Petersen wrote the machine description for the Alliant FX/8.
- Alexandre Petit-Bianco for implementing much of the Java compiler and continued Java maintainership.
- Matthias Pfaller for major improvements to the NS32k port.
- Gerald Pfeifer for his direction via the steering committee, pointing out lots of problems we need to solve, maintenance of the web pages, and taking care of documentation maintenance in general.
- Andrew Pinski for processing bug reports by the dozen.
- Ovidiu Predescu for his work on the Objective-C front end and runtime libraries.
- Jerry Quinn for major performance improvements in C++ formatted I/O.
- Ken Raeburn for various improvements to checker, MIPS ports and various cleanups in the compiler.
- Rolf W. Rasmussen for hacking on AWT.
- David Reese of Sun Microsystems contributed to the Solaris on PowerPC port.

- Volker Reichelt for keeping up with the problem reports.
- Joern Rennecke for maintaining the sh port, loop, regmove & reload hacking.
- Loren J. Rittle for improvements to libstdc++-v3 including the FreeBSD port, threading fixes, thread-related configury changes, critical threading documentation, and solutions to really tricky I/O problems, as well as keeping GCC properly working on FreeBSD and continuous testing.
- Craig Rodrigues for processing tons of bug reports.
- Ola Rönnerup for work on mt_alloc.
- Gavin Romig-Koch for lots of behind the scenes MIPS work.
- David Ronis inspired and encouraged Craig to rewrite the G77 documentation in texinfo format by contributing a first pass at a translation of the old 'g77-0.5.16/f/D0C' file.
- Ken Rose for fixes to GCC's delay slot filling code.
- Paul Rubin wrote most of the preprocessor.
- Pétur Runólfsson for major performance improvements in C++ formatted I/O and large file support in C++ filebuf.
- Chip Salzenberg for libstdc++ patches and improvements to locales, traits, Makefiles, libio, libtool hackery, and "long long" support.
- Juha Sarlin for improvements to the H8 code generator.
- Greg Satz assisted in making GCC work on HP-UX for the 9000 series 300.
- Roger Sayle for improvements to constant folding and GCC's RTL optimizers as well as for fixing numerous bugs.
- Bradley Schatz for his work on the GCJ FAQ.
- Peter Schauer wrote the code to allow debugging to work on the Alpha.
- William Schelter did most of the work on the Intel 80386 support.
- Tobias Schlüter for work on gfortran.
- Bernd Schmidt for various code generation improvements and major work in the reload pass as well a serving as release manager for GCC 2.95.3.
- Peter Schmid for constant testing of libstdc++—especially application testing, going above and beyond what was requested for the release criteria—and libstdc++ header file tweaks.
- Jason Schroeder for jcf-dump patches.
- Andreas Schwab for his work on the m68k port.
- Lars Segerlund for work on gfortran.
- Joel Sherrill for his direction via the steering committee, RTEMS contributions and RTEMS testing.
- Nathan Sidwell for many C++ fixes/improvements.
- Jeffrey Siegal for helping RMS with the original design of GCC, some code which handles the parse tree and RTL data structures, constant folding and help with the original VAX & m68k ports.
- Kenny Simpson for prompting libstdc++ fixes due to defect reports from the LWG (thereby keeping GCC in line with updates from the ISO).

- Franz Sirl for his ongoing work with making the PPC port stable for GNU/Linux.
- Andrey Slepuhin for assorted AIX hacking.
- Christopher Smith did the port for Convex machines.
- Danny Smith for his major efforts on the Mingw (and Cygwin) ports.
- Randy Smith finished the Sun FPA support.
- Scott Snyder for queue, iterator, istream, and string fixes and libstdc++ testsuite entries. Also for providing the patch to G77 to add rudimentary support for INTEGER*1, INTEGER*2, and LOGICAL*1.
- Brad Spencer for contributions to the GLIBCPP_FORCE_NEW technique.
- Richard Stallman, for writing the original GCC and launching the GNU project.
- Jan Stein of the Chalmers Computer Society provided support for Genix, as well as part of the 32000 machine description.
- Nigel Stephens for various mips16 related fixes/improvements.
- Jonathan Stone wrote the machine description for the Pyramid computer.
- Graham Stott for various infrastructure improvements.
- John Stracke for his Java HTTP protocol fixes.
- Mike Stump for his Elxsi port, G++ contributions over the years and more recently his vxworks contributions
- Jeff Sturm for Java porting help, bug fixes, and encouragement.
- Shigeya Suzuki for this fixes for the bsdi platforms.
- Ian Lance Taylor for his mips 16 work, general configury hacking, fixincludes, etc.
- Holger Teutsch provided the support for the Clipper CPU.
- Gary Thomas for his ongoing work to make the PPC work for GNU/Linux.
- Philipp Thomas for random bug fixes throughout the compiler
- Jason Thorpe for thread support in libstdc++ on NetBSD.
- Kresten Krab Thorup wrote the run time support for the Objective-C language and the fantastic Java bytecode interpreter.
- Michael Tiemann for random bug fixes, the first instruction scheduler, initial C++ support, function integration, NS32k, SPARC and M88k machine description work, delay slot scheduling.
- Andreas Tobler for his work porting libgej to Darwin.
- Teemu Torma for thread safe exception handling support.
- Leonard Tower wrote parts of the parser, RTL generator, and RTL definitions, and of the VAX machine description.
- Tom Tromey for internationalization support and for his many Java contributions and libgcj maintainership.
- Lassi Tuura for improvements to config.guess to determine HP processor types.
- Petter Urkedal for libstdc++ CXXFLAGS, math, and algorithms fixes.
- Andy Vaught for the design and initial implementation of the gfortran front end.
- Brent Verner for work with the libstdc++ cshadow files and their associated configure steps.

- Todd Vierling for contributions for NetBSD ports.
- Jonathan Wakely for contributing libstdc++ Doxygen notes and XHTML guidance.
- Dean Wakerley for converting the install documentation from HTML to texinfo in time for GCC 3.0.
- Krister Walfridsson for random bug fixes.
- Feng Wang for contributions to gfortran.
- Stephen M. Webb for time and effort on making libstdc++ shadow files work with the tricky Solaris 8+ headers, and for pushing the build-time header tree.
- John Wehle for various improvements for the x86 code generator, related infrastructure improvements to help x86 code generation, value range propagation and other work, WE32k port.
- Ulrich Weigand for work on the s390 port.
- Zack Weinberg for major work on cpplib and various other bug fixes.
- Matt Welsh for help with Linux Threads support in GCJ.
- Urban Widmark for help fixing java.io.
- Mark Wielaard for new Java library code and his work integrating with Classpath.
- Dale Wiles helped port GCC to the Tahoe.
- Bob Wilson from Tensilica, Inc. for the Xtensa port.
- Jim Wilson for his direction via the steering committee, tackling hard problems in various places that nobody else wanted to work on, strength reduction and other loop optimizations.
- Carlo Wood for various fixes.
- Tom Wood for work on the m88k port.
- Canqun Yang for work on gfortran.
- Masanobu Yuhara of Fujitsu Laboratories implemented the machine description for the Tron architecture (specifically, the Gmicro).
- Kevin Zachmann helped port GCC to the Tahoe.
- Xiaoqiang Zhang for work on gfortran.
- Gilles Zunino for help porting Java to Irix.

In addition to the above, all of which also contributed time and energy in testing GCC, we would like to thank the following for their contributions to testing:

- Michael Abd-El-Malek
- Thomas Arend
- Bonzo Armstrong
- Steven Ashe
- Chris Baldwin
- David Billinghurst
- Jim Blandy
- Stephane Bortzmeyer
- Horst von Brand

- Frank Braun
- Rodney Brown
- Sidney Cadot
- Bradford Castalia
- Jonathan Corbet
- Ralph Doncaster
- Richard Emberson
- Levente Farkas
- Graham Fawcett
- Mark Fernyhough
- Robert A. French
- Jörgen Freyh
- Mark K. Gardner
- Charles-Antoine Gauthier
- Yung Shing Gene
- David Gilbert
- Simon Gornall
- Fred Gray
- John Griffin
- Patrik Hagglund
- Phil Hargett
- Amancio Hasty
- Takafumi Hayashi
- Bryan W. Headley
- Kevin B. Hendricks
- Joep Jansen
- Christian Joensson
- Michel Kern
- David Kidd
- Tobias Kuipers
- Anand Krishnaswamy
- A. O. V. Le Blanc
- llewelly
- Damon Love
- Brad Lucier
- Matthias Klose
- Martin Knoblauch
- Rick Lutowski
- Jesse Macnish

- Stefan Morrell
- Anon A. Mous
- Matthias Mueller
- Pekka Nikander
- Rick Niles
- Jon Olson
- Magnus Persson
- Chris Pollard
- Richard Polton
- Derk Reefman
- David Rees
- Paul Reilly
- Tom Reilly
- Torsten Rueger
- Danny Sadinoff
- Marc Schifer
- Erik Schnetter
- Wayne K. Schroll
- David Schuler
- Vin Shelton
- Tim Souder
- Adam Sulmicki
- Bill Thorson
- George Talbot
- Pedro A. M. Vazquez
- Gregory Warnes
- Ian Watson
- David E. Young
- And many others

And finally we'd like to thank everyone who uses the compiler, submits bug reports and generally reminds us why we're doing this work in the first place.

Option Index

GCC's command line options are indexed here without any initial '-' or '--'. Where an option has both positive and negative forms (such as '-foption' and '-fno-option'), relevant entries in the manual are indexed under the most appropriate form; it may sometimes be useful to look up both forms.

msoft-float 12

Concept Index

!		>
'!' in constraint	182	'>' in constraint
#		?
'#' in constraint	183	'?' in constraint
# in template		
=		
#pragma 377,	310	_
		absvdi2 11
%		absvsi2 11
	100	adddf3 12
'%' in constraint		addsf3 12
% in GTY option		addtf3 12
'%' in template	171	addvdi3 11
		addvsi3 11
0_		addxf3 12
&		ashldi3 9
'&' in constraint	183	ashlsi39
		ashlti39
,		ashrdi39
		ashrsi39
(nil)	100	ashrti39
(1111)	100	builtin_args_info 310
		builtin_classify_type 310
*		builtin_next_arg
		builtin_saveregs 309
*	385	clear_cache 16
'*' in constraint	183	clzdi2 11
* in template	172	clzsi2 11
		clzti2 11
		cmpdf2 14
+		cmpdi2 10
'+' in constraint	183	cmpsf214
		cmptf214
		cmpti2 10
/		CTOR_LIST
'/c' in RTL dump	116	ctzdi2 11
'/f' in RTL dump		ctzsi2 11
'/i' in RTL dump	117	ctzti2 11
'/j' in RTL dump	117	divdf3 12
'/s' in RTL dump	117	divdi39
'/u' in RTL dump	117	divsf312
'/v' in RTL dump	110	divsi3 9
/v in itil dump		divtf3 12
		divti3 9
<		divxf3 12
		DTOR_LIST
'<' in constraint		eqdf2
		eqsf2
_		eqtf2
		extenddftf2
'=' in constraint		extenddfxf2 13
		extendsfdf213

extendsftf2	modti310
extendsfxf2 13	muldf3
ffsdi211	muldi3
ffsti211	mulsf3
fixdfdi	mulsi3
fixdfsi 13	multf3
fixdfti 13	multi3
fixsfdi 13	mulvdi3 11
fixsfsi 13	mulvsi3 11
fixsfti 13	mulxf3 12
fixtfdi 13	nedf2
fixtfsi 13	negdf2 12
fixtfti 13	negdi2 10
fixunsdfdi 13	negsf2 12
fixunsdfsi 13	negtf2 12
fixunsdfti 14	negti2 10
fixunssfdi 13	negvdi2 11
fixunssfsi 13	negvsi2 11
fixunssfti 14	negxf212
fixunstfdi 13	nesf2
fixunstfsi 13	netf2
fixunstfti 14	paritydi2 11
fixunsxfdi 13	paritysi2 11
fixunsxfsi	parityti2 11
fixunsxfti	popcountdi2
fixxfdi	popcountsi2 12
fixxfsi	popcountti2
	subdf3
fixxfti	subsf3
	subtf3
floatdisf	subvdi3
floatditf	subvsi3 11
floatdixf	subxf3
floatsidf 14	truncdfsf2
floatsisf 14	trunctfdf2
floatsitf 14	trunctfsf2
floatsixf 14	truncxfdf2
floattidf 14	truncx1d12
floattisf 14	
floattitf 14	ucmpdi2 10
floattixf 14	ucmpti2 10
gedf2 15	udivdi3 10
gesf215	udivmoddi3 10
getf2 15	udivsi3 10
gtdf2	udivti3 10
gtsf2 15	umoddi3 10
gttf2 15	umodsi3 10
ledf215	umodti3 10
lesf2	unorddf2 14
letf2 15	unordsf2 14
lshrdi39	unordtf2 14
lshrsi39	
lshrti39	\
ltdf215	,
ltsf2	\
lttf215	
main	0
moddi310	0
modsi3	'0' in constraint
mous ±0	

\mathbf{A}	ARRAY_TYPE 57
abort 5	AS_NEEDS_DASH_FOR_PIPED_INPUT
abs	ashift
abs and attributes	ashift and attributes
ABS_EXPR	ashiftrt 130
absence_set 239	ashiftrt and attributes
absm2 instruction pattern 199	ashlm3 instruction pattern 199
absolute value	ashrm3 instruction pattern 199
access to operands	ASM_APP_OFF 336
access to special operands	ASM_APP_ON 335
accessors	ASM_COMMENT_START
ACCUMULATE_OUTGOING_ARGS 296	ASM_DECLARE_CLASS_REFERENCE 347
ACCUMULATE_OUTGOING_ARGS and stack frames	ASM_DECLARE_CONSTANT_NAME
	ASM_DECLARE_FUNCTION_NAME
ADA_LONG_TYPE_SIZE	ASM_DECLARE_FUNCTION_SIZE
ADDITIONAL_REGISTER_NAMES	ASM_DECLARE_OBJECT_NAME 343
addm3 instruction pattern 198	ASM_DECLARE_REGISTER_GLOBAL
addmodecc instruction pattern 204	ASM_DECLARE_UNRESOLVED_REFERENCE
addr_diff_vec 140	ASM_FINAL_SPEC
addr_diff_vec, length of	ASM_FINISH_DECLARE_OBJECT
ADDR_EXPR 76	ASM_FORMAT_PRIVATE_NAME 346
addr_vec 140	asm_fprintf
addr_vec, length of	ASM_FPRINTF_EXTENSIONS
address constraints	ASM_GENERATE_INTERNAL_LABEL
address_operand 175, 179	asm_input 140
addressing modes	asm_input and '/v' 114
$\verb"addressof" \dots \dots$	ASM_MAYBE_OUTPUT_ENCODED_ADDR_RTX 290
AD JUST_FIELD_ALIGN	ASM_NO_SKIP_IN_TEXT358
AD JUST_INSN_LENGTH	asm_noperands
AGGR_INIT_EXPR 76	asm_operands and '/v'
aggregates as return values	asm_operands, RTL sharing 152
alias	asm_operands, usage
ALL_COP_ADDITIONAL_REGISTER_NAMES 369	ASM_OUTPUT_ADDR_DIFF_ELT 354
ALL_REGS 277	ASM_OUTPUT_ADDR_VEC_ELT
ALLOCATE_INITIAL_VALUE	ASM_OUTPUT_ALIGN
allocate_stack instruction pattern	ASM_OUTPUT_ALIGN_WITH_NOP
alternate entry points	ASM_OUTPUT_ALIGNED_BSS
and	ASM_OUTPUT_ALIGNED_COMMON
and and attributes	ASM_OUTPUT_ALIGNED_DECL_COMMON
and, canonicalization of	ASM_OUTPUT_ALIGNED_DECL_LOCAL
andm3 instruction pattern	ASM_OUTPUT_ALIGNED_LOCAL
annotations	ASM_OUTPUT_ASCII
APPLY_RESULT_SIZE	ASM_OUTPUT_BSS
ARG_POINTER_CFA_OFFSET	ASM_OUTPUT_CASE_LABEL
ARG_POINTER_REGNUM	ASM_OUTPUT_COMMON
	ASM_OUTPUT_DEBUG_LABEL
arg_pointer_rtx 293 ARGS_GROW_DOWNWARD 286	ASM_OUTPUT_DEF
argument passing	ASM_OUTPUT_DEF_FROM_DECLS
arguments in registers	ASM_OUTPUT_DWARF_DELTA
arguments on stack	ASM_OUTPUT_DWARF_OFFSET
arithmetic library	ASM_OUTPUT_DWARF_PCREL
arithmetic shift	ASM_OUTPUT_EXTERNAL
arithmetic, in RTL	ASM_OUTPUT_FDESC
ARITHMETIC_TYPE_P	ASM_OUTPUT_IDENT
array 57	ASM_OUTPUT_INTERNAL_LABEL
ARRAY_RANGE_REF	ASM_OUTPUT_LABEL
ARRAY_REF	ASM_OUTPUT_LABEL_REF

ASM_OUTPUT_LABELREF	basic block	155
ASM_OUTPUT_LOCAL 340	basic-block.h	
ASM_OUTPUT_MAX_SKIP_ALIGN	basic_block	
ASM_OUTPUT_MEASURED_SIZE	BASIC_BLOCK	155
ASM_OUTPUT_OPCODE	BB_DIRTY, clear_bb_flags,	
ASM_OUTPUT_POOL_EPILOGUE	update_life_info_in_dirty_blocks	163
ASM_OUTPUT_POOL_PROLOGUE	BB_HEAD, BB_END	
ASM_OUTPUT_REG_POP	bcond instruction pattern	
ASM_OUTPUT_REG_PUSH	BIGGEST_ALIGNMENT	
ASM OUTPUT SHARED BSS	BIGGEST_FIELD_ALIGNMENT	
ASM_OUTPUT_SHARED_COMMON	BImode	
ASM_OUTPUT_SHARED_LOCAL	BIND_EXPR	
ASM_OUTPUT_SIZE_DIRECTIVE	BINFO TYPE	
ASM_OUTPUT_SKIP	bit-fields	
ASM_OUTPUT_SOURCE_FILENAME	BIT_AND_EXPR	
ASM_OUTPUT_SPECIAL_POOL_ENTRY	BIT_IOR_EXPR	
ASM_OUTPUT_SYMBOL_REF	BIT_NOT_EXPR	
	BIT_XOR_EXPR	
ASM_OUTPUT_TYPE_DIRECTIVE	BITFIELD_NBYTES_LIMITED	
ASM_OUTPUT_WEAK_ALIAS	BITS_BIG_ENDIAN	
ASM_PREFERRED_EH_DATA_FORMAT		
ASM_SPEC	BITS_BIG_ENDIAN, effect on sign_extract	
ASM_STABD_OP	BITS_PER_UNIT	
ASM_STABN_OP	BITS_PER_WORD	
ASM_STABS_OP	bitwise complement	
ASM_WEAKEN_DECL	bitwise exclusive-or	
ASM_WEAKEN_LABEL 343	bitwise inclusive-or	
assemble_name 341	bitwise logical-and	
${\tt assemble_name_raw$	BLKmode	
assembler format	BLKmode, and function return values	
assembler instructions in RTL 142	block statement iterators 156,	
ASSEMBLER_DIALECT	BLOCK_FOR_INSN, bb_for_stmt	
assigning attribute values to insns	BLOCK_REG_PADDING	
assignment operator 68	Blocks	
asterisk in template	bool 333, 334,	
atan2m3 instruction pattern 200	BOOL_TYPE_SIZE	
attr 231, 232	BOOLEAN_TYPE	
attr_flag 231	branch prediction	
attribute expressions	BRANCH_COST	
attribute specifications	break_out_memory_refs	
attribute specifications example	BREAK_STMT	
attributes	bsi_commit_edge_inserts	162
attributes, defining	bsi_end_p	161
attributes, target-specific	bsi_insert_after	161
autoincrement addressing, availability 5	bsi_insert_before	162
autoincrement/decrement addressing	bsi_insert_on_edge	162
automata_option	bsi_last	161
automaton based pipeline description 236, 237	bsi_next	161
automaton based scheduler	bsi_prev	161
AVOID_CCMODE_COPIES	bsi_remove	
AVOID_COMODE_COM IED	bsi_start	
	BSS_SECTION_ASM_OP	
В	builtin_longjmp instruction pattern	
	builtin_setjmp_receiver instruction pattern	
backslash		210
barrier	builtin_setjmp_setup instruction pattern	
barrier and '/f'	byte_mode	
barrier and '/i' 115	BYTES_BIG_ENDIAN	
barrier and '/v'	BYTES_BIG_ENDIAN, effect on subreg	
DACE DEC CLACC 970		

\mathbf{C}	CD Imode	20
C statements for assembler output 172	CEIL_DIV_EXPR 7	
C/C++ Internal Representation	CEIL_MOD_EXPR 7	
c_register_pragma	ceilm2 instruction pattern 20	0(
c_register_pragma_with_expansion 377	CFG, Control Flow Graph 15	55
C4X_FLOAT_FORMAT	cfghooks.h	30
C99 math functions, implicit usage 315	cgraph_finalize_function 4	15
call	chain_next 40	0(
call instruction pattern	chain_prev 40	
call usage	change_address 19) 6
call, in mem	char 333, 37	70
call-clobbered register	CHAR_TYPE_SIZE 26	39
call-saved register	check_stack instruction pattern 20)9
call-used register	CHImode 12	
CALL_EXPR	class 6	33
call_insn	class definitions, register	77
call_insn and '/f' 114	class preference constraints	32
call_insn and '/i' 115	CLASS_LIKELY_SPILLED_P 28	33
call_insn and '/j' 115	CLASS_MAX_NREGS	33
call_insn and '/s'	CLASS_TYPE_P 5	59
call_insn and '/u' 113	classes of RTX codes	8(
call_insn and '/v' 113	CLASSTYPE_DECLARED_CLASS 6	33
CALL_INSN_FUNCTION_USAGE 143	CLASSTYPE_HAS_MUTABLE 6	35
call_pop instruction pattern 205	CLASSTYPE_NON_POD_P6	35
CALL_POPS_ARGS 297	CLEANUP_DECL 7	71
CALL_REALLY_USED_REGISTERS	CLEANUP_EXPR 7	71
CALL_USED_REGISTERS	CLEANUP_POINT_EXPR	76
call_used_regs	CLEANUP_STMT 7	71
call_value instruction pattern 205	Cleanups 9	1 (
call_value_pop instruction pattern 205	CLEAR_BY_PIECES_P	
CALLER_SAVE_PROFITABLE	CLEAR_INSN_CACHE	13
calling conventions	CLEAR_RATIO 32	24
calling functions in RTL	clobber	
CAN_DEBUG_WITHOUT_FP	clrmemm instruction pattern 20)2
CAN_ELIMINATE 295	clz	31
can_fallthru 155	CLZ_DEFINED_VALUE_AT_ZERO	
canadian	clzm2 instruction pattern 20	
CANNOT_CHANGE_MODE_CLASS 283	cmpm instruction pattern 20	
canonicalization of instructions	cmpmemm instruction pattern 20	
CANONICALIZE_COMPARISON 321	cmpstrm instruction pattern 20	
canonicalize_funcptr_for_compare instruction	code generation RTL sequences 21	
pattern	code macros in '.md' files 24	
CASE_USE_BIT_TESTS	code_label 14	
CASE_VALUES_THRESHOLD 372	code_label and '/i' 113, 11	
CASE_VECTOR_MODE	code_label and '/v' 11	
CASE_VECTOR_PC_RELATIVE 372	CODE_LABEL_NUMBER	
CASE_VECTOR_SHORTEN_MODE 372	codes, RTL expression	
casesi instruction pattern 206	COImode	
cbranchmode4 instruction pattern 205	COLLECT_EXPORT_LIST	
cc_status 320	COLLECT_SHARED_FINI_FUNC	
CC_STATUS_MDEP	COLLECT_SHARED_INIT_FUNC	
CC_STATUS_MDEP_INIT	COLLECT2_HOST_INITIALIZATION	
cc0	combiner pass	
cc0, RTL sharing	commit_edge_insertions 16	
cc0_rtx	compare	
CC1_SPEC	compare, canonicalization of	
CC1PLUS_SPEC	comparison_operator17	
CCmo de	compiler passes and files 4	15

complement, bitwise	constant definitions	3
COMPLEX_CST 76	CONSTANT_ADDRESS_P	6
COMPLEX_EXPR 76	CONSTANT_ALIGNMENT	3
COMPLEX_TYPE 57	CONSTANT_P 316	6
COMPONENT_REF 76	CONSTANT_POOL_ADDRESS_P 113	3
Compound Expressions 89	CONSTANT_POOL_BEFORE_FUNCTION	8
Compound Lvalues	constants in constraints	8
COMPOUND_EXPR 76	constm1_rtx 125	2
COMPOUND_LITERAL_EXPR 76	constraint modifier characters 183	3
COMPOUND_LITERAL_EXPR_DECL 85	constraint, matching 179	9
COMPOUND_LITERAL_EXPR_DECL_STMT85	CONSTRAINT_LEN	9
computed jump 158	constraints	7
computing the length of an insn	constraints, machine specific	4
cond 132	constructor	8
cond and attributes	CONSTRUCTOR 76	6
cond_exec 139	constructors, automatic calls 393	3
COND_EXPR 76	constructors, output of 348	8
condition code register	container	7
condition code status 320	CONTINUE_STMT 7	1
condition codes	contributors	1
conditional execution	controlling register usage	3
Conditional Expressions	controlling the compilation driver	7
CONDITIONAL_REGISTER_USAGE 273	conventions, run-time	7
conditional_trap instruction pattern 211	conversions	4
conditions, in patterns	CONVERT_EXPR 76	6
configuration file	copy constructor	8
configure terms	copy_rtx 318	8
CONJ_EXPR 76	copy_rtx_if_shared	
const and '/i' 115	cosm2 instruction pattern 199	9
CONST_DECL 65	costs of instructions 325	2
const_double 122	CP_INTEGRAL_TYPE	8
const_double, RTL sharing 152	cp_namespace_decls65	3
CONST_DOUBLE_CHAIN	CP_TYPE_CONST_NON_VOLATILE_P 58	8
CONST_DOUBLE_LOW 123	CP_TYPE_CONST_P 58	8
CONST_DOUBLE_MEM 122	CP_TYPE_QUALS	8
CONST_DOUBLE_OK_FOR_CONSTRAINT_P 284	CP_TYPE_RESTRICT_P	8
CONST_DOUBLE_OK_FOR_LETTER_P 284	CP_TYPE_VOLATILE_P	8
${\tt const_double_operand$	CPLUSPLUS_CPP_SPEC	9
const_int 122	CPP_SPEC 249	9
const_int and attribute tests	CQImode	0
const_int and attributes	cross compilation and floating point 368	
const_int, RTL sharing 152	CRT_CALL_STATIC_FUNCTION 33	1
const_int_operand	CRTSTUFF_T_CFLAGS 389	9
CONST_OK_FOR_CONSTRAINT_P 284	CRTSTUFF_T_CFLAGS_S	9
CONST_OK_FOR_LETTER_P 284	CS Imode	0
CONST_OR_PURE_CALL_P	CTImode	
const_string 123	ctz	1
const_string and attributes	CTZ_DEFINED_VALUE_AT_ZERO	6
const_true_rtx	ctzm2 instruction pattern 200	0
const_vector 122	CUMULATIVE_ARGS	
const_vector, RTL sharing	current_function_epilogue_delay_list 30	
const0_rtx	current_function_is_leaf 27	
CONSTO_RTX	current_function_outgoing_args_size 296	
const1_rtx 122	current_function_pops_args 300	б
CONST1_RTX	current_function_pretend_args_size 300	
const2_rtx	current_function_uses_only_leaf_regs 27	
CONST2_RTX	current_insn_predicate 244	2
constant attributes 235		

T	
D	DECL_GLOBAL_CTOR_P 68, 70
data bypass	DECL_GLOBAL_DTOR_P 68, 70
data dependence delays	DECL_INITIAL 65
data structures	DECL_LINKONCE_P
DATA_ALIGNMENT	DECL_LOCAL_FUNCTION_P 69
data_section	DECL_MAIN_P 68
DATA_SECTION_ASM_OP	DECL_NAME
DBR_OUTPUT_SEQEND	DECL_NAMESPACE_ALIAS63
dbr_sequence_length	DECL_NAMESPACE_SCOPE_P 66
DBX_BLOCKS_FUNCTION_RELATIVE	DECL_NAMESPACE_STD_P63
DBX_CONTIN_CHAR	DECL_NON_THUNK_FUNCTION_P 70
DBX_CONTIN_LENGTH	DECL_NONCONVERTING_P69
DBX_DEBUGGING_INFO	DECL_NONSTATIC_MEMBER_FUNCTION_P 69
DBX_FUNCTION_FIRST	DECL_OVERLOADED_OPERATOR_P
DBX_LINES_FUNCTION_RELATIVE	DECL_RESULT 71
DBX_NO_XREFS	DECL_SIZE 65
DBX_OUTPUT_LBRAC	DECL_STATIC_FUNCTION_P 69
DBX_OUTPUT_MAIN_SOURCE_FILE_END	DECL_STMT 71
DBX_OUTPUT_MAIN_SOURCE_FILENAME	DECL_STMT_DECL 71
DBX_OUTPUT_NFUN	DECL_THUNK_P 70
DBX_OUTPUT_NULL_N_SO_AT_MAIN_SOURCE_FILE_	DECL_VOLATILE_MEMFUNC_P 69
END	declaration
DBX_OUTPUT_RBRAC	declarations, RTL
DBX_OUTPUT_SOURCE_LINE	DECLARE_LIBRARY_RENAMES 314
DBX_REGISTER_NUMBER	decrement_and_branch_until_zero instruction
DBX_REGPARM_STABS_CODE	pattern
DBX_REGPARM_STABS_LETTER 361	default
DBX_STATIC_CONST_VAR_CODE	default_file_start
DBX_STATIC_STAB_DATA_SECTION	DEFAULT_GDB_EXTENSIONS
DBX_TYPE_DECL_STABS_CODE	DEFAULT_PCC_STRUCT_RETURN
DBX_USE_BINCL	DEFAULT_SIGNED_CHAR
DCmo de	define_asm_attributes 233
De Morgan's law	define_attr
dead_or_set_p	define_automaton
DEBUG_SYMS_TEXT	define_bypass
DEBUGGER_ARG_OFFSET	define_code_attr
DEBUGGER_AUTO_OFFSET	define_code_macro
DECL ALIGN	define_cond_exec
DECL_ANTICIPATED	define_constants
DECL_ARGUMENTS	define_cpu_unit
DECL_ARRAY_DELETE_OPERATOR_P	define_delay 235
DECL_ARTIFICIAL	define_expand
DECL_ASSEMBLER_NAME	define_insn 165
DECL_ATTRIBUTES	define_insn example 166
DECL_BASE_CONSTRUCTOR_P 69	define_insn_and_split 223
DECL_CLASS_SCOPE_P	define_insn_reservation
DECL_COMPLETE_CONSTRUCTOR_P 69	define_mode_attr
DECL_COMPLETE_DESTRUCTOR_P 70	define_mode_macro
DECL_CONST_MEMFUNC_P69	define_peephole
DECL_CONSTRUCTOR_P 68, 69	define_peephole2
DECL_CONTEXT	define_predicate 176
DECL_CONV_FN_P	define_query_cpu_unit 237
DECL_COPY_CONSTRUCTOR_P 69	define_reservation
DECL_DESTRUCTOR_P	define_special_predicate 176
DECL_EXTERN_C_FUNCTION_P 69	define_split
DECL_EXTERNAL	defining attributes and their values 228
DECL_FUNCTION_MEMBER_P 68, 69	defining jump instruction patterns 213
DECL_FUNCTION_SCOPE_P	defining looping instruction patterns 215

defining peephole optimizers 224	EDGE_ABNORMAL, EDGE_ABNORMAL_CALL	
defining predicates	EDGE_ABNORMAL, EDGE_EH	
defining RTL sequences for code generation 217	EDGE_ABNORMAL, EDGE_SIBCALL	158
delay slots, defining	EDGE_FALLTHRU, force_nonfallthru	157
DELAY_SLOTS_FOR_EPILOGUE	EDOM, implicit usage	315
deletable 400	EH_FRAME_IN_DATA_SECTION	355
DELETE_IF_ORDINARY	EH_FRAME_SECTION_NAME	355
Dependent Patterns	eh_return instruction pattern	210
desc	EH_RETURN_DATA_REGNO	
destructor	EH_RETURN_HANDLER_RTX	
destructors, output of	EH_RETURN_STACKADJ_RTX	
deterministic finite state automaton 236, 240	EH_TABLES_CAN_BE_READ_ONLY	
DFmode	EH_USES	
digits in constraint	ei_edge	
DImode	ei_end_p	
DIR_SEPARATOR	ei_last	
DIR_SEPARATOR_2	ei_next	
directory options .md		
disabling certain registers	ei_one_before_end_p	
	ei_prev	
dispatch table	ei_safe_safe	
div	ei_start	
	ELIGIBLE_FOR_EPILOGUE_DELAY	
division	ELIMINABLE_REGS	
divm3 instruction pattern	ELSE_CLAUSE	
divmodm4 instruction pattern	EMIT_MODE_SET	
DO_BODY	Empty Statements	
DO_COND71	EMPTY_CLASS_EXPR	
DO_STMT71	EMPTY_FIELD_BOUNDARY	
DOLLARS_IN_IDENTIFIERS	ENABLE_EXECUTE_STACK	
doloop_begin instruction pattern	ENDFILE_SPEC	
doloop_end instruction pattern 207	endianness	. 5
DONE	ENTRY_BLOCK_PTR, EXIT_BLOCK_PTR	155
DOUBLE_TYPE_SIZE	enum machine_mode	118
driver	enum reg_class	278
DRIVER_SELF_SPECS	ENUMERAL_TYPE	57
DUMPFILE_FORMAT387	epilogue	304
DWARF_ALT_FRAME_RETURN_COLUMN 287	epilogue instruction pattern	
DWARF_CIE_DATA_ALIGNMENT	EPILOGUE_USES	
DWARF_FRAME_REGISTERS 293	eq	
DWARF_FRAME_REGNUM	eq and attributes	
DWARF_REG_TO_UNWIND_COLUMN	eq_attr	
DWARF_ZERO_REG 288	EQ_EXPR	
DWARF2_ASM_LINE_DEBUG_INFO	equal	
DWARF2_DEBUGGING_INFO	errno, implicit usage	
DWARF2_FRAME_INFO	escape sequences	
DWARF2_FRAME_REG_OUT	EXACT_DIV_EXPR	
DWARF2_UNWIND_INFO	examining SSA_NAMEs	
DYNAMIC_CHAIN_ADDRESS	exception handling	
DINAMITO_OMATN_ADDREDS		
	exception_receiver instruction pattern	
${f E}$	exclamation point	
	exclusion_set	
'E' in constraint	exclusive-or, bitwise	
earlyclobber operand	EXIT_EXPR	
edge	EXIT_IGNORE_STACK	
edge in the flow graph	expander definitions	
edge iterators	expm2 instruction pattern	
edge splitting 162	expr_list	
EDGE_ABNORMAL	EXPR_STMT	

EXPR_STMT_EXPR 71	FLOAT_LIB_COMPARE_RETURNS_BOOL
expression	FLOAT_STORE_FLAG_VALUE 376
expression codes	float_truncate
extendmn 2 instruction pattern 203	FLOAT_TYPE_SIZE
extensible constraints	FLOAT_WORDS_BIG_ENDIAN 260
EXTRA_ADDRESS_CONSTRAINT 285	FLOAT_WORDS_BIG_ENDIAN, (lack of) effect on
EXTRA_CONSTRAINT 284	subreg 126
EXTRA_CONSTRAINT_STR	floating point and cross compilation 365
EXTRA_MEMORY_CONSTRAINT 285	Floating Point Emulation 389
EXTRA_SECTION_FUNCTIONS 332	floating point emulation library, US Software
EXTRA_SECTIONS 331	GOFAST
EXTRA_SPECS	floatmn2 instruction pattern 202
extv instruction pattern 203	floatunsmn2 instruction pattern
extzv instruction pattern 203	FLOOR_DIV_EXPR 76
	FLOOR_MOD_EXPR 76
T	floorm2 instruction pattern
\mathbf{F}	flow-insensitive alias analysis
'F' in constraint	flow-sensitive alias analysis
FAIL	FOR_BODY71
fall-thru 157	FOR_COND71
FATAL_EXIT_CODE	FOR_EXPR
FDL, GNU Free Documentation License 413	FOR_INIT_STMT 71
features, optional, in system conventions 256	FOR_STMT71
ffs	FORCE_CODE_SECTION_ALIGN 331
ffsm2 instruction pattern 200	FORCE_PREFERRED_STACK_BOUNDARY_IN_MAIN 262
FIELD_DECL 65	force_reg 195
file_end_indicate_exec_stack	frame layout
files and passes of the compiler	FRAME_GROWS_DOWNWARD
files, generated	FRAME_GROWS_DOWNWARD and virtual registers 125
final_absence_set	frame_pointer_needed
FINAL_PRESCAN_INSN	FRAME_POINTER_REGNUM
final_presence_set	FRAME_POINTER_REGNUM and virtual registers 125
final_scan_insn	FRAME_POINTER_REQUIRED
final_sequence	frame_pointer_rtx
FINALIZE_PIC	frame_related 116
FIND_BASE_TERM 317	frame_related, in insn, call_insn, jump_insn,
find_sub_basic_blocks, split_block 162	barrier, and set
FINI_SECTION_ASM_OP	frame_related, in mem
finite state automaton minimization 240	frame_related, in reg
FIRST_PARM_OFFSET	frame_related, in symbol_ref 115
FIRST_PARM_OFFSET and virtual registers 125	frequency, count, BB_FREQ_BASE 159
FIRST_PSEUDO_REGISTER 272	ftruncm2 instruction pattern
FIRST_STACK_REG 277	function
FIRST_VIRTUAL_REGISTER 124	function body
fix	function call conventions
FIX_TRUNC_EXPR 76	function entry and exit
fix_truncmn2 instruction pattern 203	function entry point, alternate function entry point
fixed register	159
FIXED_REGISTERS	function-call insns
fixed_regs	FUNCTION_ARG 297
fixmn2 instruction pattern 202	FUNCTION_ARG_ADVANCE
FIXUNS_TRUNC_LIKE_FIX_TRUNC 373	FUNCTION_ARG_BOUNDARY 301
fixuns_truncmn2 instruction pattern 203	FUNCTION_ARG_PADDING
fixunsmn 2 instruction pattern	FUNCTION_ARG_REGNO_P
flags in RTL expression	FUNCTION_BOUNDARY
float	FUNCTION_DECL
FLOAT_EXPR 76	FUNCTION_INCOMING_ARG 298
float_extend	FUNCTION_MODE

FUNCTION_OUTGOING_VALUE 302	gimplify_expr 46
FUNCTION_PROFILER	gimplify_function_tree 46
FUNCTION_TYPE 57	GLOBAL_INIT_PRIORITY
FUNCTION_VALUE 302	<pre>global_live_at_start, global_live_at_end</pre>
FUNCTION_VALUE_REGNO_P 303	$\dots \dots $
functions, leaf	global_regs 273
fundamental type	GO_IF_LEGITIMATE_ADDRESS 316
	GO_IF_MODE_DEPENDENT_ADDRESS
	GOFAST, floating point emulation library 314
G	<pre>gofast_maybe_init_libfuncs</pre>
'g' in constraint	greater than
'G' in constraint	gt
GCC and portability 5	gt and attributes
GCC_DRIVER_HOST_INITIALIZATION	GT_EXPR
gcov_type	gtu
ge	gtu and attributes
ge and attributes	GTY
GE_EXPR	
GEN_ERRNO_RTX	
gencodes51	H
	'H' in constraint
general_operand	HANDLE_PRAGMA_PACK_PUSH_POP
GENERAL_REGS	HANDLE_PRAGMA_PACK_WITH_EXPANSION 378
generated files	HANDLE_SYSV_PRAGMA
generating assembler output	HANDLER71
generating insns	HANDLER BODY 71
GENERIC 45, 46, 87	-
generic predicates	HANDLER_PARMS
genflags51	hard registers
get_attr 230	HARD_FRAME_POINTER_REGNUM
get_attr_length	HARD_REGNO_CALL_PART_CLOBBERED
GET_CLASS_NARROWEST_MODE 121	HARD_REGNO_CALLER_SAVE_MODE
GET_CODE 107	HARD_REGNO_MODE_OK
get_frame_size	HARD_REGNO_NREGS
get_insns 142	HARD_REGNO_RENAME_OK
get_last_insn 142	HAS_INIT_SECTION
GET_MODE 121	HAS_LONG_COND_BRANCH
GET_MODE_ALIGNMENT	HAS_LONG_UNCOND_BRANCH 372
GET_MODE_BITSIZE	HAVE_DOS_BASED_FILE_SYSTEM 386
GET_MODE_CLASS 121	HAVE_POST_DECREMENT
GET_MODE_MASK 121	HAVE_POST_INCREMENT
GET_MODE_NAME	HAVE_POST_MODIFY_DISP 315
GET_MODE_NUNITS	HAVE_POST_MODIFY_REG
GET_MODE_SIZE 121	HAVE_PRE_DECREMENT
GET_MODE_UNIT_SIZE	HAVE_PRE_INCREMENT
GET_MODE_WIDER_MODE	HAVE_PRE_MODIFY_DISP
GET_RTX_CLASS 108	HAVE_PRE_MODIFY_REG316
GET_RTX_FORMAT 110	HCmode
GET_RTX_LENGTH	HFmode
get_stmt_operands	high
geu	HImode 119
geu and attributes	HImode, in insn
GGC	host configuration
GIMPLE	host functions
GIMPLE Example	host hooks
GIMPLE Exception Handling	host makefile fragment
GIMPLE Expressions	HOST_BIT_BUCKET
gimplification	HOST_EXECUTABLE_SUFFIX
gimplifier	HOST_HOOKS_EXTRA_SIGNALS
gimpiniei 45	000 6ARNDIG_RAITAB_CAUUU_1001

HOST_HOOKS_GT_PCH_ALLOC_GRANULARITY 385	INIT_CUMULATIVE_LIBCALL_ARGS 299
HOST_HOOKS_GT_PCH_USE_ADDRESS	INIT_ENVIRONMENT
HOST_LACKS_INODE_NUMBERS 387	INIT_EXPANDERS 259
HOST_LONG_FORMAT 388	INIT_EXPR 76
HOST_OBJECT_SUFFIX	init_machine_status
HOT_TEXT_SECTION_NAME 330	init_one_libfunc
	INIT_SECTION_ASM_OP 331, 349
т	INITIAL_ELIMINATION_OFFSET 295
I	INITIAL_FRAME_POINTER_OFFSET
'i' in constraint	initialization routines
'I' in constraint	INITIALIZE_TRAMPOLINE 312
IBM_FLOAT_FORMAT	inlining
identifier	insert_insn_on_edge
IDENTIFIER_LENGTH	insn
IDENTIFIER_NODE	insn and '/f' 114
IDENTIFIER_OPNAME_P	insn and '/i'
IDENTIFIER_POINTER	insn and '/j' 115
IDENTIFIER_TYPENAME_P 57	insn and '/s' 113, 115
IEEE_FLOAT_FORMAT	insn and '/u' 113
IF_COND71	insn and '/v' 113
if_marked 400	insn attributes
IF_STMT71	insn canonicalization
if_then_else 132	insn includes
if_then_else and attributes 229	insn lengths, computing 234
if_then_else usage 136	insn splitting
IFCVT_EXTRA_FIELDS	insn-attr.h
IFCVT_INIT_EXTRA_FIELDS 380	INSN_ANNULLED_BRANCH_P 113
IFCVT_MODIFY_CANCEL	INSN_CODE 146
IFCVT_MODIFY_FINAL 380	INSN_DELETED_P 113
IFCVT_MODIFY_INSN	INSN_FROM_TARGET_P 113
IFCVT_MODIFY_MULTIPLE_TESTS 380	insn_list 151
IFCVT_MODIFY_TESTS	insn_list and '/i' 115
IMAGPART_EXPR 76	INSN_REFERENCES_ARE_DELAYED 379
$\verb immediate_operand$	INSN_SETS_ARE_DELAYED 379
IMMEDIATE_PREFIX	INSN_UID 142
in_data	insns
in_struct 117	insns, generating
in_struct, in code_label and note 113	insns, recognizing
in_struct, in insn and jump_insn and call_insn	instruction attributes
	instruction latency time 236, 238, 239
in_struct, in insn, jump_insn and call_insn	instruction patterns
	instruction splitting
in_struct, in label_ref 113	insv instruction pattern
in_struct, in mem	INT_TYPE_SIZE
in_struct, in subreg	INTEGER_CST
in_text	INTEGER_TYPE
include	integrated
INCLUDE_DEFAULTS	integrated, in insn, call_insn, jump_insn,
inclusive-or, bitwise	barrier, code_label, insn_list, const, and note
INCOMING_FRAME_SP_OFFSET	
INCOMING_REGNO 273 INCOMING_RETURN_ADDR_RTX 287	integrated in reg
	integrated, in symbol_ref
INDEX_REG_CLASS	interfacing to GCC output
indirect_jump instruction pattern	interlock delays
INDIRECT_REF	intermediate representation lowering
INIT_CUMULATIVE_ARGS	INTMAX_TYPE
INIT_CUMULATIVE_INCOMING_ARGS	introduction
	111110 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4

INVOKEmain	350	LE_EXPR	. 76
ior	130	leaf functions	276
ior and attributes	230	leaf_function_p	206
ior, canonicalization of	217	LEAF_REG_REMAP	277
iorm3 instruction pattern	198	LEAF_REGISTERS	
IS_ASM_LOGICAL_LINE_SEPARATOR	338	left rotate	130
		left shift	130
т		LEGITIMATE_CONSTANT_P	319
J		LEGITIMATE_PIC_OPERAND_P	
jump	117	LEGITIMIZE_ADDRESS	
jump instruction pattern		LEGITIMIZE_RELOAD_ADDRESS	
jump instruction patterns		length	
jump instructions and set		less than	
jump, in call_insn		less than or equal	
jump, in insn		leu	
jump, in mem		leu and attributes	
JUMP_ALIGN		LIB_SPEC	
jump_insn		LIB2FUNCS_EXTRA	
jump_insn and '/f'		LIBCALL_VALUE	
jump_insn and '/i'jump_insn and '/i'		'libgcc.a'	
jump_insn and '/s'		LIBGCC_SPEC	
jump_insn and '/u'jump_insn and '/u'		LIBGCC2_CFLAGS	
jump_insn and '/v'		LIBGCC2_WORDS_BIG_ENDIAN	
JUMP_LABEL		library subroutine names	
JUMP_TABLES_IN_TEXT_SECTION		LIBRARY_PATH_ENV	
Jumps		LIMIT_RELOAD_CLASS	
		LINK_COMMAND_SPEC	
${f L}$		LINK_EH_SPEC	
		LINK_ELIMINATE_DUPLICATE_LDIRECTORIES	
LABEL_ALIGN		LINK_GCC_C_SEQUENCE_SPEC	
LABEL_ALIGN_AFTER_BARRIER		LINK_LIBGCC_SPECIAL	
LABEL_ALIGN_AFTER_BARRIER_MAX_SKIP	551	LINK_LIBGCC_SPECIAL_1	
LABEL_ALIGN_MAX_SKIP	300	LINK_SPEC	
LABEL_ALT_ENTRY_P		linkage	
LABEL_ALTERNATE_NAME		list	
LABEL_DECL		Liveness representation	
LABEL_KIND		lo_sum	
LABEL_NUSES		load address instruction	
LABEL_OUTSIDE_LOOP_P		LOAD_EXTEND_OP	
LABEL_PRESERVE_P	113	<pre>load_multiple instruction pattern</pre>	
label_ref	123	LOCAL_ALIGNMENT	
label_ref and '/s'		LOCAL_CLASS_P	
label_ref and '/v'		LOCAL_INCLUDE_DIR	
label_ref, RTL sharing		LOCAL_LABEL_PREFIX	
LABEL_REF_NONLOCAL_P	114	LOCAL_REGNO	274
lang_hooks.gimplify_expr	. 46	LOG_LINKS	
lang_hooks.parse_file	. 45	Logical Operators	. 90
language-independent intermediate representati	ion	logical-and, bitwise	
	. 45	logm2 instruction pattern	199
large return values	303	LONG_DOUBLE_TYPE_SIZE	269
LARGEST_EXPONENT_IS_NORMAL		LONG_LONG_TYPE_SIZE	269
LAST_STACK_REG		LONG_TYPE_SIZE	
LAST_VIRTUAL_REGISTER		longjmp and automatic variables	
LD_FINI_SWITCH		LOOP_ALIGN	
LD_INIT_SWITCH		LOOP_ALIGN_MAX_SKIP	
LDD_SUFFIX		LOOP_EXPR	
le		looping instruction patterns	
le and attributes		Loops	91

lowering, language-dependent intermediate	MD_EXEC_PREFIX	
representation	MD_FALLBACK_FRAME_STATE_FOR	290
LSHIFT_EXPR 76	MD_HANDLE_UNWABI	290
lshiftrt 130	MD_STARTFILE_PREFIX	253
1shiftrt and attributes	MD_STARTFILE_PREFIX_1	253
1shrm3 instruction pattern	MD_UNWIND_SUPPORT	
lt	mem	127
1t and attributes	mem and '/c'	
LT_EXPR	mem and '/f'	
LTGT_EXPR 76	mem and '/j'	114
ltu	mem and '/s'	114
	mem and '/u'	
\mathbf{M}	$\mathtt{mem} \ \mathrm{and} \ \texttt{`/v'} . \ldots .$	
	mem, RTL sharing	
'm' in constraint 177	MEM_ALIAS_SET	
machine attributes	MEM_ALIGN	
machine description macros 247	MEM_EXPR	
machine descriptions	MEM_IN_STRUCT_P	
machine mode conversions	MEM_KEEP_ALIAS_SET_P	
machine modes	MEM_NOTRAP_P	
machine specific constraints	MEM_OFFSET	
machine-independent predicates	MEM_READONLY_P	
machine_mode	MEM_SCALAR_P	
macros in '.md' files	MEM_SIZE	
macros, target description	MEM_VOLATILE_P	
MAKE_DECL_ONE_ONLY	MEMBER_TYPE_FORCES_BLK	
make_safe_from	memory reference, nonoffsettable	
makefile fragment	memory references in constraints	
makefile targets	MEMORY_MOVE_COST	
marking roots	memory_operand	
MASK_RETURN_ADDR	METHOD_TYPE	
match_dup 168, 227 match_dup and attributes 234	MIN_UNITS_PER_WORD	
match_op_dup	minm3 instruction pattern	
match_operand	minus	
match_operand and attributes	minus and attributes	
match_operator	minus, canonicalization of	
match_par_dup	MINUS_EXPR	
match_parallel	MIPS coprocessor-definition macros	
match_scratch	mod	
matching constraint	mod and attributes	
matching operands	mode classes	
math library	mode macros in '.md' files	
math, in RTL	mode switching	
MATH_LIBRARY 379	MODE_AFTER	367
matherr	MODE_BASE_REG_CLASS	
MAX_BITS_PER_WORD	MODE_BASE_REG_REG_CLASS	
MAX_CONDITIONAL_EXECUTE 380	MODE_CC	121
MAX_DFA_ISSUE_RATE	MODE_COMPLEX_FLOAT	120
MAX_FIXED_MODE_SIZE	MODE_COMPLEX_INT	120
MAX_MOVE_MAX 373	MODE_ENTRY	367
MAX_OFILE_ALIGNMENT	MODE_EXIT	367
MAX_REGS_PER_ADDRESS	MODE_FLOAT	120
maxm3 instruction pattern		120
may_trap_p, tree_could_trap_p 158	MODE_HAS_INFINITIES	
$\verb maybe_undef \dots \dots$	MODE_HAS_NANS	
mcount	MODE_HAS_SIGN_DEPENDENT_ROUNDING	
MD_CAN_REDIRECT_BRANCH	MODE_HAS_SIGNED_ZEROS	266

MODE_INT 120	neg, canonicalization of	216
MODE_NEEDED 367	NEGATE_EXPR	76
MODE_PARTIAL_INT	negm2 instruction pattern	199
MODE_PRIORITY_TO_MODE	nested functions, trampolines for	312
MODE_RANDOM 121	nested_ptr	400
MODES_TIEABLE_P 276	next_bb, prev_bb, FOR_EACH_BB	155
modifiers in constraints	next_cc0_user	214
MODIFY_EXPR 76	NEXT_INSN	142
MODIFY_JNI_METHOD_CALL	NEXT_OBJC_RUNTIME	315
modify_stmt 96	nil	108
MODIFY_TARGET_NAME	NO_DBX_BNSYM_ENSYM	362
modm3 instruction pattern 198	NO_DBX_FUNCTION_END	
modulo scheduling	NO_DBX_GCC_MARKER	
MOVE_BY_PIECES_P 324	NO_DBX_MAIN_SOURCE_DIRECTORY	
MOVE_MAX 373	NO_DOLLAR_IN_LABEL	
MOVE_MAX_PIECES324	NO_DOT_IN_LABEL	
MOVE_RATIO 324	NO_FUNCTION_CSE	
movm instruction pattern	NO_IMPLICIT_EXTERN_C	
movmemm instruction pattern	no_new_pseudos	
movmisalignm instruction pattern	NO_PROFILE_COUNTERS	
movmodecc instruction pattern	NO_REGS	
movstr instruction pattern 201	NON_LVALUE_EXPR	
movstrictm instruction pattern	nondeterministic finite state automaton	
mulhisi3 instruction pattern	nonimmediate_operand	
mulm3 instruction pattern		
mulqihi3 instruction pattern	nonlocal goto handler	
mulsidi3 instruction pattern	nonlocal_goto instruction pattern	209
mult	nonlocal_goto_receiver instruction pattern	200
mult and attributes		
mult, canonicalization of	nonmemory_operand	
MULT_EXPR	nonoffsettable memory reference	
	nop instruction pattern	
MULTILIB_DEFAULTS	NOP_EXPR	
MULTILIB_DIRNAMES	normal predicates	
MULTILIB_EXCEPTIONS	not	
MULTILIB_EXTRA_OPTS	not and attributes	
MULTILIB_MATCHES	not equal	
MULTILIB_OPTIONS	not, canonicalization of	
multiple alternative constraints	note	
MULTIPLE_SYMBOL_SPACES	note and '/i' 113,	
multiplication	note and '/v'	113
MUST_USE_SJLJ_EXCEPTIONS	NOTE_INSN_BASIC_BLOCK, CODE_LABEL, notes	
N	NOTE_INSN_BLOCK_BEG	
- ·	NOTE_INSN_BLOCK_END	
'n' in constraint	NOTE_INSN_DELETED	
N_REG_CLASSES 278	NOTE_INSN_DELETED_LABEL	
$name \dots 56$	NOTE_INSN_EH_REGION_BEG	
named patterns and conditions 166	NOTE_INSN_EH_REGION_END	145
names, pattern	NOTE_INSN_FUNCTION_BEG	145
namespace	NOTE_INSN_FUNCTION_END	145
namespace, class, scope	NOTE_INSN_LOOP_BEG	145
NAMESPACE_DECL	NOTE_INSN_LOOP_CONT	145
ne	NOTE_INSN_LOOP_END	145
ne and attributes	NOTE_INSN_LOOP_VTOP	145
NE_EXPR	NOTE_INSN_SETJMP	
nearbyintm2 instruction pattern	NOTE_LINE_NUMBER	
neg	NOTE_SOURCE_FILE	
neg and attributes	NOTICE_UPDATE_CC	

NUM_MACHINE_MODES	PARM_BOUNDARY	
NUM_MODES_FOR_MODE_SWITCHING 367	PARM_DECL	
NUM_USES	PARSE_LDD_OUTPUT	
	passes and files of the compiler	
0	passing arguments	
	PATH_SEPARATOR	
'o' in constraint	PATTERN	
OB JC_GEN_METHOD_LABEL	pattern conditions	
OBJECT_FORMAT_COFF	pattern names	
OFFSET_TYPE	Pattern Ordering patterns	
offsettable address	pc	
OImode 119 one_cmplm2 instruction pattern 201	pc and attributes	
operand access	pc, RTL sharing	
operand constraints	PC_REGNUM	
Operand Iterators	pc_rtx	
operand predicates	PCC_BITFIELD_TYPE_MATTERS	
operand substitution	PCC_STATIC_STRUCT_RETURN	
operands96	PDImode	
operands	peephole optimization, RTL representation	
operator predicates	peephole optimizer definitions	
Optimization infrastructure for GIMPLE 87	per-function data	
OPTIMIZATION_OPTIONS	percent sign	
OPTIMIZE_MODE_SWITCHING 367	PHI_ARG_DEF	
OPTION_DEFAULT_SPECS	PHI_ARG_EDGE	101
optional hardware or system features 256	PHI_ARG_ELT	101
options, directory search	PHI_NUM_ARGS	101
order of register allocation	PHI_RESULT	101
ORDER_REGS_FOR_LOCAL_ALLOC	PIC	334
ORDERED_EXPR 76	PIC_OFFSET_TABLE_REG_CALL_CLOBBERED	334
Ordering of Patterns	PIC_OFFSET_TABLE_REGNUM	
ORIGINAL_REGNO 112	pipeline hazard recognizer	
other register constraints	plus	
OUTGOING_REG_PARM_STACK_SPACE 296	plus and attributes	
OUTGOING_REGNO	plus, canonicalization of	
output of assembler code	PLUS_EXPR	
output statements	Pmode	
output templates	pmode_register_operand	
OUTPUT_ADDR_CONST_EXTRA	pointer	
output_asm_insn	POINTER_SIZE	
OUTPUT_QUOTED_STRING 336 OVERLOAD 67	POINTER_TYPE	
OVERRIDE_OPTIONS		
OVL_CURRENT 67	pop_operand	
OVL_NEXT	popcountm2 instruction pattern	
OVE_NEATT	portability	
_	position independent code	
P	post_dec	
'p' in constraint	post_inc	
PAD_VARARGS_DOWN	post_modify	
parallel	POSTDECREMENT_EXPR	
param_is	POSTINCREMENT_EXPR	
parameters, c++ abi	POWI_MAX_MULTS	
parameters, miscellaneous	powm3 instruction pattern	
parameters, precompiled headers	pragma 377,	
paramn_is	pre_dec	
parity	PRE_GCC3_DWARF_FRAME_REGISTERS	
paritym2 instruction pattern 201		141

pre_modify 141	Q
PREDECREMENT_EXPR 76	QCmo de
predefined macros	QFmode
PREDICATE_CODES	QImode
predicates	QImode, in insn
predicates and machine modes	qualified type
predication	querying function unit reservations
predict.def	question mark
PREFERRED_DEBUGGING_TYPE	quotient
PREFERRED_OUTPUT_RELOAD_CLASS	quotient 129
PREFERRED_RELOAD_CLASS	
PREFERRED_STACK_BOUNDARY	\mathbf{R}
prefetch	
prefetch instruction pattern	'r' in constraint
=	RANGE_TEST_NON_SHORT_CIRCUIT 325
PREINCREMENT_EXPR	RDIV_EXPR
presence_set	READONLY_DATA_SECTION
preserving SSA form	READONLY_DATA_SECTION_ASM_OP
prev_active_insn	real operands
prev_cc0_setter	REAL_ARITHMETIC
PREV_INSN	REAL_CST
PRINT_OPERAND	REAL_LIBGCC_SPEC
PRINT_OPERAND_ADDRESS	REAL_NM_FILE_NAME
PRINT_OPERAND_PUNCT_VALID_P	REAL_TYPE
processor functional units 236, 237	REAL_VALUE_ABS
processor pipeline description	REAL_VALUE_ATOF
product	REAL_VALUE_FIX
profile feedback	REAL_VALUE_FROM_INT
profile representation	REAL_VALUE_ISINF
PROFILE_BEFORE_PROLOGUE 309	REAL_VALUE_ISNAN
PROFILE_HOOK 309	REAL_VALUE_NEGATE
profiling, code generation 308	REAL_VALUE_NEGATIVE
program counter	REAL_VALUE_TO_INT
prologue	REAL_VALUE_TO_TARGET_DOUBLE
prologue instruction pattern 210	REAL_VALUE_TO_TARGET_LONG_DOUBLE
PROMOTE_FUNCTION_MODE 261	REAL_VALUE_TO_TARGET_SINGLE
PROMOTE_MODE 261	REAL_VALUE_TRUNCATE
pseudo registers	REAL_VALUE_TYPE
PSImode	REAL_VALUE_UNSIGNED_FIX
PTRDIFF_TYPE 270	REAL_VALUES_EQUAL
PTRMEM_CST 76	REAL_VALUES_LESS
PTRMEM_CST_CLASS	REALPART_EXPR
PTRMEM_CST_MEMBER	recog_data.operand
purge_dead_edges 157, 162	recognizing insns
push address instruction	RECORD_TYPE
PUSH_ARGS 295	redirect_edge_and_branch 160
PUSH_ARGS_REVERSED	redirect_edge_and_branch, redirect_jump
push_operand	
push_reload	reference
PUSH_ROUNDING	REFERENCE_TYPE 57
PUSH_ROUNDING, interaction with	reg
PREFERRED_STACK_BOUNDARY	reg and '/f'
pushm instruction pattern	reg and '/i'
PUT_CODE	reg and '/v'
PUT_MODE	reg, RTL sharing
PUT_REG_NOTE_KIND	REG_ALLOC_ORDER
PUT_SDB	REG_BR_PRED
101_01_0100 304	REG_BR_PROB
	REG_BR_PROB_BASE, BB_FREQ_BASE, count 160

REG_BR_PROB_BASE, EDGE_FREQUENCY		REGNO_REG_CLASS	
REG_CC_SETTER		regs_ever_live	
REG_CC_USER		$regular\ expressions \dots \dots 236,$	
reg_class_contents		relative costs	
REG_CLASS_CONTENTS		RELATIVE_PREFIX_NOT_LINKDIR	
REG_CLASS_FROM_CONSTRAINT		reload pass	
REG_CLASS_FROM_LETTER		reload_completed	
REG_CLASS_NAMES		${\tt reload_in} \ instruction \ pattern \$	
REG_CROSSING_JUMP		reload_in_progress	
REG_DEAD		reload_out instruction pattern	
REG_DEAD, REG_UNUSED		reloading	
REG_DEP_ANTI		remainder	
REG_DEP_OUTPUT		reorder	
REG_EH_REGION, EDGE_ABNORMAL_CALL		representation of RTL	
REG_EQUAL		reservation delays	
REG_EQUIV		rest_of_decl_compilation	
REG_EXPR		rest_of_type_compilation	
REG_FRAME_RELATED_EXPR		restore_stack_block instruction pattern	208
REG_FUNCTION_VALUE_P		restore_stack_function instruction pattern	000
REG_INC			208
REG_LABEL		restore_stack_nonlocal instruction pattern	000
reg_label and '/v'			
REG_LIBCALL		RESULT_DECL	
REG_MODE_OK_FOR_BASE_P		return	
REG_MODE_OK_FOR_REG_BASE_P		return instruction pattern	
reg_names		return values in registers	
REG_NO_CONFLICT		RETURN_ADDR_IN_PREVIOUS_FRAME	
REG_NONNEG		RETURN_ADDR_OFFSET	
REG_NOTE_KIND	14/	RETURN_ADDR_RTX	
DEG NOTEG	1.4.0	DETUDN ADDRESS DOTHTED DESNITA	200
REG_NOTES		RETURN_ADDRESS_POINTER_REGNUM	
REG_OFFSET	112	RETURN_EXPR	71
REG_OFFSETREG_OK_FOR_BASE_P	$\frac{112}{317}$	RETURN_EXPR	$71 \\ 71$
REG_OFFSET	112 317 317	RETURN_EXPR	$71 \\ 71 \\ 296$
REG_OFFSET REG_OK_FOR_BASE_P	112 317 317 316	RETURN_EXPR	71 71 296 71
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE	112 317 317 316 296	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values.	71 71 296 71 303
REG_OFFSET	112 317 317 316 296 298	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions	71 71 296 71 303 7
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER	112 317 317 316 296 298 114	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability	71 71 296 71 303 7
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_PO INTER REG_RETVAL	112 317 317 316 296 298 114 150	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P	71 71 296 71 303 $$ 7 160 322
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_PO INTER REG_RETVAL REG_UNUSED	112 317 317 316 296 298 114 150 147	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION	71 71 296 71 303 $$ 7 160 322 321
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_PO INTER REG_RETVAL REG_UNUSED REG_USERVAR_P	112 317 317 316 296 298 114 150 147	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE	71 71 296 71 303 $$ 7 160 322 321 321
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order	112 317 317 316 296 298 114 150 147 114 274	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERSIBLE_CC_MODE right rotate	71 71 296 71 303 $$ 7 160 322 321 321 130
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions	112 317 317 316 296 298 114 150 147 114 274 277	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values. returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift	71 71 296 71 303 7 160 322 321 321 130
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register class preference constraints	112 317 317 316 296 298 114 150 147 114 274 277 182	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERSIBLE_CC_MODE right rotate right shift RISC	71 71 296 71 303 322 321 321 130 239
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register pairs	112 317 317 316 296 298 114 150 147 114 274 277 182 275	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC	71 71 296 71 303 7 160 322 321 130 130 239 401
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register class preference constraints register pairs Register Transfer Language (RTL)	112 317 317 316 296 298 114 150 147 114 274 277 182 275 107	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC	71 71 296 71 303 7 160 322 321 321 130 239 401 130
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register class preference constraints register pairs Register Transfer Language (RTL) register usage	112 317 317 316 296 298 114 150 147 114 274 277 182 275 107 272	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC	71 71 296 71 303 7 160 322 321 130 239 401 130 130
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register class preference constraints register pairs Register Transfer Language (RTL) register usage REGISTER_MOVE_COST	112 317 317 316 296 298 114 150 147 114 274 277 182 275 107 272 322	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC	71 71 296 71 303 321 321 321 130 239 401 130 130
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register class preference constraints register pairs Register Transfer Language (RTL) register usage REGISTER_MOVE_COST REGISTER_NAMES	112 317 317 316 296 298 114 150 147 114 274 277 182 275 107 272 322 351	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERSIBLE_CC_MODE right rotate right shift RISC	71 71 296 71 303 321 321 321 130 239 401 130 130 139 199
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register class preference constraints register pairs Register Transfer Language (RTL) register usage REGISTER_MOVE_COST REGISTER_NAMES register_operand	112 317 317 316 296 298 114 150 147 114 274 277 182 275 107 272 322 351 174	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERSIBLE_CC_MODE right rotate right shift RISC	711 71296 711303 3223 321133 1300 2399 401130 1300 1999 93
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register class preference constraints register pairs Register Transfer Language (RTL) register usage REGISTER_MOVE_COST REGISTER_NAMES register_Operand REGISTER_PREFIX	112 317 317 316 296 298 114 150 147 114 274 277 182 275 107 272 322 351 174	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC	711 71296 711303 3223 321130 130 239 401130 130 199 93 76
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register class preference constraints register pairs Register Transfer Language (RTL) register usage REGISTER_MOVE_COST REGISTER_NAMES register_Operand REGISTER_PREFIX REGISTER_TARGET_PRAGMAS	112 317 317 316 296 298 114 150 147 114 274 277 182 275 107 272 322 351 174 353 377	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC	711 71296 713033 7160 322321130 1300 2399 401130 1300 1999 93 766 76
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register class preference constraints register pairs Register Transfer Language (RTL) register usage REGISTER_MOVE_COST REGISTER_NAMES register_Operand REGISTER_PREFIX REGISTER_TARGET_PRAGMAS registers arguments	112 317 316 296 298 114 150 147 114 274 277 182 275 107 272 322 351 174 353 377 297	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC	71 71 296 71 303 32 160 322 321 130 239 401 130 199 93 76 76 267
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register class preference constraints register pairs Register Transfer Language (RTL) register usage REGISTER_MOVE_COST REGISTER_NAMES register_Operand REGISTER_PREFIX REGISTER_TARGET_PRAGMAS registers arguments registers in constraints	112 317 316 296 298 114 150 147 114 274 277 182 275 107 272 322 351 174 353 377 297 178	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC	71 71 296 71 303 $$ 7 160 322 321 331 130 239 401 130 199 93 76 6 267 265
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register pairs Register Transfer Language (RTL) register usage REGISTER_MOVE_COST REGISTER_NAMES register_Operand REGISTER_PREFIX REGISTER_TARGET_PRAGMAS registers arguments registers in constraints REGMODE_NATURAL_SIZE	112 317 316 296 298 114 150 147 114 274 277 182 275 107 272 322 351 174 353 377 297 178	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC. 236, roots, marking rotate rotatert rotlm3 instruction pattern rotrm3 instruction pattern ROUND_DIV_EXPR ROUND_MOD_EXPR ROUND_TOWARDS_ZERO ROUND_TYPE_ALIGN roundm2 instruction pattern	711 711 296 71 303 7 160 322 321 130 239 401 130 199 93 766 267 265 200
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register pairs Register Transfer Language (RTL) register usage REGISTER_MOVE_COST REGISTER_NAMES register_operand REGISTER_PREFIX REGISTER_TARGET_PRAGMAS registers arguments registers in constraints REGMODE_NATURAL_SIZE REGNO_MODE_OK_FOR_BASE_P	112 317 316 296 298 114 150 147 114 274 277 182 275 107 272 322 351 174 353 377 297 178 275 280	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC	71 711 296 71 303 7 160 322 321 321 130 239 401 130 199 93 76 267 265 200 76
REG_OFFSET REG_OK_FOR_BASE_P REG_OK_FOR_INDEX_P REG_OK_STRICT REG_PARM_STACK_SPACE REG_PARM_STACK_SPACE, and FUNCTION_ARG REG_POINTER REG_RETVAL REG_UNUSED REG_USERVAR_P register allocation order register class definitions register pairs Register Transfer Language (RTL) register usage REGISTER_MOVE_COST REGISTER_NAMES register_Operand REGISTER_PREFIX REGISTER_TARGET_PRAGMAS registers arguments registers in constraints REGMODE_NATURAL_SIZE	112 317 316 296 298 114 150 147 114 274 277 182 275 107 272 322 351 174 353 377 297 178 275 280 280	RETURN_EXPR RETURN_INIT RETURN_POPS_ARGS RETURN_STMT returning aggregate values returning structures and unions reverse probability REVERSE_CONDEXEC_PREDICATES_P REVERSE_CONDITION REVERS IBLE_CC_MODE right rotate right shift RISC. 236, roots, marking rotate rotatert rotlm3 instruction pattern rotrm3 instruction pattern ROUND_DIV_EXPR ROUND_MOD_EXPR ROUND_TOWARDS_ZERO ROUND_TYPE_ALIGN roundm2 instruction pattern RSHIFT_EXPR	71 71 296 71 303 3 76 322 321 130 239 401 130 199 93 76 76 267 265 200 76 128

RTL classes		SECONDARY_INPUT_RELOAD_CLASS	
RTL comparison 1		SECONDARY_MEMORY_NEEDED	
RTL comparison operations		SECONDARY_MEMORY_NEEDED_MODE	282
RTL constant expression types	122	SECONDARY_MEMORY_NEEDED_RTX	282
RTL constants 1	122	SECONDARY_OUTPUT_RELOAD_CLASS	281
RTL declarations	L35	SECONDARY_RELOAD_CLASS	281
RTL difference	128	SELECT_CC_MODE	321
RTL expression	L07	Selection Statements	. 91
RTL expressions for arithmetic $\dots 1$		sequence	139
RTL format		set	136
RTL format characters 1	L09	set and '/f'	114
RTL function-call insns	l51	SET_ASM_OP	346
RTL insn template 1	L67	set_attr	232
RTL integers	L07	set_attr_alternative	232
RTL memory expressions 1	124	SET_DEST	136
RTL object types 1	L07	SET_IS_RETURN_P	115
RTL postdecrement		SET_LABEL_KIND	144
RTL postincrement 1		set_optab_libfunc	
RTL predecrement		SET_SRC	
RTL preincrement 1		SETUP_FRAME_ADDRESSES	
RTL register expressions 1		SFmode	
RTL representation		sharing of RTL components	
RTL side effect expressions		shift	
RTL strings		SHIFT_COUNT_TRUNCATED	
RTL structure sharing assumptions 1		SHORT_IMMEDIATES_SIGN_EXTEND	
RTL subtraction		SHORT_TYPE_SIZE	
RTL subtraction with signed saturation 1		sibcall_epilogue instruction pattern	
RTL subtraction with unsigned saturation 1		sibling call	
RTL sum		SIBLING_CALL_P	
RTL vectors		sign_extend	
RTX (See RTL)		sign_extract	
RTX codes, classes of		sign_extract, canonicalization of	
RTX_FRAME_RELATED_P		signed division	
run-time conventions		signed maximumsigned maximum	
run-time target specification		signed minimumsigned minimum	
run-time target specification		9	
		SImode	
\mathbf{S}		simple constraints	
		sinm 2 instruction pattern	
's' in constraint		SIZE_ASM_OP	
same_type_p		SIZE_TYPE	
SAVE_EXPR		skip	
<pre>save_stack_block instruction pattern 2</pre>		SLOW_BYTE_ACCESS	
<pre>save_stack_function instruction pattern 2</pre>		SLOW_UNALIGNED_ACCESS	
save_stack_nonlocal instruction pattern 2		SMALL_ARG_MAX	
scalars, returned as values		SMALL_REGISTER_CLASSES	
SCHED_GROUP_P 1		smax	
SCmode		smin	
scond instruction pattern 2		sms, swing, software pipelining	
$\mathtt{scratch} \ldots \ldots$		<pre>smulm3_highpart instruction pattern</pre>	
scratch operands 1		soft float library	
$\mathtt{scratch}, \; \mathrm{RTL} \; \mathrm{sharing} \ldots \ldots \; 1$		special	
${\tt scratch_operand} \dots \dots$	L74	special predicates	
${\tt SDB_ALLOW_FORWARD_REFERENCES} \; . \; . \; . \; . \; 3$			
SDB_ALLOW_UNKNOWN_REFERENCES 3			
SDB_DEBUGGING_INFO		speed of instructions	
SDB_DELIM 3		splitting instructions	
SDB_OUTPUT_SOURCE_LINE 3		sqrt	
search options	224	sqrtm2 instruction pattern	199

square root	'store_multiple' instruction pattern 197
ss_minus 128	strcpy 263
ss_plus	STRICT_ALIGNMENT 263
ss_truncate 134	strict_low_part 135
SSA	strict_memory_address_p 318
SSA_NAME_DEF_STMT	STRING_CST 76
SSA_NAME_VERSION	STRING_POOL_ADDRESS_P 115
stack arguments	strlenm instruction pattern 202
stack frame layout	structure value address
STACK_ALIGNMENT_NEEDED	STRUCTURE_SIZE_BOUNDARY 263
STACK_BOUNDARY 262	structures, returning
STACK_CHECK_BUILTIN	subm3 instruction pattern 198
STACK_CHECK_FIXED_FRAME_SIZE	SUBOBJECT 71
STACK_CHECK_MAX_FRAME_SIZE	SUBOBJECT_CLEANUP
STACK_CHECK_MAX_VAR_SIZE	subreg
STACK_CHECK_PROBE_INTERVAL	subreg and '/s'
STACK_CHECK_PROBE_LOAD	subreg and '/u'
STACK_CHECK_PROTECT	subreg and '/u' and '/v'
STACK_DYNAMIC_OFFSET	subreg, in strict_low_part
STACK_DYNAMIC_OFFSET and virtual registers 125	subreg, special reload handling 126
STACK_GROWS_DOWNWARD	SUBREG_BYTE
STACK_PARMS_IN_REG_PARM_AREA	SUBREG_PROMOTED_UNSIGNED_P
	SUBREG_PROMOTED_UNSIGNED_SET
STACK_POINTER_OFFSET	SUBREG_PROMOTED_VAR_P
STACK_POINTER_OFFSET and virtual registers 125	
STACK_POINTER_REGNUM	SUBREG_REG
STACK_POINTER_REGNUM and virtual registers 125	SUCCESS_EXIT_CODE
stack_pointer_rtx	SUPPORTS_INIT_PRIORITY
STACK_PUSH_CODE	SUPPORTS_ONE_ONLY
STACK_REGS	SUPPORTS_WEAK 344
STACK_SAVEAREA_MODE	SWITCH_BODY 71
STACK_SIZE_MODE	SWITCH_COND 71
standard pattern names	SWITCH_CURTAILS_COMPILATION
STANDARD_INCLUDE_COMPONENT 254	SWITCH_STMT 71
STANDARD_INCLUDE_DIR	SWITCH_TAKES_ARG
STANDARD_STARTFILE_PREFIX	SWITCHES_NEED_SPACES
STANDARD_STARTFILE_PREFIX_1 253	SYMBOL_FLAG_EXTERNAL112
STANDARD_STARTFILE_PREFIX_2 253	SYMBOL_FLAG_FUNCTION112
STARTFILE_SPEC	SYMBOL_FLAG_LOCAL 112
STARTING_FRAME_OFFSET 286	SYMBOL_FLAG_SMALL
STARTING_FRAME_OFFSET and virtual registers	SYMBOL_FLAG_TLS_SHIFT 113
125	symbol_ref 123
Statement Sequences	symbol_ref and '/f' 115
statements	symbol_ref and '/i' 116
Statements 90	symbol_ref and '/u' 113
Static profile estimation	symbol_ref and '/v' 116
static single assignment	symbol_ref, RTL sharing 152
STATIC_CHAIN 293	SYMBOL_REF_DECL 112
STATIC_CHAIN_INCOMING 293	SYMBOL_REF_EXTERNAL_P 112
STATIC_CHAIN_INCOMING_REGNUM	SYMBOL_REF_FLAG
STATIC_CHAIN_REGNUM	SYMBOL_REF_FLAG, in
'stdarg.h' and register arguments	TARGET_ENCODE_SECTION_INFO
STDC_O_IN_SYSTEM_HEADERS	SYMBOL_REF_FLAGS
STMT_EXPR	SYMBOL_REF_FUNCTION_P
STMT_IS_FULL_EXPR_P71	SYMBOL_REF_LOCAL_P
STMT_USE_OPS	SYMBOL_REF_SMALL_P
storage layout	SYMBOL_REF_TLS_MODEL
STORE_BY_PIECES_P	SYMBOL_REF_USED
STORE_FLAG_VALUE 374	SYMBOL_REF_WEAK 116

symbolic label	TARGET_ASM_UNALIGNED_DI_OP 337
SYSROOT_HEADERS_SUFFIX_SPEC	TARGET_ASM_UNALIGNED_HI_OP 337
SYSROOT_SUFFIX_SPEC	TARGET_ASM_UNALIGNED_SI_OP
SYSTEM_INCLUDE_DIR	TARGET_ASM_UNALIGNED_TI_OP
DIDIEM_INGEODE_DIR	TARGET_ASM_UNIQUE_SECTION
\mathbf{T}	TARGET_ATTRIBUTE_TABLE
_	TARGET_BELL
't-target'	TARGET_BINDS_LOCAL_P
table jump	TARGET_BRANCH_TARGET_REGISTER_CALLEE_SAVED
tablejump instruction pattern 207	
tag	TARGET_BRANCH_TARGET_REGISTER_CLASS 382
tagging insns	TARGET_BS 272
tail calls	TARGET_BUILD_BUILTIN_VA_LIST
target attributes	TARGET_BUILTIN_SETJMP_FRAME_VALUE 287
target description macros	TARGET_C99_FUNCTIONS
target functions	TARGET_CALLEE_COPIES
target hooks	TARGET_CANNOT_FORCE_CONST_MEM
target makefile fragment	TARGET_CANNOT_MODIFY_JUMPS_P
	TARGET_COMP_TYPE_ATTRIBUTES
target specifications	TARGET_CPU_CPP_BUILTINS
TARGET_ADDRESS_COST	TARGET_CR
TARGET_ALIGN_ANON_BITFIELDS	
TARGET_ARG_PARTIAL_BYTES	TARGET_CXX_CDTOR_RETURNS_THIS
TARGET_ASM_ALIGNED_DI_OP 337	TARGET_CXX_COOKIE_HAS_SIZE
TARGET_ASM_ALIGNED_HI_OP 337	TARGET_CXX_EXPORT_CLASS_DATA 371
TARGET_ASM_ALIGNED_SI_OP 337	TARGET_CXX_GET_COOKIE_SIZE
TARGET_ASM_ALIGNED_TI_OP 337	TARGET_CXX_GUARD_MASK_BIT
TARGET_ASM_ASSEMBLE_VISIBILITY	TARGET_CXX_GUARD_TYPE 370
TARGET_ASM_BYTE_OP	TARGET_CXX_IMPORT_EXPORT_CLASS
TARGET_ASM_CAN_OUTPUT_MI_THUNK	TARGET_CXX_KEY_METHOD_MAY_BE_INLINE 371
TARGET_ASM_CLOSE_PAREN	TARGET_DECLSPEC
TARGET_ASM_CONSTRUCTOR	TARGET_DEFAULT_PACK_STRUCT 378
TARGET_ASM_DESTRUCTOR	TARGET_DEFAULT_SHORT_ENUMS
TARGET_ASM_EH_FRAME_SECTION	TARGET_DEFERRED_OUTPUT_DEFS 347
TARGET_ASM_EMIT_UNWIND_LABEL	TARGET_DELEGITIMIZE_ADDRESS
TARGET_ASM_EXCEPTION_SECTION	TARGET_DIGITO
TARGET_ASM_EXTERNAL_LIBCALL	TARGET_DLL IMPORT_DECL_ATTRIBUTES
	TARGET_DWARF_CALLING_CONVENTION
TARGET_ASM_FILE_END	TARGET_DWARF_HANDLE_FRAME_UNSPEC
TARGET_ASM_FILE_START	TARGET_DWARF_REGISTER_SPAN
TARGET_ASM_FILE_START_APP_OFF	
TARGET_ASM_FILE_START_FILE_DIRECTIVE 335	TARGET_EDOM
TARGET_ASM_FUNCTION_BEGIN_EPILOGUE 305	TARGET_ENCODE_SECTION_INFO
TARGET_ASM_FUNCTION_END_PROLOGUE	TARGET_ENCODE_SECTION_INFO and address
TARGET_ASM_FUNCTION_EPILOGUE	validation
TARGET_ASM_FUNCTION_EPILOGUE and trampolines	TARGET_ENCODE_SECTION_INFO usage 353
	TARGET_ESC 272
TARGET_ASM_FUNCTION_PROLOGUE	TARGET_EXECUTABLE_SUFFIX 382
TARGET_ASM_FUNCTION_PROLOGUE and trampolines	TARGET_EXPAND_BUILTIN
	TARGET_EXPAND_BUILTIN_SAVEREGS
TARGET_ASM_FUNCTION_RODATA_SECTION 332	TARGET_EXPR 76
TARGET_ASM_GLOBALIZE_LABEL	TARGET_EXTRA_INCLUDES
TARGET_ASM_INTEGER	TARGET_EXTRA_PRE_INCLUDES
TARGET_ASM_INTERNAL_LABEL	TARGET_featurename
TARGET_ASM_MARK_DECL_PRESERVED	TARGET_FF
TARGET_ASM_NAMED_SECTION	TARGET_FIXED_CONDITION_CODE_REGS
TARGET_ASM_OPEN_PAREN	target_flags
TARGET_ASM_OUTPUT_MI_THUNK	TARGET_FLOAT_FORMAT
TARGET_ASM_SELECT_RTX_SECTION	TARGET_FLT_EVAL_METHOD
TARGET_ASM_SELECT_RTA_SECTION	TARGET_FOLD_BUILTIN
TAMODI_NDH_DEDEGI_DEGITON 997	TVEGET TROUD TO THITM

TARGET_FORMAT_TYPES	TARGET_SCHED_ISSUE_RATE 32	26
TARGET_FUNCTION_ATTRIBUTE_INLINABLE_P 369	TARGET_SCHED_REORDER	
TARGET_FUNCTION_OK_FOR_SIBCALL	TARGET_SCHED_REORDER2 32	
TARGET_GIMPLIFY_VA_ARG_EXPR 301	TARGET_SCHED_VARIABLE_ISSUE 32	27
TARGET_HAS_F_SETLKW	TARGET_SECTION_TYPE_FLAGS	
TARGET_HAVE_CTORS_DTORS 350	TARGET_SET_DEFAULT_TYPE_ATTRIBUTES 36	68
TARGET_HAVE_NAMED_SECTIONS	TARGET_SETUP_INCOMING_VARARGS	11
TARGET_IN_SMALL_DATA_P 333	TARGET_SHIFT_TRUNCATION_MASK	74
TARGET_INIT_BUILTINS	TARGET_SPLIT_COMPLEX_ARG 30	01
TARGET_INIT_LIBFUNCS	TARGET_STRICT_ARGUMENT_NAMING	11
TARGET_INSERT_ATTRIBUTES 369	TARGET_STRUCT_VALUE_RTX 30	04
TARGET_LIB_INT_CMP_BIASED	TARGET_SWITCHES 25	56
TARGET_MACHINE_DEPENDENT_REORG	TARGET_TAB 27	72
TARGET_MANGLE_FUNDAMENTAL_TYPE	TARGET_UNWIND_EMIT	55
TARGET_MD_ASM_CLOBBERS	TARGET_UNWIND_INFO	56
TARGET_MERGE_DECL_ATTRIBUTES	TARGET_USE_JCR_SECTION 38	84
TARGET_MERGE_TYPE_ATTRIBUTES	TARGET_USE_LOCAL_THUNK_ALIAS_P 38	83
TARGET_MS_BITFIELD_LAYOUT_P 267	TARGET_USES_WEAK_UNWIND_INFO	90
TARGET_MUST_PASS_IN_STACK	TARGET_VALID_POINTER_MODE	01
TARGET_MUST_PASS_IN_STACK, and FUNCTION_ARG	TARGET_VECTOR_MODE_SUPPORTED_P	01
298	TARGET_VECTOR_OPAQUE_P 26	67
TARGET_N_FORMAT_TYPES 384	TARGET_VECTORIZE_BUILTIN_MASK_FOR_LOAD 31	
TARGET_NEWLINE	TARGET_VERSION 25	
TARGET_OBJECT_SUFFIX	TARGET_VT 27	72
TARGET_OBJFMT_CPP_BUILTINS 256	TARGET_VTABLE_DATA_ENTRY_DISTANCE 27	
TARGET_OPTF 383	TARGET_VTABLE_ENTRY_ALIGN 27	71
TARGET_OPTION_TRANSLATE_TABLE	TARGET_VTABLE_USES_DESCRIPTORS 27	71
TARGET_OPTIONS	TARGET_WEAK_NOT_IN_ARCHIVE_TOC 34	44
TARGET_OS_CPP_BUILTINS	targetm	47
TARGET_PASS_BY_REFERENCE	targets, makefile	
TARGET_PRETEND_OUTGOING_VARARGS_NAMED 311	TCmo de	
TARGET_PROMOTE_FUNCTION_ARGS 261	TEMPLATE_DECL 6	65
TARGET_PROMOTE_FUNCTION_RETURN 261	Temporaries 8	88
TARGET_PROMOTE_PROTOTYPES	termination routines 34	48
TARGET_PTRMEMFUNC_VBIT_LOCATION	text_section	32
TARGET_RELAXED_ORDERING	TEXT_SECTION_ASM_OP	30
TARGET_RETURN_IN_MEMORY 303	TFmode	19
TARGET_RETURN_IN_MSB	THEN_CLAUSE 7	71
TARGET_RTX_COSTS 325	THREAD_MODEL_SPEC	51
TARGET_SCALAR_MODE_SUPPORTED_P 301	THROW_EXPR 7	76
TARGET_SCHED_ADJUST_COST 327	THUNK_DECL 6	65
TARGET_SCHED_ADJUST_PRIORITY 327	THUNK_DELTA 6	
TARGET_SCHED_DEPENDENCIES_EVALUATION_HOOK	TImode 11	19
	TImode, in insn	46
TARGET_SCHED_DFA_NEW_CYCLE 329	'tm.h' macros 24	47
TARGET_SCHED_DFA_POST_CYCLE_INSN	TQFmode	19
TARGET_SCHED_DFA_PRE_CYCLE_INSN	TRAMPOLINE_ADJUST_ADDRESS	13
TARGET_SCHED_FINISH	TRAMPOLINE_ALIGNMENT	12
TARGET_SCHED_FINISH_GLOBAL 328	TRAMPOLINE_SECTION	12
TARGET_SCHED_FIRST_CYCLE_MULTIPASS_DFA_	TRAMPOLINE_SIZE	12
LOOKAHEAD 329	TRAMPOLINE_TEMPLATE	
TARGET_SCHED_FIRST_CYCLE_MULTIPASS_DFA_	trampolines for nested functions	
LOOKAHEAD_GUARD329	TRANSFER_FROM_TRAMPOLINE 31	14
TARGET_SCHED_INIT	trap instruction pattern	11
TARGET_SCHED_INIT_DFA_POST_CYCLE_INSN 329	tree 55, 5	
TARGET_SCHED_INIT_DFA_PRE_CYCLE_INSN 328	Tree SSA 8	87
TARGET_SCHED_INIT_GLOBAL 328	TREE_CODE 5	55
TARGET_SCHED_IS_COSTLY_DEPENDENCE 329	TREE_FILENAME 6	65

tree_int_cst_equal	TYPE_OVERLOADS_ARROW65
TREE_INT_CST_HIGH	TYPE_OVERLOADS_CALL_EXPR
TREE_INT_CST_LOW 76	TYPE_POLYMORPHIC_P64
tree_int_cst_lt	TYPE_PRECISION 57
TREE_LINENO 65	TYPE_PTR_P 59
TREE_LIST 57	TYPE_PTRFN_P 59
TREE_OPERAND 76	TYPE_PTRMEM_P
TREE_PUBLIC	TYPE_PTROB_P 59
TREE_PURPOSE 57	TYPE_PTROBV_P
TREE_STRING_LENGTH	TYPE_QUAL_CONST 57
TREE_STRING_POINTER	TYPE_QUAL_RESTRICT
TREE_TYPE 57, 65, 71, 76	TYPE_QUAL_VOLATILE
TREE_VALUE 57	TYPE_RAISES_EXCEPTIONS 71
TREE_VEC	TYPE_SIZE
TREE_VEC_ELT 57	TYPE_UNQUALIFIED
TREE_VEC_LENGTH 57	TYPE_VFIELD 63
Trees	TYPENAME_TYPE
TRULY_NOOP_TRUNCATION	TYPENAME_TYPE_FULLNAME 57
TRUNC_DIV_EXPR 76	TYPEOF_TYPE 57
TRUNC_MOD_EXPR 76	
truncate 134	TT
truncm2 instruction pattern	U
truncmn2 instruction pattern 203	udiv
TRUTH_AND_EXPR 76	udivm3 instruction pattern 198
TRUTH_ANDIF_EXPR 76	udivmodm 4 instruction pattern
TRUTH_NOT_EXPR 76	UINTMAX_TYPE
TRUTH_OR_EXPR 76	umax
TRUTH_ORIF_EXPR	umaxm3 instruction pattern
TRUTH_XOR_EXPR 76	umin
TRY_BLOCK 71	uminm3 instruction pattern
TRY_HANDLERS 71	umod
TRY_STMTS 71	umodm3 instruction pattern 198
tstm instruction pattern	umulhisi3 instruction pattern
type	umulm3_highpart instruction pattern 198
type declaration	umulqihi3 instruction pattern
TYPE_ALIGN 57, 58	umulsidi3 instruction pattern 198
TYPE_ARG_TYPES 57	unchanging 117
TYPE_ASM_OP 342	unchanging, in call_insn
TYPE_ATTRIBUTES 76	unchanging, in jump_insn, call_insn and insn
TYPE_BINFO 63	
TYPE_BUILT_IN 59	unchanging, in mem
TYPE_CONTEXT 57	unchanging, in subreg
TYPE_DECL 65	unchanging, in symbol_ref
TYPE_FIELDS	UNEQ_EXPR 76
TYPE_HAS_ARRAY_NEW_OPERATOR	UNGE_EXPR 76
TYPE_HAS_DEFAULT_CONSTRUCTOR	UNGT_EXPR 76
TYPE_HAS_MUTABLE_P65	UNION_TYPE 57, 63
TYPE_HAS_NEW_OPERATOR	unions, returning
TYPE_MAIN_VARIANT 57, 58	UNITS_PER_WORD 260
TYPE_MAX_VALUE 57	UNKNOWN_TYPE 57
TYPE_METHOD_BASETYPE57	UNLE_EXPR 76
TYPE_METHODS 63	UNLIKELY_EXECUTED_TEXT_SECTION_NAME 330
TYPE_MIN_VALUE 57	UNLT_EXPR 76
TYPE_NAME	UNORDERED_EXPR 76
TYPE_NOTHROW_P 71	unshare_all_rtl
TYPE_OFFSET_BASETYPE57	unsigned division
TYPE_OPERAND_FMT 342	unsigned greater than
TYPE_OVERLOADS_ARRAY_REF	unsigned less than

	WEGTON GTONE ELAG WALKE 976
unsigned minimum and maximum	VECTOR_STORE_FLAG_VALUE
unsigned_float	VIRTUAL_INCOMING_ARGS_REGNUM
	VIRTUAL_OUTGOING_ARGS_REGNUM
unspec 140 unspec_volatile 140	VIRTUAL_STACK_DYNAMIC_REGNUM
untyped_call instruction pattern	VIRTUAL_STACK_VARS_REGNUM
untyped_return instruction pattern	VLIW
UPDATE_PATH_HOST_CANONICALIZE (path) 386	VMS
US Software GOFAST, floating point emulation	VMS_DEBUGGING_INFO
library	VOID_TYPE
us_minus	VOIDmode
us_plus	volatil
US_SOFTWARE_GOFAST	volatil, in insn, call_insn, jump_insn,
us_truncate	$\mathtt{code_label}$, $\mathtt{barrier}$, and \mathtt{note} 113
use	volatil, in label_ref and reg_label 114
USE_C_ALLOCA 387	${\tt volatil}, \ in \ {\tt mem}, \ {\tt asm_operands}, \ and \ {\tt asm_input}$
USE_LD_AS_NEEDED	
USE_LOAD_POST_DECREMENT 325	volatil, in reg 114
USE_LOAD_POST_INCREMENT 324	volatil, in subreg 116
USE_LOAD_PRE_DECREMENT 325	volatil, in symbol_ref
USE_LOAD_PRE_INCREMENT 325	volatile memory references
USE_OP	voting between constraint alternatives 182
USE_OP_PTR	
use_param	\mathbf{W}
use_paramn	walk_dominator_tree
use_params	walk_use_def_chains
USE_SELECT_SECTION_FOR_FUNCTIONS	WCHAR_TYPE
USE_STORE_POST_DECREMENT 325	WCHAR_TYPE_SIZE
USE_STORE_POST_INCREMENT 325	which_alternative
USE_STORE_PRE_DECREMENT 325	WHILE_BODY 71
USE_STORE_PRE_INCREMENT 325	WHILE_COND 71
used	WHILE_STMT 71
used, in symbol_ref 116	WIDEST_HARDWARE_FP_SIZE 269
USER_LABEL_PREFIX	WINT_TYPE 270
USING_DECL	word_mode
USING_STMT 71	WORD_REGISTER_OPERATIONS
	WORD_SWITCH_TAKES_ARG
\mathbf{V}	WORDS_BIG_ENDIAN
'V' in constraint	words_big_Endian, effect off subreg 120
VA_ARG_EXPR	
values, returned by functions	\mathbf{X}
VAR_DECL	'X' in constraint
varargs implementation	'x-host'
variable	XCmo de
vars_to_rename	XCOFF_DEBUGGING_INFO
VAX_FLOAT_FORMAT	XEXP
vec_concat	XFmode119
vec_duplicate	XINT 110
vec_extractm instruction pattern	'xm-machine.h'
vec_initm instruction pattern	xor
vec_merge	xor, canonicalization of
vec_select	xorm3 instruction pattern
vec_setm instruction pattern	XSTR
vector 57 vector operations 133	XVEC
VECTOR_CST	XVECLEN
**************************************	111

GNU Compiler Collection (GCC) Internals

458

XW1N1 110	zero_extendmn2 instruction pattern 203
${f Z}$	zero_extract
zero_extend 134	zero_extract, canonicalization of 217