A Note on Vector Autoregression

Why is it called *vector* autoregression? As mentioned in class we ran write the VAR(p) system of equations in a vector/matrix notation. Recall that for r endogenous variables these equations look as follows:

$$\begin{split} Y_{1,t} &= c_1 + \sum_{i=1}^p \phi_{11,i} Y_{1,t-i} + \sum_{i=1}^p \phi_{12,i} Y_{2,t-i} + \dots + \sum_{i=1}^p \phi_{1r,i} Y_{r,t-i} + \varepsilon_{1,t} \\ Y_{2,t} &= c_2 + \sum_{i=1}^p \phi_{21,i} Y_{1,t-i} + \sum_{i=1}^p \phi_{22,i} Y_{2,t-i} + \dots + \sum_{i=1}^p \phi_{2r,i} Y_{r,t-i} + \varepsilon_{2,t} \\ &\vdots \\ Y_{r,t} &= c_r + \sum_{i=1}^p \phi_{r1,i} Y_{1,t-i} + \sum_{i=1}^p \phi_{r2,i} Y_{2,t-i} + \dots + \sum_{i=1}^p \phi_{rr,i} Y_{r,t-i} + \varepsilon_{r,t} \end{split}$$

To simplify this, we can define the $r \times 1$ vector $\mathbf{Y}_t = (Y_{1,t}, Y_{2,t}, ..., Y_{r,t})^T$ to be the vector of endogenous variable observations at time point t. Thus at every time point we observe a *vector* of values as opposed to a single value. Using this notation, we compactly write the VAR(p) systems of equations using vector/matrix notation as follows:

$$Y_t = c + A_1 Y_{t-1} + A_2 Y_{t-2} + \dots + A_r Y_{t-r} + \varepsilon_t$$

where $\mathbf{c} = (c_1, c_2, ..., c_r)$ is an $r \times 1$ vector of constants, $\mathbf{\varepsilon}_t = (\varepsilon_{1,t}, \varepsilon_{2,t}, ..., \varepsilon_{r,t})^T$ is an $r \times 1$ vector of white noise error terms and each A_k (k = 1, 2, ..., r) is an $r \times r$ matrix of coefficients given by:

$$A_{k} = \begin{bmatrix} \phi_{11,k} & \phi_{12,k} & \cdots & \phi_{1r,k} \\ \phi_{21,k} & \phi_{22,k} & \cdots & \phi_{2r,k} \\ \vdots & \vdots & \ddots & \vdots \\ \phi_{r1,k} & \phi_{r2,k} & \cdots & \phi_{rr,k} \end{bmatrix}$$