

Lightmaps are missing for initial skylight

MC-170012 LIGHTING

Status	Resolved / Fixed
Affected	1.15.1; 1.15.2 Pre-release 2; 1.15.2; 20w06a; 20w20b; 20w21a; 1.16.2; 1.16.4; 20w48a; 1.17; 1.17.1 Pre-release 1; 1.17.1; 21w37a; 21w40a; 1.18; 1.19 Pre-release 3
Fixed in	23w16a
Reported	2020-01-17
Mojira category	Lighting

REPRODUCTION TARGET

Use version: 1.15.1

Affected versions (16):

1.15.1

1.15.2 Pre-release 2

1.15.2

20w06a

20w20b

20w21a

1.16.2

1.16.4

20w48a

1.17

1.17.1 Pre-release 1

1.17.1

21w37a

21w40a

1.18

1.19 Pre-release 3

Environment:

Minecraft Java Edition 1.15.1 in a disposable singleplayer Redstone Ready superflat world. Use Creative mode with commands enabled for setup, then Spectator mode for the post-relighting approach. Use an unmodified client without shaders or lighting-altering mods. To preserve the report's intended unloaded 500-block approach, use a render distance of 16 chunks or less.

PRECONDITIONS

- Install and launch the exact affected version Minecraft Java Edition 1.15.1; do not use fix version 23w16a.
- Use a new disposable singleplayer world rather than an important existing save because the procedure optimizes the world and erases cached world data.
- Use the Redstone Ready superflat preset specified by the report.
- Enable commands by creating the world in Creative mode or otherwise enabling cheats.
- Use the default keyboard-and-mouse controls, or substitute the executor's bindings for Open Chat, Move Forward, Jump/Fly Up, and Strafe Right.
- Use a render distance of 16 chunks or less so that the construction approximately 500 blocks east of the saved player position is not loaded immediately when the optimized world opens.

STEPS TO REPRODUCE

1 **REPORT**

From the Minecraft Launcher, start an unmodified installation of Minecraft Java Edition 1.15.1. Wait at the title screen and confirm that the displayed version is 1.15.1.

SUCCESS CUE The Minecraft title screen is open and identifies the running version as 1.15.1.

2 **INFERRED**

Open the singleplayer world-creation screen by selecting Singleplayer and then Create New World.

INPUT Singleplayer -> Create New World

SUCCESS CUE The Create New World configuration screen is open.

3 **INFERRED**

Set the new world's game mode to Creative. Creative mode enables the in-game commands needed for the supplied setup and avoids survival restrictions.

INPUT Game Mode: Creative

SUCCESS CUE The world-creation screen displays Game Mode: Creative, with commands available for the world.

4 **REPORT**

Open More World Options, change World Type to Superflat, select Customize, open Presets, select the Redstone Ready preset, apply it with Use Preset, and return to the main world-creation screen with Done. Do not substitute another flat-world preset.

INPUT

More World Options... -> World Type: Superflat -> Customize -> Presets -> Redstone Ready -> Use Preset -> Done

SUCCESS CUE The world type is Superflat and its selected preset is Redstone Ready.

5 **REPORT**

Create the world and wait until world generation and terrain rendering finish. Do not continue while the loading screen is visible or while nearby terrain is still appearing.

INPUT Create New World

SUCCESS CUE The player is standing in a fully loaded, flat Redstone Ready world and movement responds normally.

6 **INFERRED**

Limit the render distance so the target construction remains outside the initially loaded area after relighting. Pause the game, open Options and Video Settings, set Render Distance to 16 chunks or lower, accept the setting, and return to the world.

INPUT

Esc -> Options... -> Video Settings... -> Render Distance: 16 chunks or lower -> Done -> Done -> Back to Game

SUCCESS CUE Gameplay has resumed with Render Distance set to no more than 16 chunks.

7 **REPORT**

Open in-game chat with T, enter the report's first teleport command exactly with its leading slash, and press Enter.

INPUT `/tp 500 56 0`

SUCCESS CUE The player is at approximately X=500, Y=56, Z=0. The command succeeds rather than displaying a syntax or permission error.

8 **INFERRED**

Wait at the destination until the surrounding flat terrain has rendered and both movement and chat commands respond normally. This ensures that the target chunks exist before the geometry is placed.

SUCCESS CUE Terrain around X=500 is visible, no loading screen is present, and player movement is responsive.

9 **REPORT**

Open chat with T and execute the supplied fill command exactly. This constructs a hollow 16-by-16-by-16 stone cube occupying X=496 through 511, Y=80 through 95, and Z=0 through 15.

INPUT `/fill 496 80 0 511 95 15 minecraft:stone hollow`

SUCCESS CUE The command reports successful block placement; a hollow stone cube now exists above the local flat surface.

10 **REPORT**

Open chat with T and execute the supplied setblock command exactly. The placed stone block is at X=487, Y=119, Z=7, in the chunk immediately west of the cube; it may be too high to see from the player's current position.

INPUT `/setblock 487 119 7 minecraft:stone`

SUCCESS CUE The command reports that the block was successfully changed at or placed at 487, 119, 7.

11 **REPORT**

Open chat with T and execute the supplied teleport command exactly. The final two arguments set yaw to 270 degrees and pitch to 0, orienting the player toward increasing X.

INPUT `/tp @s 0 56 0 270 0`

SUCCESS CUE The player is at approximately X=0, Y=56, Z=0 and is facing east, toward increasing X.

12 **INFERRED**

Pause and leave the world using Save and Quit to Title so that the constructed chunks and the player position are written to the world save.

INPUT `Esc -> Save and Quit to Title`

SUCCESS CUE The title screen is displayed and the world is no longer open.

13 **VERIFIED**

Open Singleplayer, select the newly created Redstone Ready world once, choose Edit, and then choose Optimize World. Do not create or select a different world.

INPUT `Singleplayer -> select the test world -> Edit -> Optimize World`

SUCCESS CUE The Optimize World confirmation screen for the test world is open.

14 **REPORT**

On the Optimize World screen, enable the Erase Cached Data option. Ensure the option is enabled before starting the operation; this is the report's mechanism for forcing the world's lighting data to be recomputed.

INPUT `Erase Cached Data: ON`

SUCCESS CUE The Optimize World screen visibly shows that Erase Cached Data is enabled.

15 **INFERRED**

Start optimization. Prefer the button that creates a backup and then loads the world, commonly labeled Create Backup and Load or Backup and Load. If that label is unavailable, use the proceed-without-backup button only because this is a disposable test world.

INPUT

Create Backup and Load; if unavailable, use the displayed proceed/optimization confirmation button

SUCCESS CUE An optimization progress screen appears and begins processing the selected world.

16 **REPORT**

Wait without cancelling until optimization reaches completion and the world loads. If the operation returns to the world list instead of opening the world automatically, select the same world and choose Play Selected World. Then wait until terrain around the saved origin position is rendered and movement responds normally.

SUCCESS CUE The optimized test world is open at approximately X=0, Y=56, Z=0, surrounding chunks are rendered, and movement is responsive.

17 **INFERRED**

Do not teleport after the optimized world opens. If coordinate confirmation is needed, press F3 and verify that the player remains near X=0, Y=56, Z=0 and is facing toward positive X; then close the debug overlay with F3 if it obstructs navigation.

INPUT `F3`

SUCCESS CUE The saved origin position and eastward orientation are confirmed without loading the target by teleportation.

18 **VERIFIED**

Enter Spectator mode using the version-compatible command. Open chat with T, enter the command with the leading slash, and press Enter.

INPUT `/gamemode spectator`

SUCCESS CUE The command succeeds, the player is in Spectator mode, can fly continuously, and can pass through solid blocks.

19 **INFERRED**

While remaining near the origin in X, align the flight path with the center of the target cube: hold Fly Up, Space by default, until Y is approximately 88; while still facing positive X, use Strafe Right, D by default, until Z is approximately 7. Use the F3 coordinate display if necessary. Do not use another teleport command.

INPUT `Space until Y≈88; D until Z≈7`

SUCCESS CUE The spectator is near X=0, Y=88, Z=7 and is still facing toward increasing X.

20 **REPORT**

Fly continuously toward increasing X by holding Move Forward, W by default. Do not teleport to the cube. Use normal or moderate spectator flight speed rather than maximizing speed, and pause whenever terrain ahead has not rendered; resume only after chunks appear and movement responds normally.

INPUT Hold W toward positive X

SUCCESS CUE The player's X coordinate increases from near 0 toward 480 while Y remains near 88 and Z remains near 7, with chunks loading progressively during the flight.

21 **INFERRED**

Continue east until reaching approximately X=495, Y=88, Z=7, immediately outside the cube's west face. The target is the hollow stone cube spanning X=496–511, Y=80–95, Z=0–15. Wait until the cube's exterior is fully rendered before proceeding.

INPUT Continue holding W, then stop near X=495, Y=88, Z=7

SUCCESS CUE A solid stone wall belonging to the target cube is directly in front of the spectator, and the cube is fully rendered.

22 **REPORT** **TRIGGER**

From the west side of the cube, press Move Forward once more and fly through the stone wall at X=496 into the hollow interior. Stop once the coordinates are inside X=497–510, Y=81–94, Z=1–14.

INPUT W through the west wall; stop inside X=497–510, Y=81–94, Z=1–14

SUCCESS CUE The spectator camera is stationary in the cube's enclosed air cavity, surrounded by the interior faces of the stone shell.

HANDOFF TO OBSERVATION

The world has been optimized with Erase Cached Data enabled, the player has approached the target by flying approximately 500 blocks in the positive-X direction, and the Spectator-mode camera has just entered and stopped inside the hollow stone cube. Begin lighting observation without placing, removing, or updating any blocks.

UNCERTAINTIES

- The formal Affects versions field does not include every additional version mentioned in comments, such as 1.16.3, 1.17.1 Pre-release 3, and 1.17.1 Release Candidate 2; affected_versions therefore preserves only the formal field supplied in the report.
- The report does not specify the setup game mode. Creative mode is selected as a practical method to enable the supplied commands, while Spectator mode is explicitly required for the final flight into the cube.
- The report does not specify a world seed. No fixed seed is required because the Redstone Ready preset and exact coordinates provide the controlled geometry.
- The report does not specify render distance. The plan uses 16 chunks or less as a practical safeguard so the construction 500 blocks away is not loaded immediately from the saved origin; this is not asserted as a formal bug requirement.
- The exact capitalization and proceed-button wording on the Minecraft 1.15.1 Optimize World screen may vary by language setting. The required state is that Erase Cached Data is enabled before optimization starts.
- The report says to fly 500 blocks in positive X and enter the cube but does not prescribe an exact altitude or Z coordinate for the approach. $Y \approx 88$ and $Z \approx 7$ are chosen to intersect the center of the cube's hollow interior deterministically.

MANUAL RESULT

Version used	
Reproduced?	YES / NO / PARTIAL
Trigger reached?	YES / NO
Crash file	
Notes	
Tested by / date	