

You can destroy turtle eggs by standing or jumping on them in spawn protection

MC-223321 Block states

Status	Resolved / Fixed
Affected	1.16.5, 21w15a, 21w16a, 21w18a, 21w19a, 21w20a (+11 more)
Fixed in	26.3 Snapshot 1
Reported	2021-04-15

STEPS TO REPRODUCE

1. Start a server and join it.
2. Give yourself operator permissions and switch to Creative mode.
3. Set the world spawn at your current location by entering `/setworldspawn ~ ~ ~``.
4. Place turtle eggs nearby by entering `/setblock ~ ~ ~-2 minecraft:turtle_egg[eggs=4]``.
5. Switch to Survival mode and remove your operator permissions.
6. Give operator permissions to another player to activate spawn protection.
7. Stand on or jump on the turtle eggs inside spawn protection.
8. Observe that the turtle eggs are destroyed.

OBSERVED BEHAVIOUR

A non-operator player in Survival mode can destroy turtle eggs inside the protected spawn area by walking over them or jumping on them. The eggs are trampled despite the player being unable to otherwise break or interact with blocks in spawn protection. This occurs because the turtle egg trampling logic does not verify whether the player is permitted to interact with the egg's position through the normal spawn-protection check.

EXPECTED BEHAVIOUR

Players without operator permissions should be unable to destroy or trample turtle eggs by standing or jumping on them while the eggs are within spawn protection. Turtle eggs in protected areas should remain intact, consistent with the protection applied to other blocks, while normal egg behavior should remain unchanged outside spawn protection or for players permitted to interact there.

ENVIRONMENT

Minecraft Java Edition Versions: 1.16.5, 21w15a, 21w16a, 21w18a, 21w19a, 21w20a, 1.17.1, 1.18.1, 1.18.2 Pre-release 1, 1.18.2, 1.19, 1.19.2, 1.19.3, 1.19.4, 1.20.1, 1.21, 1.21.4 (includes snapshots)

ORIGINAL DESCRIPTION

The Bug:

Players without operator permissions cannot normally interact with or destroy blocks inside spawn protection, however, you are able to destroy turtle eggs by standing or jumping on them, regardless of whether or not they're inside of spawn protection.

Steps to Reproduce:

- Start a server, join it, give operator permissions to yourself, and switch into creative mode.
- Set the world spawn to your current location and summon some turtle eggs nearby by using the commands provided below.
`/setworldspawn ~ ~ ~``
`/setblock ~ ~ ~-2 minecraft:turtle_egg[eggs=4]``
- Switch into survival mode, remove your operator permissions, and grant anyone else with them in order to activate spawn protection.
- Attempt to destroy the turtle eggs by standing or jumping on them.
- Take note as to whether or not you can destroy turtle eggs by standing or jumping on them in spawn protection.

Observed Behavior:

Turtle eggs are destroyed.

Expected Behavior:

Turtle eggs would not be destroyed.

Code Analysis:

Code analysis by Avoma can be found below.

The following is based on a decompiled version of Minecraft 1.18.1 using MCP-Reborn.

net.minecraft.world.level.block.TurtleEggBlock.java

```
public class TurtleEggBlock extends Block {  
    ...  
    private boolean canDestroyEgg(Level $l, Entity $e) {  
        if (!($e instanceof Turtle) && !($e instanceof Bat)) {  
            if (!($e instanceof LivingEntity)) {  
                return false;  
            } else {  
                return $e instanceof Player || $l.getGameRules().getBoolean(GameRules.RULE_MOBGRIEFING);  
            }  
        } else {  
            return false;  
        }  
    }  
    ...  
}
```

If we look at the above class, we can see that no checks are carried out to see whether or not the turtle egg block is within spawn protection, before allowing it to be trampled. The `mayInteract()` method (a method used for determining whether a block is inside of spawn protection and is within the world border) is never called within this piece of code, thus resulting in the problem of being able to trample turtle eggs in spawn protection.

Potential Fix:

Simply adding some lines of code that check if the turtle egg block is within spawn protection before allowing it to be trampled, should resolve this problem. This can

MANUAL RESULT

Version used	
Reproduced?	YES / NO / PARTIAL
Crash file	
Notes	
Tested by / date	

Live issue: <https://bugs.mojang.com/browse/MC/issues/MC-223321>