

The end obsidian platform resets every time entities go through the end portal, which can cause blocks to be deleted

MC-902 Block states

Status	Resolved / Fixed
Affected	Minecraft 1.4.2, 1.14.4, 1.16.1, 1.16.3, 1.16.4 Pre-release 1, 1.16.4 Pre-release 2 (+50 more)
Fixed in	1.21 Pre-Release 1
Reported	2012-10-27

STEPS TO REPRODUCE

1. Enter the End by using an end portal.
2. Place blocks on top of and around the obsidian platform where you spawn.
3. Take note of the blocks you placed.
4. Run `/kill``.
5. Enter the End again using an end portal.
6. Observe that the obsidian platform has reset and that blocks previously placed on or around it have been deleted.

OBSERVED BEHAVIOUR

When an entity enters the End through an End portal, the game regenerates the obsidian spawn platform at the End spawn position. This regeneration replaces the platform blocks and clears the surrounding space above it, regardless of whether the platform has been modified since the previous visit.

As a result, any player-placed blocks within the platform's regeneration area are removed each time the platform is regenerated. This includes block entities such as chests and shulker boxes; if they are inside the affected area, the containers and their contents are deleted. Blocks outside the regeneration area are unaffected.

EXPECTED BEHAVIOUR

Blocks placed on or around the End obsidian platform should remain in place when entities travel through the End portal. The platform should not be regenerated in a way that removes existing blocks, including chests and shulker boxes, and any containers in the affected area should retain their contents after the entity returns to the End.

ENVIRONMENT

Minecraft Java Edition Versions: 1.4.2, 1.14.4, 1.16.1, 1.16.3, 1.16.4 Pre-release 1, 1.16.4 Pre-release 2, 1.16.4 Release Candidate 1, 1.16.4, 20w45a, 20w46a, 20w48a, 20w49a, 20w51a, 21w03a, 1.16.5, 21w05a, 21w05b, 21w06a, 21w07a, 21w08b, 21w10a, 21w11a, 21w13a, 21w14a, 21w17a, 21w20a, 1.17, 1.17.1 Pre-release 1, 1.17.1, 21w39a, 21w42a, 1.18, 1.18.1, 22w05a, 1.18.2 Pre-release 1, 1.18.2 Release Candidate 1, 1.18.2, 22w14a, 1.19 Pre-release 4, 1.19 Pre-release 5, 1.19 Release Candidate 1, 1.19 Release Candidate 2, 1.19, 22w24a, 1.19.1, 1.19.2, 1.19.3, 23w03a, 23w04a, 23w05a, 1.19.4, 1.20 Release Candidate 1, 1.20, 1.20.1, 24w11a, 1.20.6 (includes snapshots)

ORIGINAL DESCRIPTION

The Bug:

The end obsidian platform resets every time entities go through the end portal, which can cause blocks to be deleted.

This notably results in containers like chests or shulker boxes which might contain valuable items within them being deleted.

Steps to Reproduce:

- Enter the end by using an end portal.
- Place some blocks on top of and around the obsidian platform that you spawn on.
- Take note of the blocks that you've just placed.

- Run the "/kill" command.
- Enter the end once again and attempt to locate the blocks you just previously placed.
- Take note as to whether or not the end obsidian platform resets every time entities go through the end portal, which can cause blocks to be deleted.

Observed Behavior:

The end obsidian platform resets every time entities go through the end portal, which can cause blocks to be deleted.

Expected Behavior:

Blocks on the end obsidian platform would not be deleted every time an entity goes through the end portal.

Code Analysis:

Code analysis by Avoma can be found below.

The following is based on a decompiled version of Minecraft 1.18.1 using MCP-Reborn.

net.minecraft.world.entity.Entity.java

```
public abstract class Entity implements Nameable, EntityAccess, CommandSource {
```

```
...
```

```
public Entity changeDimension(ServerLevel $sl) {
```

```
if (this.level instanceof ServerLevel && !this.isRemoved()) {
```

```
...
```

```
if (portalinfo == null) {
```

```
return null;
```

```
} else {
```

```
...
```

```
if (entity != null) {
```

```
...
```

```
if ($sl.dimension() == Level.END) {
```

```
ServerLevel.makeObsidianPlatform($sl);
```

```
}
```

```
}
```

```
...
```

If we look at the above class, we can see that when an entity enters the end portal, the makeObsidianPlatform() method is called. This method completely regenerates the end obsidian platform (including the space above), causing blocks previously placed at its position to be deleted.

MANUAL RESULT

Version used	
Reproduced?	YES / NO / PARTIAL
Crash file	
Notes	
Tested by / date	

Live issue: <https://bugs.mojang.com/browse/MC/issues/MC-902>