HTTPS and HTTP

Sunday, November 20, 2022 7:31 PM

Print S

Ailow 80 / 443

- o sudo iptables -A INPUT -p tcp --dport 80 -m conntrack --ctstate NEW,ESTABLISHED -j ACCEPT
- o sudo iptables -A OUTPUT -p tcp --sport 80 -m conntrack -ctstate ESTABLISHED -j ACCEPT
- o Change 80 to 443 for HTTPS

Find where webserver is located

- Site files:
 - o /var/www/html
 - o C:\Xampp\htdocs
- Apache location:
 - o /usr/local/apache2
 - o C:/Progran Files/Apache Group/Apache2

Remove Server Version Banner

Apache reports the server version in the response header by default

- 1. Go to \$Web_Server/conf folder (/etc/apache2)
- 2. Modify hhtpd.conf (apache2.conf)
- 3. Add the following:

ServerTokens Prod

ServerSignature Off

4. Restart Apache (sudo systemctl restart apache2)

Disable Directory Browsing

- 1. Modify hhtpd.conf (apache2.conf)
- 2. Find

<Directory /opt/apache/htdocs>

Options -Indexes

</Directory>

And change it to

<Directory /opt/apache/htdocs>

Options None

</Directory>

3. Restart Apache